

Run-Time Library (RTL) :
Reference guide.

Reference guide for RTL units.
Document version 2.1
September 2006

Michaël Van Canneyt

Contents

0.1	Overview	90
1	Reference for unit 'BaseUnix'	91
1.1	Used units	91
1.2	Overview	91
1.3	Constants, types and variables	91
1.3.1	Constants	91
1.3.2	Types	112
1.4	Procedures and functions	126
1.4.1	CreateShellArgV	126
1.4.2	FpAccess	126
1.4.3	FpAlarm	127
1.4.4	FpChdir	128
1.4.5	FpChmod	128
1.4.6	FpChown	129
1.4.7	FpClose	130
1.4.8	FpClosedir	130
1.4.9	FpDup	131
1.4.10	FpDup2	132
1.4.11	FpExecv	133
1.4.12	FpExecve	134
1.4.13	FpExit	135
1.4.14	FpFcntl	135
1.4.15	fpdfillset	136
1.4.16	fpFD_CLR	136
1.4.17	fpFD_ISSET	136
1.4.18	fpFD_SET	136
1.4.19	fpFD_ZERO	137
1.4.20	FpFork	137
1.4.21	FPFStat	137
1.4.22	FpFtruncate	138

1.4.23	FpGetcwd	139
1.4.24	FpGetegid	139
1.4.25	FpGetEnv	139
1.4.26	fpgeterrno	140
1.4.27	FpGeteuid	140
1.4.28	FpGetgid	141
1.4.29	FpGetgroups	141
1.4.30	FpGetpggrp	141
1.4.31	FpGetpid	142
1.4.32	FpGetppid	142
1.4.33	fpGetPriority	143
1.4.34	FpGetuid	143
1.4.35	FpIOCtl	143
1.4.36	FpKill	144
1.4.37	FpLink	144
1.4.38	FpLseek	146
1.4.39	fpLstat	146
1.4.40	FpMkdir	148
1.4.41	FpMkfifo	148
1.4.42	Fpmmmap	148
1.4.43	Fpmunmap	150
1.4.44	FpNanoSleep	150
1.4.45	fpNice	151
1.4.46	FpOpen	152
1.4.47	FpOpendir	153
1.4.48	FpPause	154
1.4.49	FpPipe	154
1.4.50	FppRead	155
1.4.51	FppWrite	155
1.4.52	FpRead	156
1.4.53	FpReaddir	157
1.4.54	fpReadLink	157
1.4.55	FpReadV	158
1.4.56	FpRename	159
1.4.57	FpRmdir	159
1.4.58	fpSelect	160
1.4.59	fpseterrno	161
1.4.60	FpSetgid	161
1.4.61	fpSetPriority	162
1.4.62	FpSetsid	162

1.4.63	fpsettimeofday	162
1.4.64	FpSetuid	163
1.4.65	FPSigaction	163
1.4.66	FpSigAddSet	164
1.4.67	FpSigDelSet	164
1.4.68	FpsigEmptySet	165
1.4.69	FpSigFillSet	165
1.4.70	FpSigIsMember	165
1.4.71	FpSignal	166
1.4.72	FpSigPending	166
1.4.73	FpSigProcMask	167
1.4.74	FpSigSuspend	167
1.4.75	FpSleep	167
1.4.76	FpStat	168
1.4.77	fpSymlink	169
1.4.78	fpS_ISBLK	170
1.4.79	fpS_ISCHR	170
1.4.80	fpS_ISDIR	171
1.4.81	fpS_ISFIFO	171
1.4.82	fpS_ISLNK	171
1.4.83	fpS_ISREG	172
1.4.84	fpS_ISSOCK	172
1.4.85	fpTime	172
1.4.86	FpTimes	173
1.4.87	FpUmask	173
1.4.88	FpUname	174
1.4.89	FpUnlink	174
1.4.90	FpUtime	174
1.4.91	FpWait	175
1.4.92	FpWaitPid	176
1.4.93	FpWrite	176
1.4.94	FpWriteV	177
1.4.95	FreeShellArgV	177
1.4.96	wexitStatus	177
1.4.97	wifexited	177
1.4.98	wifsignaled	178
1.4.99	wstopsig	178
1.4.100	wtermsig	178

2 Reference for unit 'Classes'

179

2.1	Used units	179
2.2	Overview	179
2.3	Constants, types and variables	179
2.3.1	Constants	179
2.3.2	Types	181
2.3.3	Variables	191
2.4	Procedures and functions	193
2.4.1	ActivateClassGroup	193
2.4.2	BeginGlobalLoading	193
2.4.3	BinToHex	193
2.4.4	Bounds	194
2.4.5	CheckSynchronize	194
2.4.6	ClassGroupOf	194
2.4.7	CollectionsEqual	194
2.4.8	EndGlobalLoading	195
2.4.9	ExtractStrings	195
2.4.10	FindClass	195
2.4.11	FindGlobalComponent	195
2.4.12	FindNestedComponent	196
2.4.13	GetClass	196
2.4.14	GetFixupInstanceNames	196
2.4.15	GetFixupReferenceNames	196
2.4.16	GlobalFixupReferences	197
2.4.17	GroupDescendentsWith	197
2.4.18	HexToBin	197
2.4.19	IdentToInt	197
2.4.20	InitComponentRes	198
2.4.21	InitInheritedComponent	198
2.4.22	IntToIdent	198
2.4.23	InvalidPoint	199
2.4.24	LineStart	199
2.4.25	NotifyGlobalLoading	199
2.4.26	ObjectBinaryToText	199
2.4.27	ObjectResourceToText	199
2.4.28	ObjectTextToBinary	200
2.4.29	ObjectTextToResource	200
2.4.30	Point	200
2.4.31	PointsEqual	200
2.4.32	ReadComponentRes	201
2.4.33	ReadComponentResEx	201

2.4.34	ReadComponentResFile	201
2.4.35	Rect	201
2.4.36	RedirectFixupReferences	202
2.4.37	RegisterClass	202
2.4.38	RegisterClassAlias	202
2.4.39	RegisterClasses	202
2.4.40	RegisterComponents	203
2.4.41	RegisterFindGlobalComponentProc	203
2.4.42	RegisterInitComponentHandler	203
2.4.43	RegisterIntegerConsts	203
2.4.44	RegisterNoIcon	204
2.4.45	RegisterNonActiveX	204
2.4.46	RemoveFixupReferences	204
2.4.47	RemoveFixups	205
2.4.48	SmallPoint	205
2.4.49	StartClassGroup	205
2.4.50	UnRegisterClass	205
2.4.51	UnRegisterClasses	205
2.4.52	UnregisterFindGlobalComponentProc	206
2.4.53	UnRegisterModuleClasses	206
2.4.54	WriteComponentResFile	206
2.5	EBitsError	206
2.5.1	Description	206
2.6	EClassNotFound	207
2.6.1	Description	207
2.7	EComponentError	207
2.7.1	Description	207
2.8	EFCREATEError	207
2.8.1	Description	207
2.9	EFilerError	207
2.9.1	Description	207
2.10	EFOpenError	207
2.10.1	Description	207
2.11	EInvalidImage	207
2.11.1	Description	207
2.12	EInvalidOperation	208
2.12.1	Description	208
2.13	EListError	208
2.13.1	Description	208
2.14	EMethodNotFound	208

2.14.1 Description	208
2.15 EOutOfResources	208
2.15.1 Description	208
2.16 EParserError	208
2.16.1 Description	208
2.17 EReadError	208
2.17.1 Description	208
2.18 EResNotFound	209
2.18.1 Description	209
2.19 EStreamError	209
2.19.1 Description	209
2.20 EStringListError	209
2.20.1 Description	209
2.21 EThread	209
2.21.1 Description	209
2.22 EThreadDestroyCalled	209
2.22.1 Description	209
2.23 EWriteError	210
2.23.1 Description	210
2.24 IDesignerNotify	210
2.24.1 Description	210
2.24.2 Method overview	210
2.24.3 IDesignerNotify.Modified	210
2.24.4 IDesignerNotify.Notification	210
2.25 IInterfaceList	211
2.25.1 Description	211
2.25.2 Method overview	211
2.25.3 Property overview	211
2.25.4 IInterfaceList.Get	211
2.25.5 IInterfaceList.GetCapacity	212
2.25.6 IInterfaceList.GetCount	212
2.25.7 IInterfaceList.Put	212
2.25.8 IInterfaceList.SetCapacity	212
2.25.9 IInterfaceList.SetCount	213
2.25.10 IInterfaceList.Clear	213
2.25.11 IInterfaceList.Delete	213
2.25.12 IInterfaceList.Exchange	213
2.25.13 IInterfaceList.First	214
2.25.14 IInterfaceList.IndexOf	214
2.25.15 IInterfaceList.Add	214

2.25.16	IInterfaceList.Insert	214
2.25.17	IInterfaceList.Last	214
2.25.18	IInterfaceList.Remove	215
2.25.19	IInterfaceList.Lock	215
2.25.20	IInterfaceList.Unlock	215
2.25.21	IInterfaceList.Capacity	215
2.25.22	IInterfaceList.Count	216
2.25.23	IInterfaceList.Items	216
2.26	IStreamPersist	216
2.26.1	Description	216
2.26.2	Method overview	216
2.26.3	IStreamPersist.LoadFromStream	216
2.26.4	IStreamPersist.SaveToStream	217
2.27	IStringsAdapter	217
2.27.1	Description	217
2.27.2	Method overview	217
2.27.3	IStringsAdapter.ReferenceStrings	217
2.27.4	IStringsAdapter.ReleaseStrings	217
2.28	TAbstractObjectReader	217
2.28.1	Description	217
2.28.2	Method overview	218
2.28.3	TAbstractObjectReader.NextValue	218
2.28.4	TAbstractObjectReader.ReadValue	218
2.28.5	TAbstractObjectReader.BeginRootComponent	218
2.28.6	TAbstractObjectReader.BeginComponent	219
2.28.7	TAbstractObjectReader.BeginProperty	219
2.28.8	TAbstractObjectReader.ReadBinary	219
2.28.9	TAbstractObjectReader.ReadFloat	220
2.28.10	TAbstractObjectReader.ReadSingle	220
2.28.11	TAbstractObjectReader.ReadCurrency	220
2.28.12	TAbstractObjectReader.ReadDate	220
2.28.13	TAbstractObjectReader.ReadIdent	221
2.28.14	TAbstractObjectReader.ReadInt8	221
2.28.15	TAbstractObjectReader.ReadInt16	222
2.28.16	TAbstractObjectReader.ReadInt32	222
2.28.17	TAbstractObjectReader.ReadInt64	222
2.28.18	TAbstractObjectReader.ReadSet	223
2.28.19	TAbstractObjectReader.ReadStr	223
2.28.20	TAbstractObjectReader.ReadString	223
2.28.21	TAbstractObjectReader.ReadWideString	224

2.28.22	TAbstractObjectReader.SkipComponent	224
2.28.23	TAbstractObjectReader.SkipValue	224
2.29	TAbstractObjectWriter	224
2.29.1	Description	224
2.29.2	Method overview	225
2.29.3	TAbstractObjectWriter.BeginCollection	225
2.29.4	TAbstractObjectWriter.BeginComponent	225
2.29.5	TAbstractObjectWriter.BeginList	225
2.29.6	TAbstractObjectWriter.EndList	226
2.29.7	TAbstractObjectWriter.BeginProperty	226
2.29.8	TAbstractObjectWriter.EndProperty	226
2.29.9	TAbstractObjectWriter.WriteBinary	226
2.29.10	TAbstractObjectWriter.WriteBoolean	226
2.29.11	TAbstractObjectWriter.WriteFloat	226
2.29.12	TAbstractObjectWriter.WriteSingle	227
2.29.13	TAbstractObjectWriter.WriteCurrency	227
2.29.14	TAbstractObjectWriter.WriteDate	227
2.29.15	TAbstractObjectWriter.WriteIdent	227
2.29.16	TAbstractObjectWriter.WriteInteger	227
2.29.17	TAbstractObjectWriter.WriteMethodName	228
2.29.18	TAbstractObjectWriter.WriteSet	228
2.29.19	TAbstractObjectWriter.WriteString	228
2.29.20	TAbstractObjectWriter.WriteWideString	228
2.30	TBasicAction	228
2.30.1	Description	228
2.30.2	Method overview	229
2.30.3	Property overview	229
2.30.4	TBasicAction.Create	229
2.30.5	TBasicAction.Destroy	229
2.30.6	TBasicAction.HandlesTarget	229
2.30.7	TBasicAction.UpdateTarget	230
2.30.8	TBasicAction.ExecuteTarget	230
2.30.9	TBasicAction.Execute	230
2.30.10	TBasicAction.RegisterChanges	231
2.30.11	TBasicAction.UnRegisterChanges	231
2.30.12	TBasicAction.Update	231
2.30.13	TBasicAction.ActionComponent	231
2.30.14	TBasicAction.OnExecute	232
2.30.15	TBasicAction.OnUpdate	232
2.31	TBasicActionLink	232

2.31.1	Description	232
2.31.2	Method overview	232
2.31.3	Property overview	233
2.31.4	TBasicActionLink.Create	233
2.31.5	TBasicActionLink.Destroy	233
2.31.6	TBasicActionLink.Execute	233
2.31.7	TBasicActionLink.Update	234
2.31.8	TBasicActionLink.Action	234
2.31.9	TBasicActionLink.OnChange	234
2.32	TBinaryObjectReader	234
2.32.1	Description	234
2.32.2	Method overview	235
2.32.3	TBinaryObjectReader.Create	235
2.32.4	TBinaryObjectReader.Destroy	235
2.32.5	TBinaryObjectReader.NextValue	236
2.32.6	TBinaryObjectReader.ReadValue	236
2.32.7	TBinaryObjectReader.BeginRootComponent	236
2.32.8	TBinaryObjectReader.BeginComponent	236
2.32.9	TBinaryObjectReader.BeginProperty	236
2.32.10	TBinaryObjectReader.ReadBinary	237
2.32.11	TBinaryObjectReader.ReadFloat	237
2.32.12	TBinaryObjectReader.ReadSingle	237
2.32.13	TBinaryObjectReader.ReadCurrency	237
2.32.14	TBinaryObjectReader.ReadDate	237
2.32.15	TBinaryObjectReader.ReadIdent	238
2.32.16	TBinaryObjectReader.ReadInt8	238
2.32.17	TBinaryObjectReader.ReadInt16	238
2.32.18	TBinaryObjectReader.ReadInt32	238
2.32.19	TBinaryObjectReader.ReadInt64	239
2.32.20	TBinaryObjectReader.ReadSet	239
2.32.21	TBinaryObjectReader.ReadStr	239
2.32.22	TBinaryObjectReader.ReadString	239
2.32.23	TBinaryObjectReader.ReadWideString	239
2.32.24	TBinaryObjectReader.SkipComponent	240
2.32.25	TBinaryObjectReader.SkipValue	240
2.33	TBinaryObjectWriter	240
2.33.1	Description	240
2.33.2	Method overview	241
2.33.3	TBinaryObjectWriter.Create	241
2.33.4	TBinaryObjectWriter.Destroy	241

2.33.5	TBinaryObjectWriter.BeginCollection	241
2.33.6	TBinaryObjectWriter.BeginComponent	242
2.33.7	TBinaryObjectWriter.BeginList	242
2.33.8	TBinaryObjectWriter.EndList	242
2.33.9	TBinaryObjectWriter.BeginProperty	242
2.33.10	TBinaryObjectWriter.EndProperty	242
2.33.11	TBinaryObjectWriter.WriteBinary	242
2.33.12	TBinaryObjectWriter.WriteBoolean	242
2.33.13	TBinaryObjectWriter.WriteFloat	243
2.33.14	TBinaryObjectWriter.WriteSingle	243
2.33.15	TBinaryObjectWriter.WriteCurrency	243
2.33.16	TBinaryObjectWriter.WriteDate	243
2.33.17	TBinaryObjectWriter.WriteIdent	243
2.33.18	TBinaryObjectWriter.WriteInteger	243
2.33.19	TBinaryObjectWriter.WriteMethodName	244
2.33.20	TBinaryObjectWriter.WriteSet	244
2.33.21	TBinaryObjectWriter.WriteString	244
2.33.22	TBinaryObjectWriter.WriteWideString	244
2.34	TBits	244
2.34.1	Description	244
2.34.2	Method overview	245
2.34.3	Property overview	245
2.34.4	TBits.Create	245
2.34.5	TBits.Destroy	245
2.34.6	TBits.GetFSize	246
2.34.7	TBits.SetOn	246
2.34.8	TBits.Clear	246
2.34.9	TBits.Clearall	246
2.34.10	TBits.AndBits	247
2.34.11	TBits.OrBits	247
2.34.12	TBits.XorBits	247
2.34.13	TBits.NotBits	248
2.34.14	TBits.Get	248
2.34.15	TBits.Grow	248
2.34.16	TBits.Equals	248
2.34.17	TBits.SetIndex	249
2.34.18	TBits.FindFirstBit	249
2.34.19	TBits.FindNextBit	249
2.34.20	TBits.FindPrevBit	250
2.34.21	TBits.OpenBit	250

2.34.22	TBits.Bits	250
2.34.23	TBits.Size	251
2.35	TCollection	251
2.35.1	Description	251
2.35.2	Method overview	251
2.35.3	Property overview	251
2.35.4	TCollection.Create	251
2.35.5	TCollection.Destroy	252
2.35.6	TCollection.Owner	252
2.35.7	TCollection.Add	252
2.35.8	TCollection.Assign	252
2.35.9	TCollection.BeginUpdate	253
2.35.10	TCollection.Clear	253
2.35.11	TCollection.EndUpdate	254
2.35.12	TCollection.Delete	254
2.35.13	TCollection.Insert	254
2.35.14	TCollection.FindItemID	254
2.35.15	TCollection.Count	255
2.35.16	TCollection.ItemClass	255
2.35.17	TCollection.Items	255
2.36	TCollectionItem	256
2.36.1	Description	256
2.36.2	Method overview	256
2.36.3	Property overview	256
2.36.4	TCollectionItem.Create	256
2.36.5	TCollectionItem.Destroy	256
2.36.6	TCollectionItem.Collection	257
2.36.7	TCollectionItem.ID	257
2.36.8	TCollectionItem.Index	257
2.36.9	TCollectionItem.DisplayName	258
2.37	TComponent	258
2.37.1	Description	258
2.37.2	Method overview	259
2.37.3	Property overview	259
2.37.4	TComponent.WriteState	259
2.37.5	TComponent.Create	260
2.37.6	TComponent.BeforeDestruction	260
2.37.7	TComponent.Destroy	260
2.37.8	TComponent.DestroyComponents	260
2.37.9	TComponent.Destroying	261

2.37.10	TComponent.ExecuteAction	261
2.37.11	TComponent.FindComponent	261
2.37.12	TComponent.FreeNotification	261
2.37.13	TComponent.RemoveFreeNotification	262
2.37.14	TComponent.FreeOnRelease	262
2.37.15	TComponent.GetParentComponent	262
2.37.16	TComponent.HasParent	262
2.37.17	TComponent.InsertComponent	263
2.37.18	TComponent.RemoveComponent	263
2.37.19	TComponent.SafeCallException	263
2.37.20	TComponent.SetSubComponent	263
2.37.21	TComponent.UpdateAction	264
2.37.22	TComponent.Components	264
2.37.23	TComponent.ComponentCount	264
2.37.24	TComponent.ComponentIndex	264
2.37.25	TComponent.ComponentState	265
2.37.26	TComponent.ComponentStyle	265
2.37.27	TComponent.DesignInfo	265
2.37.28	TComponent.Owner	266
2.37.29	TComponent.VCLComObject	266
2.37.30	TComponent.Name	266
2.37.31	TComponent.Tag	266
2.38	TCustomMemoryStream	267
2.38.1	Description	267
2.38.2	Method overview	267
2.38.3	Property overview	267
2.38.4	TCustomMemoryStream.GetSize	267
2.38.5	TCustomMemoryStream.Read	267
2.38.6	TCustomMemoryStream.Seek	268
2.38.7	TCustomMemoryStream.SaveToStream	268
2.38.8	TCustomMemoryStream.SaveToFile	269
2.38.9	TCustomMemoryStream.Memory	269
2.39	TDataModule	269
2.39.1	Description	269
2.39.2	Method overview	270
2.39.3	Property overview	270
2.39.4	TDataModule.Create	270
2.39.5	TDataModule.CreateNew	270
2.39.6	TDataModule.Destroy	270
2.39.7	TDataModule.AfterConstruction	271

2.39.8	TDataModule.BeforeDestruction	271
2.39.9	TDataModule.DesignOffset	271
2.39.10	TDataModule.DesignSize	272
2.39.11	TDataModule.OnCreate	272
2.39.12	TDataModule.OnDestroy	272
2.39.13	TDataModule.OldCreateOrder	272
2.40	TFile	273
2.40.1	Description	273
2.40.2	Method overview	273
2.40.3	Property overview	273
2.40.4	TFile.DefineProperty	273
2.40.5	TFile.DefineBinaryProperty	273
2.40.6	TFile.Root	273
2.40.7	TFile.LookupRoot	274
2.40.8	TFile.Ancestor	274
2.40.9	TFile.IgnoreChildren	274
2.41	TFileStream	274
2.41.1	Description	274
2.41.2	Method overview	275
2.41.3	Property overview	275
2.41.4	TFileStream.Create	275
2.41.5	TFileStream.Destroy	275
2.41.6	TFileStream.FileName	276
2.42	TFPList	276
2.42.1	Description	276
2.42.2	Method overview	276
2.42.3	Property overview	277
2.42.4	TFPList.Destroy	277
2.42.5	TFPList.Add	277
2.42.6	TFPList.Clear	277
2.42.7	TFPList.Delete	277
2.42.8	TFPList.Error	278
2.42.9	TFPList.Exchange	278
2.42.10	TFPList.Expand	278
2.42.11	TFPList.Extract	278
2.42.12	TFPList.First	279
2.42.13	TFPList.IndexOf	279
2.42.14	TFPList.Insert	279
2.42.15	TFPList.Last	279
2.42.16	TFPList.Move	280

2.42.17 TFPList.Assign	280
2.42.18 TFPList.Remove	280
2.42.19 TFPList.Pack	280
2.42.20 TFPList.Sort	281
2.42.21 TFPList.ForEachCall	281
2.42.22 TFPList.Capacity	281
2.42.23 TFPList.Count	282
2.42.24 TFPList.Items	282
2.42.25 TFPList.List	282
2.43 THandleStream	282
2.43.1 Description	282
2.43.2 Method overview	283
2.43.3 Property overview	283
2.43.4 THandleStream.Create	283
2.43.5 THandleStream.Read	283
2.43.6 THandleStream.Write	283
2.43.7 THandleStream.Seek	284
2.43.8 THandleStream.Handle	284
2.44 TInterfacedPersistent	284
2.44.1 Description	284
2.44.2 Method overview	284
2.44.3 TInterfacedPersistent.QueryInterface	284
2.44.4 TInterfacedPersistent.AfterConstruction	285
2.45 TInterfaceList	285
2.45.1 Description	285
2.45.2 Method overview	285
2.45.3 Property overview	285
2.45.4 TInterfaceList.Create	285
2.45.5 TInterfaceList.Destroy	286
2.45.6 TInterfaceList.Clear	286
2.45.7 TInterfaceList.Delete	286
2.45.8 TInterfaceList.Exchange	286
2.45.9 TInterfaceList.First	287
2.45.10 TInterfaceList.IndexOf	287
2.45.11 TInterfaceList.Add	287
2.45.12 TInterfaceList.Insert	287
2.45.13 TInterfaceList.Last	288
2.45.14 TInterfaceList.Remove	288
2.45.15 TInterfaceList.Lock	288
2.45.16 TInterfaceList.Unlock	288

2.45.17	TInterfaceList.Expand	289
2.45.18	TInterfaceList.Capacity	289
2.45.19	TInterfaceList.Count	289
2.45.20	TInterfaceList.Items	289
2.46	TList	290
2.46.1	Description	290
2.46.2	Method overview	290
2.46.3	Property overview	290
2.46.4	TList.Create	290
2.46.5	TList.Destroy	291
2.46.6	TList.Add	291
2.46.7	TList.Clear	291
2.46.8	TList.Delete	291
2.46.9	TList.Error	292
2.46.10	TList.Exchange	292
2.46.11	TList.Expand	292
2.46.12	TList.Extract	292
2.46.13	TList.First	293
2.46.14	TList.IndexOf	293
2.46.15	TList.Insert	293
2.46.16	TList.Last	293
2.46.17	TList.Move	294
2.46.18	TList.Assign	294
2.46.19	TList.Remove	294
2.46.20	TList.Pack	294
2.46.21	TList.Sort	295
2.46.22	TList.Capacity	295
2.46.23	TList.Count	295
2.46.24	TList.Items	296
2.46.25	TList.List	296
2.47	TMemoryStream	296
2.47.1	Description	296
2.47.2	Method overview	296
2.47.3	TMemoryStream.Destroy	296
2.47.4	TMemoryStream.Clear	297
2.47.5	TMemoryStream.LoadFromStream	297
2.47.6	TMemoryStream.LoadFromFile	297
2.47.7	TMemoryStream.SetSize	298
2.47.8	TMemoryStream.Write	298
2.48	TOwnedCollection	298

2.48.1	Description	298
2.48.2	Method overview	298
2.48.3	TOwnedCollection.Create	298
2.49	TOwnerStream	299
2.49.1	Description	299
2.49.2	Method overview	299
2.49.3	Property overview	299
2.49.4	TOwnerStream.Create	299
2.49.5	TOwnerStream.Destroy	299
2.49.6	TOwnerStream.Source	299
2.49.7	TOwnerStream.SourceOwner	300
2.50	TParser	300
2.50.1	Description	300
2.50.2	Method overview	300
2.50.3	Property overview	300
2.50.4	TParser.Create	301
2.50.5	TParser.Destroy	301
2.50.6	TParser.CheckToken	301
2.50.7	TParser.CheckTokenSymbol	301
2.50.8	TParser.Error	301
2.50.9	TParser.ErrorFmt	301
2.50.10	TParser.ErrorStr	302
2.50.11	TParser.HexToBinary	302
2.50.12	TParser.NextToken	302
2.50.13	TParser.SourcePos	302
2.50.14	TParser.TokenComponentIdent	302
2.50.15	TParser.TokenFloat	302
2.50.16	TParser.TokenInt	303
2.50.17	TParser.TokenString	303
2.50.18	TParser.TokenWideString	303
2.50.19	TParser.TokenSymbolIs	303
2.50.20	TParser.SourceLine	303
2.50.21	TParser.Token	304
2.51	TPersistent	304
2.51.1	Description	304
2.51.2	Method overview	304
2.51.3	TPersistent.Destroy	304
2.51.4	TPersistent.Assign	304
2.51.5	TPersistent.GetNamePath	305
2.52	TReader	305

2.52.1	Description	305
2.52.2	Method overview	306
2.52.3	Property overview	307
2.52.4	TReader.Create	307
2.52.5	TReader.Destroy	307
2.52.6	TReader.BeginReferences	307
2.52.7	TReader.CheckValue	308
2.52.8	TReader.DefineProperty	308
2.52.9	TReader.DefineBinaryProperty	308
2.52.10	TReader.EndOfList	308
2.52.11	TReader.EndReferences	308
2.52.12	TReader.FixupReferences	309
2.52.13	TReader.NextValue	309
2.52.14	TReader.ReadBoolean	309
2.52.15	TReader.ReadChar	309
2.52.16	TReader.ReadCollection	309
2.52.17	TReader.ReadComponent	309
2.52.18	TReader.ReadComponents	310
2.52.19	TReader.ReadFloat	310
2.52.20	TReader.ReadSingle	310
2.52.21	TReader.ReadCurrency	310
2.52.22	TReader.ReadDate	310
2.52.23	TReader.ReadIdent	311
2.52.24	TReader.ReadInteger	311
2.52.25	TReader.ReadInt64	311
2.52.26	TReader.ReadListBegin	311
2.52.27	TReader.ReadListEnd	311
2.52.28	TReader.ReadRootComponent	311
2.52.29	TReader.ReadString	312
2.52.30	TReader.ReadWideString	312
2.52.31	TReader.ReadValue	312
2.52.32	TReader.CopyValue	312
2.52.33	TReader.Driver	312
2.52.34	TReader.Owner	313
2.52.35	TReader.Parent	313
2.52.36	TReader.OnError	313
2.52.37	TReader.OnPropertyNotFound	313
2.52.38	TReader.OnFindMethod	314
2.52.39	TReader.OnSetMethodProperty	314
2.52.40	TReader.OnSetName	314

2.52.41 TReader.OnReferenceName	314
2.52.42 TReader.OnAncestorNotFound	314
2.52.43 TReader.OnCreateComponent	315
2.52.44 TReader.OnFindComponentClass	315
2.52.45 TReader.OnReadStringProperty	315
2.53 TRecall	315
2.53.1 Description	315
2.53.2 Method overview	316
2.53.3 Property overview	316
2.53.4 TRecall.Create	316
2.53.5 TRecall.Destroy	316
2.53.6 TRecall.Store	316
2.53.7 TRecall.Forget	317
2.53.8 TRecall.Reference	317
2.54 TResourceStream	317
2.54.1 Description	317
2.54.2 Method overview	317
2.54.3 TResourceStream.Create	317
2.54.4 TResourceStream.CreateFromID	318
2.54.5 TResourceStream.Destroy	318
2.54.6 TResourceStream.Write	318
2.55 TStream	318
2.55.1 Description	318
2.55.2 Method overview	319
2.55.3 Property overview	319
2.55.4 TStream.Read	319
2.55.5 TStream.Write	320
2.55.6 TStream.Seek	320
2.55.7 TStream.ReadBuffer	321
2.55.8 TStream.WriteBuffer	321
2.55.9 TStream.CopyFrom	321
2.55.10 TStream.ReadComponent	322
2.55.11 TStream.ReadComponentRes	322
2.55.12 TStream.WriteComponent	322
2.55.13 TStream.WriteComponentRes	323
2.55.14 TStream.WriteDescendent	323
2.55.15 TStream.WriteDescendentRes	323
2.55.16 TStream.WriteResourceHeader	323
2.55.17 TStream.FixupResourceHeader	324
2.55.18 TStream.ReadResHeader	324

2.55.19 TStream.ReadByte	324
2.55.20 TStream.ReadWord	324
2.55.21 TStream.ReadDWord	325
2.55.22 TStream.ReadAnsiString	325
2.55.23 TStream.WriteByte	325
2.55.24 TStream.WriteWord	326
2.55.25 TStream.WriteDWord	326
2.55.26 TStream.WriteAnsiString	326
2.55.27 TStream.Position	327
2.55.28 TStream.Size	327
2.56 TStringList	327
2.56.1 Description	327
2.56.2 Method overview	328
2.56.3 Property overview	328
2.56.4 TStringList.Destroy	328
2.56.5 TStringList.Add	328
2.56.6 TStringList.Clear	329
2.56.7 TStringList.Delete	329
2.56.8 TStringList.Exchange	329
2.56.9 TStringList.Find	329
2.56.10 TStringList.IndexOf	330
2.56.11 TStringList.Insert	330
2.56.12 TStringList.Sort	330
2.56.13 TStringList.CustomSort	330
2.56.14 TStringList.Duplicates	331
2.56.15 TStringList.Sorted	331
2.56.16 TStringList.CaseSensitive	331
2.56.17 TStringList.OnChange	332
2.56.18 TStringList.OnChanging	332
2.57 TStrings	332
2.57.1 Description	332
2.57.2 Method overview	333
2.57.3 Property overview	333
2.57.4 TStrings.Destroy	333
2.57.5 TStrings.Add	334
2.57.6 TStrings.AddObject	334
2.57.7 TStrings.Append	334
2.57.8 TStrings.AddStrings	334
2.57.9 TStrings.Assign	335
2.57.10 TStrings.BeginUpdate	335

2.57.11 TStrings.Clear	335
2.57.12 TStrings.Delete	336
2.57.13 TStrings.EndUpdate	336
2.57.14 TStrings.Equals	336
2.57.15 TStrings.Exchange	337
2.57.16 TStrings.GetText	337
2.57.17 TStrings.IndexOf	337
2.57.18 TStrings.IndexOfName	337
2.57.19 TStrings.IndexOfObject	338
2.57.20 TStrings.Insert	338
2.57.21 TStrings.InsertObject	338
2.57.22 TStrings.LoadFromFile	339
2.57.23 TStrings.LoadFromStream	339
2.57.24 TStrings.Move	339
2.57.25 TStrings.SaveToFile	340
2.57.26 TStrings.SaveToStream	340
2.57.27 TStrings.SetText	340
2.57.28 TStrings.GetNameValue	341
2.57.29 TStrings.Delimiter	341
2.57.30 TStrings.DelimitedText	341
2.57.31 TStrings.QuoteChar	341
2.57.32 TStrings.NameValueSeparator	341
2.57.33 TStrings.ValueFromIndex	342
2.57.34 TStrings.Capacity	342
2.57.35 TStrings.CommaText	342
2.57.36 TStrings.Count	343
2.57.37 TStrings.Names	343
2.57.38 TStrings.Objects	344
2.57.39 TStrings.Values	344
2.57.40 TStrings.Strings	344
2.57.41 TStrings.Text	345
2.57.42 TStrings.StringsAdapter	345
2.58 TStringStream	345
2.58.1 Description	345
2.58.2 Method overview	346
2.58.3 Property overview	346
2.58.4 TStringStream.Create	346
2.58.5 TStringStream.Read	346
2.58.6 TStringStream.ReadString	346
2.58.7 TStringStream.Seek	347

2.58.8	TStringStream.Write	347
2.58.9	TStringStream.WriteString	347
2.58.10	TStringStream.DataString	347
2.59	TTextObjectWriter	347
2.59.1	Description	347
2.60	TThread	348
2.60.1	Description	348
2.60.2	Method overview	348
2.60.3	Property overview	348
2.60.4	TThread.Create	348
2.60.5	TThread.Destroy	348
2.60.6	TThread.Resume	349
2.60.7	TThread.Suspend	349
2.60.8	TThread.Terminate	349
2.60.9	TThread.WaitFor	349
2.60.10	TThread.FreeOnTerminate	349
2.60.11	TThread.Handle	350
2.60.12	TThread.Priority	350
2.60.13	TThread.Suspended	350
2.60.14	TThread.ThreadID	350
2.60.15	TThread.OnTerminate	350
2.60.16	TThread.FatalException	351
2.61	TThreadList	351
2.61.1	Description	351
2.61.2	Method overview	351
2.61.3	Property overview	351
2.61.4	TThreadList.Create	351
2.61.5	TThreadList.Destroy	351
2.61.6	TThreadList.Add	352
2.61.7	TThreadList.Clear	352
2.61.8	TThreadList.LockList	352
2.61.9	TThreadList.Remove	352
2.61.10	TThreadList.UnlockList	352
2.61.11	TThreadList.Duplicates	353
2.62	TWriter	353
2.62.1	Description	353
2.62.2	Method overview	353
2.62.3	Property overview	353
2.62.4	TWriter.Create	354
2.62.5	TWriter.Destroy	354

2.62.6	TWriter.DefineProperty	354
2.62.7	TWriter.DefineBinaryProperty	354
2.62.8	TWriter.WriteBoolean	354
2.62.9	TWriter.WriteCollection	355
2.62.10	TWriter.WriteComponent	355
2.62.11	TWriter.WriteChar	355
2.62.12	TWriter.WriteDescendent	355
2.62.13	TWriter.WriteFloat	355
2.62.14	TWriter.WriteSingle	355
2.62.15	TWriter.WriteCurrency	356
2.62.16	TWriter.WriteDate	356
2.62.17	TWriter.WriteIdent	356
2.62.18	TWriter.WriteInteger	356
2.62.19	TWriter.WriteListBegin	356
2.62.20	TWriter.WriteListEnd	357
2.62.21	TWriter.WriteRootComponent	357
2.62.22	TWriter.WriteString	357
2.62.23	TWriter.WriteWideString	357
2.62.24	TWriter.RootAncestor	357
2.62.25	TWriter.OnFindAncestor	358
2.62.26	TWriter.OnWriteMethodProperty	358
2.62.27	TWriter.OnWriteStringProperty	358
2.62.28	TWriter.Driver	358
3	Reference for unit 'Crt'	359
3.1	Overview	359
3.2	Constants, types and variables	359
3.2.1	Constants	359
3.2.2	Types	362
3.2.3	Variables	362
3.3	Procedures and functions	363
3.3.1	AssignCrt	363
3.3.2	ClrEol	364
3.3.3	ClrScr	364
3.3.4	cursorbig	365
3.3.5	cursoroff	365
3.3.6	cursoron	365
3.3.7	Delay	366
3.3.8	DelLine	366
3.3.9	GotoXY	367

3.3.10	HighVideo	367
3.3.11	InsLine	368
3.3.12	KeyPressed	368
3.3.13	LowVideo	369
3.3.14	NormVideo	369
3.3.15	NoSound	370
3.3.16	ReadKey	370
3.3.17	Sound	371
3.3.18	TextBackground	371
3.3.19	TextColor	372
3.3.20	TextMode	372
3.3.21	WhereX	373
3.3.22	WhereY	373
3.3.23	Window	374
4	Reference for unit 'dateutils'	375
4.1	Used units	375
4.2	Overview	375
4.3	Constants, types and variables	375
4.3.1	Constants	375
4.4	Procedures and functions	377
4.4.1	CompareDate	377
4.4.2	CompareDateTime	378
4.4.3	CompareTime	379
4.4.4	DateOf	380
4.4.5	DateTimeToJulianDate	381
4.4.6	DateTimeToMac	381
4.4.7	DateTimeToModifiedJulianDate	381
4.4.8	DateTimeToUnix	382
4.4.9	DayOf	382
4.4.10	DayOfTheMonth	382
4.4.11	DayOfTheWeek	382
4.4.12	DayOfTheYear	383
4.4.13	DaysBetween	383
4.4.14	DaysInAMonth	384
4.4.15	DaysInAYear	385
4.4.16	DaysInMonth	385
4.4.17	DaysInYear	386
4.4.18	DaySpan	386
4.4.19	DecodeDateDay	387

4.4.20	DecodeDateMonthWeek	388
4.4.21	DecodeDateTime	388
4.4.22	DecodeDateWeek	389
4.4.23	DecodeDayOfWeekInMonth	390
4.4.24	EncodeDateDay	390
4.4.25	EncodeDateMonthWeek	391
4.4.26	EncodeDateTime	391
4.4.27	EncodeDateWeek	391
4.4.28	EncodeDayOfWeekInMonth	392
4.4.29	EndOfADay	392
4.4.30	EndOfAMonth	393
4.4.31	EndOfAWeek	393
4.4.32	EndOfAYear	394
4.4.33	EndOfTheDay	394
4.4.34	EndOfTheMonth	395
4.4.35	EndOfTheWeek	396
4.4.36	EndOfTheYear	396
4.4.37	HourOf	397
4.4.38	HourOfTheDay	397
4.4.39	HourOfTheMonth	397
4.4.40	HourOfTheWeek	398
4.4.41	HourOfTheYear	398
4.4.42	HoursBetween	398
4.4.43	HourSpan	399
4.4.44	IncDay	400
4.4.45	IncHour	401
4.4.46	IncMilliSecond	401
4.4.47	IncMinute	402
4.4.48	IncSecond	402
4.4.49	IncWeek	403
4.4.50	IncYear	403
4.4.51	InvalidDateDayError	404
4.4.52	InvalidDateMonthWeekError	404
4.4.53	InvalidDateTimeError	404
4.4.54	InvalidDateWeekError	405
4.4.55	InvalidDayOfWeekInMonthError	405
4.4.56	IsInLeapYear	405
4.4.57	IsPM	406
4.4.58	IsSameDay	406
4.4.59	IsToday	407

4.4.60	IsValidDate	407
4.4.61	IsValidDateDay	408
4.4.62	IsValidDateMonthWeek	409
4.4.63	IsValidDateTime	409
4.4.64	IsValidDateWeek	410
4.4.65	IsValidTime	411
4.4.66	JulianDateToDateTime	411
4.4.67	MacTimeStampToUnix	412
4.4.68	MacToDateTime	412
4.4.69	MilliSecondOf	412
4.4.70	MilliSecondOfTheDay	412
4.4.71	MilliSecondOfTheHour	413
4.4.72	MilliSecondOfTheMinute	413
4.4.73	MilliSecondOfTheMonth	413
4.4.74	MilliSecondOfTheSecond	413
4.4.75	MilliSecondOfTheWeek	414
4.4.76	MilliSecondOfTheYear	414
4.4.77	MilliSecondsBetween	415
4.4.78	MilliSecondSpan	415
4.4.79	MinuteOf	416
4.4.80	MinuteOfTheDay	416
4.4.81	MinuteOfTheHour	417
4.4.82	MinuteOfTheMonth	417
4.4.83	MinuteOfTheWeek	418
4.4.84	MinuteOfTheYear	418
4.4.85	MinutesBetween	418
4.4.86	MinuteSpan	419
4.4.87	ModifiedJulianDateToDateTime	420
4.4.88	MonthOf	420
4.4.89	MonthOfTheYear	420
4.4.90	MonthsBetween	421
4.4.91	MonthSpan	422
4.4.92	NthDayOfWeek	422
4.4.93	PreviousDayOfWeek	423
4.4.94	RecodeDate	423
4.4.95	RecodeDateTime	424
4.4.96	RecodeDay	425
4.4.97	RecodeHour	426
4.4.98	RecodeMilliSecond	426
4.4.99	RecodeMinute	427

4.4.100 RecodeMonth	428
4.4.101 RecodeSecond	428
4.4.102 RecodeTime	429
4.4.103 RecodeYear	430
4.4.104 SameDate	430
4.4.105 SameDateTime	431
4.4.106 SameTime	432
4.4.107 SecondOf	433
4.4.108 SecondOfTheDay	433
4.4.109 SecondOfTheHour	433
4.4.110 SecondOfTheMinute	434
4.4.111 SecondOfTheMonth	434
4.4.112 SecondOfTheWeek	434
4.4.113 SecondOfTheYear	435
4.4.114 SecondsBetween	435
4.4.115 SecondSpan	436
4.4.116 StartOfADay	437
4.4.117 StartOfAMonth	438
4.4.118 StartOfAWeek	438
4.4.119 StartOfAYear	439
4.4.120 StartOfTheDay	439
4.4.121 StartOfTheMonth	440
4.4.122 StartOfTheWeek	440
4.4.123 StartOfTheYear	441
4.4.124 TimeOf	441
4.4.125 Today	442
4.4.126 Tomorrow	442
4.4.127 TryEncodeDateDay	443
4.4.128 TryEncodeDateMonthWeek	443
4.4.129 TryEncodeDateTime	444
4.4.130 TryEncodeDateWeek	445
4.4.131 TryEncodeDayOfWeekInMonth	445
4.4.132 TryJulianDateToDateTime	446
4.4.133 TryModifiedJulianDateToDateTime	446
4.4.134 TryRecodeDateTime	447
4.4.135 UnixTimeStampToMac	448
4.4.136 UnixToDateTime	448
4.4.137 WeekOf	448
4.4.138 WeekOfTheMonth	448
4.4.139 WeekOfTheYear	449

4.4.140 WeeksBetween	450
4.4.141 WeeksInAYear	451
4.4.142 WeeksInYear	451
4.4.143 WeekSpan	452
4.4.144 WithinPastDays	453
4.4.145 WithinPastHours	454
4.4.146 WithinPastMilliSeconds	455
4.4.147 WithinPastMinutes	456
4.4.148 WithinPastMonths	456
4.4.149 WithinPastSeconds	457
4.4.150 WithinPastWeeks	458
4.4.151 WithinPastYears	459
4.4.152 YearOf	460
4.4.153 YearsBetween	461
4.4.154 YearSpan	462
4.4.155 Yesterday	463
5 Reference for unit 'Dos'	464
5.1 System information	464
5.2 Process handling	464
5.3 Directory and disk handling	464
5.4 File handling	465
5.5 File open mode constants.	465
5.6 File attributes	465
5.7 Used units	466
5.8 Overview	466
5.9 Constants, types and variables	466
5.9.1 Constants	466
5.9.2 Types	468
5.9.3 Variables	470
5.10 Procedures and functions	470
5.10.1 AddDisk	470
5.10.2 DiskFree	471
5.10.3 DiskSize	472
5.10.4 DosExitCode	473
5.10.5 DosVersion	473
5.10.6 DTToUnixDate	474
5.10.7 EnvCount	474
5.10.8 EnvStr	475
5.10.9 Exec	475

5.10.10 FExpand	475
5.10.11 FindClose	476
5.10.12 FindFirst	476
5.10.13 FindNext	477
5.10.14 FSearch	477
5.10.15 FSplit	478
5.10.16 GetCBreak	479
5.10.17 GetDate	479
5.10.18 GetEnv	480
5.10.19 GetFAttr	480
5.10.20 GetFTime	481
5.10.21 GetIntVec	482
5.10.22 GetLongName	482
5.10.23 GetMsCount	482
5.10.24 GetShortName	483
5.10.25 GetTime	483
5.10.26 GetVerify	484
5.10.27 Intr	484
5.10.28 Keep	484
5.10.29 MSDos	485
5.10.30 PackTime	485
5.10.31 SetCBreak	486
5.10.32 SetDate	486
5.10.33 SetFAttr	486
5.10.34 SetFTime	487
5.10.35 SetIntVec	487
5.10.36 SetTime	488
5.10.37 SetVerify	488
5.10.38 SwapVectors	488
5.10.39 UnixDateToDt	489
5.10.40 UnpackTime	489
5.10.41 weekday	489
6 Reference for unit 'dxeload'	490
6.1 Overview	490
6.2 Procedures and functions	490
6.2.1 dxe_load	490
7 Reference for unit 'dynlibs'	491
7.1 Overview	491
7.2 Constants, types and variables	491

7.2.1	Constants	491
7.2.2	Types	491
7.3	Procedures and functions	491
7.3.1	FreeLibrary	491
7.3.2	GetProcAddress	492
7.3.3	GetProcedureAddress	492
7.3.4	LoadLibrary	492
7.3.5	UnloadLibrary	493
8	Reference for unit 'emu387'	494
8.1	Overview	494
8.2	Procedures and functions	494
8.2.1	npxsetup	494
9	Reference for unit 'getopts'	495
9.1	Overview	495
9.2	Constants, types and variables	495
9.2.1	Constants	495
9.2.2	Types	496
9.2.3	Variables	496
9.3	Procedures and functions	497
9.3.1	GetLongOpts	497
9.3.2	GetOpt	497
10	Reference for unit 'go32'	500
10.1	Real mode callbacks	500
10.2	Executing software interrupts	501
10.3	Software interrupts	501
10.4	Hardware interrupts	501
10.5	Disabling interrupts	501
10.6	Creating your own interrupt handlers	501
10.7	Protected mode interrupts vs. Real mode interrupts	502
10.8	Handling interrupts with DPMI	502
10.9	Interrupt redirection	502
10.10	Processor access	502
10.11	I/O port access	502
10.12	dos memory access	502
10.13	FPC specialities	503
10.14	Selectors and descriptors	503
10.15	What is DPMI	503
10.16	Overview	503

10.17	Constants, types and variables	504
10.17.1	Constants	504
10.17.2	Types	506
10.17.3	Variables	507
10.18	Procedures and functions	507
10.18.1	allocate_ldt_descriptors	507
10.18.2	allocate_memory_block	510
10.18.3	copyfromdos	510
10.18.4	copytodos	510
10.18.5	create_code_segment_alias_descriptor	511
10.18.6	disable	511
10.18.7	dpmi_dosmemfillchar	511
10.18.8	dpmi_dosmemfillword	512
10.18.9	dpmi_dosmemget	512
10.18.10	dpmi_dosmemmove	512
10.18.11	dpmi_dosmemput	512
10.18.12	enable	513
10.18.13	free_ldt_descriptor	513
10.18.14	free_memory_block	513
10.18.15	free_rm_callback	514
10.18.16	get_cs	514
10.18.17	get_descriptor_access_right	514
10.18.18	get_ds	515
10.18.19	get_exception_handler	515
10.18.20	get_linear_addr	515
10.18.21	get_meminfo	516
10.18.22	get_next_selector_increment_value	517
10.18.23	get_page_size	517
10.18.24	get_pm_exception_handler	518
10.18.25	get_pm_interrupt	518
10.18.26	get_rm_callback	518
10.18.27	get_rm_interrupt	521
10.18.28	get_run_mode	522
10.18.29	get_segment_base_address	522
10.18.30	get_segment_limit	523
10.18.31	get_ss	523
10.18.32	global_dos_alloc	523
10.18.33	global_dos_free	525
10.18.34	nportb	525
10.18.35	nportl	526

10.18.36	inportw	526
10.18.37	lock_code	526
10.18.38	lock_data	527
10.18.39	lock_linear_region	527
10.18.40	map_device_in_memory_block	527
10.18.41	outportb	528
10.18.42	outportl	528
10.18.43	outportw	529
10.18.44	realintr	529
10.18.45	request_linear_region	530
10.18.46	segment_to_descriptor	530
10.18.47	seg_fillchar	530
10.18.48	seg_fillword	531
10.18.49	seg_move	532
10.18.50	set_descriptor_access_right	532
10.18.51	set_exception_handler	532
10.18.52	set_pm_exception_handler	533
10.18.53	set_pm_interrupt	533
10.18.54	set_rm_interrupt	534
10.18.55	set_segment_base_address	534
10.18.56	set_segment_limit	535
10.18.57	tb_offset	535
10.18.58	tb_segment	535
10.18.59	tb_size	536
10.18.60	transfer_buffer	536
10.18.61	unlock_code	536
10.18.62	unlock_data	537
10.18.63	unlock_linear_region	537
11	Reference for unit 'gpm'	538
11.1	Used units	538
11.2	Overview	538
11.3	Constants, types and variables	538
11.3.1	Constants	538
11.3.2	Types	540
11.3.3	Variables	542
11.4	Procedures and functions	543
11.4.1	Gpm_AnyDouble	543
11.4.2	Gpm_AnySingle	543
11.4.3	Gpm_AnyTriple	543

11.4.4	<code>gpm_close</code>	544
11.4.5	<code>gpm_fitvalues</code>	544
11.4.6	<code>gpm_fitvaluesM</code>	544
11.4.7	<code>gpm_getevent</code>	544
11.4.8	<code>gpm_getsnapshot</code>	546
11.4.9	<code>gpm_lowerroi</code>	546
11.4.10	<code>gpm_open</code>	546
11.4.11	<code>gpm_poproi</code>	547
11.4.12	<code>gpm_pushroi</code>	547
11.4.13	<code>gpm_raiseroi</code>	547
11.4.14	<code>gpm_repeat</code>	547
11.4.15	<code>Gpm_StrictDouble</code>	548
11.4.16	<code>Gpm_StrictSingle</code>	548
11.4.17	<code>Gpm_StrictTriple</code>	548
12	Reference for unit 'Graph'	549
12.1	Categorized functions: Text and font handling	549
12.2	Categorized functions: Filled drawings	549
12.3	Categorized functions: Drawing primitives	549
12.4	Categorized functions: Color management	549
12.5	Categorized functions: Screen management	550
12.6	Categorized functions: Initialization	550
12.7	Target specific issues: Linux	550
12.8	Target specific issues: DOS	552
12.9	A word about mode selection	552
12.10	Requirements	554
12.11	Overview	554
12.12	Constants, types and variables	554
12.12.1	Constants	554
12.12.2	Types	569
12.12.3	Variables	574
12.13	Procedures and functions	576
12.13.1	Arc	576
12.13.2	Bar	577
12.13.3	Bar3D	577
12.13.4	ClearDevice	577
12.13.5	Closegraph	577
12.13.6	DetectGraph	578
12.13.7	DrawPoly	578
12.13.8	Ellipse	578

12.13.9 FillEllipse	578
12.13.10 FillPoly	579
12.13.11 FloodFill	579
12.13.12 GetArcCoords	579
12.13.13 GetAspectRatio	580
12.13.14 GetBkColor	580
12.13.15 GetColor	580
12.13.16 GetDefaultPalette	580
12.13.17 GetDirectVideo	581
12.13.18 GetDriverName	581
12.13.19 GetFillPattern	581
12.13.20 GetFillSettings	581
12.13.21 GetGraphMode	582
12.13.22 GetLineSettings	582
12.13.23 GetMaxColor	582
12.13.24 GetMaxMode	582
12.13.25 GetMaxX	583
12.13.26 GetMaxY	583
12.13.27 GetModeName	583
12.13.28 GetModeRange	583
12.13.29 GetPalette	584
12.13.30 GetPaletteSize	584
12.13.31 GetTextSettings	584
12.13.32 GetViewSettings	584
12.13.33 GetX	585
12.13.34 GetY	585
12.13.35 GraphDefaults	585
12.13.36 GraphErrorMsg	585
12.13.37 GraphResult	586
12.13.38 InitGraph	586
12.13.39 InstallUserDriver	587
12.13.40 InstallUserFont	587
12.13.41 LineRel	587
12.13.42 LineTo	588
12.13.43 MoveRel	588
12.13.44 MoveTo	588
12.13.45 OutText	588
12.13.46 PieSlice	589
12.13.47 QueryAdapterInfo	589
12.13.48 Rectangle	589

12.13.4	RegisterBGIDriver	589
12.13.5	RegisterBGIfont	590
12.13.5	RestoreCrtMode	590
12.13.5	Sector	590
12.13.5	SetAspectRatio	590
12.13.5	SetBkColor	591
12.13.5	SetColor	591
12.13.5	SetDirectVideo	591
12.13.5	SetFillPattern	591
12.13.5	SetFillStyle	592
12.13.5	SetGraphMode	592
12.13.6	SetLineStyle	592
12.13.6	SetPalette	593
12.13.6	SetTextJustify	593
12.13.6	SetTextStyle	594
12.13.6	SetUserCharSize	594
12.13.6	SetViewPort	595
12.13.6	SetWriteMode	595
12.13.6	TextHeight	595
12.13.6	TextWidth	595
13	Reference for unit 'heaptrc'	597
13.1	Controlling HeapTrc with environment variables	597
13.2	HeapTrc Usage	597
13.3	Overview	598
13.4	Constants, types and variables	598
13.4.1	Constants	598
13.4.2	Types	599
13.5	Procedures and functions	599
13.5.1	DumpHeap	599
13.5.2	SetHeapExtraInfo	600
13.5.3	SetHeapTraceOutput	601
14	Reference for unit 'ipc'	602
14.1	Used units	602
14.2	Overview	602
14.3	Constants, types and variables	602
14.3.1	Constants	602
14.3.2	Types	605
14.4	Procedures and functions	609
14.4.1	ftok	609

14.4.2	msgctl	609
14.4.3	msgget	612
14.4.4	msgrcv	612
14.4.5	msgsnd	613
14.4.6	semctl	613
14.4.7	semget	618
14.4.8	semop	618
14.4.9	shmat	619
14.4.10	shmctl	620
14.4.11	shmdt	622
14.4.12	shmget	622
15	Reference for unit 'keyboard'	623
15.1	Unix specific notes	623
15.2	Writing a keyboard driver	624
15.3	Keyboard scan codes	625
15.4	Overview	625
15.5	Constants, types and variables	625
15.5.1	Constants	625
15.5.2	Types	630
15.6	Procedures and functions	631
15.6.1	AddSequence	631
15.6.2	DoneKeyboard	631
15.6.3	FindSequence	631
15.6.4	FunctionKeyName	631
15.6.5	GetKeyboardDriver	632
15.6.6	GetKeyEvent	632
15.6.7	GetKeyEventChar	633
15.6.8	GetKeyEventCode	634
15.6.9	GetKeyEventFlags	634
15.6.10	GetKeyEventShiftState	635
15.6.11	GetKeyEventUniCode	636
15.6.12	InitKeyboard	636
15.6.13	IsFunctionKey	636
15.6.14	KeyEventToString	637
15.6.15	KeyPressed	637
15.6.16	PollKeyEvent	638
15.6.17	PollShiftStateEvent	638
15.6.18	PutKeyEvent	639
15.6.19	RawReadKey	640

15.6.20 RawReadString	640
15.6.21 RestoreStartMode	640
15.6.22 SetKeyboardDriver	640
15.6.23 ShiftStateToString	641
15.6.24 TranslateKeyEvent	641
15.6.25 TranslateKeyEventUnicode	641
16 Reference for unit 'Linux'	644
16.1 Used units	644
16.2 Overview	644
16.3 Constants, types and variables	644
16.3.1 Constants	644
16.3.2 Types	649
16.4 Procedures and functions	650
16.4.1 Clone	650
16.4.2 epoll_create	652
16.4.3 epoll_ctl	652
16.4.4 epoll_wait	653
16.4.5 Sysinfo	653
17 Reference for unit 'math'	655
17.1 Geometrical functions	655
17.2 Statistical functions	655
17.3 Number converting	656
17.4 Exponential and logarithmic functions	656
17.5 Hyperbolic functions	656
17.6 Trigonometric functions	656
17.7 Angle unit conversion	656
17.8 Min/max determination	657
17.9 Used units	657
17.10 Overview	657
17.11 Constants, types and variables	658
17.11.1 Constants	658
17.11.2 Types	659
17.12 Procedures and functions	660
17.12.1 arccos	660
17.12.2 arccosh	661
17.12.3 arcosh	661
17.12.4 arcsin	662
17.12.5 arcsinh	663
17.12.6 arctan2	663

17.12.7 arctanh	663
17.12.8 arsinh	664
17.12.9 artanh	664
17.12.10 ceil	665
17.12.11 ClearExceptions	665
17.12.12 cosh	665
17.12.13 cotan	666
17.12.14 cycletorad	666
17.12.15 degtograd	667
17.12.16 degtorad	667
17.12.17 DivMod	668
17.12.18 EnsureRange	668
17.12.19 floor	668
17.12.20 Frexp	669
17.12.21 GetExceptionMask	670
17.12.22 GetPrecisionMode	670
17.12.23 GetRoundMode	670
17.12.24 GetSSECSR	670
17.12.25 gradtodeg	670
17.12.26 gradtorad	671
17.12.27 hypot	671
17.12.28 ifthen	672
17.12.29 InRange	672
17.12.30 Intpower	672
17.12.31 IsInfinite	673
17.12.32 IsNan	673
17.12.33 IsZero	673
17.12.34 dexp	674
17.12.35 Inxp1	674
17.12.36 log10	675
17.12.37 log2	675
17.12.38 ogn	676
17.12.39 Max	676
17.12.40 MaxIntValue	677
17.12.41 maxvalue	678
17.12.42 mean	679
17.12.43 meanandstddev	679
17.12.44 Min	680
17.12.45 MinIntValue	681
17.12.46 minvalue	681

17.12.47momentskewkurtosis	682
17.12.48norm	683
17.12.49operator *(float, float): float	684
17.12.50operator *(Int64, Int64): Int64	684
17.12.51popnstddev	684
17.12.52popnvariance	685
17.12.53power	685
17.12.54radto cycle	686
17.12.55radto deg	686
17.12.56radto grad	687
17.12.57randg	687
17.12.58SameValue	688
17.12.59SetExceptionMask	688
17.12.60SetPrecisionMode	689
17.12.61SetRoundMode	689
17.12.62SetSSECSR	689
17.12.63Sign	689
17.12.64sincos	690
17.12.65sinh	690
17.12.66stddev	691
17.12.67sum	691
17.12.68sumInt	692
17.12.69sumofsquares	692
17.12.70sumsandsquares	693
17.12.71tan	694
17.12.72tanh	694
17.12.73totalvariance	695
17.12.74variance	696
17.13invalidargument	696
17.13.1 Description	696
18 Reference for unit 'matrix'	697
18.1 Overview	697
18.2 Constants, types and variables	698
18.2.1 Types	698
18.3 Procedures and functions	700
18.3.1 operator *(Tvector2_double, Tvector2_double): Tvector2_double	700
18.3.2 operator *(Tvector2_extended, Tvector2_extended): Tvector2_extended	700
18.3.3 operator *(Tvector2_single, Tvector2_single): Tvector2_single	701
18.3.4 operator *(Tvector3_double, Tvector3_double): Tvector3_double	701

18.3.5 operator *(Tvector3_extended, Tvector3_extended): Tvector3_extended . . .	701
18.3.6 operator *(Tvector3_single, Tvector3_single): Tvector3_single	701
18.3.7 operator *(Tvector4_double, Tvector4_double): Tvector4_double	702
18.3.8 operator *(Tvector4_extended, Tvector4_extended): Tvector4_extended . . .	702
18.3.9 operator *(Tvector4_single, Tvector4_single): Tvector4_single	702
18.3.10 operator **(Tvector2_double, Tvector2_double): double	702
18.3.11 operator **(Tvector2_extended, Tvector2_extended): extended	703
18.3.12 operator **(Tvector2_single, Tvector2_single): single	703
18.3.13 operator **(Tvector3_double, Tvector3_double): double	703
18.3.14 operator **(Tvector3_extended, Tvector3_extended): extended	703
18.3.15 operator **(Tvector3_single, Tvector3_single): single	704
18.3.16 operator **(Tvector4_double, Tvector4_double): double	704
18.3.17 operator **(Tvector4_extended, Tvector4_extended): extended	704
18.3.18 operator **(Tvector4_single, Tvector4_single): single	704
18.3.19 operator +(Tvector2_double, Tvector2_double): Tvector2_double	705
18.3.20 operator +(Tvector2_extended, Tvector2_extended): Tvector2_extended . . .	705
18.3.21 operator +(Tvector2_single, Tvector2_single): Tvector2_single	705
18.3.22 operator +(Tvector3_double, Tvector3_double): Tvector3_double	705
18.3.23 operator +(Tvector3_extended, Tvector3_extended): Tvector3_extended . . .	706
18.3.24 operator +(Tvector3_single, Tvector3_single): Tvector3_single	706
18.3.25 operator +(Tvector4_double, Tvector4_double): Tvector4_double	706
18.3.26 operator +(Tvector4_extended, Tvector4_extended): Tvector4_extended . . .	706
18.3.27 operator +(Tvector4_single, Tvector4_single): Tvector4_single	707
18.3.28 operator -(Tvector2_double): Tvector2_double	707
18.3.29 operator -(Tvector2_double, Tvector2_double): Tvector2_double	707
18.3.30 operator -(Tvector2_extended): Tvector2_extended	707
18.3.31 operator -(Tvector2_extended, Tvector2_extended): Tvector2_extended . . .	708
18.3.32 operator -(Tvector2_single): Tvector2_single	708
18.3.33 operator -(Tvector2_single, Tvector2_single): Tvector2_single	708
18.3.34 operator -(Tvector3_double): Tvector3_double	708
18.3.35 operator -(Tvector3_double, Tvector3_double): Tvector3_double	709
18.3.36 operator -(Tvector3_extended): Tvector3_extended	709
18.3.37 operator -(Tvector3_extended, Tvector3_extended): Tvector3_extended . . .	709
18.3.38 operator -(Tvector3_single): Tvector3_single	709
18.3.39 operator -(Tvector3_single, Tvector3_single): Tvector3_single	710
18.3.40 operator -(Tvector4_double): Tvector4_double	710
18.3.41 operator -(Tvector4_double, Tvector4_double): Tvector4_double	710
18.3.42 operator -(Tvector4_extended): Tvector4_extended	710
18.3.43 operator -(Tvector4_extended, Tvector4_extended): Tvector4_extended . . .	711
18.3.44 operator -(Tvector4_single): Tvector4_single	711

18.3.45 operator -(Tvector4_single, Tvector4_single): Tvector4_single	711
18.3.46 operator :=(Tvector2_double): Tvector2_extended	711
18.3.47 operator :=(Tvector2_double): Tvector2_single	712
18.3.48 operator :=(Tvector2_double): Tvector3_double	712
18.3.49 operator :=(Tvector2_double): Tvector3_extended	712
18.3.50 operator :=(Tvector2_double): Tvector3_single	712
18.3.51 operator :=(Tvector2_double): Tvector4_double	713
18.3.52 operator :=(Tvector2_double): Tvector4_extended	713
18.3.53 operator :=(Tvector2_double): Tvector4_single	713
18.3.54 operator :=(Tvector2_extended): Tvector2_double	713
18.3.55 operator :=(Tvector2_extended): Tvector2_single	714
18.3.56 operator :=(Tvector2_extended): Tvector3_double	714
18.3.57 operator :=(Tvector2_extended): Tvector3_extended	714
18.3.58 operator :=(Tvector2_extended): Tvector3_single	714
18.3.59 operator :=(Tvector2_extended): Tvector4_double	715
18.3.60 operator :=(Tvector2_extended): Tvector4_extended	715
18.3.61 operator :=(Tvector2_extended): Tvector4_single	715
18.3.62 operator :=(Tvector2_single): Tvector2_double	715
18.3.63 operator :=(Tvector2_single): Tvector2_extended	716
18.3.64 operator :=(Tvector2_single): Tvector3_double	716
18.3.65 operator :=(Tvector2_single): Tvector3_extended	716
18.3.66 operator :=(Tvector2_single): Tvector3_single	716
18.3.67 operator :=(Tvector2_single): Tvector4_double	717
18.3.68 operator :=(Tvector2_single): Tvector4_extended	717
18.3.69 operator :=(Tvector2_single): Tvector4_single	717
18.3.70 operator :=(Tvector3_double): Tvector2_double	717
18.3.71 operator :=(Tvector3_double): Tvector2_extended	718
18.3.72 operator :=(Tvector3_double): Tvector2_single	718
18.3.73 operator :=(Tvector3_double): Tvector3_extended	718
18.3.74 operator :=(Tvector3_double): Tvector3_single	718
18.3.75 operator :=(Tvector3_double): Tvector4_double	719
18.3.76 operator :=(Tvector3_double): Tvector4_extended	719
18.3.77 operator :=(Tvector3_double): Tvector4_single	719
18.3.78 operator :=(Tvector3_extended): Tvector2_double	719
18.3.79 operator :=(Tvector3_extended): Tvector2_extended	720
18.3.80 operator :=(Tvector3_extended): Tvector2_single	720
18.3.81 operator :=(Tvector3_extended): Tvector3_double	720
18.3.82 operator :=(Tvector3_extended): Tvector3_single	720
18.3.83 operator :=(Tvector3_extended): Tvector4_double	721
18.3.84 operator :=(Tvector3_extended): Tvector4_extended	721

18.3.85 operator :=(Tvector3_extended): Tvector4_single	721
18.3.86 operator :=(Tvector3_single): Tvector2_double	721
18.3.87 operator :=(Tvector3_single): Tvector2_extended	722
18.3.88 operator :=(Tvector3_single): Tvector2_single	722
18.3.89 operator :=(Tvector3_single): Tvector3_double	722
18.3.90 operator :=(Tvector3_single): Tvector3_extended	722
18.3.91 operator :=(Tvector3_single): Tvector4_double	723
18.3.92 operator :=(Tvector3_single): Tvector4_extended	723
18.3.93 operator :=(Tvector3_single): Tvector4_single	723
18.3.94 operator :=(Tvector4_double): Tvector2_double	723
18.3.95 operator :=(Tvector4_double): Tvector2_extended	724
18.3.96 operator :=(Tvector4_double): Tvector2_single	724
18.3.97 operator :=(Tvector4_double): Tvector3_double	724
18.3.98 operator :=(Tvector4_double): Tvector3_extended	724
18.3.99 operator :=(Tvector4_double): Tvector3_single	725
18.3.100 operator :=(Tvector4_double): Tvector4_extended	725
18.3.101 operator :=(Tvector4_double): Tvector4_single	725
18.3.102 operator :=(Tvector4_extended): Tvector2_double	725
18.3.103 operator :=(Tvector4_extended): Tvector2_extended	726
18.3.104 operator :=(Tvector4_extended): Tvector2_single	726
18.3.105 operator :=(Tvector4_extended): Tvector3_double	726
18.3.106 operator :=(Tvector4_extended): Tvector3_extended	726
18.3.107 operator :=(Tvector4_extended): Tvector3_single	727
18.3.108 operator :=(Tvector4_extended): Tvector4_double	727
18.3.109 operator :=(Tvector4_extended): Tvector4_single	727
18.3.110 operator :=(Tvector4_single): Tvector2_double	727
18.3.111 operator :=(Tvector4_single): Tvector2_extended	728
18.3.112 operator :=(Tvector4_single): Tvector2_single	728
18.3.113 operator :=(Tvector4_single): Tvector3_double	728
18.3.114 operator :=(Tvector4_single): Tvector3_extended	729
18.3.115 operator :=(Tvector4_single): Tvector3_single	729
18.3.116 operator :=(Tvector4_single): Tvector4_double	729
18.3.117 operator :=(Tvector4_single): Tvector4_extended	729
18.4 Tmatrix2_double	730
18.4.1 Description	730
18.4.2 Method overview	730
18.4.3 Tmatrix2_double.init_zero	730
18.4.4 Tmatrix2_double.init_identity	730
18.4.5 Tmatrix2_double.init	730
18.4.6 Tmatrix2_double.get_column	731

18.4.7	<code>Tmatrix2_double.get_row</code>	731
18.4.8	<code>Tmatrix2_double.set_column</code>	731
18.4.9	<code>Tmatrix2_double.set_row</code>	731
18.4.10	<code>Tmatrix2_double.determinant</code>	731
18.4.11	<code>Tmatrix2_double.inverse</code>	731
18.4.12	<code>Tmatrix2_double.transpose</code>	732
18.5	<code>Tmatrix2_extended</code>	732
18.5.1	Description	732
18.5.2	Method overview	732
18.5.3	<code>Tmatrix2_extended.init_zero</code>	732
18.5.4	<code>Tmatrix2_extended.init_identity</code>	732
18.5.5	<code>Tmatrix2_extended.init</code>	733
18.5.6	<code>Tmatrix2_extended.get_column</code>	733
18.5.7	<code>Tmatrix2_extended.get_row</code>	733
18.5.8	<code>Tmatrix2_extended.set_column</code>	733
18.5.9	<code>Tmatrix2_extended.set_row</code>	733
18.5.10	<code>Tmatrix2_extended.determinant</code>	733
18.5.11	<code>Tmatrix2_extended.inverse</code>	734
18.5.12	<code>Tmatrix2_extended.transpose</code>	734
18.6	<code>Tmatrix2_single</code>	734
18.6.1	Description	734
18.6.2	Method overview	734
18.6.3	<code>Tmatrix2_single.init_zero</code>	734
18.6.4	<code>Tmatrix2_single.init_identity</code>	735
18.6.5	<code>Tmatrix2_single.init</code>	735
18.6.6	<code>Tmatrix2_single.get_column</code>	735
18.6.7	<code>Tmatrix2_single.get_row</code>	735
18.6.8	<code>Tmatrix2_single.set_column</code>	735
18.6.9	<code>Tmatrix2_single.set_row</code>	736
18.6.10	<code>Tmatrix2_single.determinant</code>	736
18.6.11	<code>Tmatrix2_single.inverse</code>	736
18.6.12	<code>Tmatrix2_single.transpose</code>	736
18.7	<code>Tmatrix3_double</code>	736
18.7.1	Description	736
18.7.2	Method overview	737
18.7.3	<code>Tmatrix3_double.init_zero</code>	737
18.7.4	<code>Tmatrix3_double.init_identity</code>	737
18.7.5	<code>Tmatrix3_double.init</code>	737
18.7.6	<code>Tmatrix3_double.get_column</code>	737
18.7.7	<code>Tmatrix3_double.get_row</code>	738

18.7.8	Tmatrix3_double.set_column	738
18.7.9	Tmatrix3_double.set_row	738
18.7.10	Tmatrix3_double.determinant	738
18.7.11	Tmatrix3_double.inverse	738
18.7.12	Tmatrix3_double.transpose	738
18.8	Tmatrix3_extended	739
18.8.1	Description	739
18.8.2	Method overview	739
18.8.3	Tmatrix3_extended.init_zero	739
18.8.4	Tmatrix3_extended.init_identity	739
18.8.5	Tmatrix3_extended.init	739
18.8.6	Tmatrix3_extended.get_column	740
18.8.7	Tmatrix3_extended.get_row	740
18.8.8	Tmatrix3_extended.set_column	740
18.8.9	Tmatrix3_extended.set_row	740
18.8.10	Tmatrix3_extended.determinant	740
18.8.11	Tmatrix3_extended.inverse	740
18.8.12	Tmatrix3_extended.transpose	741
18.9	Tmatrix3_single	741
18.9.1	Description	741
18.9.2	Method overview	741
18.9.3	Tmatrix3_single.init_zero	741
18.9.4	Tmatrix3_single.init_identity	741
18.9.5	Tmatrix3_single.init	742
18.9.6	Tmatrix3_single.get_column	742
18.9.7	Tmatrix3_single.get_row	742
18.9.8	Tmatrix3_single.set_column	742
18.9.9	Tmatrix3_single.set_row	742
18.9.10	Tmatrix3_single.determinant	743
18.9.11	Tmatrix3_single.inverse	743
18.9.12	Tmatrix3_single.transpose	743
18.10	Tmatrix4_double	743
18.10.1	Description	743
18.10.2	Method overview	743
18.10.3	Tmatrix4_double.init_zero	744
18.10.4	Tmatrix4_double.init_identity	744
18.10.5	Tmatrix4_double.init	744
18.10.6	Tmatrix4_double.get_column	744
18.10.7	Tmatrix4_double.get_row	744
18.10.8	Tmatrix4_double.set_column	745

18.10.9	Tmatrix4_double.set_row	745
18.10.10	Tmatrix4_double.determinant	745
18.10.11	Tmatrix4_double.inverse	745
18.10.12	Tmatrix4_double.transpose	745
18.11	Tmatrix4_extended	746
18.11.1	Description	746
18.11.2	Method overview	746
18.11.3	Tmatrix4_extended.init_zero	746
18.11.4	Tmatrix4_extended.init_identity	746
18.11.5	Tmatrix4_extended.init	746
18.11.6	Tmatrix4_extended.get_column	747
18.11.7	Tmatrix4_extended.get_row	747
18.11.8	Tmatrix4_extended.set_column	747
18.11.9	Tmatrix4_extended.set_row	747
18.11.10	Tmatrix4_extended.determinant	747
18.11.11	Tmatrix4_extended.inverse	748
18.11.12	Tmatrix4_extended.transpose	748
18.12	Tmatrix4_single	748
18.12.1	Description	748
18.12.2	Method overview	748
18.12.3	Tmatrix4_single.init_zero	748
18.12.4	Tmatrix4_single.init_identity	749
18.12.5	Tmatrix4_single.init	749
18.12.6	Tmatrix4_single.get_column	749
18.12.7	Tmatrix4_single.get_row	749
18.12.8	Tmatrix4_single.set_column	749
18.12.9	Tmatrix4_single.set_row	750
18.12.10	Tmatrix4_single.determinant	750
18.12.11	Tmatrix4_single.inverse	750
18.12.12	Tmatrix4_single.transpose	750
18.13	Tvector2_double	750
18.13.1	Description	750
18.13.2	Method overview	751
18.13.3	Tvector2_double.init_zero	751
18.13.4	Tvector2_double.init_one	751
18.13.5	Tvector2_double.init	751
18.13.6	Tvector2_double.length	751
18.13.7	Tvector2_double.squared_length	751
18.14	Tvector2_extended	752
18.14.1	Description	752

18.14.2 Method overview	752
18.14.3 Tvector2_extended.init_zero	752
18.14.4 Tvector2_extended.init_one	752
18.14.5 Tvector2_extended.init	752
18.14.6 Tvector2_extended.length	752
18.14.7 Tvector2_extended.squared_length	753
18.15Tvector2_single	753
18.15.1 Description	753
18.15.2 Method overview	753
18.15.3 Tvector2_single.init_zero	753
18.15.4 Tvector2_single.init_one	753
18.15.5 Tvector2_single.init	753
18.15.6 Tvector2_single.length	754
18.15.7 Tvector2_single.squared_length	754
18.16Tvector3_double	754
18.16.1 Description	754
18.16.2 Method overview	754
18.16.3 Tvector3_double.init_zero	754
18.16.4 Tvector3_double.init_one	754
18.16.5 Tvector3_double.init	755
18.16.6 Tvector3_double.length	755
18.16.7 Tvector3_double.squared_length	755
18.17Tvector3_extended	755
18.17.1 Description	755
18.17.2 Method overview	755
18.17.3 Tvector3_extended.init_zero	755
18.17.4 Tvector3_extended.init_one	756
18.17.5 Tvector3_extended.init	756
18.17.6 Tvector3_extended.length	756
18.17.7 Tvector3_extended.squared_length	756
18.18Tvector3_single	756
18.18.1 Description	756
18.18.2 Method overview	756
18.18.3 Tvector3_single.init_zero	757
18.18.4 Tvector3_single.init_one	757
18.18.5 Tvector3_single.init	757
18.18.6 Tvector3_single.length	757
18.18.7 Tvector3_single.squared_length	757
18.19Tvector4_double	757
18.19.1 Description	757

18.19.2 Method overview	758
18.19.3 Tvector4_double.init_zero	758
18.19.4 Tvector4_double.init_one	758
18.19.5 Tvector4_double.init	758
18.19.6 Tvector4_double.length	758
18.19.7 Tvector4_double.squared_length	758
18.20 Tvector4_extended	759
18.20.1 Description	759
18.20.2 Method overview	759
18.20.3 Tvector4_extended.init_zero	759
18.20.4 Tvector4_extended.init_one	759
18.20.5 Tvector4_extended.init	759
18.20.6 Tvector4_extended.length	759
18.20.7 Tvector4_extended.squared_length	760
18.21 Tvector4_single	760
18.21.1 Description	760
18.21.2 Method overview	760
18.21.3 Tvector4_single.init_zero	760
18.21.4 Tvector4_single.init_one	760
18.21.5 Tvector4_single.init	760
18.21.6 Tvector4_single.length	761
18.21.7 Tvector4_single.squared_length	761
19 Reference for unit 'mmx'	762
19.1 Overview	762
19.2 Constants, types and variables	762
19.2.1 Constants	762
19.2.2 Types	763
19.3 Procedures and functions	764
19.3.1 emms	764
19.3.2 femms	764
20 Reference for unit 'Mouse'	765
20.1 Writing a custom mouse driver	765
20.2 Overview	765
20.3 Constants, types and variables	765
20.3.1 Constants	765
20.3.2 Types	766
20.3.3 Variables	767
20.4 Procedures and functions	767
20.4.1 DetectMouse	767

20.4.2	DoneMouse	768
20.4.3	GetMouseButtons	768
20.4.4	GetMouseDriver	769
20.4.5	GetMouseEvent	769
20.4.6	GetMouseX	769
20.4.7	GetMouseY	770
20.4.8	HideMouse	770
20.4.9	InitMouse	771
20.4.10	PollMouseEvent	772
20.4.11	PutMouseEvent	772
20.4.12	SetMouseDriver	772
20.4.13	SetMouseXY	773
20.4.14	ShowMouse	773
21	Reference for unit 'Objects'	774
21.1	Overview	774
21.2	Constants, types and variables	774
21.2.1	Constants	774
21.2.2	Types	776
21.2.3	Variables	780
21.3	Procedures and functions	780
21.3.1	Abstract	780
21.3.2	CallPointerConstructor	780
21.3.3	CallPointerLocal	781
21.3.4	CallPointerMethod	781
21.3.5	CallPointerMethodLocal	781
21.3.6	CallVoidConstructor	782
21.3.7	CallVoidLocal	782
21.3.8	CallVoidMethod	782
21.3.9	CallVoidMethodLocal	783
21.3.10	DisposeStr	783
21.3.11	LongDiv	783
21.3.12	LongMul	783
21.3.13	NewStr	784
21.3.14	RegisterObjects	784
21.3.15	RegisterType	785
21.3.16	SetStr	786
21.4	TBufStream	787
21.4.1	Description	787
21.4.2	Method overview	787

21.4.3	TBufStream.Init	787
21.4.4	TBufStream.Done	788
21.4.5	TBufStream.Close	788
21.4.6	TBufStream.Flush	788
21.4.7	TBufStream.Truncate	789
21.4.8	TBufStream.Seek	789
21.4.9	TBufStream.Open	790
21.4.10	TBufStream.Read	790
21.4.11	TBufStream.Write	790
21.5	TCollection	791
21.5.1	Description	791
21.5.2	Method overview	791
21.5.3	TCollection.Init	791
21.5.4	TCollection.Load	792
21.5.5	TCollection.Done	792
21.5.6	TCollection.At	793
21.5.7	TCollection.IndexOf	793
21.5.8	TCollection.GetItem	794
21.5.9	TCollection.LastThat	795
21.5.10	TCollection.FirstThat	795
21.5.11	TCollection.Pack	796
21.5.12	TCollection.FreeAll	797
21.5.13	TCollection.DeleteAll	798
21.5.14	TCollection.Free	799
21.5.15	TCollection.Insert	799
21.5.16	TCollection.Delete	800
21.5.17	TCollection.AtFree	800
21.5.18	TCollection.FreeItem	801
21.5.19	TCollection.AtDelete	801
21.5.20	TCollection.ForEach	802
21.5.21	TCollection.SetLimit	803
21.5.22	TCollection.Error	803
21.5.23	TCollection.AtPut	804
21.5.24	TCollection.AtInsert	804
21.5.25	TCollection.Store	805
21.5.26	TCollection.PutItem	805
21.6	TDosStream	805
21.6.1	Description	805
21.6.2	Method overview	806
21.6.3	TDosStream.Init	806

21.6.4	TDosStream.Done	806
21.6.5	TDosStream.Close	807
21.6.6	TDosStream.Truncate	807
21.6.7	TDosStream.Seek	808
21.6.8	TDosStream.Open	809
21.6.9	TDosStream.Read	809
21.6.10	TDosStream.Write	810
21.7	TMemoryStream	810
21.7.1	Description	810
21.7.2	Method overview	810
21.7.3	TMemoryStream.Init	810
21.7.4	TMemoryStream.Done	811
21.7.5	TMemoryStream.Truncate	811
21.7.6	TMemoryStream.Read	812
21.7.7	TMemoryStream.Write	812
21.8	TObject	812
21.8.1	Description	812
21.8.2	Method overview	812
21.8.3	TObject.Init	812
21.8.4	TObject.Free	813
21.8.5	TObject.Is_Object	813
21.8.6	TObject.Done	814
21.9	TPoint	814
21.9.1	Description	814
21.10	TRect	814
21.10.1	Description	814
21.10.2	Method overview	814
21.10.3	TRect.Empty	815
21.10.4	TRect.Equals	816
21.10.5	TRect.Contains	816
21.10.6	TRect.Copy	816
21.10.7	TRect.Union	817
21.10.8	TRect.Intersect	817
21.10.9	TRect.Move	818
21.10.10	TRect.Grow	819
21.10.11	TRect.Assign	819
21.11	TResourceCollection	820
21.11.1	Description	820
21.11.2	Method overview	820
21.11.3	TResourceCollection.KeyOf	820

21.11.4 TResourceCollection.GetItem	821
21.11.5 TResourceCollection.FreeItem	821
21.11.6 TResourceCollection.PutItem	821
21.12 TResourceFile	821
21.12.1 Description	821
21.12.2 Method overview	822
21.12.3 TResourceFile.Init	822
21.12.4 TResourceFile.Done	822
21.12.5 TResourceFile.Count	822
21.12.6 TResourceFile.KeyAt	823
21.12.7 TResourceFile.Get	823
21.12.8 TResourceFile.SwitchTo	823
21.12.9 TResourceFile.Flush	823
21.12.10 TResourceFile.Delete	824
21.12.11 TResourceFile.Put	824
21.13 TSortedCollection	824
21.13.1 Description	824
21.13.2 Method overview	825
21.13.3 TSortedCollection.Init	825
21.13.4 TSortedCollection.Load	825
21.13.5 TSortedCollection.KeyOf	825
21.13.6 TSortedCollection.IndexOf	826
21.13.7 TSortedCollection.Compare	826
21.13.8 TSortedCollection.Search	827
21.13.9 TSortedCollection.Insert	828
21.13.10 TSortedCollection.Store	829
21.14 TStrCollection	830
21.14.1 Description	830
21.14.2 Method overview	830
21.14.3 TStrCollection.Compare	830
21.14.4 TStrCollection.GetItem	831
21.14.5 TStrCollection.FreeItem	831
21.14.6 TStrCollection.PutItem	831
21.15 TStream	832
21.15.1 Description	832
21.15.2 Method overview	832
21.15.3 TStream.Init	832
21.15.4 TStream.Get	832
21.15.5 TStream.StrRead	833
21.15.6 TStream.GetPos	834

21.15.7 TStream.GetSize	834
21.15.8 TStream.ReadStr	835
21.15.9 TStream.Open	836
21.15.10 TStream.Close	836
21.15.11 TStream.Reset	836
21.15.12 TStream.Flush	837
21.15.13 TStream.Truncate	837
21.15.14 TStream.Put	837
21.15.15 TStream.StrWrite	838
21.15.16 TStream.WriteStr	838
21.15.17 TStream.Seek	838
21.15.18 TStream.Error	838
21.15.19 TStream.Read	839
21.15.20 TStream.Write	839
21.15.21 TStream.CopyFrom	840
21.16 TStringCollection	840
21.16.1 Description	840
21.16.2 Method overview	841
21.16.3 TStringCollection.GetItem	841
21.16.4 TStringCollection.Compare	841
21.16.5 TStringCollection.FreeItem	842
21.16.6 TStringCollection.PutItem	842
21.17 TStringList	842
21.17.1 Description	842
21.17.2 Method overview	843
21.17.3 TStringList.Load	843
21.17.4 TStringList.Done	843
21.17.5 TStringList.Get	843
21.18 TStrListMaker	844
21.18.1 Description	844
21.18.2 Method overview	844
21.18.3 TStrListMaker.Init	844
21.18.4 TStrListMaker.Done	844
21.18.5 TStrListMaker.Put	844
21.18.6 TStrListMaker.Store	845
21.19 TUnSortedStrCollection	845
21.19.1 Description	845
21.19.2 Method overview	845
21.19.3 TUnSortedStrCollection.Insert	845

22 Reference for unit 'objpas'	847
22.1 Overview	847
22.2 Constants, types and variables	847
22.2.1 Constants	847
22.2.2 Types	847
22.3 Procedures and functions	848
22.3.1 AssignFile	848
22.3.2 CloseFile	849
22.3.3 GetResourceStringCurrentValue	849
22.3.4 GetResourceStringDefaultValue	850
22.3.5 GetResourceStringHash	851
22.3.6 GetResourceStringName	851
22.3.7 Hash	852
22.3.8 LoadResString	853
22.3.9 ParamStr	853
22.3.10 ResetResourceTables	853
22.3.11 ResourceStringCount	854
22.3.12 ResourceStringTableCount	854
22.3.13 SetResourceStrings	854
22.3.14 SetResourceStringValue	855
23 Reference for unit 'oldlinux'	857
23.1 Utility routines	857
23.2 Terminal functions	857
23.3 System information	857
23.4 Signals	858
23.5 Process handling	858
23.6 Directory handling routines	858
23.7 Pipes, FIFOs and streams	859
23.8 General File handling routines	859
23.9 File Input/Output routines	859
23.10 Overview	859
23.11 Constants, types and variables	859
23.11.1 Constants	859
23.11.2 Types	899
23.11.3 Variables	908
23.12 Procedures and functions	908
23.12.1 Access	908
23.12.2 Alarm	909
23.12.3 AssignPipe	910

23.12.4 AssignStream	911
23.12.5 Basename	912
23.12.6 CFMakeRaw	913
23.12.7 CFSetISpeed	913
23.12.8 CFSetOSpeed	913
23.12.9 Chmod	914
23.12.10 Chown	915
23.12.11 Clone	916
23.12.12 CloseDir	918
23.12.13 CreateShellArgV	918
23.12.14 Dirname	919
23.12.15 Dup	920
23.12.16 Dup2	920
23.12.17 EpochToLocal	921
23.12.18 Execl	922
23.12.19 Execle	923
23.12.20 Execlp	923
23.12.21 Execv	924
23.12.22 Execve	925
23.12.23 Execvp	926
23.12.24 ExitProcess	927
23.12.25 Fcntl	927
23.12.26 fdClose	928
23.12.27 fdFlush	928
23.12.28 fdOpen	929
23.12.29 fdRead	930
23.12.30 fdSeek	931
23.12.31 fdTruncate	931
23.12.32 fdWrite	932
23.12.33 FD_Clr	932
23.12.34 FD_IsSet	932
23.12.35 FD_Set	932
23.12.36 FD_Zero	933
23.12.37 FExpand	933
23.12.38 Flock	933
23.12.39 FNMatch	934
23.12.40 Fork	935
23.12.41 FReName	935
23.12.42 FSearch	936
23.12.43 FSplit	936

23.12.4	F Stat	937
23.12.4	F Stat	938
23.12.4	G etDate	939
23.12.4	G etDateTime	939
23.12.4	G etDomainName	940
23.12.4	G etEGid	940
23.12.5	G etEnv	941
23.12.5	G etEpochTime	941
23.12.5	G etEUid	942
23.12.5	G etFS	942
23.12.5	G etGid	943
23.12.5	G etHostName	943
23.12.5	G etLocalTimezone	944
23.12.5	G etPid	944
23.12.5	G etPPid	945
23.12.5	G etPriority	945
23.12.6	G etTime	946
23.12.6	G etTimeOfDay	946
23.12.6	G etTimezoneFile	947
23.12.6	G etUid	947
23.12.6	G lob	947
23.12.6	G lobfree	948
23.12.6	O ctl	948
23.12.6	O perm	949
23.12.6	O PL	949
23.12.6	I sATTY	950
23.12.7	K ill	950
23.12.7	L ink	950
23.12.7	L ocalToEpoch	951
23.12.7	L stat	952
23.12.7	l nkFifo	954
23.12.7	M Map	954
23.12.7	M UnMap	955
23.12.7	N anoSleep	956
23.12.7	N ice	957
23.12.7	O ctal	957
23.12.8	O penDir	958
23.12.8	P ause	959
23.12.8	P Close	959
23.12.8	P Open	959

23.12.8ReadDir	960
23.12.8ReadLink	961
23.12.8ReadTimezoneFile	962
23.12.8SeekDir	962
23.12.8Select	962
23.12.8SelectText	964
23.12.9SetDate	964
23.12.9SetDateTime	964
23.12.9SetPriority	965
23.12.9SetTime	965
23.12.9Shell	965
23.12.9SigAction	966
23.12.9Signal	967
23.12.9SigPending	968
23.12.9SigProcMask	968
23.12.9SigRaise	969
23.12.10SigSuspend	970
23.12.10StringToPPChar	970
23.12.10SymLink	971
23.12.10SysCall	972
23.12.10Sysinfo	972
23.12.105_ISBLK	973
23.12.106_ISCHR	974
23.12.107_ISDIR	974
23.12.108_ISFIFO	974
23.12.109_ISLNK	974
23.12.110_ISREG	975
23.12.111_ISSOCK	975
23.12.112CDrain	976
23.12.113CFlow	976
23.12.114CFlush	976
23.12.115CGetAttr	977
23.12.116CGetPGrp	977
23.12.117CSendBreak	978
23.12.118CSetAttr	978
23.12.119CSetPGrp	979
23.12.120ellDir	979
23.12.121TTYname	979
23.12.122mask	980
23.12.123name	980

23.12.12	lnLink	980
23.12.13	time	981
23.12.12	WaitPid	982
23.12.12	WaitProcess	982
23.12.12	WEXITSTATUS	983
23.12.12	WIFEXITED	983
23.12.13	WIFSIGNALED	983
23.12.13	WIFSTOPPED	983
23.12.13	WSTOPSIG	984
23.12.13	WTERMSIG	984
23.12.13	W_EXITCODE	984
23.12.13	W_STOPCODE	984
24	Reference for unit 'ports'	985
24.1	Overview	985
24.2	Constants, types and variables	985
24.2.1	Variables	985
24.3	tport	986
24.3.1	Description	986
24.3.2	Property overview	986
24.3.3	tport.pp	986
24.4	tportl	986
24.4.1	Description	986
24.4.2	Property overview	987
24.4.3	tportl.pp	987
24.5	tportw	987
24.5.1	Description	987
24.5.2	Property overview	987
24.5.3	tportw.pp	987
25	Reference for unit 'printer'	988
25.1	Overview	988
25.2	Constants, types and variables	988
25.2.1	Variables	988
25.3	Procedures and functions	988
25.3.1	AssignLst	988
25.3.2	InitPrinter	989
25.3.3	IsLstAvailable	989
26	Reference for unit 'Sockets'	990
26.1	Used units	990

26.2 Overview	990
26.3 Constants, types and variables	990
26.3.1 Constants	990
26.3.2 Types	1009
26.3.3 Variables	1011
26.4 Procedures and functions	1011
26.4.1 Accept	1011
26.4.2 Bind	1013
26.4.3 CloseSocket	1013
26.4.4 Connect	1014
26.4.5 faccept	1016
26.4.6 fbind	1016
26.4.7 fconnect	1016
26.4.8 fgetpeername	1016
26.4.9 fgetsockname	1016
26.4.10 fgetsockopt	1016
26.4.11 flisten	1016
26.4.12 frecv	1017
26.4.13 frecvfrom	1017
26.4.14 fsend	1017
26.4.15 fsendto	1017
26.4.16 fsetsockopt	1017
26.4.17 fshutdown	1017
26.4.18 fsocket	1017
26.4.19 fsocketpair	1018
26.4.20 GetPeerName	1018
26.4.21 GetSocketName	1018
26.4.22 GetSocketOptions	1019
26.4.23 HostAddrToStr	1019
26.4.24 HostAddrToStr6	1019
26.4.25 HostToNet	1020
26.4.26 htonl	1020
26.4.27 htons	1020
26.4.28 Listen	1020
26.4.29 NetAddrToStr	1021
26.4.30 NetAddrToStr6	1021
26.4.31 NetToHost	1021
26.4.32 NToHl	1021
26.4.33 NToHs	1022
26.4.34 Recv	1022

26.4.35 RecvFrom	1022
26.4.36 Send	1023
26.4.37 SendTo	1023
26.4.38 SetSocketOptions	1023
26.4.39 ShortHostToNet	1024
26.4.40 ShortNetToHost	1024
26.4.41 Shutdown	1024
26.4.42 Sock2File	1025
26.4.43 Sock2Text	1025
26.4.44 Socket	1025
26.4.45 SocketPair	1026
26.4.46 Str2UnixSockAddr	1026
26.4.47 StrToHostAddr	1026
26.4.48 StrToHostAddr6	1027
26.4.49 StrToNetAddr	1027
26.4.50 StrToNetAddr6	1027
27 Reference for unit 'strings'	1028
27.1 Overview	1028
27.2 Procedures and functions	1028
27.2.1 stralloc	1028
27.2.2 strcat	1028
27.2.3 strcmp	1029
27.2.4 strcpy	1029
27.2.5 strdispose	1030
27.2.6 strecopy	1030
27.2.7 strend	1031
27.2.8 stricmp	1032
27.2.9 strlcat	1032
27.2.10 strlcomp	1033
27.2.11 strlcopy	1034
27.2.12 strlen	1034
27.2.13 strlicomp	1035
27.2.14 strlower	1035
27.2.15 strmove	1036
27.2.16 strnew	1036
27.2.17 strpas	1037
27.2.18 strpcopy	1038
27.2.19 strpos	1038
27.2.20 strrscan	1039

27.2.21	strscan	1039
27.2.22	strupper	1040
28	Reference for unit 'strutils'	1041
28.1	Used units	1041
28.2	Constants, types and variables	1041
28.2.1	Constants	1041
28.2.2	Types	1042
28.3	Procedures and functions	1042
28.3.1	AddChar	1042
28.3.2	AddCharR	1043
28.3.3	AnsiContainsStr	1043
28.3.4	AnsiContainsText	1043
28.3.5	AnsiEndsStr	1043
28.3.6	AnsiEndsText	1044
28.3.7	AnsiIndexStr	1044
28.3.8	AnsiIndexText	1044
28.3.9	AnsiLeftStr	1045
28.3.10	AnsiMatchStr	1045
28.3.11	AnsiMatchText	1045
28.3.12	AnsiMidStr	1045
28.3.13	AnsiProperCase	1046
28.3.14	AnsiReplaceStr	1046
28.3.15	AnsiReplaceText	1046
28.3.16	AnsiResemblesText	1047
28.3.17	AnsiReverseString	1047
28.3.18	AnsiRightStr	1047
28.3.19	AnsiStartsStr	1047
28.3.20	AnsiStartsText	1048
28.3.21	BinToHex	1048
28.3.22	Copy2Space	1048
28.3.23	Copy2SpaceDel	1049
28.3.24	Copy2Symb	1049
28.3.25	Copy2SymbDel	1049
28.3.26	Dec2Numb	1050
28.3.27	DecodeSoundexInt	1050
28.3.28	DecodeSoundexWord	1050
28.3.29	DelChars	1050
28.3.30	DelSpace	1051
28.3.31	DelSpace1	1051

28.3.32 DupeString	1051
28.3.33 ExtractDelimited	1051
28.3.34 ExtractSubstr	1052
28.3.35 ExtractWord	1052
28.3.36 ExtractWordPos	1053
28.3.37 FindPart	1053
28.3.38 GetCmdLineArg	1053
28.3.39 Hex2Dec	1054
28.3.40 HexToBin	1054
28.3.41 IfThen	1054
28.3.42 IntToBin	1055
28.3.43 IntToRoman	1055
28.3.44 IsEmptyStr	1055
28.3.45 IsWild	1055
28.3.46 IsWordPresent	1056
28.3.47 LeftBStr	1056
28.3.48 LeftStr	1056
28.3.49 MidBStr	1057
28.3.50 MidStr	1057
28.3.51 NPos	1057
28.3.52 Numb2Dec	1058
28.3.53 Numb2USA	1058
28.3.54 PadCenter	1058
28.3.55 PadLeft	1059
28.3.56 PadRight	1059
28.3.57 PosEx	1059
28.3.58 PosSet	1059
28.3.59 PosSetEx	1060
28.3.60 RandomFrom	1060
28.3.61 Removeleadingchars	1060
28.3.62 RemovePadChars	1061
28.3.63 RemoveTrailingChars	1061
28.3.64 ReverseString	1061
28.3.65 RightBStr	1061
28.3.66 RightStr	1062
28.3.67 RomanToInt	1062
28.3.68 RPos	1062
28.3.69 RPosEx	1063
28.3.70 SearchBuf	1063
28.3.71 Soundex	1063

28.3.72 SoundexCompare	1064
28.3.73 SoundexInt	1064
28.3.74 SoundexProc	1064
28.3.75 SoundexSimilar	1065
28.3.76 SoundexWord	1065
28.3.77 StuffString	1065
28.3.78 Tab2Space	1066
28.3.79 TrimLeftSet	1066
28.3.80 TrimRightSet	1066
28.3.81 TrimSet	1066
28.3.82 WordCount	1067
28.3.83 WordPosition	1067
28.3.84 XorDecode	1067
28.3.85 XorEncode	1068
28.3.86 XorString	1068
29 Reference for unit 'System'	1069
29.1 Miscellaneous functions	1069
29.2 Operating System functions	1069
29.3 String handling	1069
29.4 Mathematical routines	1069
29.5 Memory management functions	1070
29.6 File handling functions	1070
29.7 Overview	1070
29.8 Constants, types and variables	1071
29.8.1 Constants	1071
29.8.2 Types	1090
29.8.3 Variables	1109
29.9 Procedures and functions	1112
29.9.1 abs	1112
29.9.2 AbstractError	1112
29.9.3 AcquireExceptionObject	1112
29.9.4 AddExitProc	1113
29.9.5 Addr	1113
29.9.6 Align	1114
29.9.7 AllocMem	1114
29.9.8 AnsiToUtf8	1114
29.9.9 Append	1114
29.9.10 arctan	1115
29.9.11 ArrayStringToPPchar	1115

29.9.12 Assert	1116
29.9.13 Assign	1116
29.9.14 Assigned	1117
29.9.15 BasicEventCreate	1118
29.9.16 basiceventdestroy	1118
29.9.17 basiceventResetEvent	1118
29.9.18 basiceventSetEvent	1118
29.9.19 basiceventWaitFor	1118
29.9.20 BeginThread	1119
29.9.21 BEtoN	1119
29.9.22 binStr	1119
29.9.23 BlockRead	1120
29.9.24 BlockWrite	1121
29.9.25 Break	1121
29.9.26 chdir	1122
29.9.27 chr	1123
29.9.28 Close	1123
29.9.29 CompareByte	1124
29.9.30 CompareChar	1125
29.9.31 CompareChar0	1126
29.9.32 CompareDWord	1127
29.9.33 CompareWord	1128
29.9.34 Concat	1129
29.9.35 Continue	1129
29.9.36 cos	1130
29.9.37 Cseg	1131
29.9.38 Dec	1131
29.9.39 DefaultAnsi2WideMove	1132
29.9.40 DefaultWide2AnsiMove	1132
29.9.41 Delete	1133
29.9.42 Dispose	1133
29.9.43 DoneCriticalsection	1134
29.9.44 Dseg	1134
29.9.45 Dump_Stack	1135
29.9.46 DynArraySetLength	1135
29.9.47 EndThread	1136
29.9.48 EnterCriticalsection	1136
29.9.49 EOF	1136
29.9.50 EOLn	1137
29.9.51 Erase	1138

29.9.52 Error	1138
29.9.53 Exclude	1139
29.9.54 Exit	1140
29.9.55 exp	1141
29.9.56 FilePos	1141
29.9.57 FileSize	1142
29.9.58 FillByte	1143
29.9.59 FillChar	1144
29.9.60 FillDWord	1144
29.9.61 FillWord	1145
29.9.62 FindResource	1145
29.9.63 Flush	1146
29.9.64 fpc_AbstractErrorIntern	1147
29.9.65 fpc_abs_real	1147
29.9.66 fpc_Addref	1147
29.9.67 fpc_ansi_str_append_ansi_string	1147
29.9.68 fpc_ansi_str_append_char	1147
29.9.69 fpc_ansi_str_append_shortstring	1147
29.9.70 fpc_AnsiStr_Assign	1147
29.9.71 fpc_AnsiStr_CheckRange	1148
29.9.72 fpc_AnsiStr_CheckZero	1148
29.9.73 fpc_AnsiStr_Compare	1148
29.9.74 fpc_AnsiStr_Concat	1148
29.9.75 fpc_ansi_str_Copy	1148
29.9.76 fpc_ansi_str_decr_ref	1148
29.9.77 fpc_AnsiStr_Float	1149
29.9.78 fpc_ansi_str_incr_ref	1149
29.9.79 fpc_ansi_str_int64	1149
29.9.80 fpc_ansi_str_qword	1149
29.9.81 fpc_AnsiStr_SetLength	1149
29.9.82 fpc_AnsiStr_sint	1149
29.9.83 fpc_ansi_str_to_chararray	1149
29.9.84 fpc_AnsiStr_To_ShortStr	1150
29.9.85 fpc_ansi_str_to_widechararray	1150
29.9.86 fpc_AnsiStr_To_WideStr	1150
29.9.87 fpc_AnsiStr_uint	1150
29.9.88 fpc_ansi_str_Unique	1150
29.9.89 fpc_arctan_real	1150
29.9.90 fpc_assert	1151
29.9.91 fpc_Catches	1151

29.9.92 fpc_chararray_Float	1151
29.9.93 fpc_chararray_int64	1151
29.9.94 fpc_chararray_qword	1151
29.9.95 fpc_chararray_sint	1151
29.9.96 fpc_CharArray_To_AnsiStr	1152
29.9.97 fpc_chararray_to_shortstr	1152
29.9.98 fpc_CharArray_To_WideStr	1152
29.9.99 fpc_chararray_uint	1152
29.9.100 fpc_char_copy	1152
29.9.101 fpc_Char_To_AnsiStr	1152
29.9.102 fpc_Char_To_WideStr	1153
29.9.103 fpc_class_as_intf	1153
29.9.104 fpc_cos_real	1153
29.9.105 fpc_DecRef	1153
29.9.106 fpc_divbyzero	1153
29.9.107 fpc_div_int64	1153
29.9.108 fpc_div_qword	1153
29.9.109 fpc_do_as	1154
29.9.110 fpc_do_is	1154
29.9.111 fpc_dynarray_clear	1154
29.9.112 fpc_dynarray_copy	1154
29.9.113 fpc_dynarray_decr_ref	1154
29.9.114 fpc_dynarray_high	1154
29.9.115 fpc_dynarray_incr_ref	1154
29.9.116 fpc_dynarray_length	1155
29.9.117 fpc_dynarray_setlength	1155
29.9.118 fpc_dynarray_to_variant	1155
29.9.119 fpc_exp_real	1155
29.9.120 fpc_finalize	1155
29.9.121 fpc_finalize_array	1155
29.9.122 fpc_frac_real	1155
29.9.123 fpc_freemem	1156
29.9.124 fpc_getmem	1156
29.9.125 fpc_get_input	1156
29.9.126 fpc_get_output	1156
29.9.127 fpc_help_constructor	1156
29.9.128 fpc_help_destructor	1156
29.9.129 fpc_help_fail	1156
29.9.130 fpc_Initialize	1157
29.9.131 fpc_InitializeUnits	1157

29.9.132	pc_interface_to_variant	1157
29.9.133	pc_intf_as	1157
29.9.134	pc_intf_assign	1157
29.9.135	pc_intf_decr_ref	1157
29.9.136	pc_intf_incr_ref	1157
29.9.137	pc_int_real	1158
29.9.138	pc_iocheck	1158
29.9.139	pc_ln_real	1158
29.9.140	pc_mod_int64	1158
29.9.141	pc_mod_qword	1158
29.9.142	pc_mul_int64	1158
29.9.143	pc_mul_qword	1158
29.9.144	pc_overflow	1159
29.9.145	pc_pchar_length	1159
29.9.146	pc_PChar_To_AnsiStr	1159
29.9.147	pc_pchar_to_shortstr	1159
29.9.148	pc_PChar_To_WideStr	1159
29.9.149	pc_pi_real	1159
29.9.150	pc_PopAddrStack	1159
29.9.151	pc_PopObjectStack	1160
29.9.152	pc_PopSecondObjectStack	1160
29.9.153	pc_PushExceptAddr	1160
29.9.154	pc_PushExceptObj	1160
29.9.155	pc_pwchar_length	1160
29.9.156	pc_PWideChar_To_AnsiStr	1160
29.9.157	pc_PWideChar_To_ShortStr	1160
29.9.158	pc_PWideChar_To_WideStr	1161
29.9.159	pc_Raiseexception	1161
29.9.160	pc_rangeerror	1161
29.9.161	pc_ReadLn_End	1161
29.9.162	pc_Read_End	1161
29.9.163	pc_Read_Text_AnsiStr	1161
29.9.164	pc_Read_Text_Char	1161
29.9.165	pc_Read_Text_Float	1162
29.9.166	pc_Read_Text_Int64	1162
29.9.167	pc_Read_Text_PChar_As_Array	1162
29.9.168	pc_Read_Text_PChar_As_Pointer	1162
29.9.169	pc_Read_Text_QWord	1162
29.9.170	pc_Read_Text_ShortStr	1162
29.9.171	pc_Read_Text_SInt	1162

29.9.17 Tpc_Read_Text_UInt	1163
29.9.17 Tpc_ReRaise	1163
29.9.17 Tpc_reset_typed	1163
29.9.17 Tpc_rewrite_typed	1163
29.9.17 Tpc_round_real	1163
29.9.17 Tpc_set_add_sets	1163
29.9.17 Tpc_set_comp_sets	1163
29.9.17 Tpc_set_contains_sets	1164
29.9.18 Tpc_set_create_element	1164
29.9.18 Tpc_set_in_byte	1164
29.9.18 Tpc_set_load_small	1164
29.9.18 Tpc_set_mul_sets	1164
29.9.18 Tpc_set_set_byte	1164
29.9.18 Tpc_set_set_range	1165
29.9.18 Tpc_set_sub_sets	1165
29.9.18 Tpc_set_symdif_sets	1165
29.9.18 Tpc_set_unset_byte	1165
29.9.18 Tpc_shortstr_append_shortstr	1165
29.9.19 Tpc_shortstr_compare	1165
29.9.19 Tpc_shortstr_concat	1166
29.9.19 Tpc_shortstr_Copy	1166
29.9.19 Tpc_ShortStr_Float	1166
29.9.19 Tpc_shortstr_int64	1166
29.9.19 Tpc_shortstr_qword	1166
29.9.19 Tpc_Shortstr_SetLength	1166
29.9.19 Tpc_ShortStr_sint	1166
29.9.19 Tpc_ShortStr_To_AnsiStr	1167
29.9.19 Tpc_shortstr_to_chararray	1167
29.9.20 Tpc_shortstr_to_shortstr	1167
29.9.20 Tpc_shortstr_to_widechararray	1167
29.9.20 Tpc_ShortStr_To_WideStr	1167
29.9.20 Tpc_shortstr_uint	1167
29.9.20 Tpc_sin_real	1168
29.9.20 Tpc_sqrt_real	1168
29.9.20 Tpc_sqr_real	1168
29.9.20 Tpc_trunc_real	1168
29.9.20 Tpc_typed_read	1168
29.9.20 Tpc_typed_write	1168
29.9.21 Tpc_Val_int64_AnsiStr	1168
29.9.21 Tpc_val_int64_shortstr	1169

29.9.21	Tpc_Val_int64_WideStr	1169
29.9.21	Tpc_Val_qword_AnsiStr	1169
29.9.21	Tpc_val_qword_shortstr	1169
29.9.21	Tpc_Val_qword_WideStr	1169
29.9.21	Tpc_Val_Real_AnsiStr	1169
29.9.21	Tpc_Val_Real_ShortStr	1170
29.9.21	Tpc_Val_Real_WideStr	1170
29.9.21	Tpc_Val_SInt_AnsiStr	1170
29.9.22	Tpc_Val_SInt_ShortStr	1170
29.9.22	Tpc_Val_SInt_WideStr	1170
29.9.22	Tpc_Val_UInt_AnsiStr	1170
29.9.22	Tpc_Val_UInt_Shortstr	1171
29.9.22	Tpc_Val_UInt_WideStr	1171
29.9.22	Tpc_vararray_get	1171
29.9.22	Tpc_vararray_put	1171
29.9.22	Tpc_variant_copy	1171
29.9.22	Tpc_variant_to_dynarray	1171
29.9.22	Tpc_variant_to_interface	1172
29.9.23	Tpc_WideCharArray_To_AnsiStr	1172
29.9.23	Tpc_WideCharArray_To_ShortStr	1172
29.9.23	Tpc_WideCharArray_To_WideStr	1172
29.9.23	Tpc_WideStr_Assign	1172
29.9.23	Tpc_WideStr_CheckRange	1172
29.9.23	Tpc_WideStr_CheckZero	1172
29.9.23	Tpc_WideStr_Compare	1173
29.9.23	Tpc_WideStr_Concat	1173
29.9.23	Tpc_widestr_Copy	1173
29.9.23	Tpc_WideStr_Decr_Ref	1173
29.9.24	Tpc_WideStr_Float	1173
29.9.24	Tpc_WideStr_Incr_Ref	1173
29.9.24	Tpc_widestr_int64	1174
29.9.24	Tpc_widestr_qword	1174
29.9.24	Tpc_WideStr_SetLength	1174
29.9.24	Tpc_WideStr_sint	1174
29.9.24	Tpc_WideStr_To_AnsiStr	1174
29.9.24	Tpc_widestr_to_chararray	1174
29.9.24	Tpc_WideStr_To_ShortStr	1174
29.9.24	Tpc_widestr_to_widechararray	1175
29.9.25	Tpc_WideStr_uint	1175
29.9.25	Tpc_widestr_Unique	1175

29.9.25	<code>pc_WriteLn_End</code>	1175
29.9.25	<code>pc_Write_End</code>	1175
29.9.25	<code>pc_Write_Text_AnsiStr</code>	1175
29.9.25	<code>pc_Write_Text_Boolean</code>	1175
29.9.25	<code>pc_Write_Text_Char</code>	1176
29.9.25	<code>pc_Write_Text_Float</code>	1176
29.9.25	<code>pc_write_text_int64</code>	1176
29.9.25	<code>pc_Write_Text_Pchar_as_Array</code>	1176
29.9.26	<code>pc_Write_Text_PChar_As_Pointer</code>	1176
29.9.26	<code>pc_write_text_qword</code>	1176
29.9.26	<code>pc_Write_Text_ShortStr</code>	1177
29.9.26	<code>pc_Write_Text_SInt</code>	1177
29.9.26	<code>pc_Write_Text_UInt</code>	1177
29.9.26	<code>pc_write_text_variant</code>	1177
29.9.26	<code>pc_Write_Text_WideChar</code>	1177
29.9.26	<code>pc_Write_Text_WideStr</code>	1177
29.9.26	<code>rac</code>	1178
29.9.26	<code>Freemem</code>	1178
29.9.27	<code>Freememory</code>	1179
29.9.27	<code>FreeResource</code>	1179
29.9.27	<code>GetCurrentThreadId</code>	1179
29.9.27	<code>getdir</code>	1179
29.9.27	<code>GetFPCHeapStatus</code>	1180
29.9.27	<code>GetHeapStatus</code>	1180
29.9.27	<code>GetMem</code>	1180
29.9.27	<code>GetMemory</code>	1181
29.9.27	<code>GetMemoryManager</code>	1181
29.9.27	<code>GetProcessID</code>	1181
29.9.28	<code>GetThreadID</code>	1181
29.9.28	<code>GetThreadManager</code>	1182
29.9.28	<code>GetVariantManager</code>	1182
29.9.28	<code>GetWideStringManager</code>	1182
29.9.28	<code>get_caller_addr</code>	1182
29.9.28	<code>get_caller_frame</code>	1183
29.9.28	<code>get_frame</code>	1183
29.9.28	<code>halt</code>	1183
29.9.28	<code>hexStr</code>	1184
29.9.28	<code>hi</code>	1184
29.9.29	<code>High</code>	1185
29.9.29	<code>HINSTANCE</code>	1186

29.9.29 Inc	1186
29.9.29 Include	1187
29.9.29 IndexByte	1187
29.9.29 IndexChar	1188
29.9.29 IndexChar0	1189
29.9.29 IndexDWord	1189
29.9.29 Indexword	1190
29.9.29 InitCriticalSection	1191
29.9.30 InitThread	1191
29.9.30 InitThreadVars	1191
29.9.30 Insert	1191
29.9.30 Int	1192
29.9.30 IOResult	1193
29.9.30 IsMemoryManagerSet	1194
29.9.30 IsVariantManagerSet	1194
29.9.30 KillThread	1194
29.9.30 LeaveCriticalsection	1195
29.9.30 LEtoN	1195
29.9.31 Ln	1195
29.9.31 Lo	1196
29.9.31 LoadResource	1196
29.9.31 LockResource	1197
29.9.31 longjmp	1197
29.9.31 Low	1197
29.9.31 lowerCase	1198
29.9.31 MemSize	1198
29.9.31 nkdir	1199
29.9.31 Move	1199
29.9.32 MoveChar0	1199
29.9.32 New	1200
29.9.32 NtoBE	1200
29.9.32 NtoLE	1201
29.9.32 OctStr	1201
29.9.32 Odd	1201
29.9.32 Ofs	1202
29.9.32 operator *(variant, variant): variant	1203
29.9.32 operator **(variant, variant): variant	1203
29.9.32 operator +(variant, variant): variant	1203
29.9.33 operator -(variant): variant	1203
29.9.33 operator -(variant, variant): variant	1204

29.9.332operator /(variant, variant): variant	1204
29.9.333operator :=(ansistring): olevariant	1204
29.9.334operator :=(ansistring): variant	1204
29.9.335operator :=(Boolean): olevariant	1205
29.9.336operator :=(Boolean): variant	1205
29.9.337operator :=(Byte): olevariant	1205
29.9.338operator :=(Byte): variant	1205
29.9.339operator :=(Char): olevariant	1205
29.9.340operator :=(Char): variant	1206
29.9.341operator :=(currency): olevariant	1206
29.9.342operator :=(currency): variant	1206
29.9.343operator :=(double): olevariant	1206
29.9.344operator :=(double): variant	1206
29.9.345operator :=(DWord): olevariant	1207
29.9.346operator :=(DWord): variant	1207
29.9.347operator :=(Int64): olevariant	1207
29.9.348operator :=(Int64): variant	1207
29.9.349operator :=(longbool): olevariant	1207
29.9.350operator :=(longbool): variant	1208
29.9.351operator :=(LongInt): olevariant	1208
29.9.352operator :=(LongInt): variant	1208
29.9.353operator :=(olevariant): ansistring	1208
29.9.354operator :=(olevariant): Boolean	1209
29.9.355operator :=(olevariant): Byte	1209
29.9.356operator :=(olevariant): Char	1209
29.9.357operator :=(olevariant): currency	1209
29.9.358operator :=(olevariant): double	1209
29.9.359operator :=(olevariant): DWord	1210
29.9.360operator :=(olevariant): Int64	1210
29.9.361operator :=(olevariant): longbool	1210
29.9.362operator :=(olevariant): LongInt	1210
29.9.363operator :=(olevariant): qword	1211
29.9.364operator :=(olevariant): ShortInt	1211
29.9.365operator :=(olevariant): shortstring	1211
29.9.366operator :=(olevariant): SmallInt	1211
29.9.367operator :=(olevariant): TDateTime	1212
29.9.368operator :=(olevariant): TError	1212
29.9.369operator :=(olevariant): variant	1212
29.9.370operator :=(olevariant): widechar	1212
29.9.371operator :=(olevariant): widestring	1213

29.9.372operator :=(olevariant): Word	1213
29.9.373operator :=(olevariant): wordbool	1213
29.9.374operator :=(qword): olevariant	1213
29.9.375operator :=(qword): variant	1213
29.9.376operator :=(real48): double	1214
29.9.377operator :=(ShortInt): olevariant	1214
29.9.378operator :=(ShortInt): variant	1214
29.9.379operator :=(shortstring): olevariant	1214
29.9.380operator :=(shortstring): variant	1215
29.9.381operator :=(SmallInt): olevariant	1215
29.9.382operator :=(SmallInt): variant	1215
29.9.383operator :=(TDateTime): olevariant	1215
29.9.384operator :=(TDateTime): variant	1216
29.9.385operator :=(TError): olevariant	1216
29.9.386operator :=(TError): variant	1216
29.9.387operator :=(variant): ansistring	1216
29.9.388operator :=(variant): Boolean	1216
29.9.389operator :=(variant): Byte	1217
29.9.390operator :=(variant): Char	1217
29.9.391operator :=(variant): currency	1217
29.9.392operator :=(variant): double	1217
29.9.393operator :=(variant): DWord	1217
29.9.394operator :=(variant): Int64	1218
29.9.395operator :=(variant): longbool	1218
29.9.396operator :=(variant): LongInt	1218
29.9.397operator :=(variant): olevariant	1218
29.9.398operator :=(variant): qword	1218
29.9.399operator :=(variant): ShortInt	1219
29.9.400operator :=(variant): shortstring	1219
29.9.401operator :=(variant): SmallInt	1219
29.9.402operator :=(variant): TDateTime	1219
29.9.403operator :=(variant): TError	1220
29.9.404operator :=(variant): widechar	1220
29.9.405operator :=(variant): widestring	1220
29.9.406operator :=(variant): Word	1220
29.9.407operator :=(variant): wordbool	1220
29.9.408operator :=(widechar): olevariant	1221
29.9.409operator :=(widechar): variant	1221
29.9.410operator :=(widestring): olevariant	1221
29.9.411operator :=(widestring): variant	1221

29.9.412operator :=(Word): olevariant	1222
29.9.413operator :=(Word): variant	1222
29.9.414operator :=(wordbool): olevariant	1222
29.9.415operator :=(wordbool): variant	1222
29.9.416operator <(variant, variant): Boolean	1222
29.9.417operator <=(variant, variant): Boolean	1223
29.9.418operator =(variant, variant): Boolean	1223
29.9.419operator >(variant, variant): Boolean	1223
29.9.420operator >=(variant, variant): Boolean	1223
29.9.421operator and(variant, variant): variant	1224
29.9.422operator div(variant, variant): variant	1224
29.9.423operator mod(variant, variant): variant	1224
29.9.424operator not(variant): variant	1224
29.9.425operator or(variant, variant): variant	1225
29.9.426operator shl(variant, variant): variant	1225
29.9.427operator shr(variant, variant): variant	1225
29.9.428operator xor(variant, variant): variant	1225
29.9.429Ord	1226
29.9.430Paramcount	1226
29.9.431ParamStr	1227
29.9.432pi	1227
29.9.433Pos	1228
29.9.434Pred	1229
29.9.435prefetch	1229
29.9.436ptr	1229
29.9.437RaiseList	1230
29.9.438Random	1230
29.9.439Randomize	1231
29.9.440Read	1231
29.9.441ReadLn	1232
29.9.442Real2Double	1232
29.9.443ReAllocMem	1233
29.9.444ReAllocMemory	1233
29.9.445ReleaseExceptionObject	1234
29.9.446Rename	1234
29.9.447Reset	1234
29.9.448ResumeThread	1235
29.9.449Rewrite	1236
29.9.450mdir	1236
29.9.451round	1237

29.9.45RTLEventCreate	1238
29.9.45RTLeventdestroy	1238
29.9.45RTLeventResetEvent	1238
29.9.45RTLeventSetEvent	1238
29.9.45RTLeventStartWait	1239
29.9.45RTLeventsync	1239
29.9.45RTLeventWaitFor	1239
29.9.45RunError	1239
29.9.46Seek	1240
29.9.46SeekEOF	1241
29.9.46SeekEOLn	1241
29.9.46Seg	1242
29.9.46Setjmp	1242
29.9.46SetMemoryManager	1243
29.9.46SetMemoryMutexManager	1243
29.9.46SetNoThreadManager	1244
29.9.46SetString	1244
29.9.46SetTextBuf	1244
29.9.47SetTextLineEnding	1245
29.9.47SetThreadManager	1246
29.9.47SetVariantManager	1246
29.9.47SetWideStringManager	1246
29.9.474in	1247
29.9.47SizeOf	1247
29.9.47SizeofResource	1248
29.9.47Space	1248
29.9.47Sptr	1248
29.9.479qr	1249
29.9.480qrt	1249
29.9.48Bseg	1250
29.9.48Bstr	1250
29.9.48BstringOfChar	1251
29.9.48BstringToPPChar	1251
29.9.48BstringToWideChar	1252
29.9.486strlen	1252
29.9.487trpas	1252
29.9.488Succ	1252
29.9.48SuspendThread	1253
29.9.49Swap	1253
29.9.49SysAllocMem	1254

29.9.49	SysAssert	1254
29.9.49	SysBackTraceStr	1254
29.9.49	SysFreemem	1254
29.9.49	SysFreememSize	1255
29.9.49	SysGetFPCHeapStatus	1255
29.9.49	SysGetHeapStatus	1255
29.9.49	SysGetmem	1255
29.9.49	SysInitExceptions	1255
29.9.50	SysInitStdIO	1256
29.9.50	SysMemSize	1256
29.9.50	SysReAllocMem	1256
29.9.50	SysResetFPU	1256
29.9.50	SysTryResizeMem	1256
29.9.50	ThreadGetPriority	1257
29.9.50	ThreadSetPriority	1257
29.9.50	ThreadSwitch	1257
29.9.50	Trunc	1257
29.9.50	Truncate	1258
29.9.51	UCS4StringToWideString	1258
29.9.51	UnicodeToUtf8	1259
29.9.51	UniqueString	1259
29.9.51	UnlockResource	1259
29.9.51	UpCase	1260
29.9.51	UTF8Decode	1260
29.9.51	UTF8Encode	1260
29.9.51	Utf8ToAnsi	1261
29.9.51	Utf8ToUnicode	1261
29.9.51	Val	1261
29.9.52	VarArrayRedim	1262
29.9.52	VarCast	1262
29.9.52	WaitForThreadTerminate	1262
29.9.52	WideCharLenToString	1262
29.9.52	WideCharLenToStrVar	1263
29.9.52	WideCharToString	1263
29.9.52	WideCharToStrVar	1263
29.9.52	WideStringToUCS4String	1263
29.9.52	Write	1264
29.9.52	WriteLn	1264
29.10	IDispatch	1265
29.10.1	Description	1265

29.10.2 Method overview	1265
29.10.3 IDispatch.GetTypeInfoCount	1265
29.10.4 IDispatch.GetTypeInfo	1265
29.10.5 IDispatch.GetIDsOfNames	1265
29.10.6 IDispatch.Invoke	1266
29.11 IInvokable	1266
29.11.1 Description	1266
29.12 IUnknown	1266
29.12.1 Description	1266
29.12.2 Method overview	1266
29.12.3 IUnknown.QueryInterface	1266
29.12.4 IUnknown._AddRef	1266
29.12.5 IUnknown._Release	1267
29.13 TInterfacedObject	1267
29.13.1 Description	1267
29.13.2 Method overview	1267
29.13.3 Property overview	1267
29.13.4 TInterfacedObject.AfterConstruction	1267
29.13.5 TInterfacedObject.BeforeDestruction	1267
29.13.6 TInterfacedObject.NewInstance	1268
29.13.7 TInterfacedObject.RefCount	1268
29.14 TObject	1268
29.14.1 Description	1268
29.14.2 Method overview	1269
29.14.3 TObject.Create	1269
29.14.4 TObject.Destroy	1269
29.14.5 TObject.newInstance	1270
29.14.6 TObject.FreeInstance	1270
29.14.7 TObject.SafeCallException	1270
29.14.8 TObject.DefaultHandler	1271
29.14.9 TObject.Free	1271
29.14.10 TObject.InitInstance	1271
29.14.11 TObject.CleanupInstance	1271
29.14.12 TObject.ClassType	1272
29.14.13 TObject.ClassInfo	1272
29.14.14 TObject.ClassName	1272
29.14.15 TObject.ClassNameIs	1272
29.14.16 TObject.ClassParent	1273
29.14.17 TObject.InstanceSize	1273
29.14.18 TObject.InheritsFrom	1273

29.14.19TObject.StringMessageTable	1273
29.14.20TObject.Dispatch	1274
29.14.21TObject.DispatchStr	1274
29.14.22TObject.MethodAddress	1274
29.14.23TObject.MethodName	1274
29.14.24TObject.FieldAddress	1275
29.14.25TObject.AfterConstruction	1275
29.14.26TObject.BeforeDestruction	1275
29.14.27TObject.DefaultHandlerStr	1275
29.14.28TObject.GetInterface	1276
29.14.29TObject.GetInterfaceByStr	1276
29.14.30TObject.GetInterfaceEntry	1276
29.14.31TObject.GetInterfaceEntryByStr	1276
29.14.32TObject.GetInterfaceTable	1277
30 Reference for unit 'sysutils'	1278
30.1 Miscellaneous conversion routines	1278
30.2 Date/time routines	1278
30.3 FileName handling routines	1278
30.4 File input/output routines	1278
30.5 PChar related functions	1279
30.6 Date and time formatting characters	1281
30.7 Formatting strings	1282
30.8 String functions	1282
30.9 Used units	1282
30.10Overview	1282
30.11Constants, types and variables	1282
30.11.1 Constants	1282
30.11.2 Types	1291
30.11.3 Variables	1296
30.12Procedures and functions	1297
30.12.1 AbandonSignalHandler	1297
30.12.2 Abort	1297
30.12.3 AddDisk	1298
30.12.4 AddTerminateProc	1298
30.12.5 AdjustLineBreaks	1298
30.12.6 AnsiCompareFileName	1299
30.12.7 AnsiCompareStr	1299
30.12.8 AnsiCompareText	1300
30.12.9 AnsiExtractQuotedStr	1301

30.12.10AnsiLastChar	1302
30.12.11AnsiLowerCase	1302
30.12.12AnsiLowerCaseFileName	1303
30.12.13AnsiPos	1303
30.12.14AnsiQuotedStr	1304
30.12.15AnsiSameStr	1304
30.12.16AnsiSameText	1304
30.12.17AnsiStrComp	1304
30.12.18AnsiStrIComp	1305
30.12.19AnsiStrLastChar	1306
30.12.20AnsiStrLComp	1307
30.12.21AnsiStrLIComp	1307
30.12.22AnsiStrLower	1308
30.12.23AnsiStrPos	1309
30.12.24AnsiStrRScan	1309
30.12.25AnsiStrScan	1309
30.12.26AnsiStrUpper	1310
30.12.27AnsiUpperCase	1310
30.12.28AnsiUpperCaseFileName	1311
30.12.29AppendStr	1311
30.12.30ApplicationName	1312
30.12.31AssignStr	1312
30.12.3BCDToInt	1313
30.12.3Beep	1313
30.12.34BoolToStr	1313
30.12.35ByteToCharIndex	1314
30.12.36ByteToCharLen	1314
30.12.37ByteType	1314
30.12.38CallTerminateProcs	1314
30.12.39ChangeFileExt	1315
30.12.40CharToByteLen	1315
30.12.41CompareMem	1315
30.12.42CompareMemRange	1316
30.12.43CompareStr	1316
30.12.44CompareText	1317
30.12.45ComposeDateTime	1318
30.12.46CreateDir	1318
30.12.47CreateGUID	1319
30.12.48CurrentYear	1319
30.12.49CurrToStr	1319

30.12.50CurrToStrF	1320
30.12.51Date	1320
30.12.52DateTimeToFileDate	1320
30.12.53DateTimeToStr	1321
30.12.54DateTimeToString	1321
30.12.55DateTimeToSystemTime	1322
30.12.56DateTimeToTimeStamp	1323
30.12.57DateToStr	1323
30.12.58DayOfWeek	1324
30.12.59DecodeDate	1324
30.12.60DecodeDateFully	1325
30.12.61DecodeTime	1325
30.12.62DeleteFile	1326
30.12.63DirectoryExists	1326
30.12.64DiskFree	1327
30.12.65DiskSize	1327
30.12.66DisposeStr	1328
30.12.67DoDirSeparators	1328
30.12.68EncodeDate	1329
30.12.69EncodeTime	1329
30.12.70ExceptAddr	1330
30.12.71ExceptFrameCount	1330
30.12.72ExceptFrames	1331
30.12.73ExceptionErrorMessage	1331
30.12.74ExceptObject	1331
30.12.75ExcludeTrailingBackslash	1331
30.12.76ExcludeTrailingPathDelimiter	1332
30.12.77ExecuteProcess	1332
30.12.78ExpandFileName	1332
30.12.79ExpandUNCFileName	1333
30.12.80ExtractFileDir	1333
30.12.81ExtractFileDrive	1334
30.12.82ExtractFileExt	1334
30.12.83ExtractFileName	1334
30.12.84ExtractFilePath	1335
30.12.85ExtractRelativepath	1335
30.12.86FileAge	1336
30.12.87FileClose	1336
30.12.88FileCreate	1337
30.12.89FileDateToDateTime	1338

30.12.90	FileExists	1338
30.12.9	FileGetAttr	1339
30.12.9	FileGetDate	1340
30.12.9	FileIsReadOnly	1340
30.12.94	FileOpen	1341
30.12.9	FileRead	1341
30.12.96	FileSearch	1342
30.12.97	FileSeek	1342
30.12.98	FileSetAttr	1343
30.12.99	FileSetDate	1343
30.12.100	FileTruncate	1344
30.12.10	FileWrite	1344
30.12.103	FindClose	1344
30.12.103	FindCmdLineSwitch	1345
30.12.104	FindFirst	1345
30.12.105	FindNext	1346
30.12.106	FloatToCurr	1346
30.12.107	FloatToDateTime	1346
30.12.108	FloatToDecimal	1347
30.12.109	FloatToStr	1347
30.12.11	FloatToStrF	1348
30.12.11	FloatToText	1350
30.12.11	FloatToTextFmt	1351
30.12.11	FmtStr	1351
30.12.11	ForceDirectories	1352
30.12.11	Format	1352
30.12.11	FormatBuf	1357
30.12.11	FormatCurr	1358
30.12.11	FormatDateTime	1358
30.12.11	FormatFloat	1359
30.12.117	FreeAndNil	1360
30.12.117	GetAppConfigDir	1360
30.12.117	GetAppConfigFile	1361
30.12.117	GetCurrentDir	1361
30.12.117	GetDirs	1362
30.12.117	GetEnvironmentString	1362
30.12.117	GetEnvironmentVariable	1363
30.12.117	GetEnvironmentVariableCount	1363
30.12.117	GetFileHandle	1364
30.12.117	GetLastError	1364

30.12.130	GetLocalTime	1364
30.12.131	GetTempDir	1364
30.12.132	GetTempFileName	1365
30.12.133	GUIDToString	1365
30.12.134	HookSignal	1365
30.12.135	IncludeTrailingBackslash	1366
30.12.136	IncludeTrailingPathDelimiter	1366
30.12.137	IsMonth	1366
30.12.138	RequireSignal	1367
30.12.139	InterLockedDecrement	1367
30.12.140	InterLockedExchange	1367
30.12.141	InterLockedExchangeAdd	1367
30.12.142	InterLockedIncrement	1368
30.12.143	IntToHex	1368
30.12.144	IntToStr	1368
30.12.145	IsDelimiter	1369
30.12.146	EqualGUID	1369
30.12.147	IsLeapYear	1370
30.12.148	PathDelimiter	1370
30.12.149	ValidIdent	1370
30.12.150	LastDelimiter	1371
30.12.151	LeftStr	1372
30.12.152	LoadStr	1372
30.12.153	LowerCase	1372
30.12.154	MSecsToTimeStamp	1373
30.12.155	NewStr	1373
30.12.156	Now	1374
30.12.157	OutOfMemoryError	1374
30.12.158	QuotedStr	1375
30.12.159	RaiseLastOSError	1375
30.12.160	RemoveDir	1375
30.12.161	RenameFile	1376
30.12.162	RightStr	1376
30.12.163	SameFileName	1377
30.12.164	SameText	1377
30.12.165	SetCurrentDir	1377
30.12.166	SetDirSeparators	1378
30.12.167	ShowException	1378
30.12.168	Sleep	1378
30.12.169	Scanf	1379

30.12.17	StrAlloc	1379
30.12.17	StrBufSize	1380
30.12.17	StrByteType	1380
30.12.17	Strcat	1380
30.12.17	StrCharLength	1381
30.12.17	Strcomp	1381
30.12.17	Strcopy	1382
30.12.17	StrDispose	1382
30.12.17	Strncpy	1383
30.12.17	Strrend	1383
30.12.18	StrFmt	1384
30.12.18	Stricmp	1384
30.12.18	StringReplace	1385
30.12.18	StringToGUID	1385
30.12.18	Strlcat	1386
30.12.18	Strlcomp	1386
30.12.18	Strlcopy	1387
30.12.18	Strlen	1388
30.12.18	StrLFmt	1388
30.12.18	Strlicomp	1389
30.12.19	StrLower	1389
30.12.19	Strmove	1390
30.12.19	Strnew	1390
30.12.19	StrPas	1391
30.12.19	StrPCopy	1391
30.12.19	StrPLCopy	1391
30.12.19	Strpos	1392
30.12.19	Strrscan	1392
30.12.19	Strscan	1392
30.12.19	StrToBool	1393
30.12.20	StrToCurr	1393
30.12.20	StrToCurrDef	1393
30.12.20	StrToDate	1394
30.12.20	StrToDateTime	1394
30.12.20	StrToFloat	1395
30.12.20	StrToFloatDef	1396
30.12.20	StrToInt	1396
30.12.20	StrToInt64	1397
30.12.20	StrToInt64Def	1397
30.12.20	StrToIntDef	1398

30.12.2 StrToQWord	1398
30.12.2 StrToQWordDef	1399
30.12.2 StrToTime	1399
30.12.2 StrUpper	1399
30.12.2 Supports	1400
30.12.2 SysErrorMessage	1400
30.12.2 SystemTimeToDateTime	1400
30.12.2 TextToFloat	1401
30.12.2 Time	1402
30.12.2 TimeStampToDateTime	1402
30.12.2 TimeStampToMSecs	1403
30.12.2 TimeToStr	1403
30.12.2 Trim	1404
30.12.2 TrimLeft	1405
30.12.2 TrimRight	1405
30.12.2 TryEncodeDate	1406
30.12.2 TryEncodeTime	1406
30.12.2 TryFloatToCurr	1406
30.12.2 TryStrToCurr	1407
30.12.2 TryStrToDate	1407
30.12.2 TryStrToDateTime	1407
30.12.2 TryStrToFloat	1408
30.12.2 TryStrToInt	1408
30.12.2 TryStrToInt64	1408
30.12.2 TryStrToQWord	1409
30.12.2 TryStrToTime	1409
30.12.2 UnhookSignal	1409
30.12.2 UpperCase	1409
30.12.2 WideCompareStr	1410
30.12.2 WideCompareText	1410
30.12.2 WideFmtStr	1411
30.12.2 WideFormat	1411
30.12.2 WideFormatBuf	1411
30.12.2 WideLowerCase	1411
30.12.2 WideSameStr	1412
30.12.2 WideSameText	1412
30.12.2 WideUpperCase	1412
30.12.2 WrapText	1412
30.13 EAbort	1413
30.13.1 Description	1413

30.14EAbstractError	1413
30.14.1 Description	1413
30.15EAccessViolation	1413
30.15.1 Description	1413
30.16EAssertionFailed	1413
30.16.1 Description	1413
30.17EBusError	1413
30.17.1 Description	1413
30.18EControlC	1413
30.18.1 Description	1413
30.19EConvertError	1413
30.19.1 Description	1413
30.20EDivByZero	1414
30.20.1 Description	1414
30.21EEExternal	1414
30.21.1 Description	1414
30.22EEExternalException	1414
30.22.1 Description	1414
30.23EFormatError	1414
30.23.1 Description	1414
30.24EHeapMemoryError	1414
30.24.1 Description	1414
30.25EInOutError	1414
30.25.1 Description	1414
30.26EInterror	1414
30.26.1 Description	1414
30.27EIntfCastError	1415
30.27.1 Description	1415
30.28EIntOverflow	1415
30.28.1 Description	1415
30.29EInvalidCast	1415
30.29.1 Description	1415
30.30EInvalidContainer	1415
30.30.1 Description	1415
30.31EInvalidInsert	1415
30.31.1 Description	1415
30.32EInvalidOp	1415
30.32.1 Description	1415
30.33EInvalidPointer	1415
30.33.1 Description	1415

30.34EMathError	1416
30.34.1 Description	1416
30.35ENoThreadSupport	1416
30.35.1 Description	1416
30.36EOSError	1416
30.36.1 Description	1416
30.37EOutOfMemory	1416
30.37.1 Description	1416
30.38EOverflow	1416
30.38.1 Description	1416
30.39EPackageError	1416
30.39.1 Description	1416
30.40EPrivilege	1416
30.40.1 Description	1416
30.41EPropReadOnly	1417
30.41.1 Description	1417
30.42EPropWriteOnly	1417
30.42.1 Description	1417
30.43ERangeError	1417
30.43.1 Description	1417
30.44ESafecallException	1417
30.44.1 Description	1417
30.45EStackOverflow	1417
30.45.1 Description	1417
30.46EUnderflow	1417
30.46.1 Description	1417
30.47EVariantError	1417
30.47.1 Description	1417
30.47.2 Method overview	1417
30.47.3 EVariantError.CreateCode	1418
30.48Exception	1418
30.48.1 Description	1418
30.48.2 Method overview	1418
30.48.3 Property overview	1418
30.48.4 Exception.Create	1418
30.48.5 Exception.CreateFmt	1419
30.48.6 Exception.CreateRes	1419
30.48.7 Exception.CreateResFmt	1419
30.48.8 Exception.CreateHelp	1419
30.48.9 Exception.CreateFmtHelp	1420

30.48.1	Exception.CreateResHelp	1420
30.48.1	Exception.CreateResFmtHelp	1420
30.48.1	Exception.HelpContext	1420
30.48.1	Exception.Message	1421
30.49	EZeroDivide	1421
30.49.1	Description	1421
30.50	IReadWriteSync	1421
30.50.1	Description	1421
30.50.2	Method overview	1421
30.50.3	IReadWriteSync.BeginRead	1421
30.50.4	IReadWriteSync.EndRead	1422
30.50.5	IReadWriteSync.BeginWrite	1422
30.50.6	IReadWriteSync.EndWrite	1422
30.51	TMultiReadExclusiveWriteSynchronizer	1422
30.51.1	Description	1422
30.51.2	Method overview	1423
30.51.3	TMultiReadExclusiveWriteSynchronizer.Create	1423
30.51.4	TMultiReadExclusiveWriteSynchronizer.Destroy	1423
30.51.5	TMultiReadExclusiveWriteSynchronizer.Beginwrite	1423
30.51.6	TMultiReadExclusiveWriteSynchronizer.Endwrite	1424
30.51.7	TMultiReadExclusiveWriteSynchronizer.Beginread	1424
30.51.8	TMultiReadExclusiveWriteSynchronizer.Endread	1424
31	Reference for unit 'typinfo'	1425
31.1	Auxiliary functions	1425
31.2	Getting or setting property values	1425
31.3	Examining published property information	1425
31.4	Used units	1425
31.5	Overview	1425
31.6	Constants, types and variables	1426
31.6.1	Constants	1426
31.6.2	Types	1428
31.7	Procedures and functions	1432
31.7.1	FindPropInfo	1432
31.7.2	GetEnumName	1433
31.7.3	GetEnumNameCount	1434
31.7.4	GetEnumProp	1434
31.7.5	GetEnumValue	1435
31.7.6	GetFloatProp	1436
31.7.7	GetInt64Prop	1437

31.7.8	GetMethodProp	1437
31.7.9	GetObjectProp	1439
31.7.10	GetObjectPropClass	1440
31.7.11	GetOrdProp	1441
31.7.12	GetPropInfo	1442
31.7.13	GetPropInfos	1442
31.7.14	GetPropList	1443
31.7.15	GetPropValue	1444
31.7.16	GetSetProp	1445
31.7.17	GetStrProp	1446
31.7.18	GetTypeData	1447
31.7.19	GetVariantProp	1447
31.7.20	GetWideStrProp	1447
31.7.21	IsPublishedProp	1448
31.7.22	IsStoredProp	1449
31.7.23	PropIsType	1450
31.7.24	PropType	1450
31.7.25	SetEnumProp	1451
31.7.26	SetFloatProp	1452
31.7.27	SetInt64Prop	1452
31.7.28	SetMethodProp	1452
31.7.29	SetObjectProp	1453
31.7.30	SetOrdProp	1453
31.7.31	SetPropValue	1454
31.7.32	SetSetProp	1454
31.7.33	SetStrProp	1455
31.7.34	SetToString	1455
31.7.35	SetVariantProp	1456
31.7.36	SetWideStrProp	1456
31.7.37	StringToSet	1457
31.8	EPropertyError	1457
31.8.1	Description	1457
32	Reference for unit 'Unix'	1458
32.1	Used units	1458
32.2	Constants, types and variables	1458
32.2.1	Constants	1458
32.2.2	Types	1464
32.2.3	Variables	1471
32.3	Procedures and functions	1471

32.3.1	AssignPipe	1471
32.3.2	AssignStream	1472
32.3.3	FpExecL	1474
32.3.4	FpExecLE	1475
32.3.5	FpExecLP	1475
32.3.6	FpExecV	1476
32.3.7	FpExecVP	1477
32.3.8	FpExecVPE	1478
32.3.9	fpFlock	1479
32.3.10	fpgettimeofday	1480
32.3.11	fpSystem	1480
32.3.12	FSearch	1480
32.3.13	fStatFS	1481
32.3.14	fsync	1482
32.3.15	GetDomainName	1483
32.3.16	GetHostName	1483
32.3.17	GetLocalTimezone	1484
32.3.18	GetTimezoneFile	1484
32.3.19	PClose	1484
32.3.20	POpen	1485
32.3.21	ReadTimezoneFile	1486
32.3.22	SeekDir	1486
32.3.23	SelectText	1486
32.3.24	Shell	1487
32.3.25	SigRaise	1487
32.3.26	StatFS	1488
32.3.27	TellDir	1489
32.3.28	WaitProcess	1490
32.3.29	WIFSTOPPED	1490
32.3.30	W_EXITCODE	1490
32.3.31	W_STOPCODE	1491
33	Reference for unit 'unixtype'	1492
33.1	Overview	1492
33.2	Constants, types and variables	1492
33.2.1	Constants	1492
33.2.2	Types	1493
34	Reference for unit 'unixutil'	1504
34.1	Overview	1504
34.2	Constants, types and variables	1504

34.2.1	Types	1504
34.2.2	Variables	1504
34.3	Procedures and functions	1505
34.3.1	ArrayStringToPPchar	1505
34.3.2	Basename	1505
34.3.3	Dirname	1506
34.3.4	EpochToLocal	1506
34.3.5	FNMatch	1507
34.3.6	FSplit	1508
34.3.7	GetFS	1508
34.3.8	GregorianToJulian	1509
34.3.9	JulianToGregorian	1509
34.3.10	LocalToEpoch	1509
34.3.11	StringToPPChar	1510
35	Reference for unit 'video'	1512
35.1	Examples utility unit	1512
35.2	Writing a custom video driver	1512
35.3	Overview	1513
35.4	Constants, types and variables	1514
35.4.1	Constants	1514
35.4.2	Types	1518
35.4.3	Variables	1520
35.5	Procedures and functions	1521
35.5.1	ClearScreen	1521
35.5.2	DefaultErrorHandler	1522
35.5.3	DoneVideo	1522
35.5.4	GetCapabilities	1522
35.5.5	GetCursorType	1523
35.5.6	GetLockScreenCount	1524
35.5.7	GetVideoDriver	1525
35.5.8	GetVideoMode	1526
35.5.9	GetVideoModeCount	1526
35.5.10	GetVideoModeData	1527
35.5.11	InitVideo	1527
35.5.12	LockScreenUpdate	1528
35.5.13	SetCursorPos	1528
35.5.14	SetCursorType	1529
35.5.15	SetVideoDriver	1530
35.5.16	SetVideoMode	1530

35.5.17 UnlockScreenUpdate	1531
35.5.18 UpdateScreen	1531
36 Reference for unit 'x86'	1532
36.1 Used units	1532
36.2 Overview	1532
36.3 Procedures and functions	1532
36.3.1 fpIOperm	1532
36.3.2 fpIoPL	1533
36.3.3 ReadPort	1533
36.3.4 ReadPortB	1533
36.3.5 ReadPortL	1534
36.3.6 ReadPortW	1534
36.3.7 WritePort	1534
36.3.8 WritePortB	1535
36.3.9 WritePortl	1535
36.3.10 WritePortW	1535

About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the Free Pascal Run-Time library (RTL).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

Declaration The exact declaration of the function.

Description What does the procedure exactly do ?

Errors What errors can occur.

See Also Cross references to other related functions/commands.

0.1 Overview

The Run-Time Library is the basis of all Free Pascal programs. It contains the basic units that most programs will use, and are made available on all platforms supported by Free pascal (well, more or less).

There are units for compatibility with the Turbo Pascal Run-Time library, and there are units for compatibility with Delphi.

On top of these two sets, there are also a series of units to handle keyboard/mouse and text screens in a cross-platform way.

Other units include platform specific units that implement the specifics of a platform, these are usually needed to support the Turbo Pascal or Delphi units.

Units that fall outside the above outline do not belong in the RTL, but should be included in the packages, or in the FCL.

Chapter 1

Reference for unit 'BaseUnix'

1.1 Used units

Table 1.1: Used units by unit 'BaseUnix'

Name	Page
unixtype	1492

1.2 Overview

The `BaseUnix` unit was implemented by Marco Van de Voort. It contains basic unix functionality. It supersedes the `Linux` unit of version 1.0.X of the compiler, but does not implement all functionality of the `linux` unit.

People that have code which heavily uses the old `Linux` unit, can simply change `linux` by `oldlinux` in the `uses` clause of their projects, but they should really consider moving to the `Unix` and `BaseUnix` units.

For porting FPC to new unix-like platforms, it should be sufficient to implement the functionality in this unit for the new platform.

1.3 Constants, types and variables

1.3.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`BITSINWORD = 8 * sizeof (longint)`

Number of bits in a word.

`ESysE2BIG = 7`

System error: Argument list too long

ESysEACCES = 13

System error: Permission denied

ESysEADDRINUSE = 98

System error: Address already in use

ESysEADDRNOTAVAIL = 99

System error: Cannot assign requested address

ESysEADV = 68

System error: Advertise error

ESysEAFNOSUPPORT = 97

System error: Address family not supported by protocol

ESysEAGAIN = 11

System error: Try again

ESysEALREADY = 114

System error: Operation already in progress

ESysEBADE = 52

System error: Invalid exchange

ESysEBADF = 9

System error: Bad file number

ESysEBADFD = 77

System error: File descriptor in bad state

ESysEBADMSG = 74

System error: Not a data message

ESysEBADR = 53

System error: Invalid request descriptor

ESysEBADRQC = 56

System error: Invalid request code

ESysEBADSLT = 57

System error: Invalid slot

ESysEBFONT = 59

System error: Bad font file format

ESysEBUSY = 16

System error: Device or resource busy

ESysECHILD = 10

System error: No child processes

ESysECHRNG = 44

System error: Channel number out of range

ESysECOMM = 70

System error: Communication error on send

ESysECONNABORTED = 103

System error: Software caused connection abort

ESysECONNREFUSED = 111

System error: Connection refused

ESysECONNRESET = 104

System error: Connection reset by peer

ESysEDEADLK = 35

System error: Resource deadlock would occur

ESysEDEADLOCK = 58

System error: File locking deadlock error

ESysEDESTADDRREQ = 89

System error: Destination address required

ESysEDOM = 33

System error: Math argument out of domain of func

ESysEDOTDOT = 73

System error: RFS specific error

ESysEDQUOT = 122

System error: Quota exceeded

ESysEEXIST = 17

System error: File exists

ESysEFAULT = 14

System error: Bad address

ESysEFBIG = 27

System error: File too large

ESysEHOSTDOWN = 112

System error: Host is down

ESysEHOSTUNREACH = 113

System error: No route to host

ESysEIDRM = 43

System error: Identifier removed

ESysEILSEQ = 84

System error: Illegal byte sequence

ESysEINPROGRESS = 115

System error: Operation now in progress

ESysEINTR = 4

System error: Interrupted system call

ESysEINVAL = 22

System error: Invalid argument

ESysEIO = 5

System error: I/O error

ESysEISCONN = 106

System error: Transport endpoint is already connected

ESysEISDIR = 21

System error: Is a directory

ESysEISNAM = 120

System error: Is a named type file

ESysEL2HLT = 51

System error: Level 2 halted

ESysEL2NSYNC = 45

System error: Level 2 not synchronized

ESysEL3HLT = 46

System error: Level 3 halted

ESysEL3RST = 47

System error: Level 3 reset

ESysELIBACC = 79

System error: Can not access a needed shared library

ESysELIBBAD = 80

System error: Accessing a corrupted shared library

ESysELIBEXEC = 83

System error: Cannot exec a shared library directly

ESysELIBMAX = 82

System error: Attempting to link in too many shared libraries

ESysELIBSCN = 81

System error: .lib section in a.out corrupted

ESysELNRNG = 48

System error: Link number out of range

ESysELOOP = 40

System error: Too many symbolic links encountered

ESysEMFILE = 24

System error: Too many open files

ESysEMLINK = 31

System error: Too many links

ESysEMSGSIZE = 90

System error: Message too long

ESysEMULTIHOP = 72

System error: Multihop attempted

ESysENAMETOOLONG = 36

System error: File name too long

ESysENAVAIL = 119

System error: No XENIX semaphores available

ESysENETDOWN = 100

System error: Network is down

ESysENETRESET = 102

System error: Network dropped connection because of reset

ESysENETUNREACH = 101

System error: Network is unreachable

ESysENFILE = 23

System error: File table overflow

ESysENOANO = 55

System error: No anode

ESysENOBUFFS = 105

System error: No buffer space available

ESysENOC SI = 50

System error: No CSI structure available

ESysENODATA = 61

System error: No data available

ESysENODEV = 19

System error: No such device

ESysENOENT = 2

System error: No such file or directory

ESysENOEXEC = 8

System error: Exec format error

ESysENOLCK = 37

System error: No record locks available

ESysENOLINK = 67

System error: Link has been severed

ESysENOMEM = 12

System error: Out of memory

ESysENOMSG = 42

System error: No message of desired type

ESysENONET = 64

System error: Machine is not on the network

ESysENOPKG = 65

System error: Package not installed

ESysENOPROTOOPT = 92

System error: Protocol not available

ESysENOSPC = 28

System error: No space left on device

ESysENOSR = 63

System error: Out of streams resources

ESysENOSTR = 60

System error: Device not a stream

ESysENOSYS = 38

System error: Function not implemented

ESysENOTBLK = 15

System error: Block device required

ESysENOTCONN = 107

System error: Transport endpoint is not connected

ESysENOTDIR = 20

System error: Not a directory

ESysENOTEMPTY = 39

System error: Directory not empty

ESysENOTNAM = 118

System error: Not a XENIX named type file

ESysENOTSOCK = 88

System error: Socket operation on non-socket

ESysENOTTY = 25

System error: Not a typewriter

ESysENOTUNIQ = 76

System error: Name not unique on network

ESysENXIO = 6

System error: No such device or address

ESysEOPNOTSUPP = 95

System error: Operation not supported on transport endpoint

ESysEOVERFLOW = 75

System error: Value too large for defined data type

ESysEPERM = 1

System error: Operation not permitted.

ESysEPFNOSUPPORT = 96

System error: Protocol family not supported

ESysEPIPE = 32

System error: Broken pipe

ESysEPROTO = 71

System error: Protocol error

ESysEPROTONOSUPPORT = 93

System error: Protocol not supported

ESysEPROTOTYPE = 91

System error: Protocol wrong type for socket

ESysERANGE = 34

System error: Math result not representable

ESysEREMCHG = 78

System error: Remote address changed

ESysEREMOTE = 66

System error: Object is remote

ESysEREMOTEIO = 121

System error: Remote I/O error

ESysERESTART = 85

System error: Interrupted system call should be restarted

ESysEROFS = 30

System error: Read-only file system

ESysESHUTDOWN = 108

System error: Cannot send after transport endpoint shutdown

ESysESOCKTNOSUPPORT = 94

System error: Socket type not supported

ESysESPIPE = 29

System error: Illegal seek

ESysESRCH = 3

System error: No such process

ESysESRMNT = 69

System error: Srmount error

ESysESTALE = 116

System error: Stale NFS file handle

ESysESTRPIPE = 86

System error: Streams pipe error

ESysETIME = 62

System error: Timer expired

ESysETIMEDOUT = 110

System error: Connection timed out

ESysETOOMANYREFS = 109

System error: Too many references: cannot splice

ESysETXTBSY = 26

System error: Text (code segment) file busy

ESysEUCLEAN = 117

System error: Structure needs cleaning

ESysEUNATCH = 49

System error: Protocol driver not attached

`ESysEUSERS = 87`

System error: Too many users

`ESysEWOULDBLOCK = ESysEAGAIN`

System error: Operation would block

`ESysEXDEV = 18`

System error: Cross-device link

`ESysEXFULL = 54`

System error: Exchange full

`FD_MAXFDSET = 1024`

Maximum elements in a `TFDSet` (120) array.

`FPE_FLTDIV = 3`

Value signalling floating point divide by zero in case of `SIGFPE` signal

`FPE_FLTINV = 7`

Value signalling floating point invalid operation in case of `SIGFPE` signal

`FPE_FLTOVF = 4`

Value signalling floating point overflow in case of `SIGFPE` signal

`FPE_FLTRES = 6`

Value signalling floating point inexact result in case of `SIGFPE` signal

`FPE_FLTSUB = 8`

Value signalling floating point subscript out of range in case of `SIGFPE` signal

`FPE_FLTUND = 5`

Value signalling floating point underflow in case of `SIGFPE` signal

`FPE_INTDIV = 1`

Value signalling integer divide in case of `SIGFPE` signal

`FPE_INTOVF = 2`

Value signalling integer overflow in case of SIGFPE signal

`F_GetFd = 1`

`fpFCntl (135)` command: Get close-on-exec flag

`F_GetFl = 3`

`fpFCntl (135)` command: Get filedescriptor flags

`F_GetLk = 5`

`fpFCntl (135)` command: Get lock

`F_GetOwn = 9`

`fpFCntl (135)` command: get owner of filedescriptor events

`F_OK = 0`

`fpAccess (126)` call test: file exists.

`F_SetFd = 2`

`fpFCntl (135)` command: Set close-on-exec flag

`F_SetFl = 4`

`fpFCntl (135)` command: Set filedescriptor flags

`F_SetLk = 6`

`fpFCntl (135)` command: Set lock

`F_SetLkW = 7`

`fpFCntl (135)` command: Test lock

`F_SetOwn = 8`

`fpFCntl (135)` command: Set owner of filedescriptor events

`ln2bitmask = 1 shl ln2bitsinword - 1`

Last bit in word.

`ln2bitsinword = 5`

Power of 2 number of bits in word.

`MAP_ANONYMOUS = $20`

FpMMap (148) map type: Don't use a file

MAP_PRIVATE = 2

FpMMap (148) map type: Changes are private

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

O_APPEND = \$400

fpOpen (152) file open mode: Append to file

O_CREAT = \$40

fpOpen (152) file open mode: Create if file does not yet exist.

O_DIRECT = \$4000

fpOpen (152) file open mode: Minimize caching effects

O_DIRECTORY = \$10000

fpOpen (152) file open mode: File must be directory.

O_EXCL = \$80

fpOpen (152) file open mode: Open exclusively

O_LARGEFILE = \$8000

fpOpen (152) file open mode: Open for 64-bit I/O

O_NDELAY = O_NONBLOCK

fpOpen (152) file open mode: Alias for O_NonBlock (103)

O_NOCTTY = \$100

fpOpen (152) file open mode: No TTY control.

O_NOFOLLOW = \$20000

fpOpen (152) file open mode: Fail if file is symbolic link.

O_NONBLOCK = \$800

fpOpen (152) file open mode: Open in non-blocking mode

O_RDONLY = 0

`fpOpen (152)` file open mode: Read only

`O_RDWR = 2`

`fpOpen (152)` file open mode: Read/Write

`O_SYNC = $1000`

`fpOpen (152)` file open mode: Write to disc at once

`O_TRUNC = $200`

`fpOpen (152)` file open mode: Truncate file to length 0

`O_WRONLY = 1`

`fpOpen (152)` file open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`RLIMIT_AS = 9`

RLimit request address space limit

`RLIMIT_CORE = 4`

RLimit request max core file size

`RLIMIT_CPU = 0`

RLimit request CPU time in ms

`RLIMIT_DATA = 2`

RLimit request max data size

`RLIMIT_FSIZE = 1`

RLimit request maximum filesize

`RLIMIT_LOCKS = 10`

RLimit request maximum file locks held

`RLIMIT_MEMLOCK = 8`

RLimit request max locked-in-memory address space

`RLIMIT_NOFILE = 7`

RLimit request max number of open files

RLIMIT_NPROC = 6

RLimit request max number of processes

RLIMIT_RSS = 5

RLimit request max resident set size

RLIMIT_STACK = 3

RLimit request max stack size

R_OK = 4

fpAccess (126) call test: read allowed

SA_INTERRUPT = \$20000000

Sigaction options: ?

SA_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA_NOCLDWAIT = 2

Sigaction options: ?

SA_NOMASK = \$40000000

Sigaction options: Do not prevent the signal from being received when it is handled.

SA_ONESHOT = \$80000000

Sigaction options: Restore the signal action to the default state.

SA_ONSTACK = \$08000000

SA_ONSTACK is used in the `fp_sigaction` (163) to indicate the signal handler must be called on an alternate signal stack provided by `fp_sigaltstack` (91). If an alternate stack is not available, the default stack will be used.

SA_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA_RESTORER = \$04000000

Signal restorer handler

SA_SIGINFO = 4

Signal options: The signal handler takes 3 arguments, not one.

SEEK_CUR = 1

fpLSeek (146) option: Set position relative to current position.

SEEK_END = 2

fpLSeek (146) option: Set position relative to end of file.

SEEK_SET = 0

fpLSeek (146) option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTerm = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)

SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)

SIGUSR1 = 10

Signal: USR1 (User-defined signal 1)

SIGUSR2 = 12

Signal: USR2 (User-defined signal 2)

SIGVTALRM = 26

Signal: VTALRM (Virtual alarm clock)

SIGWINCH = 28

Signal: WINCH (Window/Terminal size change)

SIGXCPU = 24

Signal: XCPU (CPU limit exceeded)

SIGXFSZ = 25

Signal: XFSZ (File size limit exceeded)

SIG_BLOCK = 0

Sigprocmask flags: Add signals to the set of blocked signals.

SIG_DFL = 0

Signal handler: Default signal handler

`SIG_ERR = -1`

Signal handler: error

`SIG_IGN = 1`

Signal handler: Ignore signal

`SIG_MAXSIG = UnixType.SIG_MAXSIG`

Maximum system signal number.

`SIG_SETMASK = 2`

Sigprocmask flags: Set of blocked signals is given.

`SIG_UNBLOCK = 1`

Sigprocmask flags: Remove signals from the set set of blocked signals.

`SI_PAD_SIZE = ((128 div sizeof (longint)) - 3)`

Signal information pad size.

`SYS_NMLN = UnixType.SYS_NMLN`

Max system name length.

`S_IFBLK = 24576`

File (#rtl.baseunix.stat (120) record) mode: Block device

`S_IFCHR = 8192`

File (#rtl.baseunix.stat (120) record) mode: Character device

`S_IFDIR = 16384`

File (#rtl.baseunix.stat (120) record) mode: Directory

`S_IFIFO = 4096`

File (#rtl.baseunix.stat (120) record) mode: FIFO

`S_IFLNK = 40960`

File (#rtl.baseunix.stat (120) record) mode: Link

`S_IFMT = 61440`

File (#rtl.baseunix.stat (120) record) mode: File type bit mask

`S_IFREG = 32768`

File (`#rtl.baseunix.stat` (120) record) mode: Regular file

`S_IFSOCK = 49152`

File (`#rtl.baseunix.stat` (120) record) mode: Socket

`S_IRGRP = %0000100000`

Mode flag: Read by group.

`S_IROTH = %0000000100`

Mode flag: Read by others.

`S_IRUSR = %0100000000`

Mode flag: Read by owner.

`S_IRWXU = S_IRUSR or S_IWUSR or S_IXUSR`

Mode flag: Read, write, execute by user.

`S_IWGRP = %0000010000`

Mode flag: Write by group.

`S_IWOTH = %0000000010`

Mode flag: Write by others.

`S_IWUSR = %0010000000`

Mode flag: Write by owner.

`S_IXGRP = %0000001000`

Mode flag: Execute by group.

`S_IXOTH = %0000000001`

Mode flag: Execute by others.

`S_IXUSR = %0001000000`

Mode flag: Execute by owner.

`UTSNAME_DOMAIN_LENGTH = UTSNAME_LENGTH`

Max length of `utsname` (125) domain name.

UTSNAME_LENGTH = SYS_NMLN

Max length of utsname (125) system name, release, version, machine.

UTSNAME_NODENAME_LENGTH = UTSNAME_LENGTH

Max length of utsname (125) node name.

WNOHANG = 1

#rtl.baseunix.fpWaitpid (176) option: Do not wait for processes to terminate.

wordsinfdset = FD_MAXFDSET div BITSINWORD

Number of words in a TFDSet (120) array

wordsinsigset = SIG_MAXSIG div BITSINWORD

Number of words in a signal set.

WUNTRACED = 2

#rtl.baseunix.fpWaitpid (176) option: Also report children which were stopped but not yet reported

W_OK = 2

fpAccess (126) call test: write allowed

X_OK = 1

fpAccess (126) call test: execute allowed

_STAT_VER = _STAT_VER_LINUX

Stat version number

_STAT_VER_KERNEL = 1

Current version of stat record

_STAT_VER_LINUX = 3

Version of linux stat record

_STAT_VER_LINUX_OLD = 1

Old kernel definition of stat

_STAT_VER_SVR4 = 2

SVR 4 definition of stat

1.3.2 Types

`Blkcnt_t = cUInt`

Block count type.

`Blksize_t = cUInt`

Block size type.

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([1493](#))

`cDouble = UnixType.cDouble`

Double precision real format.

`cFloat = UnixType.cFloat`

Floating-point real format

`cInt = UnixType.cInt`

C type: integer (natural size)

`cInt16 = UnixType.cInt16`

C type: 16 bits sized, signed integer.

`cInt32 = UnixType.cInt32`

C type: 32 bits sized, signed integer.

`cInt64 = UnixType.cInt64`

C type: 64 bits sized, signed integer.

`cInt8 = UnixType.cInt8`

C type: 8 bits sized, signed integer.

`clDouble = UnixType.clDouble`

Long double precision real format (Extended)

`clock_t = UnixType.clock_t`

Clock ticks type

`cLong = UnixType.cLong`

C type: long signed integer (double sized)

```
cshort = UnixType.cshort
```

C type: short signed integer (half sized)

```
cuchar = UnixType.cuchar
```

Alias for #rtl.UnixType.cuchar ([1494](#))

```
cUInt = UnixType.cUInt
```

C type: unsigned integer (natural size)

```
cUInt16 = UnixType.cUInt16
```

C type: 16 bits sized, unsigned integer.

```
cUInt32 = UnixType.cUInt32
```

C type: 32 bits sized, unsigned integer.

```
cUInt64 = UnixType.cUInt64
```

C type: 64 bits sized, unsigned integer.

```
cUInt8 = UnixType.cUInt8
```

C type: 8 bits sized, unsigned integer.

```
cuLong = UnixType.cuLong
```

C type: long unsigned integer (double sized)

```
cunsigned = UnixType.cunsigned
```

Alias for #rtl.unixtype.cunsigned ([1495](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
Dir = record
  dd_fd : Integer;
  dd_loc : LongInt;
  dd_size : Integer;
  dd_buf : pDirent;
  dd_nextoff : LongInt;
  dd_max : Integer;
  dd_lock : pointer;
end
```

Record used in `fpOpenDir` (153) and `fpReadDir` (157) calls

```
Dirent = packed record
  d_fileno : ino_t;
  d_off : off_t;
  d_reclen : cushort;
  d_name : Array[0..(255+1)-1] of Char;
end
```

Record used in the `fpReadDir` (157) function to return files in a directory.

```
FLock = record
  l_type : cshort;
  l_whence : cshort;
  l_start : off_t;
  l_len : off_t;
  l_pid : pid_t;
end
```

Lock description type for `fpFCntl` (135) lock call.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
Ino64_t = cInt64
```

64-bit inode type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
iovec = record
  iov_base : pointer;
  iov_len : size_t;
end
```

`iovec` is used in `freadv` (158) for IO to multiple buffers to describe a buffer location.

```
mode_t = UnixType.mode_t
```

Inode mode type.

```
nlink_t = UnixType.nlink_t
```

Number of links type.

```
Off64_t = cInt64
```

64-bit offset type.

`off_t = UnixType.off_t`

Offset type.

`PBlkCnt = ^Blkcnt_t`

pointer to TBlkCnt (120) type.

`PBlkSize = ^Blksize_t`

Pointer to TBlkSize (120) type.

`pcchar = UnixType.pcchar`

Alias for `#rtl.UnixType.pcchar` (1496)

`pcDouble = UnixType.pcDouble`

Pointer to cdouble (112) type.

`pcFloat = UnixType.pcFloat`

Pointer to cfloat (112) type.

`pcInt = UnixType.pcInt`

Pointer to cInt (112) type.

`pclDouble = UnixType.pclDouble`

Pointer to cldouble (112) type.

`pClock = UnixType.pClock`

Pointer to TClock (120) type.

`pcLong = UnixType.pcLong`

Pointer to cLong (113) type.

`pcshort = UnixType.pcsshort`

Pointer to cShort (113) type.

`pcuchar = UnixType.pcuchar`

Alias for `#rtl.UnixType.pcuchar` (1496)

`pcUInt = UnixType.pcUInt`

Pointer to cUInt (113) type.

```
pculong = UnixType.pculong
```

Pointer to cuLong (113) type.

```
pcunsigned = UnixType.punsigned
```

Alias for #rtl.unixtype.punsigned (1497)

```
pcushort = UnixType.pcushort
```

Pointer to cuShort (113) type.

```
pDev = UnixType.pDev
```

Pointer to TDev (120) type.

```
pDir = ^Dir
```

Pointer to TDir (120) record

```
pDirent = ^Dirent
```

Pointer to TDirent (120) record.

```
pFDSet = ^TFDSet
```

Pointer to TFDSet (120) type.

```
pFilDes = ^TFilDes
```

Pointer to TFilDes (121) type.

```
pfpstate = ^tfpstate
```

Pointer to tfpstate (121) record.

```
pGid = UnixType.pGid
```

Pointer to TGid (121) type.

```
pGrpArr = ^TGrpArr
```

Pointer to TGrpArr (121) array.

```
pid_t = UnixType.pid_t
```

Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (122) type.

`PIno64 = ^Ino64_t`

Pointer to TIno64 (122) type.

`piovec = ^tiovec`

pointer to a iovec (114) record

`pMode = UnixType.pMode`

Pointer to TMode (122) type.

`pnLink = UnixType.pnLink`

Pointer to TnLink (122) type.

`pOff = UnixType.pOff`

Pointer to TOff (122) type.

`POff64 = ^Off64_t`

Pointer to TOff64 (122) type.

`pPid = UnixType.pPid`

Pointer to TPid (122) type.

`PRLimit = ^TRLimit`

Pointer to TRLimit (122) record

`psigactionrec = ^sigactionrec`

Pointer to SigActionRec (119) record type.

`PSigContext = ^TSigContext`

Pointer to #rtl.baseunix.TSigContext (123) record type.

`psiginfo = ^tsiginfo`

Pointer to #rtl.baseunix.TSigInfo (124) record type.

`psigset = ^tsigset`

Pointer to SigSet (91) type.

`pSize = UnixType.pSize`

Pointer to TSize (124) type.

`pSocklen = UnixType.pSocklen`

Pointer to TSockLen (124) type.

`psSize = UnixType.psSize`

Pointer to TsSize (124) type

`PStat = ^Stat`

Pointer to TStat (124) type.

`pthread_cond_t = UnixType.pthread_cond_t`

Thread conditional variable type.

`pthread_mutex_t = UnixType.pthread_mutex_t`

Thread mutex type.

`pthread_t = UnixType.pthread_t`

Posix thread type.

`pTime = UnixType.pTime`

Pointer to TTime (124) type.

`ptimespec = UnixType.ptimespec`

Pointer to timespec (121) type.

`ptimeval = UnixType.ptimeval`

Pointer to timeval (121) type.

`ptimezone = ^timezone`

Pointer to TimeZone (121) record.

`ptime_t = UnixType.ptime_t`

Pointer to time_t (122) type.

`PTms = ^tms`

Pointer to TTms (125) type.

`Pucontext = ^Tucontext`

Pointer to TUContext (125) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (125) type.

```
pUtimBuf = ^UtimBuf
```

Pointer to TUTimBuf (125) type.

```
PUtsName = TUtfName
```

Pointer to TUtfName (125) type.

```
rlim_t = cuLong
```

rlim_t is used as the type for the various fields in the TRLimit (122) record.

```
sigactionhandler = sigactionhandler_t
```

When installing a signal handler, the actual signal handler must be of type SigActionHandler.

```
sigactionhandler_t = procedure(signal: LongInt; info: psiginfo;  
                               context: PSigContext)
```

Standard signal action handler prototype

```
sigactionrec = record  
  sa_handler : sigactionhandler_t;  
  sa_flags : cuLong;  
  sa_restorer : sigrestorerhandler_t;  
  sa_mask : sigset_t;  
end
```

Record used in fpSigAction (163) call.

```
signalhandler = signalhandler_t
```

Simple signal handler prototype

```
signalhandler_t = procedure(signal: LongInt)
```

Standard signal handler prototype

```
sigrestorerhandler = sigrestorerhandler_t
```

Alias for sigrestorerhandler_t (120) type.

```
sigrestorerhandler_t = procedure
```

Standard signal action restorer prototype

```
sigset_t = Array[0..wordsinsigset-1] of cuLong
```

Signal set type

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
Stat = packed record
end
```

Record describing an inode (file) in the FPFstat (137) call.

```
TBlkCnt = Blkcnt_t
```

Alias for Blkcnt_t (112) type.

```
TBlkSize = Blksize_t
```

Alias for blksize_t (112) type.

```
TClock = UnixType.TClock
```

Alias for clock_t (112) type.

```
TDev = UnixType.TDev
```

Alias for dev_t (113) type.

```
TDir = Dir
```

Alias for Dir (114) type.

```
TDirent = Dirent
```

Alias for Dirent (114) type.

```
TFDSet = Array[0..(FD_MAXFDSETdivBITSINWORD)-1] of cuLong
```

File descriptor set for fpSelect (160) call.

TFileDes = Array[0..1] of cInt

Array of file descriptors as used in fpPipe (154) call.

```
tfpreg = record
  significand : Array[0..3] of Word;
  exponent : Word;
end
```

Record describing floating point register in signal handler.

```
tfpstate = record
  cw : cardinal;
  sw : cardinal;
  tag : cardinal;
  ipoff : cardinal;
  cssel : cardinal;
  dataoff : cardinal;
  datasel : cardinal;
  st : Array[0..7] of tfpreg;
  status : cardinal;
end
```

Record describing floating point unit in signal handler.

TGid = UnixType.TGid

Alias for gid_t (114) type.

TGrpArr = Array[0..0] of TGid

Array of gid_t (114) IDs

timespec = UnixType.timespec

Short time specification type.

timeval = UnixType.timeval

Time specification type.

```
timezone = packed record
  tz_minuteswest : cInt;
  tz_dsttime : cInt;
end
```

Record describing a timezone

time_t = UnixType.time_t

Time span type

```
TIno = UnixType.TIno
```

Alias for `ino_t` (114) type.

```
TIno64 = Ino64_t
```

Alias for `Ino64_t` (114) type.

```
tiovec = iovec
```

Alias for the `iovec` (114) record type.

```
TMode = UnixType.TMode
```

Alias for `mode_t` (114) type.

```
tms = packed record
  tms_utime : clock_t;
  tms_stime : clock_t;
  tms_cutime : clock_t;
  tms_cstime : clock_t;
end
```

Record containing timings for `fpTimes` (173) call.

```
TnLink = UnixType.TnLink
```

Alias for `nlink_t` (114) type.

```
TOff = UnixType.TOff
```

Alias for `off_t` (115) type.

```
TOff64 = Off64_t
```

Alias for `Ino64_t` (114) type.

```
TPid = UnixType.TPid
```

Alias for `pid_t` (116) type.

```
TRLimit = record
  rlim_cur : rlim_t;
  rlim_max : rlim_t;
end
```

`TRLimit` is the structure used by the kernel to return resource limit information in.

```
tsigactionhandler = sigactionhandler_t
```

Alias for sigactionhandler_t (119) type.

```
tsigaltstack = record
    ss_sp : pointer;
    ss_flags : LongInt;
    ss_size : LongInt;
end
```

Provide the location of an alternate signal handler stack.

```
TSigContext = record
    gs : Word;
    __gsh : Word;
    fs : Word;
    __fsh : Word;
    es : Word;
    __esh : Word;
    ds : Word;
    __dsh : Word;
    edi : cardinal;
    esi : cardinal;
    ebp : cardinal;
    esp : cardinal;
    ebx : cardinal;
    edx : cardinal;
    ecx : cardinal;
    eax : cardinal;
    trapno : cardinal;
    err : cardinal;
    eip : cardinal;
    cs : Word;
    __csh : Word;
    eflags : cardinal;
    esp_at_signal : cardinal;
    ss : Word;
    __ssh : Word;
    fpstate : pfpstate;
    oldmask : cardinal;
    cr2 : cardinal;
end
```

This type is CPU dependent. Cross-platform code should not use the contents of this record.

```
tsiginfo = record
    si_signo : LongInt;
    si_errno : LongInt;
    si_code : LongInt;
    _sifields : record
    end;
```


end

This type describes the signal that occurred.

`tsignalhandler = signalhandler_t`

Alias for `signalhandler_t` (119) type.

`tsigrestorerhandler = sigrestorerhandler_t`

Alias for `sigrestorerhandler_t` (120) type.

`tsigset = sigset_t`

Alias for `SigSet` (91) type.

`TSize = UnixType.TSize`

Alias for `size_t` (120) type

`TSocklen = UnixType.TSocklen`

Alias for `socklen_t` (120) type.

`TsSize = UnixType.TsSize`

Alias for `ssize_t` (120) type

`TStat = Stat`

Alias for `Stat` (120) type.

`tstatfs = UnixType.TStatFs`

Record describing a file system in the `baseunix.fpstatfs` (91) call.

`TTime = UnixType.TTime`

Alias for `TTime` (124) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (121) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (121) type.

`TTimeZone = timezone`

Alias for TimeZone (121) record.

```
TTms = tms
```

Alias for Tms (122) record type.

```
TUcontext = record
  uc_flags : cardinal;
  uc_link : Pucontext;
  uc_stack : tsigaltstack;
  uc_mcontext : TSigContext;
  uc_sigmask : tsigset;
end
```

This structure is used to describe the user context in a program or thread. It is not used in this unit, but is provided for completeness.

```
TUUid = UnixType.TUUid
```

Alias for uid_t (125) type.

```
TUtimBuf = UtimBuf
```

Alias for UtimBuf (125) type.

```
TUtsName = UtsName
```

Alias for UtsName (125) type.

```
uid_t = UnixType.uid_t
```

User ID type

```
UtimBuf = record
  actime : time_t;
  modtime : time_t;
end
```

Record used in fpUtime (174) to set file access and modification times.

```
UtsName = record
  Sysname : Array[0..UTSNAME_LENGTH-1] of Char;
  Nodename : Array[0..UTSNAME_NODENAME_LENGTH-1] of Char;
  Release : Array[0..UTSNAME_LENGTH-1] of Char;
  Version : Array[0..UTSNAME_LENGTH-1] of Char;
  Machine : Array[0..UTSNAME_LENGTH-1] of Char;
  Domain : Array[0..UTSNAME_DOMAIN_LENGTH-1] of Char;
end
```

The elements of this record are null-terminated C style strings, you cannot access them directly.

1.4 Procedures and functions

1.4.1 CreateShellArgV

Synopsis: Create a null-terminated array of strings from a command-line string

Declaration: `function CreateShellArgV(const prog: String) : ppchar`
`function CreateShellArgV(const prog: Ansistring) : ppchar`

Visibility: default

Description: `CreateShellArgV` creates a command-line string for executing a shell command using 'sh -c'. The result is a null-terminated array of null-terminated strings suitable for use in `fpExecv` (133) and friends.

Errors: If no more memory is available, a heap error may occur.

See also: `fpExecv` (133), `FreeShellArgV` (177)

1.4.2 FpAccess

Synopsis: Check file access

Declaration: `function FpAccess(pathname: pChar;aMode: cInt) : cInt`
`function FpAccess(pathname: AnsiString;aMode: cInt) : cInt`

Visibility: default

Description: `FpAccess` tests user's access rights on the specified file. Mode is a mask existing of one or more of the following:

R_OKUser has read rights.

W_OKUser has write rights.

X_OKUser has execute rights.

F_OKFile exists.

The test is done with the real user ID, instead of the effective user ID. If the user has the requested rights, zero is returned. If access is denied, or an error occurred, a nonzero value is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

sys_eaccessThe requested access is denied, either to the file or one of the directories in its path.

sys_einvalMode was incorrect.

sys_enoentA directory component in `Path` doesn't exist or is a dangling symbolic link.

sys_enotdirA directory component in `Path` is not a directory.

sys_enomemInsufficient kernel memory.

sys_eloop`Path` has a circular symbolic link.

See also: `FpChown` (129), `FpChmod` (128)

Listing: `./bunixex/ex26.pp`

Program Example26;

{ Program to demonstrate the Access function. }

Uses BaseUnix;

```
begin
  if fpAccess ( '/etc/passwd',W_OK)=0 then
    begin
      Writeln ( 'Better check your system. ');
      Writeln ( 'I can write to the /etc/passwd file ! ');
    end;
  end.

```

1.4.3 FpAlarm

Synopsis: Schedule an alarm signal to be delivered

Declaration: `function FpAlarm(seconds: cUInt) : cUInt`

Visibility: default

Description: `FpAlarm` schedules an alarm signal to be delivered to your process in `Seconds` seconds. When `Seconds` seconds have elapsed, the system will send a `SIGALRM` signal to the current process. If `Seconds` is zero, then no new alarm will be set. Whatever the value of `Seconds`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none. A negative value indicates an error.

See also: `fpSigAction` ([163](#)), `fpPause` ([154](#))

Listing: `./bunixex/ex59.pp`

Program Example59;

{ Program to demonstrate the Alarm function. }

Uses BaseUnix;

Procedure `AlarmHandler`(`Sig : cint`);**cdecl**;

```
begin
  Writeln ( 'Got to alarm handler ');
end;

begin
  Writeln ( 'Setting alarm handler ');
  fpSignal(SIGALRM,SignalHandler(@AlarmHandler));
  Writeln ( 'Scheduling Alarm in 10 seconds ');
  fpAlarm(10);
  Writeln ( 'Pausing ');
  fpPause;
  Writeln ( 'Pause returned ');
end.

```

1.4.4 FpChdir

Synopsis: Change current working directory.

Declaration: `function FpChdir(path: pChar) : cInt`
`function FpChdir(path: AnsiString) : cInt`

Visibility: default

Description: `fpChDir` sets the current working directory to `Path`.

It returns zero if the call was succesful, -1 on error.

Note: There exist a portable alternative to `fpChDir`: `system.chdir`. Please use `fpChDir` only if you are writing Unix specific code. `System.chdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([140](#)).

See also: `fpGetCwd` ([139](#))

1.4.5 FpChmod

Synopsis: Change file permission bits

Declaration: `function FpChmod(path: pChar;Mode: TMode) : cInt`
`function FpChmod(path: AnsiString;Mode: TMode) : cInt`

Visibility: default

Description: `fpChmod` sets the `Mode` bits of the file in `Path` to `Mode`. `Mode` can be specified by 'or'-ing the following values:

S_ISUIDSet user ID on execution.

S_ISGIDSet Group ID on execution.

S_ISVTXSet sticky bit.

S_IRUSRRead by owner.

S_IWUSRWrite by owner.

S_IXUSRExecute by owner.

S_IRGRPRead by group.

S_IWGRPWrite by group.

S_IXGRPExecute by group.

S_IROTHRead by others.

S_IWOTHWrite by others.

S_IXOTHExecute by others.

S_IRWXORead, write, execute by others.

S_IRWXGRead, write, execute by groups.

S_IRWXURead, write, execute by user.

If the function is successful, zero is returned. A nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only filesystem.

sys_eloop`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChown` (129), `fpAccess` (126)

Listing: `./bunixex/ex23.pp`

Program `Example23`;

{ Program to demonstrate the Chmod function. }

Uses `BaseUnix`, `Unix`;

Var `F` : `Text`;

begin

```
{ Create a file }
Assign (f, 'testex21');
Rewrite (F);
Writeln (f, '#!/bin/sh');
Writeln (f, 'echo Some text for this file');
Close (F);
fpChmod ('testex21', &777);
{ File is now executable }
execl ('./testex21');
```

end.

1.4.6 FpChown

Synopsis: Change owner of file

Declaration: `function FpChown(path: pChar;owner: TUid;group: TGid) : cInt`
`function FpChown(path: AnsiString;owner: TUid;group: TGid) : cInt`

Visibility: `default`

Description: `fpChown` sets the User ID and Group ID of the file in `Path` to `Owner,Group`.

The function returns zero if the call was succesfull, a nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only filesystem.

sys_eloopPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: [fpChmod \(128\)](#), [fpAccess \(126\)](#)

Listing: `./bunixex/ex24.pp`

Program Example24;

{ Program to demonstrate the Chown function. }

Uses BaseUnix;

Var UID : TUid;
GID : TGid;
F : Text;

begin

```

  Writeln ( 'This will only work if you are root.' );
  Write ( 'Enter a UID : ' ); readln (UID);
  Write ( 'Enter a GID : ' ); readln (GID);
  Assign ( f, 'test.txt' );
  Rewrite ( f );
  Writeln ( f, 'The owner of this file should become : ' );
  Writeln ( f, 'UID : ', UID );
  Writeln ( f, 'GID : ', GID );
  Close ( F );
  if fpChown ( 'test.txt', UID, GID ) <> 0 then
    if fpgeterrno = ESysEPERM then
      Writeln ( 'You are not root !' )
    else
      Writeln ( 'Chmod failed with exit code : ', fpgeterrno )
  else
    Writeln ( 'Changed owner successfully !' );
end.
```

1.4.7 FpClose

Synopsis: Close file descriptor

Declaration: `function FpClose(fd: cInt) : cInt`

Visibility: default

Description: `FpClose` closes a file with file descriptor `Fd`. The function returns zero if the file was closed successfully, a nonzero return value indicates an error.

For an example, see [FpOpen \(152\)](#).

Errors: Extended error information can be retrieved using [fpGetErrno \(140\)](#).

See also: [FpOpen \(152\)](#), [FpRead \(156\)](#), [FpWrite \(176\)](#), [FpFTruncate \(138\)](#), [FpLSeek \(146\)](#)

1.4.8 FpClosedir

Synopsis: Close directory file descriptor

Declaration: `function FpClosedir(var dirp: Dir) : cInt`

Visibility: default

Description: `FpCloseDir` closes the directory pointed to by `dirp`. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see `fpOpenDir` (153).

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpOpenDir` (153), `FpReadDir` (157)

1.4.9 FpDup

Synopsis: Duplicate a file handle

Declaration: `function FpDup(fildes: cInt) : cInt`
`function FpDup(var oldfile: text;var newfile: text) : cInt`
`function FpDup(var oldfile: file;var newfile: file) : cInt`

Visibility: default

Description: `FpDup` returns a file descriptor that is a duplicate of the file descriptor `fildes`.

The second and third forms make `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, these calls do not have the same functionality as the `dup` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns a negative value in case of an error, a positive value is a file handle, and indicates succes.

Errors: A negative value can be one of the following error codes:

sys_ebadf`OldFile` hasn't been assigned.

sys_emfileMaximum number of open files for the process is reached.

See also: `fpDup2` (132)

Listing: `./bunixex/ex31.pp`

program Example31;

{ Program to demonstrate the Dup function. }

uses baseunix;

var f : text;

begin

if `fpdup (output,f)<>0` **then**

Writeln ('Dup Failed ! ');

writeln ('This is written to stdout.');

writeln (f, 'This is written to the dup file , and flushed'); **flush**(f);

writeln

end.

1.4.10 FpDup2

Synopsis: Duplicate one filehandle to another

Declaration: `function FpDup2(fildes: cInt;fildes2: cInt) : cInt`
`function FpDup2(var oldfile: text;var newfile: text) : cInt`
`function FpDup2(var oldfile: file;var newfile: file) : cInt`

Visibility: default

Description: Makes `fildes2` or `NewFile` an exact copy of `fildes` or `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

After a call to `fdup2`, the 2 file descriptors point to the same physical device (a file, socket, or a terminal).

`NewFile` can be an assigned file. If `newfile` or `fildes` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns zero if succesful, a nonzero return value means the call failed.

Errors: In case of error, the following error codes can be reported:

sys_ebadf`OldFile` (or `fildes`) hasn't been assigned.

sys_emfileMaximum number of open files for the process is reached.

See also: `fpDup` ([131](#))

Listing: `./bunixex/ex32.pp`

```

program Example31;

{ Program to demonstrate the FpDup2 function. }

uses BaseUnix;

var f : text;
    i : longint;

begin
  Assign (f, 'text.txt');
  Rewrite (F);
  For i:=1 to 10 do writeln (F, 'Line : ',i);
  if fpdup2 (output,f)=-1 then
    writeln ('Dup2 Failed !');
  writeln ('This is written to stdout. ');
  writeln (f, 'This is written to the dup file , and flushed');
  flush(f);
  writeln ;
  { Remove file. Comment this if you want to check flushing. }
  fpUnlink ('text.txt');
end.

```

1.4.11 FpExecv

Synopsis: Execute process

Declaration: `function FpExecv(path: PChar;argv: PPChar) : cInt`
`function FpExecv(path: AnsiString;argv: PPchar) : cInt`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted `\textit{noexec}`.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecve` ([134](#)), `fpFork` ([137](#))

Listing: `./bunixex/ex8.pp`

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/lS';
 Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP,3*SizeOf(Pchar));
 PP[0]:=Arg0;
 PP[1]:=Arg1;
 PP[3]:=Nil;
{ Execute '/bin/lS -l', with current environment }
 fpExecv ('/bin/lS',pp);

end.

1.4.12 FpExecve

Synopsis: Execute process using environment

Declaration: `function FpExecve(path: PChar;argv: PPChar;envp: PPChar) : cInt`
`function FpExecve(path: AnsiString;argv: PPChar;envp: PPChar) : cInt`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`, and the environment in `envp`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. On success, `execve` does not return.

Errors: Extended error information can be retrieved with `fpGetErrno` (140), and includes the following:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted `\textit{noexec}`.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecv` (133), `fpFork` (137)

Listing: `./bunixex/ex7.pp`

Program Example7;

{ Program to demonstrate the Execve function. }

Uses BaseUnix, strings;

Const Arg0 : PChar = '/bin/l';
 Arg1 : PChar = '-l';

Var PP : PPChar;

begin

GetMem (PP, 3*SizeOf(PChar));
 PP[0] := Arg0;
 PP[1] := Arg1;
 PP[3] := Nil;
{ Execute '/bin/l -l', with current environment }
{ Env is defined in system.inc }
 fpExecVe ('/bin/l', pp, envp);

end.

1.4.13 FpExit

Synopsis: Exit the current process

Declaration: `procedure FpExit (Status: cInt)`

Visibility: default

Description: `FpExit` exits the currently running process, and report `Status` as the exit status.

Remark: If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the `Halt` call instead.

Errors: None.

See also: `FpFork` ([137](#)), `FpExecve` ([134](#))

1.4.14 FpFcntl

Synopsis: File control operations.

Declaration: `function FpFcntl (fildes: cInt; cmd: cInt) : cInt`
`function FpFcntl (fildes: cInt; cmd: cInt; arg: cInt) : cInt`
`function FpFcntl (fildes: cInt; cmd: cInt; var arg: FLock) : cInt`

Visibility: default

Description: Read/set a file's attributes. `Fildes` a valid file descriptor. `Cmd` specifies what to do, and is one of the following:

F_GetFd Read the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

F_GetFl Read the descriptor's flags.

F_GetOwn Get the Process ID of the owner of a socket.

F_SetFd Set the `close_on_exec` flag of `fildes`. (only the least significant bit is used).

F_GetLk Return the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock of there is no obstruction. `Arg` is the `flock` record.

F_SetLk Set the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

F_GetLkw Same as for **F_Setlk**, but wait until the lock is released.

F_SetOwn Set the Process or process group that owns a socket.

The function returns 0 if successful, -1 otherwise.

Errors: On error, -1 is returned. Use `fpGetErrno` ([140](#)) for extended error information.

sys_ebadf `Fd` has a bad file descriptor.

sys_eagain or **sys_eaccess** For `\textbf{F_SetLk}`, if the lock is held by another process.

1.4.15 fpfdfillset

Synopsis: Set all filedescriptors in the set.

Declaration: `function fpfdfillset(var nset: TFDSet) : cInt`

Visibility: default

Description: `fpfdfillset` sets all filedescriptors in `nset`.

See also: `FpSelect` (160), `FpFD_ZERO` (137), `FpFD_IsSet` (136), `FpFD_Clr` (136), `FpFD_Set` (136)

1.4.16 fpFD_CLR

Synopsis: Clears a filedescriptor in a set

Declaration: `function fpFD_CLR(fdno: cInt;var nset: TFDSet) : cInt`

Visibility: default

Description: `FpFD_Clr` clears file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (160).

Errors: None.

See also: `FpSelect` (160), `FpFD_ZERO` (137), `FpFD_Set` (136), `FpFD_IsSet` (136)

1.4.17 fpFD_ISSET

Synopsis: Check whether a filedescriptor is set

Declaration: `function fpFD_ISSET(fdno: cInt;const nset: TFDSet) : cInt`

Visibility: default

Description: `FpFD_Set` Checks whether file descriptor `fdNo` in filedescriptor set `fds` is set. It returns zero if the descriptor is not set, 1 if it is set. If the number of the filedescriptor it wrong, -1 is returned.

For an example, see `FpSelect` (160).

Errors: If an invald file descriptor number is passed, -1 is returned.

See also: `FpSelect` (160), `FpFD_ZERO` (137), `FpFD_Clr` (136), `FpFD_Set` (136)

1.4.18 fpFD_SET

Synopsis: Set a filedescriptor in a set

Declaration: `function fpFD_SET(fdno: cInt;var nset: TFDSet) : cInt`

Visibility: default

Description: `FpFD_Set` sets file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (160).

Errors: None.

See also: `FpSelect` (160), `FpFD_ZERO` (137), `FpFD_Clr` (136), `FpFD_IsSet` (136)

1.4.19 fpFD_ZERO

Synopsis: Clear all file descriptors in set

Declaration: `function fpFD_ZERO(var nset: TFDSet) : cInt`

Visibility: default

Description: `FpFD_ZERO` clears all the filedescriptors in the file descriptor set `nset`.

For an example, see `FpSelect` (160).

Errors: None.

See also: `FpSelect` (160), `FpFD_Clr` (136), `FpFD_Set` (136), `FpFD_IsSet` (136)

1.4.20 FpFork

Synopsis: Create child process

Declaration: `function FpFork : TPid`

Visibility: default

Description: `FpFork` creates a child process which is a copy of the parent process. `FpFork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `fpGetPPid` (142)).

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainNot enough memory to create child process.

See also: `fpExecve` (134), `#rtl.linux.Clone` (650)

1.4.21 FPFStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpFStat(fd: cInt;var sb: Stat) : cInt`
`function FPFStat(var F: Text;var Info: Stat) : Boolean`
`function FPFStat(var F: File;var Info: Stat) : Boolean`

Visibility: default

Description: `FpFStat` gets information about the file specified in one of the following:

Fda valid file descriptor.

Fan opened text file or untyped file.

and stores it in `Info`, which is of type `stat` (120). The function returns zero if the call was succesfull, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

sys_enoent`Path` does not exist.

See also: `FpStat` (168), `FpLStat` (146)

Listing: `./bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
    { Make a file }
    assign (f, 'test.fil');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil', info) <> 0 then
        begin
            writeln ('Fstat failed. Errno : ', fpgeterrno);
            halt (1);
        end;
    writeln;
    writeln ('Result of fstat on file ''test.fil''.');
    writeln ('Inode   : ', info.st_ino);
    writeln ('Mode    : ', info.st_mode);
    writeln ('nlink   : ', info.st_nlink);
    writeln ('uid     : ', info.st_uid);
    writeln ('gid     : ', info.st_gid);
    writeln ('rdev    : ', info.st_rdev);
    writeln ('Size    : ', info.st_size);
    writeln ('Blksize : ', info.st_blksize);
    writeln ('Blocks  : ', info.st_blocks);
    writeln ('atime   : ', info.st_atime);
    writeln ('mtime   : ', info.st_mtime);
    writeln ('ctime   : ', info.st_ctime);
    { Remove file }
    erase (f);
end.

```

1.4.22 FpFtruncate

Synopsis: Truncate file on certain size.

Declaration: `function FpFtruncate(fd: cInt; flength: TOff) : cInt`

Visibility: default

Description: `FpFtruncate` sets the length of a file in `fd` on `flength` bytes, where `flength` must be less than or equal to the current length of the file in `fd`.

The function returns zero if the call was successful, a nonzero return value indicates that an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` ([140](#)).

See also: `FpOpen` ([152](#)), `FpClose` ([130](#)), `FpRead` ([156](#)), `FpWrite` ([176](#)), `FpLSeek` ([146](#))

1.4.23 FpGetcwd

Synopsis: Retrieve the current working directory.

Declaration: `function FpGetcwd(path: pChar; siz: TSize) : pChar`
`function FpGetcwd : AnsiString`

Visibility: default

Description: `fpgetCWD` returns the current working directory of the running process. It is returned in `Path`, which points to a memory location of at least `siz` bytes.

If the function is succesful, a pointer to `Path` is returned, or a string with the result. On error `Nil` or an empty string are returned.

Errors: On error `Nil` or an empty string are returned.

See also: `FpGetPID` (142), `FpGetUID` (143)

1.4.24 FpGetegid

Synopsis: Return effective group ID

Declaration: `function FpGetegid : TGid`

Visibility: default

Description: `FpGetegid` returns the effective group ID of the currently running process.

Errors: None.

See also: `FpGetGid` (141), `FpGetUid` (143), `FpGetEUid` (140), `FpGetPid` (142), `FpGetPPid` (142), `fpSetUID` (163), `FpSetGid` (161)

Listing: `./bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ', fpgetgid, ' Effective group Id = ', fpgetegid);`
end.

1.4.25 FpGetEnv

Synopsis: Return value of environment variable.

Declaration: `function FpGetEnv(name: pChar) : pChar`
`function FpGetEnv(name: String) : pChar`

Visibility: default

Description: `FPGetEnv` returns the value of the environment variable in `Name`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accomodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

Errors: None.

Listing: ./bunixex/ex41.pp

```

Program Example41 ;

{ Program to demonstrate the GetEnv function . }

Uses BaseUnix ;

begin
  WriteLn ( 'Path is : ',fpGetenv( 'PATH' ) );
end .

```

1.4.26 fpgeterrno

Synopsis: Retrieve extended error information.

Declaration: `function fpgeterrno : LongInt`

Visibility: default

Description: `fpgeterrno` returns extended information on the latest error. It is set by all functions that communicate with the kernel or C library.

Errors: None.

See also: `fpseterrno` ([161](#))

1.4.27 FpGeteuid

Synopsis: Return effective user ID

Declaration: `function FpGeteuid : TUid`

Visibility: default

Description: `FpGeteuid` returns the effective user ID of the currently running process.

Errors: None.

See also: `FpGetUid` ([143](#)), `FpGetGid` ([141](#)), `FpGetEGid` ([139](#)), `FpGetPid` ([142](#)), `FpGetPPid` ([142](#)), `fpSetUID` ([163](#)), `FpSetGid` ([161](#))

Listing: ./bunixex/ex17.pp

```

Program Example17 ;

{ Program to demonstrate the GetUid and GetEUid functions . }

Uses BaseUnix ;

begin
  writeLn ( 'User Id = ',fpgetuid, ' Effective user Id = ',fpgeteuid );
end .

```

1.4.28 FpGetgid

Synopsis: Return real group ID

Declaration: `function FpGetgid : TGid`

Visibility: default

Description: `FpGetgid` returns the real group ID of the currently running process.

Errors: None.

See also: `FpGetEGid` (139), `FpGetUid` (143), `FpGetEUid` (140), `FpGetPid` (142), `FpGetPPid` (142), `fpSetUID` (163), `FpSetGid` (161)

Listing: `./bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid , ' Effective group Id = ',fpgetegid);`
end.

1.4.29 FpGetgroups

Synopsis: Get the list of supplementary groups.

Declaration: `function FpGetgroups(gidsetsize: cInt;var grouplist: TGrpArr) : cInt`

Visibility: default

Description: `FpGetgroups` returns up to `gidsetsize` groups in `GroupList`

If the function is successful, then number of groups that were stored is returned. On error, -1 is returned.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (140)

See also: `FpGetpgrp` (141), `FpGetGID` (141), `FpGetEGID` (139)

1.4.30 FpGetpgrp

Synopsis: Get process group ID

Declaration: `function FpGetpgrp : TPid`

Visibility: default

Description: `FpGetpgrp` returns the process group ID of the current process.

Errors: None.

See also: `fpGetPID` (142), `fpGetPPID` (142), `FpGetGID` (141), `FpGetUID` (143)

1.4.31 FpGetpid

Synopsis: Return current process ID

Declaration: `function FpGetpid : TPid`

Visibility: default

Description: `FpGetpid` returns the process ID of the currently running process.

Note: There exist a portable alternative to `fpGetpid`: `system.GetProcessID`. Please use `fpGetpid` only if you are writing Unix specific code. `System.GetProcessID` will work on all operating systems.

Errors: None.

See also: `FpGetPPid` ([142](#))

Listing: `./bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid , GetPPid function . }

Uses `BaseUnix;`

begin

WriteLn ('Process Id = ', `fpgetpid` , ' Parent process Id = ', `fpgetppid`);

end.

1.4.32 FpGetppid

Synopsis: Return parent process ID

Declaration: `function FpGetppid : TPid`

Visibility: default

Description: `FpGetppid` returns the Process ID of the parent process.

Errors: None.

See also: `FpGetPid` ([142](#))

Listing: `./bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid , GetPPid function . }

Uses `BaseUnix;`

begin

WriteLn ('Process Id = ', `fpgetpid` , ' Parent process Id = ', `fpgetppid`);

end.

1.4.33 fpGetPriority

Synopsis: Return process priority

Declaration: `function fpGetPriority(Which: cInt;Who: cInt) : cInt`

Visibility: default

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined Prio_Process, Prio_PGrp, Prio_User, in which case Who is the process ID, Process group ID or User ID, respectively.

For an example, see FpNice (151).

Errors: Error information is returned solely by the FpGetErrno (140) function: a priority can be a positive or negative value.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

See also: FpSetPriority (162), FpNice (151)

1.4.34 FpGetuid

Synopsis: Return current user ID

Declaration: `function FpGetuid : TUid`

Visibility: default

Description: FpGetuid returns the real user ID of the currently running process.

Errors: None.

See also: FpGetGid (141), FpGetEUid (140), FpGetEGid (139), FpGetPid (142), FpGetPPid (142), fpSetUID (163)

Listing: ./bunixex/ex17.pp

Program Example17;

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses BaseUnix;

begin

writeln ('User Id = ',fpgetuid, ' Effective user Id = ',fpgeteuid);

end.

1.4.35 FpIOctl

Synopsis: General kernel IOCTL call.

Declaration: `function FpIOctl(Handle: cInt;Ndx: cuLong;Data: Pointer) : cInt`

Visibility: default

Description: This is a general interface to the Unix/ linux ioctl call. It performs various operations on the filedescriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under linux.

Errors: Extended error information can be retrieved using `fpGetErrno` ([140](#)).

Listing: `./bunixex/ex54.pp`

Program `Example54`;

uses `BaseUnix`, `Termio`;

{ Program to demonstrate the IOCTL function. }

var

`tios` : `Termios`;

begin

{ \$ifdef FreeBSD }

`fpIOCtl(1,TIOCGETA,@tios);` *// these constants are very OS dependant.*

// see the tcgetattr example for a better way

{ \$endif }

WriteLn (`'Input Flags : $'`, `hexstr(tios.c_iflag,8)`);

WriteLn (`'Output Flags : $'`, `hexstr(tios.c_oflag,8)`);

WriteLn (`'Line Flags : $'`, `hexstr(tios.c_lflag,8)`);

WriteLn (`'Control Flags: $'`, `hexstr(tios.c_cflag,8)`);

end.

1.4.36 FpKill

Synopsis: Send a signal to a process

Declaration: `function FpKill(pid: TPid;sig: cInt) : cInt`

Visibility: `default`

Description: `fpKill` sends a signal `Sig` to a process or process group. If `Pid`>0 then the signal is sent to `Pid`, if it equals -1, then the signal is sent to all processes except process 1. If `Pid`<-1 then the signal is sent to process group -`Pid`.

The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: Extended error information can be retrieved using `fpGetErrno` ([140](#)):

sys_einvalAn invalid signal is sent.

sys_esrchThe `Pid` or process group don't exist.

sys_epermThe effective userid of the current process doesn't math the one of process `Pid`.

See also: `FpSigAction` ([163](#)), `FpSignal` ([166](#))

1.4.37 FpLink

Synopsis: Create a hard link to a file

Declaration: `function FpLink(existing: pChar;newone: pChar) : cInt`
`function FpLink(existing: AnsiString;newone: AnsiString) : cInt`

Visibility: default

Description: `fpLink` makes `NewOne` point to the same file als `Existing`. The two files then have the same inode number. This is known as a 'hard' link. The function returns zero if the call was succesfull, and returns a non-zero value if the call failed.

Errors: The following error codes are returned:

sys_exdev `Existing` and `NewOne` are not on the same filesystem.
sys_eperm The filesystem containing `Existing` and `NewOne` doesn't support linking files.
sys_eaccess Write access for the directory containing `NewOne` is disallowed, or one of the directories in `Existing` or `NewOne` has no search (=execute) permission.
sys_enoent A directory entry in `Existing` or `NewOne` does not exist or is a symbolic link pointing to a non-existent directory.
sys_enotdir A directory entry in `Existing` or `NewOne` is nor a directory.
sys_enomem Insufficient kernel memory.
sys_erofs The files are on a read-only filesystem.
sys_eexist `NewOne` already exists.
sys_mlink `Existing` has reached maximal link count.
sys_eloop `existing` or `NewOne` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.
sys_enosp The device containing `NewOne` has no room for another entry.
sys_eperm `Existing` points to `.` or `..` of a directory.

See also: `fpSymLink` (169), `fpUnLink` (174)

Listing: `./bunixex/ex21.pp`

Program `Example21`;

{ Program to demonstrate the Link and UnLink functions. }

Uses `BaseUnix`;

Var `F` : `Text`;

`S` : **String**;

begin

`Assign (F, 'test.txt');`

Rewrite (`F`);

Writeln (`F`, 'This is written to test.txt');

`Close(f);`

{ new.txt and test.txt are now the same file }

if `fpLink ('test.txt', 'new.txt') <> 0` **then**

`writeln ('Error when linking !');`

{ Removing test.txt still leaves new.txt }

If `fpUnlink ('test.txt') <> 0` **then**

`Writeln ('Error when unlinking !');`

`Assign (f, 'new.txt');`

```

Reset (F);
While not EOF(f) do
  begin
    Readln(F,S);
    Writeln ('> ',s);
  end;
Close (f);
{ Remove new.txt also }
If not FUnlink ('new.txt')<>0 then
  Writeln ('Error when unlinking !');
end.

```

1.4.38 FpLseek

Synopsis: Set file pointer position.

Declaration: `function FpLseek(fd: cInt;offset: TOff;whence: cInt) : TOff`

Visibility: default

Description: `FpLseek` sets the current fileposition of file `fd` to `Offset`, starting from `Whence`, which can be one of the following:

`Seek_SetOffset` is the absolute position in the file.

`Seek_CurOffset` is relative to the current position.

`Seek_endOffset` is relative to the end of the file.

The function returns the new fileposition, or -1 of an error occurred.

For an example, see `FpOpen` (152).

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpOpen` (152), `FpWrite` (176), `FpClose` (130), `FpRead` (156), `FpFTruncate` (138)

1.4.39 fpLstat

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function fpLstat(path: pchar;Info: PStat) : cInt`
`function fpLstat(Filename: ansistring;Info: PStat) : cInt`

Visibility: default

Description: `fpLstat` gets information about the link specified in `Path` (or `FileName`, and stores it in `Info`, which points to a record of type `TStat`. Contrary to `FpFstat` (137), it stores information about the link, not about the file the link points to. The function returns zero if the call was succesful, a nonzero return value indicates failure. failed.

Errors: Extended error information is returned by the `FpGetErrno` (140) function.

`sys_enoentPath` does not exist.

See also: `FpFStat` (137), `#rtl.unix.StatFS` (1488)

Listing: `./unixex/ex29.pp`

```

program example29;

{ Program to demonstrate the LStat function. }

uses BaseUnix, Unix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if fpstat ('test.fil', info) <> 0 then
    begin
      writeln ('Fstat failed. Errno : ', fpgeterrno);
      halt (1);
    end;
  writeln;
  writeln ('Result of stat on file ''test.fil''.');
  writeln ('Inode   : ', info.st_ino);
  writeln ('Mode    : ', info.st_mode);
  writeln ('nlink   : ', info.st_nlink);
  writeln ('uid     : ', info.st_uid);
  writeln ('gid     : ', info.st_gid);
  writeln ('rdev    : ', info.st_rdev);
  writeln ('Size    : ', info.st_size);
  writeln ('Blksize : ', info.st_blksize);
  writeln ('Blocks  : ', info.st_blocks);
  writeln ('atime   : ', info.st_atime);
  writeln ('mtime   : ', info.st_mtime);
  writeln ('ctime   : ', info.st_ctime);

  if fpSymLink ('test.fil', 'test.lnk') <> 0 then
    writeln ('Link failed ! Errno : ', fpgeterrno);

  if fplstat ('test.lnk', @info) <> 0 then
    begin
      writeln ('LStat failed. Errno : ', fpgeterrno);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.lnk''.');
  writeln ('Inode   : ', info.st_ino);
  writeln ('Mode    : ', info.st_mode);
  writeln ('nlink   : ', info.st_nlink);
  writeln ('uid     : ', info.st_uid);
  writeln ('gid     : ', info.st_gid);
  writeln ('rdev    : ', info.st_rdev);
  writeln ('Size    : ', info.st_size);
  writeln ('Blksize : ', info.st_blksize);
  writeln ('Blocks  : ', info.st_blocks);
  writeln ('atime   : ', info.st_atime);
  writeln ('mtime   : ', info.st_mtime);

```

```

writeln ( 'ctime    : ',info.st_ctime);
{ Remove file and link }
erase (f);
fpunlink ( 'test.lnk' );
end.

```

1.4.40 FpMkdir

Synopsis: Create a new directory

Declaration: `function FpMkdir(path: pChar;Mode: TMode) : cInt`
`function FpMkdir(path: AnsiString;Mode: TMode) : cInt`

Visibility: default

Description: `FpMkDir` creates a new directory `Path`, and sets the new directory's mode to `Mode`. `Path` can be an absolute path or a relative path. Note that only the last element of the directory will be created, higher level directories must already exist, and must be writeable by the current user.

On succes, 0 is returned. if the function fails, -1 is returned.

Note: There exist a portable alternative to `fpMkDir`: `system.mkdir`. Please use `fpMkDir` only if you are writing Unix specific code. `System.mkdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([140](#)).

See also: `fpGetCWD` ([139](#)), `fpChDir` ([128](#))

1.4.41 FpMkfifo

Synopsis: Create FIFO (named pipe) in file system

Declaration: `function FpMkfifo(path: pChar;Mode: TMode) : cInt`
`function FpMkfifo(path: AnsiString;Mode: TMode) : cInt`

Visibility: default

Description: `fpMkFifo` creates named a named pipe in the filesystem, with name `Path` and mode `Mode`.

The function returns zero if the command was succesful, and nonzero if it failed.

Errors: The error codes include:

sys_emfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

1.4.42 Fpmmmap

Synopsis: Create memory map of a file

Declaration: `function Fpmmmap(start: pointer;len: size_t;prot: cInt;flags: cInt;`
`fd: cInt;offst: off_t) : pointer`

Visibility: default

Description: `FpMMap` maps or unmaps files or devices into memory. The different arguments determine what and how the file is mapped:

adrAddress where to mmap the device. This address is a hint, and may not be followed.

lenSize (in bytes) of area to be mapped.

protProtection of mapped memory. This is a OR-ed combination of the following constants:

PROT_EXECThe memory can be executed.

PROT_READThe memory can be read.

PROT_WRITEThe memory can be written.

PROT_NONEThe memory can not be accessed.

flagsContains some options for the mmap call. It is an OR-ed combination of the following constants:

MAP_FIXEDDo not map at another address than the given address. If the address cannot be used, `mmap` will fail.

MAP_SHAREDShare this map with other processes that map this object.

MAP_PRIVATECreate a private map with copy-on-write semantics.

MAP_ANONYMOUS`fd` does not have to be a file descriptor.

One of the options `MAP_SHARED` and `MAP_PRIVATE` must be present, but not both at the same time.

fdFile descriptor from which to map.

offOffset to be used in file descriptor `fd`.

The function returns a pointer to the mapped memory, or a -1 in case of an error.

Errors: On error, -1 is returned and extended error information is returned by the `FpGetErrno` (140) function.

Sys_EBADF`fd` is not a valid file descriptor and `MAP_ANONYMOUS` was not specified.

Sys_EACCES`MAP_PRIVATE` was specified, but `fd` is not open for reading. Or `MAP_SHARED` was asked and `PROT_WRITE` is set, `fd` is not open for writing

Sys_EINVALOne of the record fields `Start`, `length` or `offset` is invalid.

Sys_ETXTBUSY`MAP_DENYWRITE` was set but the object specified by `fd` is open for writing.

Sys_EAGAIN`fd` is locked, or too much memory is locked.

Sys_ENOMEMNot enough memory for this operation.

See also: `FpMUnMap` (150)

Listing: ./unixex/ex66.pp

Program Example66;

{ Program to demonstrate the MMap function. }

Uses BaseUnix, Unix;

Var S : String;

fd : cint;

Len : longint;

// args : tmmmapargs;

P : PChar;

begin

s:= 'This is the string';

Len:=Length(S);

fd:=fpOpen('testfile.txt',O_wrOnly or o_creat);

If fd=-1 then

```

    Halt(1);
    If fpWrite(fd,S[1],Len)=-1 then
        Halt(2);
    fpClose(fd);
    fd:=fpOpen('testfile.txt',O_rdOnly);
    if fd=-1 then
        Halt(3);
    P:=Pchar(fpmmap(nil, len+1, PROT_READ or PROT_WRITE, MAP_PRIVATE, fd, 0));

    If longint(P)=-1 then
        Halt(4);
    WriteLn('Read in memory :',P);
    fpclose(fd);
    if fpMUnMap(P, Len)<>0 Then
        Halt(fpgeterrno);
end.

```

1.4.43 Fpmunmap

Synopsis: Unmap previously mapped memory block

Declaration: `function Fpmunmap(start: pointer; len: size_t) : cInt`

Visibility: default

Description: `FpMUnMap` unmaps the memory block of size `Len`, pointed to by `Adr`, which was previously allocated with `FpMMap` (148).

The function returns `True` if successful, `False` otherwise.

For an example, see `FpMMap` (148).

Errors: In case of error the function returns a nonzero value, extended error information is returned by the `FpGetErrno` (140) function. See `FpMMap` (148) for possible error values.

See also: `FpMMap` (148)

1.4.44 FpNanoSleep

Synopsis: Suspend process for a short time

Declaration: `function FpNanoSleep(req: ptimespec; rem: ptimespec) : cInt`

Visibility: default

Description: `FpNanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be -1, and `LinuxError` will be set to `EINTR`

If the function returns without error, the return value is zero.

Errors: If an error occurred or the call was interrupted, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpPause` (154), `FpAlarm` (127)

Listing: `./bunixex/ex72.pp`

```

program example72;

{ Program to demonstrate the NanoSleep function. }

uses BaseUnix;

Var
  Req, Rem : TimeSpec;
  Res : Longint;

begin
  With Req do
    begin
      tv_sec:=10;
      tv_nsec:=100;
    end;
  Write( 'NanoSleep returned : ');
  Flush( Output );
  Res:=( fpNanoSleep (@Req,@rem));
  WriteLn( res );
  If ( res<>0) then
    With rem do
      begin
        WriteLn( 'Remaining seconds      : ',tv_sec);
        WriteLn( 'Remaining nanoseconds : ',tv_nsec);
      end;
end.

```

1.4.45 fpNice

Synopsis: Set process priority

Declaration: `function fpNice(N: cInt) : cInt`

Visibility: default

Description: `Nice` adds `-N` to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative `N`, i.e. increase the rate at which the process is run.

If the function is succesful, zero is returned. On error, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` ([140](#)) function.

sys_epermA non-superuser tried to specify a negative `N`, i.e. do a priority increase.

See also: `FpGetPriority` ([143](#)), `FpSetPriority` ([162](#))

Listing: `./unixex/ex15.pp`

```

Program Example15;

{ Program to demonstrate the Nice and Get/SetPriority functions. }

Uses BaseUnix, Unix;

begin

```

```

writeln ( 'Setting priority to 5 ');
fpsetpriority (prio_process,fpgetpid,5);
writeln ( 'New priority = ',fpgetpriority (prio_process,fpgetpid));
writeln ( 'Doing nice 10 ');
fpnice (10);
writeln ( 'New Priority = ',fpgetpriority (prio_process,fpgetpid));
end.

```

1.4.46 FpOpen

Synopsis: Open file and return file descriptor

Declaration: function FpOpen(path: PChar;flags: cInt;Mode: TMode) : cInt
 function FpOpen(path: PChar;flags: cInt) : cInt
 function FpOpen(path: AnsiString;flags: cInt) : cInt
 function FpOpen(path: AnsiString;flags: cInt;Mode: TMode) : cInt
 function FpOpen(path: String;flags: cInt) : cInt
 function FpOpen(path: String;flags: cInt;Mode: TMode) : cInt

Visibility: default

Description: FpOpen opens a file in Path with flags flags and mode Mode One of the following:

O_RdOnlyFile is opened Read-only

O_WrOnlyFile is opened Write-only

O_RdWrFile is opened Read-Write

The flags may beOR-ed with one of the following constants:

O_CreatFile is created if it doesn't exist.

O_ExclIf the file is opened with **O_Creat** and it already exists, the call wil fail.

O_NoCttyIf the file is a terminal device, it will NOT become the process' controlling terminal.

O_TruncIf the file exists, it will be truncated.

O_Appendthe file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

O_NonBlockThe file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

O_NDelayIdem as **O_NonBlock**

O_SyncThe file is opened for synchronous IO. Any write operation on the file will not return untill the data is physically written to disk.

O_NoFollowif the file is a symbolic link, the open fails. (linux 2.1.126 and higher only)

O_Directoryif the file is not a directory, the open fails. (linux 2.1.126 and higher only)

Path can be of type PChar or String. The optional mode argument specifies the permissions to set when opening the file. This is modified by the umask setting. The real permissions are Mode and not umask. The return value of the function is the filedescriptor, or a negative value if there was an error.

Errors: Extended error information can be retrieved using fpGetErrno (140).

See also: FpClose (130), FpRead (156), FpWrite (176), FpFTruncate (138), FpLSeek (146)

Listing: ./bunixex/ex19.pp

Program Example19;

{ Program to demonstrate the fdOpen, fdwrite and fdCLose functions. }

Uses BaseUnix;

Const Line : **String**[80] = 'This is easy writing !';

Var FD : CInt;

begin

FD:=fpOpen ('Test.dat',O_WrOnly or O_Creat);

if FD>0 **then**

begin

if **length**(Line)<>fpwrite (FD,Line[1],**Length**(Line)) **then**

WriteLn ('Error when writing to file !');

fpClose(FD);

end;

end.

1.4.47 FpOpendir

Synopsis: Open a directory for reading

Declaration: function FpOpendir(dirname: pChar) : pDir
 function FpOpendir(dirname: AnsiString) : pDir
 function FpOpendir(dirname: shortString) : pDir

Visibility: default

Description: FpOpenDir opens the directory DirName, and returns a pdir pointer to a Dir ([114](#)) record, which can be used to read the directory structure. If the directory cannot be opened, nil is returned.

Errors: Extended error information can be retrieved using fpGetErrno ([140](#)).

See also: FpCloseDir ([130](#)), FpReadDir ([157](#))

Listing: ./bunixex/ex35.pp

Program Example35;

*{ Program to demonstrate the
 OpenDir, ReadDir, SeekDir and TellDir functions. }*

Uses BaseUnix;

Var TheDir : PDir;
 ADirent : PDirent;
 Entry : Longint;

begin

TheDir:=fpOpenDir('./. ');

Repeat

// Entry:=fpTellDir (TheDir);

ADirent:=fpReadDir (TheDir^);

If ADirent<>Nil **then**

```

    With ADirent^ do
    begin
        Writeln ( 'Entry No : ', Entry );
        Writeln ( 'Inode   : ', d_fileno );
        //      Writeln ( 'Offset  : ', d_off );
        Writeln ( 'Reclen   : ', d_reclen );
        Writeln ( 'Name     : ', pchar(@d_name[0]));
    end;
    Until ADirent=Nil;
    Repeat
        Write ( 'Entry No. you would like to see again (-1 to stop): ');
        ReadLn ( Entry );
        If Entry <> -1 then
        begin
            //      fpSeekDir ( TheDir, Entry );           // not implemented for various platforms
            ADirent:=fpReadDir ( TheDir^ );
            If ADirent <> Nil then
            With ADirent^ do
            begin
                Writeln ( 'Entry No : ', Entry );
                Writeln ( 'Inode     : ', d_fileno );
                //      Writeln ( 'Offset  : ', d_off );
                Writeln ( 'Reclen    : ', d_reclen );
                Writeln ( 'Name      : ', pchar(@d_name[0]));
            end;
        end;
    Until Entry=-1;
    fpCloseDir ( TheDir^ );
end.

```

1.4.48 FpPause

Synopsis: Wait for a signal to arrive

Declaration: `function FpPause : cInt`

Visibility: default

Description: `FpPause` puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

For an example, see `fpAlarm` ([127](#)).

1.4.49 FpPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function FpPipe(var fildes: TFilDes) : cInt`

Visibility: default

Description: `FpPipe` creates a pipe, i.e. two file objects, one for input, one for output. The filehandles are returned in the array `fildes`. The input handle is in the 0-th element of the array, the output handle is in the 1-st element.

The function returns zero if everything went successfully, a nonzero return value indicates an error.

Errors: In case the function fails, the following return values are possible:

sys_emfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

See also: #rtl.unix.POpen (1485), fpMkFifo (148)

Listing: ./bunixex/ex36.pp

Program Example36 ;

```
{ Program to demonstrate the AssignPipe function. }
```

Uses BaseUnix , Unix ;

```
Var pipi ,pipo : Text;  
    s : String;
```

```
begin
  Writeln ( 'Assigning Pipes.' );
  If assignpipe (pipi , pipo) <> 0 then
    Writeln ( 'Error assigning pipes ! ', fpgeterrno );
  Writeln ( 'Writing to pipe , and flushing.' );
  Writeln ( pipo , 'This is a textstring' ); close (pipo);
  Writeln ( 'Reading from pipe.' );
  While not eof (pipi) do
    begin
      Readln ( pipi , s );
      Writeln ( 'Read from pipe : ', s );
    end;
  close ( pipi );
  writeln ( 'Closed pipes.' );
  writeln
end.
```

1.4.50 FppRead

Synopsis: Positional read: read from file descriptor at a certain position.

```
Declaration: function FpPRead(fd: cInt;buf: pChar;nbytes: TSize;offset: TOff)
              : TsSize
              function FppRead(fd: cInt;var buf;nbytes: TSize;offset: TOff) : TsSize
```

Visibility: default

Description: `FpPRead` reads `nbytes` bytes from file descriptor `fd` into buffer `buf` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually read, or -1 on error.

Errors: On error, -1 is returned.

See also: [FpReadV \(158\)](#), [FpPWrite \(155\)](#)

1.4.51 FppWrite

Synopsis: Positional write: write to file descriptor at a certain position.

Declaration: `function FppWrite(fd: cInt;buf: pChar;nbytes: TSize;offset: TOff) : TsSize`
`function FppWrite(fd: cInt;const buf;nbytes: TSize;offset: TOff) : TsSize`

Visibility: default

Description: `FppWrite` writes `nbytes` bytes from buffer `buf` into file descriptor `fd` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually written, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpPRead` (155), `FpWriteV` (177)

1.4.52 FpRead

Synopsis: Read data from file descriptor

Declaration: `function FpRead(fd: cInt;buf: pChar;nbytes: TSize) : TsSize`
`function FpRead(fd: cInt;var buf;nbytes: TSize) : TsSize`

Visibility: default

Description: `FpdRead` reads at most `nbytes` bytes from the file descriptor `fd`, and stores them in `buf`.

The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of `buf` is done.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpOpen` (152), `FpClose` (130), `FpWrite` (176), `FpFTruncate` (138), `FpLSeek` (146)

Listing: `./bunixex/ex20.pp`

Program `Example20`;

{ Program to demonstrate the fdRead and fdTruncate functions. }

Uses `BaseUnix`;

Const `Data : string[10] = '1234567890'`;

Var `FD : cint`;
`l : longint`;

begin

```
FD:=fpOpen('test.dat',o_wronly or o_creat,&666);
if fd>0 then
  begin
    { Fill file with data }
    for l:=1 to 10 do
      if fpWrite (FD,Data[l],10)<>10 then
        begin
          writeln ('Error when writing !');
```

```

        halt(1);
    end;
    fpClose(FD);
    FD:=fpOpen('test.dat',o_rdonly);
    { Read data again }
    If FD>0 then
    begin
        For l:=1 to 5 do
            if fpRead (FD,Data[1],10)<>10 then
            begin
                WriteLn ('Error when Reading !');
                Halt(2);
            end;
            fpClose(FD);
            { Truncating file at 60 bytes }
            { For truncating , file must be open or write }
            FD:=fpOpen('test.dat',o_wronly,&666);
            if FD>0 then
            begin
                if fpfTruncate(FD,60)<>0 then
                    WriteLn('Error when truncating !');
                fpClose (FD);
            end;
        end;
    end;
end.

```

1.4.53 FpReaddir

Synopsis: Read entry from directory

Declaration: `function FpReaddir(var dirp: Dir) : pDirent`

Visibility: default

Description: `FpReadDir` reads the next entry in the directory pointed to by `dirp`. It returns a `pdirent` pointer to a `dirent` (114) record describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `FpOpenDir` (153).

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpCloseDir` (130), `FpOpenDir` (153)

1.4.54 fpReadLink

Synopsis: Read destination of symbolic link

Declaration: `function fpReadLink(name: pchar;linkname: pchar;maxlen: size_t) : cInt`
`function fpReadLink(Name: ansistring) : ansistring`

Visibility: default

Description: `FpReadLink` returns the file the symbolic link name is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. Extended error information is returned by the `FpGetErrno` (140) function.

SYS_ENOTDIRA part of the path in `Name` is not a directory.

SYS_EINVAL`maxlen` is not positive, or the file is not a symbolic link.

SYS_ENAMETOOLONGA `pathname`, or a component of a `pathname`, was too long.

SYS_ENOENTthe link `name` does not exist.

SYS_EACCESNo permission to search a directory in the path

SYS_ELOOPToo many symbolic links were encountered in translating the `pathname`.

SYS_EIOAn I/O error occurred while reading from the file system.

SYS_EFAULTThe buffer is not part of the process's memory space.

SYS_ENOMEMNot enough kernel memory was available.

See also: `FpSymLink` (169)

Listing: `./unixex/ex62.pp`

Program `Example62`;

{ Program to demonstrate the ReadLink function. }

Uses `BaseUnix, Unix`;

Var `F : Text;`
 `S : String;`

```
begin
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'This is written to test.txt');
  Close(f);
  { new.txt and test.txt are now the same file }
  if fpSymLink ('test.txt', 'new.txt') <> 0 then
    writeln ('Error when symlinking !');
  S:=fpReadLink('new.txt');
  if S='' then
    Writeln ('Error reading link !')
  Else
    Writeln ('Link points to : ',S);
  { Now remove links }
  if fpUnlink ('new.txt') <> 0 then
    Writeln ('Error when unlinking !');
  if fpUnlink ('test.txt') <> 0 then
    Writeln ('Error when unlinking !');
end.
```

1.4.55 FpReadV

Synopsis: Vector read: Read into multiple buffers

Declaration: `function FpReadV(fd: cInt; const iov: piovec; iovcnt: cInt) : TsSize`

Visibility: default

Description: `FpReadV` reads data from file descriptor `fd` and writes it into `iovcnt` buffers described by the `tiovec` (122) buffers pointed to by `iov`. It works like `fpRead` (156) only on multiple buffers.

Errors: On error, -1 is returned.

See also: `FpWriteV` (177), `FpPWrite` (155), `FpPRead` (155)

1.4.56 FpRename

Synopsis: Rename file

Declaration: `function FpRename(old: pChar; newpath: pChar) : cInt`
`function FpRename(old: AnsiString; newpath: AnsiString) : cInt`

Visibility: default

Description: `FpRename` renames the file `Old` to `NewPath`. `NewPath` can be in a different directory than `Old`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `Old` file will be preserved.

The function returns zero on success, a nonzero value indicates failure.

Note: There exist a portable alternative to `fpRename`: `system.rename`. Please use `fpRename` only if you are writing Unix specific code. `System.rename` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

sys_eisdir `NewPath` exists and is a directory, but `Old` is not a directory.

sys_exdev `NewPath` and `Old` are on different devices.

sys_enotempty or sys_eexist `NewPath` is an existing, non-empty directory.

sys_ebusy `Old` or `NewPath` is a directory and is in use by another process.

sys_einval `NewPath` is part of `Old`.

sys_emlink `OldPath` or `NewPath` already have the maximum amount of links pointing to them.

sys_enotdir part of `Old` or `NewPath` is not directory.

sys_efault For the `pchar` case: One of the pointers points to an invalid address.

sys_eaccess access is denied when attempting to move the file.

sys_enametoolong Either `Old` or `NewPath` is too long.

sys_enoent a directory component in `Old` or `NewPath` didn't exist.

sys_enomem not enough kernel memory.

sys_erofs `NewPath` or `Old` is on a read-only file system.

sys_eloop too many symbolic links were encountered trying to expand `Old` or `NewPath`

sys_enosp the filesystem has no room for the new directory entry.

See also: `FpUnLink` (174)

1.4.57 FpRmdir

Synopsis: Remove a directory.

Declaration: `function FpRmdir(path: pChar) : cInt`
`function FpRmdir(path: AnsiString) : cInt`

Visibility: default

Description: `FpRmdir` removes the directory `Path` from the system. The directory must be empty for this call to succeed, and the user must have the necessary permissions in the parent directory. Only the last component of the directory is removed, i.e. higher-lying directories are not removed.

On success, zero is returned. A nonzero return value indicates failure.

Note: There exist a portable alternative to `fpRmdir`: `system.rmdir`. Please use `fpRmdir` only if you are writing Unix specific code. `System.rmdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

1.4.58 fpSelect

Synopsis: Wait for events on file descriptors

Declaration: `function FPSelect(N: cInt; readfds: pFDSet; writefds: pFDSet;`
`exceptfds: pFDSet; Timeout: ptimeval) : cInt`
`function fpSelect(N: cInt; readfds: pFDSet; writefds: pFDSet;`
`exceptfds: pFDSet; Timeout: cInt) : cInt`
`function fpSelect(var T: Text; Timeout: ptimeval) : cInt`
`function fpSelect(var T: Text; Timeout: time_t) : cInt`

Visibility: default

Description: `FpSelect` checks one of the file descriptors in the `FDSets` to see if its status changed.

`readfds`, `writefds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if characters become available for reading. The entries in `writefds` are checked to see if it is OK to write to them, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions `fpFD_ZERO` (137), `fpFD_Clr` (136), `fpFD_Set` (136) or `fpFD_IsSet` (136) to manipulate the individual elements of a set.

The pointers can be `Nil`.

`N` is the largest index of a nonzero entry plus 1. (= the largest file-descriptor + 1).

`Timeout` can be used to set a time limit. If `Timeout` can be two types :

1. `Timeout` is of type `ptimeval` and contains a zero time, the call returns immediately. If `Timeout` is `Nil`, the kernel will wait forever, or until a status changed.
2. `Timeout` is of type `cint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `Timeout` contains a time in milliseconds.

When the `Timeout` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

The variant with the text file will execute the `FpSelect` call on the file descriptor associated with the text file `T`

Errors: On error, the function returns -1. Extended error information can be retrieved using `fpGetErrno` (140).

SYS_EBADFAn invalid descriptor was specified in one of the sets.

SYS_EINTRA non blocked signal was caught.

SYS_EINVALN is negative or too big.

SYS_ENOMEM`Select` was unable to allocate memory for its internal tables.

See also: `fpFD_ZERO` (137), `fpFD_Clr` (136), `fpFD_Set` (136), `fpFD_IsSet` (136)

Listing: `./bunixex/ex33.pp`

Program `Example33`;

{ Program to demonstrate the Select function. }

Uses `BaseUnix`;

Var `FDS : Tfdset`;

begin

`fpfd_zero(FDS);`

`fpfd_set(0,FDS);`

Writeln ('Press the <ENTER> to continue the program.');

{ Wait until File descriptor 0 (=Input) changes }

`fpSelect (1,@FDS,nil,nil,nil);`

{ Get rid of <ENTER> in buffer }

readln;

Writeln ('Press <ENTER> key in less than 2 seconds...');

`Fpfd_zero(FDS);`

`FpFd_set (0,FDS);`

if `fpSelect (1,@FDS,nil,nil,2000)>0` **then**

Writeln ('Thank you !')

{ FD_ISSET(0,FDS) would be true here. }

else

Writeln ('Too late !');

end.

1.4.59 `fpseterrno`

Synopsis: Set extended error information.

Declaration: `procedure fpseterrno(err: LongInt)`

Visibility: default

Description: `fpseterrno` sets the extended information on the latest error. It is called by all functions that communicate with the kernel or C library.

Unless a direct kernel call is performed, there should never be any need to call this function.

Errors:

See also: `fpgeterrno` (140)

1.4.60 FpSetgid

Synopsis: Set the current group ID

Declaration: `function FpSetgid(gid: TGid) : cInt`

Visibility: default

Description: `fpSetUID` sets the group ID of the current process. This call will only work if it is executed as root, or the program is `setgid` root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` (140).

See also: `FpSetUid` (163), `FpGetGid` (141), `FpGetUid` (143), `FpGetEUid` (140), `FpGetEGid` (139), `FpGetPid` (142), `FpGetPPid` (142)

1.4.61 fpSetPriority

Synopsis: Set process priority

Declaration: `function fpSetPriority(Which: cInt;Who: cInt;What: cInt) : cInt`

Visibility: default

Description: `fpSetPriority` sets the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. `Which` can be one of the pre-defined constants:

Prio_Process`Who` is interpreted as process ID

Prio_PGrp`Who` is interpreted as process group ID

Prio_User`Who` is interpreted as user ID

`Prio` is a value in the range -20 to 20.

For an example, see `FpNice` (151).

The function returns zero on success, -1 on failure

Errors: Extended error information is returned by the `FpGetErrno` (140) function.

sys_esrchNo process found using `which` and `who`.

sys_einval`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

sys_epermA process was found, but neither its effective or real user ID match the effective user ID of the caller.

sys_eaccessA non-superuser tried to a priority increase.

See also: `FpGetPriority` (143), `FpNice` (151)

1.4.62 FpSetsid

Synopsis: Create a new session.

Declaration: `function FpSetsid : TPid`

Visibility: default

Description: `FpSetsid` creates a new session (process group). It returns the new process group id (as returned by `FpGetpgrp` (141)). This call will fail if the current process is already the process group leader.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (140)

1.4.63 fpsettimeofday

Synopsis: Set kernel time

Declaration: `function fpsettimeofday(tp: ptimeval; tzp: ptimezone) : cInt`

Visibility: default

Description: `FpSetTimeOfDay` sets the kernel time to the number of seconds since 00:00, January 1 1970, GMT specified in the `tp` record. This time NOT corrected any way, not taking into account time-zones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

See also: `#rtl.unix.FPGetTimeOfDay` ([1480](#))

1.4.64 FpSetuid

Synopsis: Set the current user ID

Declaration: `function FpSetuid(uid: TUid) : cInt`

Visibility: default

Description: `fpSetUID` sets the user ID of the current process. This call will only work if it is executed as root, or the program is `setuid` root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` ([140](#)).

See also: `FpGetGid` ([141](#)), `FpGetUid` ([143](#)), `FpGetEUid` ([140](#)), `FpGetEGid` ([139](#)), `FpGetPid` ([142](#)), `FpGetPPid` ([142](#)), `FpSetGid` ([161](#))

1.4.65 FPSigaction

Synopsis: Install signal handler

Declaration: `function FPSigaction(sig: cInt; act: psigactionrec; oact: psigactionrec) : cInt`

Visibility: default

Description: `FPSigaction` changes the action to take upon receipt of a signal. `Act` and `Oact` are pointers to a `SigActionRec` ([119](#)) record. `Sig` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `Sig` is taken from it. If `Oact` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

SA_NOCLDSTOP If `sig` is **SIGCHLD** do not receive notification when child processes stop.

SA_ONESHOT or **SA_RESETHAND** Restore the signal action to the default state once the signal handler has been called.

SA_RESTART For compatibility with BSD signals.

SA_NOMASK or **SA_NODEFER** Do not prevent the signal from being received from within its own signal handler.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

sys_einval an invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

sys_efault `Act`, `OldAct` point outside this process address space

sys_eintr System call was interrupted.

See also: `FpSigProcMask` (167), `FpSigPending` (166), `FpSigSuspend` (167), `FpKill` (144)

Listing: `./bunixex/ex57.pp`

Program `example57`;

```
{ Program to demonstrate the SigAction function. }

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses BaseUnix;

Var
    oa, na : PSigActionRec;

Procedure DoSig(sig : cint); cdecl;

begin
    writeln ( 'Receiving signal: ', sig );
end;

begin
    new(na);
    new(oa);
    na^.sa_Handler := SigActionHandler (@DoSig);
    fillchar (na^.Sa_Mask, sizeof(na^.sa_mask), #0);
    na^.Sa_Flags := 0;
    { $ifdef Linux } // Linux specific
    na^.Sa_Restorer := Nil;
    { $endif }
    if fpSigAction (SigUsr1, na, oa) <> 0 then
        begin
            writeln ( 'Error: ', fpgeterrno, '.' );
            halt (1);
        end;
    Writeln ( 'Send USR1 signal or press <ENTER> to exit' );
    readln;
end.
```

1.4.66 FpSigAddSet

Synopsis: Set a signal in a signal set.

Declaration: `function FpSigAddSet (var nset: tsigset; signo: cInt) : cInt`

Visibility: default

Description: `FpSigAddSet` adds signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (165), `FpSigFillSet` (165), `FpSigDelSet` (164), `FpSigIsMember` (165)

1.4.67 `FpSigDelSet`

Synopsis: Remove a signal from a signal set.

Declaration: `function FpSigDelSet (var nset: tsigset; signo: cInt) : cInt`

Visibility: default

Description: `FpSigDelSet` removes signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (165), `FpSigFillSet` (165), `FpSigAddSet` (164), `FpSigIsMember` (165)

1.4.68 `FpsigEmptySet`

Synopsis: Clear all signals from signal set.

Declaration: `function FpsigEmptySet (var nset: tsigset) : cInt`

Visibility: default

Description: `FpSigEmptySet` clears all signals from the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigFillSet` (165), `FpSigAddSet` (164), `FpSigDelSet` (164), `FpSigIsMember` (165)

1.4.69 `FpSigFillSet`

Synopsis: Set all signals in signal set.

Declaration: `function FpSigFillSet (var nset: tsigset) : cInt`

Visibility: default

Description: `FpSigFillSet` sets all signals in the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigEmptySet` (165), `FpSigAddSet` (164), `FpSigDelSet` (164), `FpSigIsMember` (165)

1.4.70 `FpSigIsMember`

Synopsis: Check whether a signal appears in a signal set.

Declaration: `function FpSigIsMember (const nset: tsigset; signo: cInt) : cInt`

Visibility: default

Description: `FpSigIsMember` checks whether `Signo` appears in the set `nset`. If it is a member, then 1 is returned. If not, zero is returned.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (165), `FpSigFillSet` (165), `FpSigAddSet` (164), `FpSigDelSet` (164)

1.4.71 FpSignal

Synopsis: Install signal handler (deprecated)

Declaration: `function FpSignal(signum: LongInt; Handler: signalhandler)
: signalhandler`

Visibility: default

Description: `FpSignal` installs a new signal handler (specified by `Handler`) for signal `SigNum`.

This call has a subset of the functionality provided by the `FpSigAction` (163) call. The return value for `FpSignal` is the old signal handler, or nil on error.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

SIG_ERR An error occurred.

See also: `FpSigAction` (163), `FpKill` (144)

Listing: `./bunixex/ex58.pp`

Program `example58;`

{ Program to demonstrate the Signal function. }

*{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}*

uses `BaseUnix;`

Procedure `DoSig(sig : cint); cdecl;`

begin

`writeln('Receiving signal: ', sig);`

end;

begin

`if fpSignal(SigUsr1, SignalHandler(@DoSig)) = signalhandler(SIG_ERR) then`

`begin`

`writeln('Error: ', fpGetErrno, '.');`

`halt(1);`

`end;`

`Writeln('Send USR1 signal or press <ENTER> to exit');`

`readln;`

end.

1.4.72 FpSigPending

Synopsis: Return set of currently pending signals

Declaration: `function FpSigPending(var nset: tsigset) : cInt`

Visibility: default

Description: `fpSigpending` allows the examination of pending signals (which have been raised while blocked.)

The signal mask of pending signals is returned.

Errors: None

See also: [fpSigAction \(163\)](#), [fpSigProcMask \(167\)](#), [fpSigSuspend \(167\)](#), [fpSignal \(166\)](#), [fpKill \(144\)](#)

1.4.73 FpSigProcMask

Synopsis: Set list of blocked signals

Declaration:

```
function FpSigProcMask(how: cInt;nset: psigset;oset: psigset) : cInt
function FpSigProcMask(how: cInt;const nset: tsigset;var oset: tsigset)
: cInt
```

Visibility: default

Description: Changes the list of currently blocked signals. The behaviour of the call depends on `How` :

SIG_BLOCKThe set of blocked signals is the union of the current set and the `nset` argument.

SIG_UNBLOCKThe signals in `nset` are removed from the set of currently blocked signals.

SIG_SETMASKThe list of blocked signals is set so `nset`.

If `oset` is non-nil, then the old set is stored in it.

Errors: `Errno` is used to report errors.

sys_efault`oset` or `nset` point to an adress outside the range of the process.

sys_eintrSystem call was interrupted.

See also: [fpSigAction \(163\)](#), [fpSigPending \(166\)](#), [fpSigSuspend \(167\)](#), [fpKill \(144\)](#)

1.4.74 FpSigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration:

```
function FpSigSuspend(const sigmask: tsigset) : cInt
```

Visibility: default

Description: `fpSigSuspend` temporarily replaces the signal mask for the process with the one given in `SigMask`, and then suspends the process until a signal is received.

Errors: None

See also: [fpSigAction \(163\)](#), [fpSigProcMask \(167\)](#), [fpSigPending \(166\)](#), [fpSignal \(166\)](#), [fpKill \(144\)](#)

1.4.75 FpSleep

Synopsis: Suspend process for several seconds

Declaration:

```
function FpSleep(seconds: cUInt) : cUInt
```

Visibility: default

Description: `FpSleep` suspends the process till a time period as specified in `seconds` has passed, then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and the return value is the remaining time till the end of the intended period.

If the function returns without error, the return value is zero.

See also: [fpPause \(154\)](#), [fpAlarm \(127\)](#), [fpNanoSleep \(150\)](#)

Listing: ./bunixex/ex73.pp

```

program example73;

  { Program to demonstrate the FpSleep function. }

uses BaseUnix;

Var
  Res : Longint;

begin
  Write( 'Sleep returned : ');
  Flush(Output);
  Res:=(fpSleep(10));
  WriteLn(res);
  If (res<>0) then
    WriteLn( 'Remaining seconds      : ',res);
end.

```

1.4.76 FpStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpStat(path: pChar;var buf: Stat) : cInt`
`function FpStat(path: AnsiString;var buf: Stat) : cInt`
`function FpStat(path: String;var buf: Stat) : cInt`

Visibility: default

Description: `FpFStat` gets information about the file specified in `Path`, and stores it in `Info`, which is of type `stat` ([120](#)). The function returns zero if the call was succesfull, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` ([140](#)).

`sys_enoent``Path` does not exist.

See also: [FpStat \(168\)](#), [FpLStat \(146\)](#)

Listing: ./bunixex/ex28.pp

```

program example28;

  { Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil ');

```

```

rewrite (f);
for i:=1 to 10 do writeln (f,'Testline # ',i);
close (f);
{ Do the call on made file. }
if fpstat ('test.fil',info)<>0 then
begin
    writeln('Fstat failed. Errno : ',fpgeterrno);
    halt (1);
end;
writeln;
writeln ('Result of fstat on file ''test.fil''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);
{ Remove file }
erase (f);
end.

```

1.4.77 fpSymlink

Synopsis: Create a symbolic link

Declaration: `function fpSymlink(oldname: pchar;newname: pchar) : cInt`

Visibility: default

Description: `SymLink` makes `NewName` point to the file in `OldName`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns zero if the call was succesful, a nonzero value if the call failed.

Errors: Extended error information is returned by the `FpGetErrno` (140) function.

sys_epermThe filesystem containing `oldpath` and `newpath` does not support linking files.

sys_eaccessWrite access for the directory containing `Newpath` is disallowed, or one of the directories in `OldPath` or `NewPath` has no search (=execute) permission.

sys_enoentA directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in `OldPath` or `NewPath` is nor a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only filesystem.

sys_eexist`NewPath` already exists.

sys_eloop`OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospc The device containing `NewPath` has no room for another entry.

See also: `FpLink` (144), `FpUnLink` (174), `FpReadLink` (157)

Listing: `./unixex/ex22.pp`

Program `Example22;`

{ Program to demonstrate the SymLink and UnLink functions. }

Uses `baseunix, Unix;`

Var `F : Text;`
 `S : String;`

begin
 `Assign (F, 'test.txt');`
 `Rewrite (F);`
 `Writeln (F, 'This is written to test.txt');`
 `Close(f);`
 { new.txt and test.txt are now the same file }
 if `fpSymLink ('test.txt', 'new.txt') <> 0` **then**
 `writeln ('Error when symlinking !');`
 { Removing test.txt still leaves new.txt
 Pointing now to a non-existent file ! }
 if `fpUnlink ('test.txt') <> 0` **then**
 `Writeln ('Error when unlinking !');`
 `Assign (f, 'new.txt');`
 { This should fail, since the symbolic link
 points to a non-existent file ! }
 { \$i- }
 `Reset (F);`
 { \$i+ }
 if `IOResult=0` **then**
 `Writeln ('This shouldn't happen');`
 { Now remove new.txt also }
 if `fpUnlink ('new.txt') <> 0` **then**
 `Writeln ('Error when unlinking !');`
end.

1.4.78 `fpS_ISBLK`

Synopsis: Is file a block device

Declaration: `function fpS_ISBLK(m: TMode) : Boolean`

Visibility: `default`

Description: `FpS_ISBLK` checks the file mode `m` to see whether the file is a block device file. If so it returns `True`.

See also: `FpFStat` (137), `FpS_ISLNK` (171), `FpS_ISREG` (172), `FpS_ISDIR` (171), `FpS_ISCHR` (170), `FpS_ISFIFO` (171), `FpS_ISSOCK` (172)

1.4.79 `fpS_ISCHR`

Synopsis: Is file a character device

Declaration: `function fpS_ISCHR(m: TMode) : Boolean`

Visibility: `default`

Description: `fpS_ISCHR` checks the file mode `m` to see whether the file is a character device file. If so it returns `True`.

See also: `FpFStat` (137), `FpS_ISLNK` (171), `FpS_ISREG` (172), `FpS_ISDIR` (171), `FpS_ISBLK` (170), `FpS_ISFIFO` (171), `FpS_ISSOCK` (172)

1.4.80 `fpS_ISDIR`

Synopsis: Is file a directory

Declaration: `function fpS_ISDIR(m: TMode) : Boolean`

Visibility: `default`

Description: `fpS_ISDIR` checks the file mode `m` to see whether the file is a directory. If so, it returns `True`

See also: `FpFStat` (137), `FpS_ISLNK` (171), `FpS_ISREG` (172), `FpS_ISCHR` (170), `FpS_ISBLK` (170), `fpS_ISFIFO` (171), `FpS_ISSOCK` (172)

1.4.81 `fpS_ISFIFO`

Synopsis: Is file a FIFO

Declaration: `function fpS_ISFIFO(m: TMode) : Boolean`

Visibility: `default`

Description: `FpS_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FpFStat` (137), `FpS_ISLNK` (171), `FpS_ISREG` (172), `FpS_ISCHR` (170), `FpS_ISBLK` (170), `FpS_ISDIR` (171), `FpS_ISSOCK` (172)

1.4.82 `fpS_ISLNK`

Synopsis: Is file a symbolic link

Declaration: `function fpS_ISLNK(m: TMode) : Boolean`

Visibility: `default`

Description: `FpS_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FpFStat` (137), `FpS_ISFIFO` (171), `FpS_ISREG` (172), `FpS_ISCHR` (170), `FpS_ISBLK` (170), `FpS_ISDIR` (171), `FpS_ISSOCK` (172)

Listing: `./bunixex/ex53.pp`

Program `Example53`;

{ Program to demonstrate the S_ISLNK function. }

Uses `BaseUnix, Unix`;

```

Var Info : Stat;

begin
  if fpLStat (paramstr(1),@info)=0 then
    begin
      if fpS_ISLNK(info.st_mode) then
        Writeln ('File is a link');
      if fpS_ISREG(info.st_mode) then
        Writeln ('File is a regular file');
      if fpS_ISDIR(info.st_mode) then
        Writeln ('File is a directory');
      if fpS_ISCHR(info.st_mode) then
        Writeln ('File is a character device file');
      if fpS_ISBLK(info.st_mode) then
        Writeln ('File is a block device file');
      if fpS_ISFIFO(info.st_mode) then
        Writeln ('File is a named pipe (FIFO)');
      if fpS_ISSOCK(info.st_mode) then
        Writeln ('File is a socket');
    end;
  end.

```

1.4.83 fpS_ISREG

Synopsis: Is file a regular file

Declaration: `function fpS_ISREG(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISREG` checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: `FpFStat` ([137](#)), `FpS_ISFIFO` ([171](#)), `FpS_ISLNK` ([171](#)), `FpS_ISCHR` ([170](#)), `FpS_ISBLK` ([170](#)), `FpS_ISDIR` ([171](#)), `FpS_ISSOCK` ([172](#))

1.4.84 fpS_ISSOCK

Synopsis: Is file a unix socket

Declaration: `function fpS_ISSOCK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISSOCK` checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: `FpFStat` ([137](#)), `FpS_ISFIFO` ([171](#)), `FpS_ISLNK` ([171](#)), `FpS_ISCHR` ([170](#)), `FpS_ISBLK` ([170](#)), `FpS_ISDIR` ([171](#)), `FpS_ISREG` ([172](#))

1.4.85 fptime

Synopsis: Return the current unix time

Declaration: `function FpTime(var tloc: TTime) : TTime`
`function fptime : time_t`

Visibility: default

Description: `FpTime` returns the number of seconds since 00:00:00 GMT, January 1, 1970. It is adjusted to the local time zone, but not to DST. The result is also stored in `tlloc`, if it is specified.

Errors: On error, -1 is returned. Extended error information can be retrieved using `fpGetErrno` ([140](#)).

Listing: `./bunixex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the GetEpochTime function. }

Uses `Unix`;

begin

Write ('Secs past the start of the Epoch (00:00 1/1/1980) : ');

Writeln (`GetEpochTime`);

end.

1.4.86 FpTimes

Synopsis: Return execution times for the current process

Declaration: `function FpTimes (var buffer: tms) : TClock`

Visibility: `default`

Description: `fpTimes` stores the execution time of the current process and child processes in `buffer`.

The return value (on linux) is the number of clock ticks since boot time. On error, -1 is returned, and extended error information can be retrieved with `fpGetErrno` ([140](#)).

See also: `fpUtime` ([174](#))

1.4.87 FpUmask

Synopsis: Set file creation mask.

Declaration: `function FpUmask (cmask: TMode) : TMode`

Visibility: `default`

Description: `fpUmask` changes the file creation mask for the current user to `cmask`. The current mask is returned.

See also: `fpChmod` ([128](#))

Listing: `./bunixex/ex27.pp`

Program `Example27`;

{ Program to demonstrate the Umask function. }

Uses `BaseUnix`;

begin

Writeln ('Old Umask was : ', `fpUmask`(&111));

Writeln ('New Umask is : ', &111);

end.

1.4.88 FpUname

Synopsis: Return system name.

Declaration: `function FpUname(var name: UtsName) : cInt`

Visibility: default

Description: `Uname` gets the name and configuration of the current linux kernel, and returns it in the `name` record.

On success, 0 is returned, on error, -1 is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpUTime` (174)

1.4.89 FpUnlink

Synopsis: Unlink (i.e. remove) a file.

Declaration: `function FpUnlink(path: pChar) : cInt`
`function FpUnlink(path: AnsiString) : cInt`

Visibility: default

Description: `FpUnlink` decreases the link count on file `Path`. `Path` can be of type `AnsiString` or `PChar`. If the link count is zero, the file is removed from the disk.

The function returns zero if the call was succesfull, a nonzero value indicates failure.

Note: There exist a portable alternative to erase files: `system.erase`. Please use `fpUnlink` only if you are writing Unix specific code. `System.erase` will work on all operating systems.

For an example, see `FpLink` (144).

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

sys_eaccess You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

sys_eperm The directory containing pathname has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

sys_enoent A component of the path doesn't exist.

sys_enotdir A directory component of the path is not a directory.

sys_eisdir `Path` refers to a directory.

sys_enomem Insufficient kernel memory.

sys_erofs `Path` is on a read-only filesystem.

See also: `FpLink` (144), `FpSymLink` (169)

1.4.90 FpUtime

Synopsis: Set access and modification times of a file (touch).

Declaration: `function FpUtime(path: pChar; times: pUtimBuf) : cInt`
`function FpUtime(path: AnsiString; times: pUtimBuf) : cInt`

Visibility: default

Description: `FpUtime` sets the access and modification times of the file specified in `Path`. the times record contains 2 fields, `actime`, and `modtime`, both of type `time_t` (commonly a `longint`). They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

The function returns zero on success, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

sys_eaccess One of the directories in `Path` has no search (=execute) permission.

sys_enoent A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: `FpTime` (172), `FpChown` (129), `FpAccess` (126)

Listing: `./bunixex/ex25.pp`

Program `Example25`;

{ Program to demonstrate the UTime function. }

Uses `BaseUnix`, `Unix`, `UnixUtil`;

Var `utim` : `utimbuf`;
 `year`, `month`, `day`, `hour`, `minute`, `second` : `Word`;

begin
 { Set access and modification time of executable source }
 `GetTime` (`hour`, `minute`, `second`);
 `GetDate` (`year`, `month`, `day`);
 `utim.actime` := `LocalToEpoch` (`year`, `month`, `day`, `hour`, `minute`, `second`);
 `utim.modtime` := `utim.actime` ;
 if `Fputime` ('ex25.pp', @`utim`) <> 0 **then**
 writeln ('Call to UTime failed !')
 else
 begin
 Write ('Set access and modification times to : ');
 Write (`Hour`:2, ': ', `minute`:2, ': ', `second`, ' ', ');
 Writeln (`Day`:2, ' / ', `month`:2, ' / ', `year`:4);
 end ;
end.

1.4.91 FpWait

Synopsis: Wait for a child to exit.

Declaration: `function FpWait` (`var stat_loc`: `cInt`) : `TPid`

Visibility: `default`

Description: `fpWait` suspends the current process and waits for any child to exit or stop due to a signal. It reports the exit status of the exited child in `stat_loc`.

The return value of the function is the process ID of the child that exited, or -1 on error.

Errors: Extended error information can be retrieved using `fpgetErrno` (140).

See also: `fpFork` (137), `fpExecve` (134), `fpWaitPid` (176)

1.4.92 FpWaitPid

Synopsis: Wait for a process to terminate

Declaration: `function FpWaitpid(pid: TPid; stat_loc: pcInt; options: cInt) : TPid`
`function FpWaitPid(pid: TPid; var Status: cInt; Options: cInt) : TPid`

Visibility: default

Description: `fpWaitPid` waits for a child process with process ID `Pid` to exit. The value of `Pid` can be one of the following:

Pid < -1 Causes `fpWaitPid` to wait for any child process whose process group ID equals the absolute value of `pid`.

Pid = -1 Causes `fpWaitPid` to wait for any child process.

Pid = 0 Causes `fpWaitPid` to wait for any child process whose process group ID equals the one of the calling process.

Pid > 0 Causes `fpWaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `fpWaitPid` behaves:

WNOHANG Causes `fpWaitpid` to return immediately if no child has exited.

WUNTRACED Causes `fpWaitPid` to return also for children which are stopped, but whose status has not yet been reported.

__WCLONE Causes `fpWaitPid` also to wait for threads created by the `#rtl.linux.Clone` (650) call.

The exit status of the process that caused `fpWaitPID` is reported in `stat_loc` or `Status`.

Upon return, it returns the process id of the process that exited, 0 if no process exited, or -1 in case of failure.

For an example, see `fpFork` (137).

Errors: Extended error information can be retrieved using `fpgetErrno` (140).

See also: `fpFork` (137), `fpExecve` (134), `fpWait` (175)

1.4.93 FpWrite

Synopsis: Write data to file descriptor

Declaration: `function FpWrite(fd: cInt; buf: pChar; nbytes: TSize) : TsSize`
`function FpWrite(fd: cInt; const buf; nbytes: TSize) : TsSize`

Visibility: default

Description: `FpWrite` writes at most `nbytes` bytes from `buf` to file descriptor `fd`.

The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` (140).

See also: `FpOpen` (152), `FpClose` (130), `FpRead` (156), `FpFTruncate` (138), `FpLSeek` (146)

1.4.94 FpWriteV

Synopsis: Vector write: Write from multiple buffers to a file descriptor

Declaration: `function FpWriteV(fd: cInt; const iov: piovec; iovcnt: cInt) : TsSize`

Visibility: default

Description: `FpWriteV` writes data to file descriptor `fd`. The data is taken from `iovcnt` buffers described by the `tiovec` (122) buffers pointed to by `iov`. It works like `fpWrite` (176) only from multiple buffers.

Errors: On error, -1 is returned.

See also: `FpReadV` (158), `FpPWrite` (155), `FpPRead` (155)

1.4.95 FreeShellArgV

Synopsis: Free the result of a `CreateShellArgV` (126) function

Declaration: `procedure FreeShellArgV(p: ppchar)`

Visibility: default

Description: `FreeShellArgV` frees the memory pointed to by `P`, which was allocated by a call to `CreateShellArgV` (126).

Errors: None.

See also: `CreateShellArgV` (126)

1.4.96 wexitStatus

Synopsis: Extract the exit status from the `fpWaitPID` (176) result.

Declaration: `function wexitStatus(Status: cInt) : cInt`

Visibility: default

Description: `WEXITSTATUS` can be used to extract the exit status from `Status`, the result of the `FpWaitPID` (176) call.

See also: `FpWaitPID` (176), `WTERMSIG` (178), `WSTOPSIG` (178), `WIFEXITED` (177), `WIFSIGNALED` (178)

1.4.97 wifexited

Synopsis: Check whether the process exited normally

Declaration: `function wifexited(Status: cInt) : Boolean`

Visibility: default

Description: `WIFEXITED` checks `Status` and returns `True` if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: `FpWaitPID` (176), `WTERMSIG` (178), `WSTOPSIG` (178), `WIFSIGNALED` (178), `WEXITSTATUS` (177)

1.4.98 wifsignaled

Synopsis: Check whether the process was exited by a signal.

Declaration: `function wifsignaled(Status: cInt) : Boolean`

Visibility: default

Description: `WIFSIGNALED` returns `True` if `Status` indicates that the process exited because it received a signal.

See also: `FpWaitPID` (176), `WTERMSIG` (178), `WSTOPSIG` (178), `WIFEXITED` (177), `WEXITSTATUS` (177)

1.4.99 wstopsig

Synopsis: Return the exit code from the process.

Declaration: `function wstopsig(Status: cInt) : cInt`

Visibility: default

Description: `WSTOPSIG` is an alias for `WEXITSTATUS` (177).

See also: `FpWaitPID` (176), `WTERMSIG` (178), `WIFEXITED` (177), `WIFSIGNALED` (178), `WEXITSTATUS` (177)

1.4.100 wtermsig

Synopsis: Return the signal that caused a process to exit.

Declaration: `function wtermsig(Status: cInt) : cInt`

Visibility: default

Description: `WTERMSIG` extracts from `Status` the signal number which caused the process to exit.

See also: `FpWaitPID` (176), `WSTOPSIG` (178), `WIFEXITED` (177), `WIFSIGNALED` (178), `WEXITSTATUS` (177)

Chapter 2

Reference for unit 'Classes'

2.1 Used units

Table 2.1: Used units by unit 'Classes'

Name	Page
rtlconsts	179
sysutils	1278
types	179
typinfo	1425

2.2 Overview

This documentation describes the FPC `classes` unit. The `Classes` unit contains basic classes for the Free Component Library (FCL):

- a `TList` ([290](#)) class for maintaining lists of pointers,
- `TStringList` ([327](#)) for lists of strings,
- `TCollection` ([251](#)) to manage collections of objects
- `TStream` ([318](#)) classes to support streaming.

Furthermore it introduces methods for object persistence, and classes that understand an owner-owned relationship, with automatic memory management.

2.3 Constants, types and variables

2.3.1 Constants

`BITSHIFT = 5`

Used to calculate the size of a bits array

`FilerSignature : Array[1..4] of Char = 'TPF0'`

Constant that is found at the start of a binary stream containing a streamed component.

`fmCreate = $FFFF`

`TFileStream.Create` (275) creates a new file if needed.

`fmOpenRead = 0`

`TFileStream.Create` (275) opens a file with read-only access.

`fmOpenReadWrite = 2`

`TFileStream.Create` (275) opens a file with read-write access.

`fmOpenWrite = 1`

`TFileStream.Create` (275) opens a file with write-only access.

`MASK = 31`

Bitmask with all bits on.

`MaxBitFlags = MaxBitRec * 32`

Maximum number of bits in TBits collection.

`MaxBitRec = $FFFF div (SizeOf (longint))`

Maximum number of bit records in TBits.

`MaxListSize = Maxint div 16`

This constant sets the maximum number of elements in a TList (290).

`scAlt = $8000`

Indicates ALT key in a keyboard shortcut.

`scCtrl = $4000`

indicates CTRL key in a keyboard shortcut.

`scNone = 0`

Indicates no special key is pressed in a keyboard shortcut.

`scShift = $2000`

Indicates Shift key in a keyboard shortcut.

`soFromBeginning = 0`

Seek (320) starts relative to the stream origin.

`soFromCurrent = 1`

Seek (320) starts relative to the current position in the stream.

`soFromEnd = 2`

Seek (320) starts relative to the stream end.

`toEOF = Char (0)`

Value returned by `TParser.Token` (304) when the end of the input stream was reached.

`toFloat = Char (4)`

Value returned by `TParser.Token` (304) when a floating point value was found in the input stream.

`toInteger = Char (3)`

Value returned by `TParser.Token` (304) when an integer was found in the input stream.

`toString = Char (2)`

Value returned by `TParser.Token` (304) when a string was found in the input stream.

`toSymbol = Char (1)`

Value returned by `TParser.Token` (304) when a symbol was found in the input stream.

2.3.2 Types

`HMODULE = LongInt`

FPC doesn't support modules yet, so this is a dummy type.

`HRSRC = LongInt`

This type is provided for Delphi compatibilty, it is used for resource streams.

`PPointerList = ^TPointerList`

Pointer to an array of pointers.

`PStringItem = ^TStringItem`

Pointer to a `TStringItem` (190) record.

Table 2.2: Enumeration values for type TActiveXRegType

Value	Explanation
axrComponentOnly	
axrIncludeDescendants	

Table 2.3: Enumeration values for type TAlignment

Value	Explanation
taCenter	Text is displayed centered.
taLeftJustify	Text is displayed aligned to the left
taRightJustify	Text is displayed aligned to the right.

PStringItemList = ^TStringItemList

Pointer to a TStringItemList ([190](#)).

TActiveXRegType = (axrComponentOnly, axrIncludeDescendants)

This type is provided for compatibility only, and is currently not used in Free Pascal.

TAlignment = (taLeftJustify, taRightJustify, taCenter)

The TAlignment type is used to specify the alignment of the text in controls that display a text.

```
TAncestorNotFoundEvent = procedure (Reader: TReader;
                                     const ComponentName: String;
                                     ComponentClass: TPersistentClass;
                                     var Component: TComponent) of object
```

This event occurs when an ancestor component cannot be found.

TBasicActionClass = Class of TBasicAction

TBasicAction ([228](#)) class reference.

TBasicActionLinkClass = Class of TBasicActionLink

TBasicActionLink ([232](#)) class reference.

```
TBiDiMode = (bdLeftToRight, bdRightToLeft, bdRightToLeftNoAlign,
             bdRightToLeftReadingOnly)
```

TBiDiMode describes bi-directional support for displaying texts.

TBitArray = Array[0..MaxBitRec-1] of cardinal

Array to store bits.

Table 2.4: Enumeration values for type TBiDiMode

Value	Explanation
bdLeftToRight	Texts read from left to right.
bdRightToLeft	Texts read from right to left.
bdRightToLeftNoAlign	Texts read from right to left, but not right-aligned
bdRightToLeftReadingOnly	Texts read from right to left

`TCollectionItemClass = Class of TCollectionItem`

`TCollectionItemClass` is used by the `TCollection.ItemClass` (255) property of `TCollection` (251) to identify the descendent class of `TCollectionItem` (256) which should be created and managed.

`TCollectionNotification = (cnAdded, cnExtracting, cnDeleting)`

Table 2.5: Enumeration values for type TCollectionNotification

Value	Explanation
cnAdded	An item is added to the collection.
cnDeleting	An item is deleted from the collection.
cnExtracting	An item is extracted from the collection.

`TCollectionNotification` is used in the `TCollection` (251) class to send notifications about changes to the collection.

`TComponentClass = Class of TComponent`

The `TComponentClass` type is used when constructing `TComponent` (258) descendent instances and when registering components.

`TComponentName = String`

Names of components are of type `TComponentName`. By specifying a different type, the Object inspector can handle this property differently than a standard string property.

`TComponentState= Set of (csLoading, csReading, csWriting, csDestroying, csDesigning, csAncestor, csUpdating, csFixups, csFreeNotification, csInline, csDesignInstance)`

Indicates the state of the component during the streaming process.

`TComponentStyle= Set of (csInheritable, csCheckPropAvail, csSubComponent, csTransient)`

Describes the style of the component.

`TCreateComponentEvent = procedure (Reader: TReader;
ComponentClass: TComponentClass;
var Component: TComponent) of object`

Event handler type, occurs when a component instance must be created when a component is read from a stream.

```
TDuplicates = (dupIgnore, dupAccept, dupError)
```

Table 2.6: Enumeration values for type TDuplicates

Value	Explanation
dupAccept	Duplicate values can be added to the list.
dupError	If an attempt is made to add a duplicate value to the list, an EStringListError (209) exception is raised.
dupIgnore	Duplicate values will not be added to the list, but no error will be triggered.

Type to describe what to do with duplicate values in a TStringlist (327).

```
TFilerFlag = (ffInherited, ffChildPos, ffInline)
```

Table 2.7: Enumeration values for type TFilerFlag

Value	Explanation
ffChildPos	The position of the child on it's parent is included.
ffInherited	Stored object is an inherited object.
ffInline	Used for frames.

The TFiler class uses this enumeration type to decide whether the streamed object was streamed as part of an inherited form or not.

```
TFilerFlags= Set of (ffChildPos, ffInherited, ffInline)
```

Set of TFilerFlag (184)

```
TFindAncestorEvent = procedure(Writer: TWriter; Component: TComponent;
                               const Name: String;
                               var Ancestor: TComponent;
                               var RootAncestor: TComponent) of object
```

Event that occurs w

```
TFindComponentClassEvent = procedure(Reader: TReader;
                                     const ClassName: String;
                                     var ComponentClass: TComponentClass)
  of object
```

Event handler type, occurs when a component class pointer must be found when reading a component from a stream.

```
TFindGlobalComponent = function(const Name: String) : TComponent
```

`TFindGlobalComponent` is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

The variable `FindGlobalComponent` (195) is a callback of type `TFindGlobalComponent`. It can be set by the IDE when an unknown reference is found, to offer the designer to redirect the link to a new component.

```
TFindMethodEvent = procedure(Reader: TReader; const MethodName: String;
                             var Address: Pointer; var Error: Boolean)
                             of object
```

If a `TReader` (305) instance needs to locate a method and it doesn't find it in the streamed form, then the `OnFindMethod` (314) event handler will be called, if one is installed. This event can be assigned in order to use different locating methods. If a method is found, then its address should be returned in `Address`. The `Error` should be set to `True` if the reader should raise an exception after the event was handled. If it is set to `False` no exception will be raised, even if no method was found. On entry, `Error` will be set to `True`.

```
TGetChildProc = procedure(Child: TComponent) of object
```

Callback used when obtaining child components.

```
TGetStrProc = procedure(const S: String) of object
```

This event is used as a callback to retrieve string values. It is used, among other things, to pass along string properties in property editors.

```
THandle = System.THandle
```

This type is used as the handle for `THandleStream` (282) stream descendents

```
THelpContext = -MaxLongint..MaxLongint
```

Range type to specify help contexts.

```
THelpEvent = function(Command: Word; Data: LongInt; var CallHelp: Boolean)
                : Boolean of object
```

This event is used for display of online help.

```
THelpType = (htKeyword, htContext)
```

Table 2.8: Enumeration values for type `THelpType`

Value	Explanation
<code>htContext</code>	Help type: Context ID help.
<code>htKeyword</code>	Help type: Keyword help

Enumeration type specifying the kind of help requested.

```
TIdentMapEntry = record
  Value : Integer;
  Name : String;
end
```

TIdentMapEntry is used internally by the [IdentToInt \(197\)](#) and [IntToIdent \(198\)](#) calls to store the mapping between the identifiers and the integers they represent.

```
TIdentToInt = function(const Ident: String;var Int: LongInt) : Boolean
```

TIdentToInt is a callback used to look up identifiers (Ident) and return an integer value corresponding to this identifier (Int). The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIdentToInt should be specified when an integer is registered using the RegisterIntegerConsts ([203](#)) call.

```
TInitComponentHandler = function(Instance: TComponent;
                                RootAncestor: TClass) : Boolean
```

TInitComponentHandler is a callback type. It is used in the InitInheritedComponent (??) call to initialize a component. Callbacks of this type are registered with the RegisterInitComponentHandler ([203](#)) call.

```
TIntToIdent = function(Int: LongInt;var Ident: String) : Boolean
```

TIntToIdent is a callback used to look up integers (Ident) and return an identifier (Ident) that can be used to represent this integer value in an IDE. The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIntToIdent should be specified when an integer is registered using the RegisterIntegerConsts ([203](#)) call.

```
TLeftRight = ..taRightJustify
```

TLeftRight is a subrange type based on the TAlignment ([182](#)) enumerated type. It contains only the left and right alignment constants.

```
TListCallback = procedure(data: pointer;arg: pointer) of object
```

TListCallback is the method callback prototype for the function that is passed to the TFPList.ForEachCall ([281](#)) call. The data argument will be filled with all the pointers in the list (one per call) and the arg argument is the Arg argument passed to the ForEachCall call.

```
TListNotification = (lnAdded,lnExtracted,lnDeleted)
```

Kind of list notification event.

```
TListSortCompare = function(Item1: Pointer;Item2: Pointer) : Integer
```

Callback type for the list sort algorithm.

Table 2.9: Enumeration values for type TListNotification

Value	Explanation
InAdded	List change notification: Element added to the list.
InDeleted	List change notification: Element deleted from the list.
InExtracted	List change notification: Element extracted from the list.

```
TListStaticCallback = procedure(data: pointer;arg: pointer)
```

TListCallback is the procedural callback prototype for the function that is passed to the TF-PList.ForEachCall (281) call. The data argument will be filled with all the pointers in the list (one per call) and the arg argument is the Arg argument passed to the ForEachCall call.

```
TNotifyEvent = procedure(Sender: TObject) of object
```

Most event handlers are implemented as a property of type TNotifyEvent. When this is set to a certain method of a class, when the event occurs, the method will be called, and the class that generated the event will pass itself along as the Sender argument.

```
TOperation = (opInsert,opRemove)
```

Table 2.10: Enumeration values for type TOperation

Value	Explanation
opInsert	A new component is being inserted in the child component list.
opRemove	A component is being removed from the child component list.

Operation of which a component is notified.

```
TPersistentClass = Class of TPersistent
```

TPersistentClass is the class reference type for the TPersistent (304) class.

```
TPoint = Types.TPoint
```

This record describes a coordinate. It is used to handle the Top (258) and Left (258) properties of TComponent (258).

X represents the X-Coordinate of the point described by the record. Y represents the Y-Coordinate of the point described by the record.

```
TPointerList = Array[0..MaxListSize-1] of Pointer
```

Type for an Array of pointers.

```
TPropertyNotFoundEvent = procedure(Reader: TReader;
    Instance: TPersistent;
    var PropName: String;IsPath: Boolean;
    var Handled: Boolean;
    var Skip: Boolean) of object
```


`TPropertyNotFoundEvent` is the prototype for the `TReader.OnPropertyNotFound` (313) event. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read. `Handled` should be set to `True` if the handler redirected the unknown property successfully, and `Skip` should be set to `True` if the value should be skipped. `IsPath` determines whether the property refers to a sub-property.

`TReadComponentsProc` = procedure(`Component`: `TComponent`) of object

Callback type when reading a component from a stream

`TReaderError` = procedure(`Reader`: `TReader`; const `Message`: `String`;
var `Handled`: `Boolean`) of object

Event handler type, called when an error occurs during the streaming.

`TReaderProc` = procedure(`Reader`: `TReader`) of object

The `TReaderProc` reader procedure is a callback procedure which will be used by a `TPersistent` (304) descendent to read user properties from a stream during the streaming process. The `Reader` argument is the writer object which can be used read properties from the stream.

`TReadWriteStringPropertyEvent` = procedure(`Sender`: `TObject`;
const `Instance`: `TPersistent`;
`PropInfo`: `PPropInfo`;
var `Content`: `String`) of object

`TReadWriteStringPropertyEvent` is the prototype for the `TReader.OnReadStringProperty` (315) event handler. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read. `Content` is the string as it was read from the stream.

`TRect` = `Types.TRect`

`TRect` describes a rectangle in space with its upper-left (in (`Top`,`Left`>)) and lower-right (in (`Bottom`,`Right`)) corners.

`TReferenceNameEvent` = procedure(`Reader`: `TReader`; var `Name`: `String`)
of object

Occurs when a named object needs to be looked up.

`TSeekOrigin` = (`soBeginning`, `soCurrent`, `soEnd`)

Table 2.11: Enumeration values for type `TSeekOrigin`

Value	Explanation
<code>soBeginning</code>	Offset is interpreted relative to the start of the stream.
<code>soCurrent</code>	Offset is interpreted relative to the current position in the stream.
<code>soEnd</code>	Offset is interpreted relative to the end of the stream.

Specifies the origin of the `TStream.Seek` (320) method.

```
TSetMethodPropertyEvent = procedure(Reader: TReader;
                                     Instance: TPersistent;
                                     PropInfo: PPropInfo;
                                     const TheMethodName: String;
                                     var Handled: Boolean) of object
```

TSetMethodPropertyEvent is the prototype for the TReader.OnSetMethodProperty (314) event. Reader is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being read, and TheMethodName is the name of the method that the property should be set to. Handled should be set to True if the handler set the property successfully.

```
TSetNameEvent = procedure(Reader: TReader;Component: TComponent;
                          var Name: String) of object
```

Occurs when the reader needs to set a component's name.

```
TShiftState= Set of (ssShift,ssAlt,ssCtrl,ssLeft,ssRight,ssMiddle,
                     ssDouble,ssMeta,ssSuper,ssHyper,ssAltGr,ssCaps,
                     ssNum,ssScroll,ssTriple,ssQuad)
```

This type is used when describing a shortcut key or when describing what special keys are pressed on a keyboard when a key event is generated.

The set contains the special keys that can be used in combination with a 'normal' key.

```
TShiftStateEnum = (ssShift,ssAlt,ssCtrl,ssLeft,ssRight,ssMiddle,
                   ssDouble,ssMeta,ssSuper,ssHyper,ssAltGr,ssCaps,ssNum,
                   ssScroll,ssTriple,ssQuad)
```

Table 2.12: Enumeration values for type TShiftStateEnum

Value	Explanation
ssAlt	Alt key pressed
ssAltGr	Alt-GR key pressed.
ssCaps	Caps lock key pressed
ssCtrl	Ctrl key pressed
ssDouble	Double mouse click.
ssHyper	Hyper key pressed.
ssLeft	Left mouse button pressed.
ssMeta	Meta key pressed.
ssMiddle	Middle mouse button pressed.
ssNum	Num lock key pressed
ssQuad	Quadruple mouse click
ssRight	Right mouse button pressed.
ssScroll	Scroll lock key pressed
ssShift	Shift key pressed
ssSuper	Super key pressed.
ssTriple	Triple mouse click

Keyboard/Mouse shift state enumerator

```
TShortCut = ( Word )..High ( Word )
```

Enumeration type to identify shortcut key combinations.

```
TSmallPoint = record
    x : SmallInt;
    y : SmallInt;
end
```

Same as TPoint (187), only the X and Y ranges are limited to 2-byte integers instead of 4-byte integers.

```
TStreamProc = procedure(Stream: TStream) of object
```

Procedure type used in streaming.

```
TStringItem = record
    FString : String;
    FObject : TObject;
end
```

The TStringItem is used to store the string and object items in a TStringList (327) string list instance. It should never be used directly.

```
TStringItemList = Array[0..MaxListSize] of TStringItem
```

This declaration is provided for Delphi compatibility, it is not used in Free Pascal.

```
TStringListSortCompare = function(List: TStringList; Index1: Integer;
    Index2: Integer) : Integer
```

Callback type used in stringlist compares.

```
TSynchronizeProcVar = procedure
```

Synchronize callback type

```
TThreadMethod = procedure of object
```

Procedure variable used when synchronizing threads.

```
TThreadPriority = (tpIdle, tpLowest, tpLower, tpNormal, tpHigher, tpHighest,
    tpTimeCritical)
```

Enumeration specifying the priority at which a thread runs.

```
TValueType = (vaNull, vaList, vaInt8, vaInt16, vaInt32, vaExtended, vaString,
    vaIdent, vaFalse, vaTrue, vaBinary, vaSet, vaLString, vaNil,
    vaCollection, vaSingle, vaCurrency, vaDate, vaWString, vaInt64,
    vaUTF8String)
```

Table 2.13: Enumeration values for type TThreadPriority

Value	Explanation
tpHigher	Thread runs at high priority
tpHighest	Thread runs at highest possible priority.
tpIdle	Thread only runs when other processes are idle.
tpLower	Thread runs at a lower priority.
tpLowest	Thread runs at the lowest priority.
tpNormal	Thread runs at normal process priority.
tpTimeCritical	Thread runs at realtime priority.

Enumerated type used to identify the kind of streamed property

```
TWriteMethodPropertyEvent = procedure(Writer: TWriter;
                                     Instance: TPersistent;
                                     PropInfo: PPropInfo;
                                     const MethodValue: TMethod;
                                     const DefMethodCodeValue: Pointer;
                                     var Handled: Boolean) of object
```

TWriteMethodPropertyEvent is the prototype for the TWriter.OnWriteMethodProperty (358) event. Writer is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being written, and MethodValue is the value of the method that the property was set to. DefMethodCodeValue is set to the default value of the property (Nil or the parent value). Handled should be set to True if the handler set the property successfully.

```
TWriterProc = procedure(Writer: TWriter) of object
```

The TWriterProc writer procedure is a callback procedure which will be used by a TPersistent (304) descendent to write user properties from a stream during the streaming process. The Writer argument is the writer object which can be used write properties to the stream.

2.3.3 Variables

```
AddDataModule : procedure(DataModule: TDataModule) of object
```

AddDataModule can be set by an IDE or a streaming mechanism to receive notification when a new instance of a TDataModule (269) descendent is created.

```
ApplicationHandleException : procedure(Sender: TObject) of object
```

ApplicationHandleException can be set by an application object to handle any exceptions that may occur when a TDataModule (269) is created.

```
ApplicationShowException : procedure(E: Exception) of object
```

Unused.

```
GlobalNameSpace : IReadWriteSync
```

Table 2.14: Enumeration values for type TValueType

Value	Explanation
vaBinary	Binary data follows.
vaCollection	Collection follows
vaCurrency	Currency value follows
vaDate	Date value follows
vaExtended	Extended value.
vaFalse	Boolean False value.
vaIdent	Identifier.
vaInt16	Integer value, 16 bits long.
vaInt32	Integer value, 32 bits long.
vaInt64	Integer value, 64 bits long.
vaInt8	Integer value, 8 bits long.
vaList	Identifies the start of a list of values
vaLString	Ansistring data follows.
vaNil	Nil pointer.
vaNull	Empty value. Ends a list.
vaSet	Set data follows.
vaSingle	Single type follows.
vaString	String value.
vaTrue	Boolean True value.
vaUTF8String	UTF8 encoded unicode string.
vaWString	Widestring value follows.

An interface protecting the global namespace. Used when reading/writing to the global namespace list during streaming of forms.

MainThreadID : TThreadID

ID of main thread. Unused at this point.

RegisterComponentsProc : procedure(const Page: String;
ComponentClasses: Array[] of TComponentClass)

RegisterComponentsProc can be set by an IDE to be notified when new components are being registered. Application programmers should never have to set RegisterComponentsProc

RegisterNoIconProc : procedure(ComponentClasses: Array[] of TComponentClass)

RegisterNoIconProc can be set by an IDE to be notified when new components are being registered, and which do not need an Icon in the component palette. Application programmers should never have to set RegisterComponentsProc

RemoveDataModule : procedure(DataModule: TDataModule) of object

RemoveDataModule can be set by an IDE or a streaming mechanism to receive notification when an instance of a TDataModule (269) descendent is freed.

WakeMainThread : TNotifyEvent = nil

`WakeMainThread` is called by the `TThread.synchronize` (348) call. It should alert the main program thread that a thread is waiting for synchronization. The call is executed by the thread, and should therefore NOT synchronize the thread, but should somehow signal the main thread that a thread is waiting for synchronization. For example, by sending a message.

2.4 Procedures and functions

2.4.1 ActivateClassGroup

Synopsis: Activates a class group

Declaration: `function ActivateClassGroup(AClass: TPersistentClass) : TPersistentClass`

Visibility: default

Description: `ActivateClassGroup` activates the group of classes to which `AClass` belongs. The function returns the class that was last used to activate the class group.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors: If `AClass` does not belong to a class group, an exception is raised.

See also: `StartClassGroup` (205), `GroupDescendentsWith` (197), `ClassGroupOf` (194)

2.4.2 BeginGlobalLoading

Synopsis: Not yet implemented

Declaration: `procedure BeginGlobalLoading`

Visibility: default

Description: Not yet implemented

2.4.3 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex(BinValue: PChar; HexValue: PChar; BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size $2 * \text{BufSize}$.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` (197)

2.4.4 Bounds

Synopsis: Returns a `TRect` structure with the bounding rect of the given location and size.

Declaration: `function Bounds (ALeft: Integer; ATop: Integer; AWidth: Integer;
AHeight: Integer) : TRect`

Visibility: default

Description: `Bounds` returns a `TRect` (188) record with the given origin (`ALeft`, `ATop`) and dimensions (`AWidth`, `AHeight`) filled in.

2.4.5 CheckSynchronize

Synopsis: Check whether there are any synchronize calls in the synchronize queue.

Declaration: `procedure CheckSynchronize (timeout: LongInt)`

Visibility: default

Description: `CheckSynchronize` should be called regularly by the main application thread to handle any `TThread.synchronize` (348) calls that may be waiting for execution by the main thread.

See also: `TThread.synchronize` (348)

2.4.6 ClassGroupOf

Synopsis: Returns the class group to which an instance or class belongs

Declaration: `function ClassGroupOf (AClass: TPersistentClass) : TPersistentClass
function ClassGroupOf (Instance: TPersistent) : TPersistentClass`

Visibility: default

Description: `ClassGroupOf` returns the class group to which `AClass` or `Instance` belongs.

Errors: The result is `Nil` if no matching class group is found.

See also: `StartClassGroup` (205), `ActivateClassGroup` (193), `GroupDescendentsWith` (197)

2.4.7 CollectionsEqual

Synopsis: Returns `True` if two collections are equal.

Declaration: `function CollectionsEqual (C1: TCollection; C2: TCollection) : Boolean
function CollectionsEqual (C1: TCollection; C2: TCollection;
Owner1: TComponent; Owner2: TComponent)
: Boolean`

Visibility: default

Description: `CollectionsEqual` is not yet implemented. It simply returns `False`

2.4.8 EndGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure EndGlobalLoading`

Visibility: `default`

Description: Not yet implemented.

2.4.9 ExtractStrings

Synopsis: Split a string in different words.

Declaration: `function ExtractStrings(Separators: TSysCharSet; WhiteSpace: TSysCharSet;
Content: PChar; Strings: TStrings) : Integer`

Visibility: `default`

Description: `ExtractStrings` splits `Content` (a null-terminated string) into words, and adds the words to the `Strings` stringlist. The words are separated by `Separators` and any characters in whitespace are stripped from the strings. The space and CR/LF characters are always considered whitespace.

Errors: No length checking is performed on `Content`. If no null-termination character is present, an access violation may occur. Likewise, if `Strings` is not valid, an access violation may occur.

2.4.10 FindClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function FindClass(const AClassName: String) : TPersistentClass`

Visibility: `default`

Description: `FindClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, an exception is raised. The `GetClass` (196) function does not raise an exception when it does not find the class, but returns a `Nil` pointer instead.

See also: `RegisterClass` (202), `GetClass` (196)

2.4.11 FindGlobalComponent

Synopsis: Callback used when a component must be found.

Declaration: `function FindGlobalComponent(const Name: String) : TComponent`

Visibility: `default`

Description: `FindGlobalComponent` is a callback of type `TFindGlobalComponent` (185). It can be set by the IDE when an unknown reference is found, to offer the user to redirect the link to a new component.

It is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

See also: `TFindGlobalComponent` (185)

2.4.12 FindNestedComponent

Synopsis: Finds the component with name path starting at the indicated root component.

Declaration: `function FindNestedComponent (Root: TComponent; const NamePath: String)
: TComponent`

Visibility: default

Description: `FindNestedComponent` will descend through the list of owned components (starting at `Root`) and will return the component whose name path matches `NamePath`. As a path separator the characters `.` (dot), `-` (dash) and `>` (greater than) can be used

See also: `GlobalFixupReferences` ([197](#))

2.4.13 GetClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function GetClass (const AClassName: String) : TPersistentClass`

Visibility: default

Description: `GetClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, `Nil` is returned.

The `FindClass` ([195](#)) function will raise an exception if it does not find the class.

See also: `RegisterClass` ([202](#)), `GetClass` ([196](#))

2.4.14 GetFixupInstanceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component, whose reference contains `ReferenceRootName`

Declaration: `procedure GetFixupInstanceNames (Root: TComponent;
const ReferenceRootName: String;
Names: TStrings)`

Visibility: default

Description: `GetFixupInstanceNames` examines the list of unresolved references and returns the names of classes that contain unresolved references to the `Root` component in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupReferenceNames` ([196](#)), `GlobalFixupReferences` ([197](#))

2.4.15 GetFixupReferenceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component.

Declaration: `procedure GetFixupReferenceNames (Root: TComponent; Names: TStrings)`

Visibility: default

Description: `GetFixupReferenceNames` examines the list of unresolved references and returns the names of properties that must be resolved for the component `Root` in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupInstanceNames` ([196](#)), `GlobalFixupReferences` ([197](#))

2.4.16 GlobalFixupReferences

Synopsis: Called to resolve unresolved references after forms are loaded.

Declaration: `procedure GlobalFixupReferences`

Visibility: default

Description: `GlobalFixupReferences` runs over the list of unresolved references and tries to resolve them. This routine should under normal circumstances not be called in an application programmer's code. It is called automatically by the streaming system after a component has been instantiated and its properties read from a stream. It will attempt to resolve references to other global components.

See also: `GetFixupReferenceNames` ([196](#)), `GetFixupInstanceNames` ([196](#))

2.4.17 GroupDescendentsWith

Synopsis: Add class to the group of another class.

Declaration: `procedure GroupDescendentsWith (AClass: TPersistentClass;
AClassGroup: TPersistentClass)`

Visibility: default

Description: `GroupDescendentsWith` adds `AClass` to the group that `AClassGroup` belongs to. If `AClassGroup` belongs to more than 1 group, then it is added to the group which contains the nearest ancestor.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors:

See also: `StartClassGroup` ([205](#)), `ActivateClassGroup` ([193](#)), `ClassGroupOf` ([194](#))

2.4.18 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin (HexValue: PChar; BinValue: PChar; BinBufSize: Integer)
: Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` ([193](#))

2.4.19 IdentToInt

Synopsis: Looks up an integer value in a integer-to-identifier map list.

Declaration: `function IdentToInt (const Ident: String; var Int: LongInt;
const Map: Array[] of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Name` field matches `Ident` and returns the corresponding integer value in `Int`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: `TIdentToInt` ([186](#)), `TIntToIdent` ([186](#)), `IntToIdent` ([198](#)), `TIdentMapEntry` ([186](#))

2.4.20 InitComponentRes

Synopsis: Provided for Delphi compatibility only

Declaration: `function InitComponentRes(const ResName: String; Instance: TComponent) : Boolean`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns `false`.

See also: `ReadComponentRes` ([201](#))

2.4.21 InitInheritedComponent

Synopsis: Initializes a component descending from `RootAncestor`

Declaration: `function InitInheritedComponent(Instance: TComponent; RootAncestor: TClass) : Boolean`

Visibility: default

Description: `InitInheritedComponent` should be called from a constructor to read properties of the component `Instance` from the streaming system. The `RootAncestor` class is the root class from which `Instance` is a descendent. This must be one of `TDatamodule`, `TCustomForm` or `TFrame`. The function returns `True` if the properties were successfully read from a stream or `False` if some error occurred.

See also: `ReadComponentRes` ([201](#)), `ReadComponentResEx` ([201](#)), `ReadComponentResFile` ([201](#))

2.4.22 IntTIdent

Synopsis: Looks up an identifier for an integer value in a identifier-to-integer map list.

Declaration: `function IntToIdent(Int: LongInt; var Ident: String; const Map: Array[] of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Value` field matches `Int` and returns the corresponding identifier in `Ident`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: `TIdentToInt` ([186](#)), `TIntToIdent` ([186](#)), `IdentToInt` ([197](#)), `TIdentMapEntry` ([186](#))

2.4.23 InvalidPoint

Synopsis: Check whether a point is invalid.

Declaration: `function InvalidPoint (X: Integer; Y: Integer) : Boolean`
`function InvalidPoint (const At: TPoint) : Boolean`
`function InvalidPoint (const At: TSmallPoint) : Boolean`

Visibility: default

Description: `InvalidPoint` returns `True` if the X and Y coordinates (of the `TPoint` or `TSmallPoint` records, if one of these versions is used) are -1.

See also: `TPoint` ([187](#)), `TSmallPoint` ([190](#)), `PointsEqual` ([200](#))

2.4.24 LineStart

Synopsis: Finds the start of a line in `Buffer` before `BufPos`.

Declaration: `function LineStart (Buffer: PChar; BufPos: PChar) : PChar`

Visibility: default

Description: `LineStart` reversely scans `Buffer` starting at `BufPos` for a linefeed character. It returns a pointer at the linefeed character.

2.4.25 NotifyGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure NotifyGlobalLoading`

Visibility: default

Description: Not yet implemented.

2.4.26 ObjectBinaryToText

Synopsis: Converts an object stream from a binary to a text format.

Declaration: `procedure ObjectBinaryToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectBinaryToText` reads an object stream in binary format from `Input` and writes the object stream in text format to `Output`. No components are instantiated during the process, this is a pure conversion routine.

See also: `ObjectTextToBinary` ([200](#))

2.4.27 ObjectResourceToText

Synopsis: Converts an object stream from a (windows) resource to a text format.

Declaration: `procedure ObjectResourceToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectResourceToText` reads the resource header from the `Input` stream and then passes the streams to `ObjectBinaryToText` ([199](#))

See also: `ObjectBinaryToText` ([199](#)), `ObjectTextToResource` ([200](#))

2.4.28 ObjectTextToBinary

Synopsis: Converts an object stream from a text to a binary format.

Declaration: `procedure ObjectTextToBinary(Input: TStream;Output: TStream)`

Visibility: default

Description: Converts an object stream from a text to a binary format.

2.4.29 ObjectTextToResource

Synopsis: Converts an object stream from a text to a (windows) resource format.

Declaration: `procedure ObjectTextToResource(Input: TStream;Output: TStream)`

Visibility: default

Description: `ObjectTextToResource` reads an object stream in text format from `Input` and writes a resource stream to `Output`.

Note that for the current implementation of this method in Free Pascal, the output stream should support positioning. (e.g. it should not be a pipe)

See also: `ObjectBinaryToText` ([199](#)), `ObjectResourceToText` ([199](#))

2.4.30 Point

Synopsis: Returns a `TPoint` record with the given coordinates.

Declaration: `function Point(AX: Integer;AY: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` ([187](#)) record with the given coordinates `AX` and `AY` filled in.

See also: `TPoint` ([187](#)), `SmallPoint` ([205](#)), `Rect` ([201](#)), `Bounds` ([194](#))

2.4.31 PointsEqual

Synopsis: Check whether two `TPoint` variables are equal.

Declaration: `function PointsEqual(const P1: TPoint;const P2: TPoint) : Boolean`
`function PointsEqual(const P1: TSmallPoint;const P2: TSmallPoint)`
`: Boolean`

Visibility: default

Description: `PointsEqual` compares the `P1` and `P2` points (of type `TPoint` ([187](#)) or `TSmallPoint` ([190](#))) and returns `True` if the `X` and `Y` coordinates of the points are equal, or `False` otherwise.

See also: `TPoint` ([187](#)), `TSmallPoint` ([190](#)), `InvalidPoint` ([199](#))

2.4.32 ReadComponentRes

Synopsis: Read component properties from a resource in the current module

Declaration: `function ReadComponentRes(const ResName: String; Instance: TComponent)
: TComponent`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns Nil.

2.4.33 ReadComponentResEx

Synopsis: Read component properties from a resource in the specified module

Declaration: `function ReadComponentResEx(HInstance: THandle; const ResName: String)
: TComponent`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns Nil.

2.4.34 ReadComponentResFile

Synopsis: Read component properties from a specified resource file

Declaration: `function ReadComponentResFile(const FileName: String;
Instance: TComponent) : TComponent`

Visibility: default

Description: `ReadComponentResFile` starts reading properties for `Instance` from the file `FileName`. It creates a filestream from `FileName` and then calls the `TStream.ReadComponentRes` (322) method to read the state of the component from the stream.

See also: `TStream.ReadComponentRes` (322), `WriteComponentResFile` (206)

2.4.35 Rect

Synopsis: Returns a `TRect` record with the given coordinates.

Declaration: `function Rect(ALeft: Integer; ATop: Integer; ARight: Integer;
ABottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a `TRect` (188) record with the given top-left (`ALeft`, `ATop`) and bottom-right (`ABottom`, `ARight`) corners filled in.

No checking is done to see whether the coordinates are valid.

See also: `TRect` (188), `Point` (200), `SmallPoint` (205), `Bounds` (194)

2.4.36 RedirectFixupReferences

Synopsis: Redirects references under the `root` object from `OldRootName` to `NewRootName`

Declaration: `procedure RedirectFixupReferences (Root: TComponent;
const OldRootName: String;
const NewRootName: String)`

Visibility: default

Description: `RedirectFixupReferences` examines the list of unresolved references and replaces references to a root object named `OldRootName` with references to root object `NewRootName`.

An application programmer should never need to call `RedirectFixupReferences`. This function can be used by an IDE to support redirection of broken component links.

See also: `RemoveFixupReferences` ([204](#))

2.4.37 RegisterClass

Synopsis: Registers a class with the streaming system.

Declaration: `procedure RegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `RegisterClass` registers the class `AClass` in the streaming system. After the class has been registered, it can be read from a stream when a reference to this class is encountered.

See also: `RegisterClasses` ([202](#)), `RegisterClassAlias` ([202](#)), `RegisterComponents` ([203](#)), `UnregisterClass` ([205](#))

2.4.38 RegisterClassAlias

Synopsis: Registers a class alias with the streaming system.

Declaration: `procedure RegisterClassAlias (AClass: TPersistentClass;
const Alias: String)`

Visibility: default

Description: `RegisterClassAlias` registers a class alias in the streaming system. If a reference to a class `Alias` is encountered in a stream, then an instance of the class `AClass` will be created instead by the streaming code.

See also: `RegisterClass` ([202](#)), `RegisterClasses` ([202](#)), `RegisterComponents` ([203](#)), `UnregisterClass` ([205](#))

2.4.39 RegisterClasses

Synopsis: Registers multiple classes with the streaming system.

Declaration: `procedure RegisterClasses (AClasses: Array[] of TPersistentClass)`

Visibility: default

Description: `RegisterClasses` registers the specified classes `AClass` in the streaming system. After the classes have been registered, they can be read from a stream when a reference to this class is encountered.

See also: `RegisterClass` ([202](#)), `RegisterClassAlias` ([202](#)), `RegisterComponents` ([203](#)), `UnregisterClass` ([205](#))

2.4.40 RegisterComponents

Synopsis: Registers components for the component palette.

Declaration: `procedure RegisterComponents(const Page: String;
ComponentClasses: Array[] of TComponentClass)`

Visibility: default

Description: `RegisterComponents` registers the component on the appropriate component page. The component pages can be used by an IDE to display the known components so an application programmer may pick and use the components in his programs.

`RegisterComponents` inserts the component class in the correct component page. If the `RegisterComponentsProc` procedure is set, this is called as well. Note that this behaviour is different from Delphi's behaviour where an exception will be raised if the procedural variable is not set.

See also: `RegisterClass` ([202](#)), `RegisterNoIcon` ([204](#))

2.4.41 RegisterFindGlobalComponentProc

Synopsis: Register a component searching handler

Declaration: `procedure RegisterFindGlobalComponentProc
(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `RegisterFindGlobalComponentProc` registers a global component search callback `AFindGlobalComponent`. When `FindGlobalComponent` ([195](#)) is called, then this callback will be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` ([195](#)), `UnRegisterFindGlobalComponentProc` ([206](#))

2.4.42 RegisterInitComponentHandler

Synopsis: Register a component initialization handler

Declaration: `procedure RegisterInitComponentHandler(ComponentClass: TComponentClass;
Handler: TInitComponentHandler)`

Visibility: default

Description: `RegisterInitComponentHandler` registers a component initialization handler `Handler` for the component `ComponentClass`. This handler will be used to initialize descendents of `ComponentClass` in the `InitInheritedComponent` ([198](#)) call.

See also: `InitInheritedComponent` ([198](#)), `TInitComponentHandler` ([186](#))

2.4.43 RegisterIntegerConsts

Synopsis: Registers some integer-to-identifier mappings.

Declaration: `procedure RegisterIntegerConsts(IntegerType: Pointer;
IdentToIntFn: TIdentToInt;
IntToIdentFn: TIntToIdent)`

Visibility: default

Description: `RegisterIntegerConsts` registers a pair of callbacks to be used when an integer of type `IntegerType` must be mapped to an identifier (using `IntToIdentFn`) or when an identifier must be mapped to an integer (using `IdentToIntFn`).

Component programmers can use `RegisterIntegerConsts` to associate a series of identifier strings with integer values for a property. A necessary condition is that the property should have a separate type declared using the `type integer` syntax. If a type of integer is defined in this way, an IDE can show symbolic names for the values of these properties.

The `IntegerType` should be a pointer to the type information of the integer type. The `IntToIdentFn` and `IdentToIntFn` are two callbacks that will be used when converting between the identifier and integer value and vice versa. The functions `IdentToInt` (197) and `IntToIdent` (198) can be used to implement these callback functions.

See also: `TIdentToInt` (186), `TIntToIdent` (186), `IdentToInt` (197), `IntToIdent` (198)

2.4.44 RegisterNoIcon

Synopsis: Registers components that have no icon on the component palette.

Declaration: `procedure RegisterNoIcon(ComponentClasses: Array[] of TComponentClass)`

Visibility: default

Description: `RegisterNoIcon` performs the same function as `RegisterComponents` (203) except that it calls `RegisterNoIconProc` (192) instead of `RegisterComponentsProc` (192)

See also: `RegisterNoIconProc` (192), `RegisterComponents` (203)

2.4.45 RegisterNonActiveX

Synopsis: Register non-activex component.

Declaration: `procedure RegisterNonActiveX
(ComponentClasses: Array[] of TComponentClass;
AxRegType: TActiveXRegType)`

Visibility: default

Description: Not yet implemented in Free Pascal

2.4.46 RemoveFixupReferences

Synopsis: Removes references to rootname from the fixup list.

Declaration: `procedure RemoveFixupReferences(Root: TComponent; const RootName: String)`

Visibility: default

Description: `RemoveFixupReferences` examines the list of unresolved references and removes references to a root object pointing at `Root` or a root component named `RootName`.

An application programmer should never need to call `RemoveFixupReferences`. This function can be used by an IDE to support removal of broken component links.

See also: `RedirectFixupReferences` (202)

2.4.47 RemoveFixups

Synopsis: Removes Instance from the fixup list.

Declaration: `procedure RemoveFixups (Instance: TPersistent)`

Visibility: default

Description: `RemoveFixups` removes all entries for component Instance from the list of unresolved references.

See also: [RedirectFixupReferences \(202\)](#), [RemoveFixupReferences \(204\)](#)

2.4.48 SmallPoint

Synopsis: Returns a `TSmallPoint` record with the given coordinates.

Declaration: `function SmallPoint (AX: SmallInt; AY: SmallInt) : TSmallPoint`

Visibility: default

Description: `SmallPoint` returns a `TSmallPoint` (190) record with the given coordinates AX and AY filled in.

See also: [TSmallPoint \(190\)](#), [Point \(200\)](#), [Rect \(201\)](#), [Bounds \(194\)](#)

2.4.49 StartClassGroup

Synopsis: Start new class group.

Declaration: `procedure StartClassGroup (AClass: TPersistentClass)`

Visibility: default

Description: `StartClassGroup` starts a new class group and adds AClass to it.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

See also: [GroupDescendentsWith \(197\)](#), [ActivateClassGroup \(193\)](#), [ClassGroupOf \(194\)](#)

2.4.50 UnRegisterClass

Synopsis: Unregisters a class from the streaming system.

Declaration: `procedure UnRegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `UnregisterClass` removes the class AClass from the class definitions in the streaming system.

See also: [UnRegisterClasses \(205\)](#), [UnRegisterModuleClasses \(206\)](#), [RegisterClass \(202\)](#)

2.4.51 UnRegisterClasses

Synopsis: Unregisters multiple classes from the streaming system.

Declaration: `procedure UnRegisterClasses (AClasses: Array[] of TPersistentClass)`

Visibility: default

Description: `UnregisterClasses` removes the classes in AClasses from the class definitions in the streaming system.

2.4.52 UnregisterFindGlobalComponentProc

Synopsis: Remove a previously registered component searching handler.

Declaration: `procedure UnregisterFindGlobalComponentProc`
`(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `UnRegisterFindGlobalComponentProc` unregisters the previously registered global component search callback `AFindGlobalComponent`. After this call, when `FindGlobalComponent` (195) is called, then this callback will be no longer be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (195), `RegisterFindGlobalComponentProc` (203)

2.4.53 UnRegisterModuleClasses

Synopsis: Unregisters classes registered by module.

Declaration: `procedure UnRegisterModuleClasses (Module: HMODULE)`

Visibility: default

Description: `UnRegisterModuleClasses` unregisters all classes which reside in the module `Module`. For each registered class, the definition pointer is checked to see whether it resides in the module, and if it does, the definition is removed.

See also: `UnRegisterClass` (205), `UnRegisterClasses` (205), `RegisterClasses` (202)

2.4.54 WriteComponentResFile

Synopsis: Write component properties to a specified resource file

Declaration: `procedure WriteComponentResFile (const FileName: String;`
`Instance: TComponent)`

Visibility: default

Description: `WriteComponentResFile` starts writing properties of `Instance` to the file `FileName`. It creates a filestream from `FileName` and then calls `TStream.WriteComponentRes` (323) method to write the state of the component to the stream.

See also: `TStream.WriteComponentRes` (323), `ReadComponentResFile` (201)

2.5 EBitsError

2.5.1 Description

When an index of a bit in a `TBits` (244) is out of the valid range (0 to `Count-1`) then a `EBitsError` exception is raised.

2.6 EClassNotFound

2.6.1 Description

When the streaming system needs to create a component, it looks for the class pointer (VMT) in the list of registered classes by its name. If this name is not found, then an `EClassNotFound` is raised.

2.7 EComponentError

2.7.1 Description

When an error occurs during the registration of a component, or when naming a component, then a `EComponentError` is raised. Possible causes are:

1. An name with an illegal character was assigned to a component.
2. A component with the same name and owner already exists.
3. The component registration system isn't set up properly.

2.8 EFCreateError

2.8.1 Description

When the operating system reports an error during creation of a new file in the Filestream Constructor (275), a `EFCreateError` is raised.

2.9 EFilerError

2.9.1 Description

This class serves as an ancestor class for exceptions that are raised when an error occurs during component streaming. A `EFilerError` exception is raised when a class is registered twice.

2.10 EFOpenError

2.10.1 Description

When the operating system reports an error during the opening of a file in the Filestream Constructor (275), a `EFOpenError` is raised.

2.11 EInvalidImage

2.11.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

2.12 EInvalidOperation

2.12.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

2.13 EListError

2.13.1 Description

If an error occurs in one of the `TList` (290) or `TStrings` (332) methods, then a `EListError` exception is raised. This can occur in one of the following cases:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. An attempt was made to reduce the capacity of the list below the current element count.
4. An attempt was made to set the list count to a negative value.
5. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
6. An attempt was made to move an item to a position outside the list's bounds.

2.14 EMethodNotFound

2.14.1 Description

This exception is no longer used in the streaming system. This error is replaced by a `EReadError` (208).

2.15 EOutOfResources

2.15.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

2.16 EParserError

2.16.1 Description

When an error occurs during the parsing of a stream, an `EParserError` is raised. Usually this indicates that an invalid token was found on the input stream, or the token read from the stream wasn't the expected token.

2.17 EReadError

2.17.1 Description

If an error occurs when reading from a stream, a `EReadError` exception is raised. Possible causes for this are:

1. Not enough data is available when reading from a stream
2. The stream containing a component's data contains invalid data. this will occur only when reading a component from a stream.

2.18 EResNotFound

2.18.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

2.19 EStreamError

2.19.1 Description

An `EStreamError` is raised when an error occurs during reading from or writing to a stream: Possible causes are

1. Not enough data is available in the stream.
2. Trying to seek beyond the beginning or end of the stream.
3. Trying to set the capacity of a memory stream and no memory is available.
4. Trying to write to a resource stream.

2.20 EStringListError

2.20.1 Description

When an error occurs in one of the methods of `TStrings` (332) then an `EStringListError` is raised. This can have one of the following causes:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
4. An attempt was made to add a duplicate entry to a `TStringList` (327) when `TStringList.AllowDuplicates` (327) is `False`.

2.21 EThread

2.21.1 Description

Thread error exception.

2.22 EThreadDestroyCalled

2.22.1 Description

Exception raised when a thread is destroyed illegally.

2.23 EWriteError

2.23.1 Description

If an error occurs when writing to a stream, a `EWriteError` exception is raised. Possible causes for this are:

1. The stream doesn't allow writing.
2. An error occurred when writing a property to a stream.

2.24 IDesignerNotify

2.24.1 Description

`IDesignerNotify` is an interface that can be used to communicate changes to a designer mechanism. It offers functionality for detecting changes, and notifications when the component is destroyed.

2.24.2 Method overview

Page	Property	Description
210	Modified	Notify that the component is modified.
210	Notification	Notification of owner changes

2.24.3 IDesignerNotify.Modified

Synopsis: Notify that the component is modified.

Declaration: `procedure Modified`

Visibility: default

Description: `Modified` can be used to notify a designer of changes, indicating that components should be streamed.

2.24.4 IDesignerNotify.Notification

Synopsis: Notification of owner changes

Declaration: `procedure Notification (AnObject: TPersistent; Operation: TOperation)`

Visibility: default

Description: `Notification` is the interface counterpart of `TComponent.Notification` ([258](#)) which is used to communicate adds to the components.

See also: `TComponent.Notification` ([258](#))

2.25 IInterfaceList

2.25.1 Description

`IInterfaceList` is an interface for maintaining a list of interfaces, strongly resembling the standard `TList` (290) class. It offers the same list of public methods as `TList`, with the exception that it uses interfaces instead of pointers.

All interfaces in the list should descend from `IUnknown`.

More detailed descriptions of how the various methods behave can be found in the `TList` reference.

2.25.2 Method overview

Page	Property	Description
214	Add	Add an interface to the list
213	Clear	Clear the list
213	Delete	Remove an interface from the list
213	Exchange	Exchange 2 interfaces in the list
214	First	Return the first non-empty interface in the list.
211	Get	Retrieve an interface pointer from the list.
212	GetCapacity	Return the capacity of the list.
212	GetCount	Return the current number of elements in the list.
214	IndexOf	Return the index of an interface.
214	Insert	Insert an interface in the list.
214	Last	Returns the last non-nil interface in the list.
215	Lock	Lock the list
212	Put	Write an item to the list
215	Remove	Remove an interface from the list
212	SetCapacity	Set the capacity of the list
213	SetCount	Set the number of items in the list
215	Unlock	Unlock the list.

2.25.3 Property overview

Page	Property	Access	Description
215	Capacity	rw	Capacity of the list
216	Count	rw	Current number of elements in the list.
216	Items	rw	Provides Index-based, sequential, access to the interfaces in the list.

2.25.4 IInterfaceList.Get

Synopsis: Retrieve an interface pointer from the list.

Declaration: `function Get(i: Integer) : IUnknown`

Visibility: default

Description: `Get` returns the interface pointer at position `i` in the list. It serves as the `Read` method for the `Items` (216) property.

See also: `IInterfaceList.Items` (216), `TList.Items` (296)

2.25.5 **InterfaceList.GetCapacity**

Synopsis: Return the capacity of the list.

Declaration: `function GetCapacity : Integer`

Visibility: default

Description: `GetCapacity` returns the current capacity of the list. It serves as the `Read` method for the `Capacity` (215) property.

See also: `InterfaceList.Capacity` (215), `TList.Capacity` (295)

2.25.6 **InterfaceList.GetCount**

Synopsis: Return the current number of elements in the list.

Declaration: `function GetCount : Integer`

Visibility: default

Description: It serves as the `Read` method for the `Count` (216) property.

See also: `InterfaceList.Count` (216), `TList.Count` (295)

2.25.7 **InterfaceList.Put**

Synopsis: Write an item to the list

Declaration: `procedure Put (i: Integer; item: IUnknown)`

Visibility: default

Description: `Put` writes the interface `Item` at position `I` in the list. It servers as the `Write` method for the `Items` (216) property.

See also: `InterfaceList.Items` (216), `TList.Items` (296)

2.25.8 **InterfaceList.SetCapacity**

Synopsis: Set the capacity of the list

Declaration: `procedure SetCapacity (NewCapacity: Integer)`

Visibility: default

Description: `SetCapacity` sets the capacity of the list to `NewCapacity`. It serves as the `Write` method for the `Capacity` (215) property.

See also: `InterfaceList.Capacity` (215), `TList.Capacity` (295)

2.25.9 **IInterfaceList.SetCount**

Synopsis: Set the number of items in the list

Declaration: `procedure SetCount (NewCount: Integer)`

Visibility: default

Description: `SetCount` sets the count of the list to `NewCount`. It serves as the `Write` method for the `Capacity` (215)

See also: `IInterfaceList.Count` (216), `TList.Count` (295)

2.25.10 **IInterfaceList.Clear**

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: default

Description: `Clear` removes all interfaces from the list. All interfaces in the list will be cleared (i.e. their reference count will decrease with 1)

See also: `TList.Clear` (291)

2.25.11 **IInterfaceList.Delete**

Synopsis: Remove an interface from the list

Declaration: `procedure Delete (index: Integer)`

Visibility: default

Description: `Delete` removes the interface at position `Index` from the list. It does this by explicitly clearing the interface and then removing the slot.

See also: `TList.Clear` (291), `IInterfaceList.Add` (214), `IInterfaceList.Delete` (213), `IInterfaceList.Insert` (214)

2.25.12 **IInterfaceList.Exchange**

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange (index1: Integer; index2: Integer)`

Visibility: default

Description: `Exchange` exchanges 2 interfaces in the list at locations `index1` and `Index2`.

See also: `TList.Exchange` (292), `IInterfaceList.Add` (214), `IInterfaceList.Delete` (213), `IInterfaceList.Insert` (214)

2.25.13 **InterfaceList.First**

Synopsis: Return the first non-empty interface in the list.

Declaration: `function First : IUnknown`

Visibility: default

Description: `First` returns the first non-empty interface in the list.

See also: `TList.First` (293), `InterfaceList.IndexOf` (214), `InterfaceList.Last` (214)

2.25.14 **InterfaceList.IndexOf**

Synopsis: Return the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: default

Description: `IndexOf` returns the location in the list of the interface `Item`. If there is no such interface in the list, then -1 is returned.

See also: `TList.IndexOf` (293), `InterfaceList.First` (214), `InterfaceList.Last` (214)

2.25.15 **InterfaceList.Add**

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: default

Description: `Add` adds the interface `Item` to the list, and returns the position at which it has been added.

See also: `TList.Add` (291), `InterfaceList.Insert` (214), `InterfaceList.Delete` (213)

2.25.16 **InterfaceList.Insert**

Synopsis: Insert an interface in the list.

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: default

Description: `Insert` inserts the interface `Item` in the list, at position `I`, shifting all items one position.

See also: `TList.Insert` (293), `InterfaceList.Add` (214), `InterfaceList.Delete` (213)

2.25.17 **InterfaceList.Last**

Synopsis: Returns the last non-nil interface in the list.

Declaration: `function Last : IUnknown`

Visibility: default

Description: `Last` returns the last non-empty interface in the list.

See also: `TList.Last` (293), `InterfaceList.First` (214), `InterfaceList.IndexOf` (214)

2.25.18 **IInterfaceList.Remove**

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: default

Description: `Remove` searches for the first occurrence of `Item` in the list and deletes it.

See also: `TList.Remove` ([294](#)), `IInterfaceList.Delete` ([213](#)), `IInterfaceList.IndexOf` ([214](#))

2.25.19 **IInterfaceList.Lock**

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: default

Description: `Lock` locks the list and returns an instance to the internal list. After a call to lock, the object list can only be accessed by the current thread, until `UnLock` ([215](#)) is called.

See also: `TList.Lock` ([290](#)), `IInterfaceList.Unlock` ([215](#))

2.25.20 **IInterfaceList.Unlock**

Synopsis: Unlock the list.

Declaration: `procedure Unlock`

Visibility: default

Description: `Unlock` unlocks a locked list. After a call to `UnLock`, other lists are again able to access the list.

See also: `TList.UnLock` ([290](#)), `IInterfaceList.Lock` ([215](#))

2.25.21 **IInterfaceList.Capacity**

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: default

Access: Read,Write

Description: `Capacity` is the maximum number of elements the list can hold without needing to reallocate memory for the list. It can be set to improve speed when adding a lot of items to the list.

See also: `TList.Capacity` ([295](#)), `IInterfaceList.Count` ([216](#))

2.25.22 **InterfaceList.Count**

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: default

Access: Read,Write

Description: `Count` is the current number of elements in the list. Setting it to a larger number will allocate empty slots. Setting it to a smaller number will clear any interfaces that fall outside the new border.

See also: `InterfaceList.Capacity` (215), `TList.Count` (295)

2.25.23 **InterfaceList.Items**

Synopsis: Provides Index-based, sequential, access to the interfaces in the list.

Declaration: `Property Items[index: Integer]: IUnknown; default`

Visibility: default

Access: Read,Write

Description: `Items` is the default property of the interface list and provides index-based array access to the interfaces in the list. Allowed values for `Index` include 0 to `Count-1`

See also: `InterfaceList.Count` (216), `TList.Items` (296)

2.26 **IStreamPersist**

2.26.1 **Description**

`IStreamPersist` defines an interface for object persistence streaming to a stream. Any class implementing this interface is expected to be able to save or load it's state from or to a stream.

2.26.2 **Method overview**

Page	Property	Description
216	<code>LoadFromStream</code>	Load persistent data from stream.
217	<code>SaveToStream</code>	Save persistent data to stream.

2.26.3 **IStreamPersist.LoadFromStream**

Synopsis: Load persistent data from stream.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: default

Description: `LoadFromStream` is the method called when the object should load it's state from the stream stream. It should be able to read the data which was written using the `SaveToStream` method.

See also: `TPersistent` (304), `TComponent` (258), `TStream` (318), `IStreamPersist.SaveToStream` (217)

2.26.4 IStreamPersist.SaveToStream

Synopsis: Save persistent data to stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: default

Description: `SaveFromStream` is the method called when the object should load it's state from the stream `stream`. The data written by this method should be readable by the `LoadFromStream` method.

See also: `TPersistent` (304), `TComponent` (258), `TStream` (318), `IStreamPersist.LoadFromStream` (216)

2.27 IStringsAdapter

2.27.1 Description

Is not yet supported in Free Pascal.

2.27.2 Method overview

Page	Property	Description
217	<code>ReferenceStrings</code>	Add a reference to the indicated strings.
217	<code>ReleaseStrings</code>	Release the reference to the strings.

2.27.3 IStringsAdapter.ReferenceStrings

Synopsis: Add a reference to the indicated strings.

Declaration: `procedure ReferenceStrings(S: TStrings)`

Visibility: default

2.27.4 IStringsAdapter.ReleaseStrings

Synopsis: Release the reference to the strings.

Declaration: `procedure ReleaseStrings`

Visibility: default

2.28 TAbstractObjectReader

2.28.1 Description

The Free Pascal streaming mechanism, while compatible with Delphi's mechanism, differs from it in the sense that the streaming mechanism uses a driver class when streaming components. The `TAbstractObjectReader` class is the base driver class for reading property values from streams. It consists entirely of abstract methods, which must be implemented by descendent classes.

Different streaming mechanisms can be implemented by making a descendent from `TAbstractObjectReader`. The `TBinaryObjectReader` (234) class is such a descendent class, which streams data in binary (Delphi compatible) format.

All methods described in this class, mustbe implemented by descendent classes.

2.28.2 Method overview

Page	Property	Description
219	BeginComponent	Marks the reading of a new component.
219	BeginProperty	Marks the reading of a property value.
218	BeginRootComponent	Starts the reading of the root component.
218	NextValue	Returns the type of the next value in the stream.
219	ReadBinary	Read binary data from the stream.
220	ReadCurrency	Read a currency value from the stream.
220	ReadDate	Read a date value from the stream.
220	ReadFloat	Read a float value from the stream.
221	ReadIdent	Read an identifier from the stream.
222	ReadInt16	Read a 16-bit integer from the stream.
222	ReadInt32	Read a 32-bit integer from the stream.
222	ReadInt64	Read a 64-bit integer from the stream.
221	ReadInt8	Read an 8-bit integer from the stream.
223	ReadSet	Reads a set from the stream.
220	ReadSingle	Read a single (real-type) value from the stream.
223	ReadStr	Read a shortstring from the stream
223	ReadString	Read a string of type <code>StringType</code> from the stream.
218	ReadValue	Reads the type of the next value.
224	ReadWideString	Read a widestring value from the stream.
224	SkipComponent	Skip till the end of the component.
224	SkipValue	Skip the current value.

2.28.3 TAbstractObjectReader.NextValue

Synopsis: Returns the type of the next value in the stream.

Declaration: `function NextValue : TValueType; Virtual; Abstract`

Visibility: `public`

Description: This function should return the type of the next value in the stream, but should not read it, i.e. the stream position should not be altered by this method. This is used to 'peek' in the stream what value is next.

See also: `TAbstractObjectReader.ReadValue` ([218](#))

2.28.4 TAbstractObjectReader.ReadValue

Synopsis: Reads the type of the next value.

Declaration: `function ReadValue : TValueType; Virtual; Abstract`

Visibility: `public`

Description: This function returns the type of the next value in the stream and reads it. i.e. after the call to this method, the stream is positioned to read the value of the type returned by this function.

See also: `TAbstractObjectReader.ReadValue` ([218](#))

2.28.5 TAbstractObjectReader.BeginRootComponent

Synopsis: Starts the reading of the root component.

Declaration: `procedure BeginRootComponent; Virtual; Abstract`

Visibility: `public`

Description: This function can be used to initialize the driver class for reading a component. It is called once at the beginning of the read process, and is immediatly followed by a call to `BeginComponent` (219).

See also: `TAbstractObjectReader.BeginComponent` (219)

2.28.6 TAbstractObjectReader.BeginComponent

Synopsis: Marks the reading of a new component.

Declaration: `procedure BeginComponent(var Flags: TFileFlags;var AChildPos: Integer;
var CompClassName: String;var CompName: String)
; Virtual; Abstract`

Visibility: `public`

Description: This method is called when the streaming process wants to start reading a new component.

Descendent classes should override this method to read the start of a component new component definition and return the needed arguments. `Flags` should be filled with any flags that were found at the component definition, as well as `AChildPos`. The `CompClassName` should be filled with the class name of the streamed component, and the `CompName` argument should be filled with the name of the component.

See also: `TAbstractObjectReader.BeginRootComponent` (218), `TAbstractObjectReader.BeginProperty` (219)

2.28.7 TAbstractObjectReader.BeginProperty

Synopsis: Marks the reading of a property value.

Declaration: `function BeginProperty : String; Virtual; Abstract`

Visibility: `public`

Description: `BeginProperty` is called by the streaming system when it wants to read a new property. The return value of the function is the name of the property which can be read from the stream.

See also: `TAbstractObjectReader.BeginComponent` (219)

2.28.8 TAbstractObjectReader.ReadBinary

Synopsis: Read binary data from the stream.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Virtual; Abstract`

Visibility: `public`

Description: `ReadBinary` is called when binary data should be read from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaBinary`). The data should be stored in the `DestData` memory stream by descendent classes.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadStr` (223), `TabstractObjectReader.ReadString` (223)

2.28.9 TAbstractObjectReader.ReadFloat

Synopsis: Read a float value from the stream.

Declaration: `function ReadFloat : Extended; Virtual; Abstract`

Visibility: `public`

Description: `ReadFloat` is called by the streaming system when it wants to read a float from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaExtended`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadString` (223)

2.28.10 TAbstractObjectReader.ReadSingle

Synopsis: Read a single (real-type) value from the stream.

Declaration: `function ReadSingle : Single; Virtual; Abstract`

Visibility: `public`

Description: `ReadSingle` is called by the streaming system when it wants to read a single-type float from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaSingle`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadString` (223)

2.28.11 TAbstractObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Virtual; Abstract`

Visibility: `public`

Description: `ReadCurrency` is called when a currency-typed value should be read from the stream. This abstract method should be overridden by descendent classes, and should return the currency value read from the stream.

See also: `TAbstractObjectWriter.WriteCurrency` (227)

2.28.12 TAbstractObjectReader.ReadDate

Synopsis: Read a date value from the stream.

Declaration: `function ReadDate : TDateTime; Virtual; Abstract`

Visibility: `public`

Description: `ReadDate` is called by the streaming system when it wants to read a date/time value from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaDate`). The return value should be the date/time value. (This value can be stored as a float, since `TDateTime` is nothing but a float.)

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TAbstractObjectReader.ReadSet` (223), `TAbstractObjectReader.ReadStr` (223), `TAbstractObjectReader.ReadString` (223)

2.28.13 TAbstractObjectReader.ReadIdent

Synopsis: Read an identifier from the stream.

Declaration: `function ReadIdent(ValueType: TValueType) : String; Virtual; Abstract`

Visibility: public

Description: `ReadIdent` is called by the streaming system if it expects to read an identifier of type `ValueType` from the stream after a call to `ReadValue` (218) returned `vaIdent`. The identifier should be returned as a string. Note that in some cases the identifier does not actually have to be in the stream;

Table 2.15:

ValueType	Expected value
<code>vaIdent</code>	Read from stream.
<code>vaNil</code>	'Nil'. This does not have to be read from the stream.
<code>vaFalse</code>	'False'. This does not have to be read from the stream.
<code>vaTrue</code>	'True'. This does not have to be read from the stream.
<code>vaNull</code>	'Null'. This does not have to be read from the stream.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TAbstractObjectReader.ReadSet` (223), `TAbstractObjectReader.ReadStr` (223), `TAbstractObjectReader.ReadString` (223)

2.28.14 TAbstractObjectReader.ReadInt8

Synopsis: Read an 8-bit integer from the stream.

Declaration: `function ReadInt8 : ShortInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt8` is called by the streaming process if it expects to read an integer value with a size of 8 bits (1 byte) from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaInt8`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 1 byte.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TAbstractObjectReader.ReadSet` (223), `TAbstractObjectReader.ReadStr` (223), `TAbstractObjectReader.ReadString` (223)

2.28.15 TAbstractObjectReader.ReadInt16

Synopsis: Read a 16-bit integer from the stream.

Declaration: `function ReadInt16 : SmallInt; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt16` is called by the streaming process if it expects to read an integer value with a size of 16 bits (2 bytes) from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaInt16`). The return value is the value if the integer. Note that the size of the value in the stream does not actually have to be 2 bytes.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadStr` (223), `TabstractObjectReader.ReadString` (223)

2.28.16 TAbstractObjectReader.ReadInt32

Synopsis: Read a 32-bit integer from the stream.

Declaration: `function ReadInt32 : LongInt; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt32` is called by the streaming process if it expects to read an integer value with a size of 32 bits (4 bytes) from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaInt32`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 4 bytes.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadStr` (223), `TabstractObjectReader.ReadString` (223)

2.28.17 TAbstractObjectReader.ReadInt64

Synopsis: Read a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt64` is called by the streaming process if it expects to read an `int64` value with a size of 64 bits (8 bytes) from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaInt64`). The return value is the value if the integer. Note that the size of the value in the stream does not actually have to be 8 bytes.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadStr` (223), `TabstractObjectReader.ReadString` (223)

2.28.18 TAbstractObjectReader.ReadSet

Synopsis: Reads a set from the stream.

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Virtual; Abstract`

Visibility: public

Description: This method is called by the streaming system if it expects to read a set from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaSet`). The return value is the contents of the set, encoded in a bitmask the following way:

For each (enumerated) value in the set, the bit corresponding to the ordinal value of the enumerated value should be set. i.e. as `1 shl ord(value)`.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadStr` (223), `TabstractObjectReader.ReadString` (223)

2.28.19 TAbstractObjectReader.ReadStr

Synopsis: Read a shortstring from the stream

Declaration: `function ReadStr : String; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a shortstring from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaLString`, `vaWString` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadString` (223)

2.28.20 TAbstractObjectReader.ReadString

Synopsis: Read a string of type `StringType` from the stream.

Declaration: `function ReadString (StringType: TValueType) : String; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (218) returned a valuetype of `vaLString`, `vaWString` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (220), `TAbstractObjectReader.ReadDate` (220), `TAbstractObjectReader.ReadSingle` (220), `TAbstractObjectReader.ReadIdent` (221), `TAbstractObjectReader.ReadInt8` (221), `TAbstractObjectReader.ReadInt16` (222), `TAbstractObjectReader.ReadInt32` (222), `TAbstractObjectReader.ReadInt64` (222), `TabstractObjectReader.ReadSet` (223), `TabstractObjectReader.ReadStr` (223)

2.28.21 TAbstractObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Virtual; Abstract`

Visibility: public

Description: `ReadWideString` is called when a widestring-typed value should be read from the stream. This abstract method should be overridden by descendent classes.

See also: `TAbstractObjectWriter.WriteWideString` ([228](#))

2.28.22 TAbstractObjectReader.SkipComponent

Synopsis: Skip till the end of the component.

Declaration: `procedure SkipComponent (SkipComponentInfos: Boolean); Virtual
; Abstract`

Visibility: public

Description: This method is used to skip the entire declaration of a component in the stream. Each descendent of `TAbstractObjectReader` should implement this in a way which is optimal for the implemented stream format.

See also: `TAbstractObjectReader.BeginComponent` ([219](#)), `TAbstractObjectReader.SkipValue` ([224](#))

2.28.23 TAbstractObjectReader.SkipValue

Synopsis: Skip the current value.

Declaration: `procedure SkipValue; Virtual; Abstract`

Visibility: public

Description: `SkipValue` should be used when skipping a value in the stream; The method should determine the type of the value which should be skipped by itself, if this is necessary.

See also: `TAbstractObjectReader.SkipComponent` ([224](#))

2.29 TAbstractObjectWriter

2.29.1 Description

Abstract driver class for writing component data.

2.29.2 Method overview

Page	Property	Description
225	BeginCollection	Start writing a collection.
225	BeginComponent	Start writing a component
225	BeginList	Start writing a list.
226	BeginProperty	Start writing a property
226	EndList	Mark the end of a list.
226	EndProperty	Marks the end of writing of a property.
226	WriteBinary	Writes binary data to the stream.
226	WriteBoolean	Writes a boolean value to the stream.
227	WriteCurrency	Write a currency value to the stream
227	WriteDate	Writes a date type to the stream.
226	WriteFloat	Writes a float value to the stream.
227	WriteIdent	Writes an identifier to the stream.
227	WriteInteger	Writes an integer value to the stream
228	WriteMethodName	Writes a methodname to the stream.
228	WriteSet	Writes a set value to the stream.
227	WriteSingle	Writes a single-type real value to the stream.
228	WriteString	Writes a string value to the stream.
228	WriteWideString	Write a widestring value to the stream

2.29.3 TAbstractObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Virtual; Abstract`

Visibility: `public`

Description: Start writing a collection.

2.29.4 TAbstractObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent (Component: TComponent; Flags: TFileFlags;
ChildPos: Integer); Virtual; Abstract`

Visibility: `public`

Description: Start writing a component

2.29.5 TAbstractObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Virtual; Abstract`

Visibility: `public`

Description: Start writing a list.

2.29.6 TAbstractObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Virtual; Abstract`

Visibility: `public`

Description: Mark the end of a list.

2.29.7 TAbstractObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: String); Virtual; Abstract`

Visibility: `public`

Description: Start writing a property

2.29.8 TAbstractObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Virtual; Abstract`

Visibility: `public`

Description: Marks the end of writing of a property.

2.29.9 TAbstractObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: Writes binary data to the stream.

2.29.10 TAbstractObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Virtual; Abstract`

Visibility: `public`

Description: Writes a boolean value to the stream.

2.29.11 TAbstractObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Virtual; Abstract`

Visibility: `public`

Description: Writes a float value to the stream.

2.29.12 TAbstractObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Virtual; Abstract`

Visibility: public

Description: Writes a single-type real value to the stream.

2.29.13 TAbstractObjectWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency); Virtual; Abstract`

Visibility: public

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendent classes.

See also: `TAbstractObjectReader.ReadCurrency` ([220](#))

2.29.14 TAbstractObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Virtual; Abstract`

Visibility: public

Description: Writes a date type to the stream.

2.29.15 TAbstractObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: String); Virtual; Abstract`

Visibility: public

Description: Writes an identifier to the stream.

2.29.16 TAbstractObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream

Declaration: `procedure WriteInteger(Value: Int64); Virtual; Abstract`

Visibility: public

Description: Writes an integer value to the stream

2.29.17 TAbstractObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: String); Virtual; Abstract`

Visibility: public

Description: Writes a methodname to the stream.

2.29.18 TAbstractObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Virtual; Abstract`

Visibility: public

Description: Writes a set value to the stream.

2.29.19 TAbstractObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: String); Virtual; Abstract`

Visibility: public

Description: Writes a string value to the stream.

2.29.20 TAbstractObjectWriter.WriteWideString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString); Virtual; Abstract`

Visibility: public

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendent classes.

See also: `TAbstractObjectReader.ReadWideString` ([224](#))

2.30 TBasicAction

2.30.1 Description

`TBasicAction` implements a basic action class from which all actions are derived. It introduces all basic methods of an action, and implements functionality to maintain a list of clients, i.e. components that are connected with this action.

Do not create instances of `TBasicAction`. Instead, create a descendent class and create an instance of this class instead.

2.30.2 Method overview

Page	Property	Description
229	Create	Creates a new instance of a TBasicAction (228) class.
229	Destroy	Destroys the action.
230	Execute	Triggers the OnExecute (232) event
230	ExecuteTarget	Executes the action on the Target object
229	HandlesTarget	Determines whether Target can be handled by this action
231	RegisterChanges	Registers a new client with the action.
231	UnRegisterChanges	Unregisters a client from the list of clients
231	Update	Triggers the OnUpdate (232) event
230	UpdateTarget	Notify client controls when the action updates itself.

2.30.3 Property overview

Page	Property	Access	Description
231	ActionComponent	rw	Returns the component that initiated the action.
232	OnExecute	rw	Event triggered when the action executes.
232	OnUpdate	rw	Event triggered when the application is idle.

2.30.4 TBasicAction.Create

Synopsis: Creates a new instance of a TBasicAction ([228](#)) class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` calls the inherited constructor, and then initializes the list of clients controls (or action lists) by adding the `AClient` argument to the list of client controls.

Under normal circumstances it should not be necessary to create a TBasicAction descendent manually, actions are created in an IDE.

See also: TBasicAction.Destroy ([229](#)), TBasicAction.AssignClient ([228](#))

2.30.5 TBasicAction.Destroy

Synopsis: Destroys the action.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the list of client controls and then calls the inherited destructor.

An application programmer should not call `Destroy` directly; Instead `Free` should be called, if it needs to be called at all. Normally the controlling class (e.g. a TActionList) will destroy the action.

2.30.6 TBasicAction.HandlesTarget

Synopsis: Determines whether Target can be handled by this action

Declaration: `function HandlesTarget(Target: TObject) : Boolean; Virtual`

Visibility: `public`

Description: `HandlesTarget` returns `True` if `Target` is a valid client for this action and if so, if it is in a suitable state to execute the action. An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

In `TBasicAction` this method is empty; descendent classes should override this method to implement appropriate checks.

See also: `TBasicAction.UpdateTarget` (230), `TBasicAction.ExecuteTarget` (230)

2.30.7 TBasicAction.UpdateTarget

Synopsis: Notify client controls when the action updates itself.

Declaration: `procedure UpdateTarget(Target: TObject); Virtual`

Visibility: `public`

Description: `UpdateTarget` should update the client control specified by `Target` when the action updates itself. In `TBasicAction`, the implementation of `UpdateTarget` is empty. Descendent classes should override and implement `UpdateTarget` to actually update the `Target` object.

An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

See also: `TBasicAction.HandlesTarget` (229), `TBasicAction.ExecuteTarget` (230)

2.30.8 TBasicAction.ExecuteTarget

Synopsis: Executes the action on the `Target` object

Declaration: `procedure ExecuteTarget(Target: TObject); Virtual`

Visibility: `public`

Description: `ExecuteTarget` performs the action on the `Target` object. In `TBasicAction` this method does nothing. Descendent classes should implement the action to be performed. For instance an action to post data in a dataset could call the `Post` method of the dataset.

An application programmer should never call `ExecuteTarget` directly.

See also: `TBasicAction.HandlesTarget` (229), `TBasicAction.ExecuteTarget` (230), `TBasicAction.Execute` (230)

2.30.9 TBasicAction.Execute

Synopsis: Triggers the `OnExecute` (232) event

Declaration: `function Execute : Boolean; Dynamic`

Visibility: `public`

Description: `Execute` triggers the `OnExecute` event, if one is assigned. It returns `True` if the event handler was called, `False` otherwise.

2.30.10 TBasicAction.RegisterChanges

Synopsis: Registers a new client with the action.

Declaration: `procedure RegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `RegisterChanges` adds `Value` to the list of clients.

See also: `TBasicAction.UnregisterChanges` ([231](#))

2.30.11 TBasicAction.UnRegisterChanges

Synopsis: Unregisters a client from the list of clients

Declaration: `procedure UnRegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `UnregisterChanges` removes `Value` from the list of clients. This is called for instance when the action is destroyed, or when the client is assigned a new action.

See also: `TBasicAction.UnregisterChanges` ([231](#)), `TBasicAction.Destroy` ([229](#))

2.30.12 TBasicAction.Update

Synopsis: Triggers the `OnUpdate` ([232](#)) event

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` triggers the `OnUpdate` event, if one is assigned. It returns `True` if the event was triggered, or `False` if no event was assigned.

Application programmers should never run `Update` directly. The `Update` method is called automatically by the action mechanism; Normally this is in the Idle time of an application. An application programmer should assign the `OnUpdate` ([232](#)) event, and perform any checks in that handler.

See also: `TBasicAction.OnUpdate` ([232](#)), `TBasicAction.Execute` ([230](#)), `TBasicAction.UpdateTarget` ([230](#))

2.30.13 TBasicAction.ActionComponent

Synopsis: Returns the component that initiated the action.

Declaration: `Property ActionComponent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: `ActionComponent` is set to the component that caused the action to execute, e.g. a `toolbutton` or a `menu item`. The property is set just before the action executes, and is reset to `nil` after the action was executed.

See also: `TBasicAction.Execute` ([230](#)), `TBasicAction.OnExecute` ([232](#))

2.30.14 TBasicAction.OnExecute

Synopsis: Event triggered when the action executes.

Declaration: Property OnExecute : TNotifyEvent

Visibility: public

Access: Read,Write

Description: OnExecute is the event triggered when the action is activated (executed). The event is triggered e.g. when the user clicks e.g. on a menu item or a button associated to the action. The application programmer should provide a OnExecute event handler to execute whatever code is necessary when the button is pressed or the menu item is chosen.

Note that assigning an OnExecute handler will result in the Execute (230) method returning a True value. Predefined actions (such as dataset actions) will check the result of Execute and will not perform their normal task if the OnExecute handler was called.

See also: TBasicAction.Execute (230), TBasicAction.OnUpdate (232)

2.30.15 TBasicAction.OnUpdate

Synopsis: Event triggered when the application is idle.

Declaration: Property OnUpdate : TNotifyEvent

Visibility: public

Access: Read,Write

Description: OnUpdate is the event triggered when the application is idle, and the action is being updated. The OnUpdate event can be used to set the state of the action, for instance disable it if the action cannot be executed at this point in time.

See also: TBasicAction.Update (231), TBasicAction.OnExecute (232)

2.31 TBasicActionLink

2.31.1 Description

TBasicActionLink links an Action to its clients. With each client for an action, a TBasicActionLink class is instantiated to handle the communication between the action and the client. It passes events between the action and its clients, and thus presents the action with a uniform interface to the clients.

An application programmer should never use a TBasicActionLink instance directly; They are created automatically when an action is associated with a component. Component programmers should create specialized descendents of TBasicActionLink which communicate changes in the action to the component.

2.31.2 Method overview

Page	Property	Description
233	Create	Creates a new instance of the TBasicActionLink class
233	Destroy	Destroys the TBasicActionLink instance.
233	Execute	Calls the action's Execute method.
234	Update	Calls the action's Update method

2.31.3 Property overview

Page	Property	Access	Description
234	Action	rw	The action to which the link was assigned.
234	OnChange	rw	Event handler triggered when the action's properties change

2.31.4 TBasicActionLink.Create

Synopsis: Creates a new instance of the TBasicActionLink class

Declaration: `constructor Create(AClient: TObject); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a TBasicActionLink and assigns `AClient` as the client of the link.

Application programmers should never instantiate TBasicActionLink classes directly. An instance is created automatically when an action is assigned to a control (client).

Component programmers can override the create constructor to initialize further properties.

See also: TBasicActionLink.Destroy ([233](#))

2.31.5 TBasicActionLink.Destroy

Synopsis: Destroys the TBasicActionLink instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unregisters the TBasicActionLink with the action, and then calls the inherited destructor.

Application programmers should never call `Destroy` directly. If a link should be destroyed at all, the `Free` method should be called instead.

See also: TBasicActionLink.Create ([233](#))

2.31.6 TBasicActionLink.Execute

Synopsis: Calls the action's Execute method.

Declaration: `function Execute(AComponent: TComponent) : Boolean; Virtual`

Visibility: `public`

Description: `Execute` sets the `ActionComponent` ([231](#)) property of the associated Action ([234](#)) to `AComponent` and then calls the Action's `execute` ([230](#)) method. After the action has executed, the `ActionComponent` property is cleared again.

The return value of the function is the return value of the Action's `execute` method.

Application programmers should never call `Execute` directly. This method will be called automatically when the associated control is activated. (e.g. a button is clicked on)

Component programmers should call `Execute` whenever the action should be activated.

See also: TBasicActionLink.Action ([234](#)), TBasicAction.ActionComponent ([231](#)), TBasicAction.Execute ([230](#)), TBasicAction.onExecute ([232](#))

2.31.7 TBasicActionLink.Update

Synopsis: Calls the action's Update method

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` calls the associated Action's `Update` (231) method.

Component programmers can override the `Update` method to provide additional processing when the `Update` method occurs.

2.31.8 TBasicActionLink.Action

Synopsis: The action to which the link was assigned.

Declaration: `Property Action : TBasicAction`

Visibility: `public`

Access: `Read,Write`

Description: `Action` represents the Action (228) which was assigned to the client. Setting this property will unregister the client at the old action (if one existed) and registers the client at the new action.

See also: `TBasicAction` (228)

2.31.9 TBasicActionLink.OnChange

Synopsis: Event handler triggered when the action's properties change

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` is the event triggered when the action's properties change.

Application programmers should never need to assign this event. Component programmers can assign this event to have a client control reflect any changes in an Action's properties.

See also: `TBasicActionLink.Change` (232), `TBasicAction.Change` (228)

2.32 TBinaryObjectReader

2.32.1 Description

The `TBinaryObjectReader` class reads component data stored in binary form in a file. For this, it overrides or implements all abstract methods from `TAbstractObjectReader` (217). No new functionality is added by this class, it is a driver class for the streaming system.

2.32.2 Method overview

Page	Property	Description
236	<code>BeginComponent</code>	Start reading a component.
236	<code>BeginProperty</code>	Start reading a property.
236	<code>BeginRootComponent</code>	Start reading the root component.
235	<code>Create</code>	Creates a new binary data reader instance.
235	<code>Destroy</code>	Destroys the binary data reader.
236	<code>NextValue</code>	Return the type of the next value.
237	<code>ReadBinary</code>	Start reading a binary value.
237	<code>ReadCurrency</code>	Read a currency value from the stream.
237	<code>ReadDate</code>	Read a date.
237	<code>ReadFloat</code>	Read a float value
238	<code>ReadIdent</code>	Read an identifier
238	<code>ReadInt16</code>	Read a 16-bits integer.
238	<code>ReadInt32</code>	Read a 32-bits integer.
239	<code>ReadInt64</code>	Read a 64-bits integer.
238	<code>ReadInt8</code>	Read an 8-bits integer.
239	<code>ReadSet</code>	Read a set
237	<code>ReadSingle</code>	Read a single-size float value
239	<code>ReadStr</code>	Read a short string
239	<code>ReadString</code>	Read a string
236	<code>ReadValue</code>	Read the next value in the stream
239	<code>ReadWideString</code>	Read a widestring value from the stream.
240	<code>SkipComponent</code>	Skip a component's data
240	<code>SkipValue</code>	Skip a value's data

2.32.3 TBinaryObjectReader.Create

Synopsis: Creates a new binary data reader instance.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new binary component data reader. The `Stream` stream is the stream from which data will be read. The `BufSize` argument is the size of the internal buffer that will be used by the reader. This can be used to optimize the reading process.

See also: `TAbstractObjectReader` ([217](#))

2.32.4 TBinaryObjectReader.Destroy

Synopsis: Destroys the binary data reader.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the buffer allocated when the instance was created. It also positions the stream on the last used position in the stream (the buffering may cause the reader to read more bytes than were actually used.)

See also: `TBinaryObjectReader.Create` ([235](#))

2.32.5 TBinaryObjectReader.NextValue

Synopsis: Return the type of the next value.

Declaration: `function NextValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` returns the type of the next value in a binary stream, but does not read the value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.6 TBinaryObjectReader.ReadValue

Synopsis: Read the next value in the stream

Declaration: `function ReadValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` reads the next value in a binary stream and returns the type of the read value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.7 TBinaryObjectReader.BeginRootComponent

Synopsis: Start reading the root component.

Declaration: `procedure BeginRootComponent; Override`

Visibility: `public`

Description: `BeginRootComponent` starts reading the root component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.8 TBinaryObjectReader.BeginComponent

Synopsis: Start reading a component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags; var AChildPos: Integer;
var CompClassName: String; var CompName: String)
; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.9 TBinaryObjectReader.BeginProperty

Synopsis: Start reading a property.

Declaration: `function BeginProperty : String; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.10 TBinaryObjectReader.ReadBinary

Synopsis: Start reading a binary value.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Override`

Visibility: `public`

Description: `ReadBinary` reads a binary value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.11 TBinaryObjectReader.ReadFloat

Synopsis: Read a float value

Declaration: `function ReadFloat : Extended; Override`

Visibility: `public`

Description: `ReadFloat` reads a float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.12 TBinaryObjectReader.ReadSingle

Synopsis: Read a single-size float value

Declaration: `function ReadSingle : Single; Override`

Visibility: `public`

Description: `ReadSingle` reads a single-sized float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.13 TBinaryObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Override`

Visibility: `public`

Description: `var>ReadCurrency` reads a currency-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([217](#)).

See also: `TAbstractObjectReader.ReadCurrency` ([220](#)), `TBinaryObjectWriter.WriteCurrency` ([243](#))

2.32.14 TBinaryObjectReader.ReadDate

Synopsis: Read a date.

Declaration: `function ReadDate : TDateTime; Override`

Visibility: `public`

Description: `ReadDate` reads a date value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.15 `TBinaryObjectReader.ReadIdent`

Synopsis: Read an identifier

Declaration: `function ReadIdent (ValueType: TValueType) : String; Override`

Visibility: public

Description: `ReadIdent` reads an identifier from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.16 `TBinaryObjectReader.ReadInt8`

Synopsis: Read an 8-bits integer.

Declaration: `function ReadInt8 : ShortInt; Override`

Visibility: public

Description: `Read8Int` reads an 8-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.17 `TBinaryObjectReader.ReadInt16`

Synopsis: Read a 16-bits integer.

Declaration: `function ReadInt16 : SmallInt; Override`

Visibility: public

Description: `Read16Int` reads a 16-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.18 `TBinaryObjectReader.ReadInt32`

Synopsis: Read a 32-bits integer.

Declaration: `function ReadInt32 : LongInt; Override`

Visibility: public

Description: `Read32Int` reads a 32-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.32.19 TBinaryObjectReader.ReadInt64

Synopsis: Read a 64-bits integer.

Declaration: `function ReadInt64 : Int64; Override`

Visibility: `public`

Description: `Read64Int` reads a 64-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.20 TBinaryObjectReader.ReadSet

Synopsis: Read a set

Declaration: `function ReadSet(EnumType: Pointer) : Integer; Override`

Visibility: `public`

Description: `ReadSet` reads a set from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.21 TBinaryObjectReader.ReadStr

Synopsis: Read a short string

Declaration: `function ReadStr : String; Override`

Visibility: `public`

Description: `ReadStr` reads a short string from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.22 TBinaryObjectReader.ReadString

Synopsis: Read a string

Declaration: `function ReadString(StringType: TValueType) : String; Override`

Visibility: `public`

Description: `ReadStr` reads a string of type `StringType` from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([217](#))

2.32.23 TBinaryObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Override`

Visibility: `public`

Description: `var>ReadWideString` reads a widestring-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` (217).

See also: `TAbstractObjectReader.ReadWideString` (224), `TBinaryObjectWriter.WriteWideString` (244)

2.32.24 `TBinaryObjectReader.SkipComponent`

Synopsis: Skip a component's data

Declaration: `procedure SkipComponent (SkipComponentInfos: Boolean);` `Override`

Visibility: `public`

Description: `SkipComponent` skips the data of a component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217).

2.32.25 `TBinaryObjectReader.SkipValue`

Synopsis: Skip a value's data

Declaration: `procedure SkipValue;` `Override`

Visibility: `public`

Description: `SkipComponent` skips the data of the next value in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (217)

2.33 `TBinaryObjectWriter`

2.33.1 Description

Driver class which stores component data in binary form.

2.33.2 Method overview

Page	Property	Description
241	BeginCollection	Start writing a collection.
242	BeginComponent	Start writing a component
242	BeginList	Start writing a list.
242	BeginProperty	Start writing a property
241	Create	Creates a new instance of a binary object writer.
241	Destroy	Destroys an instance of the binary object writer.
242	EndList	Mark the end of a list.
242	EndProperty	Marks the end of writing of a property.
242	WriteBinary	Writes binary data to the stream.
242	WriteBoolean	Writes a boolean value to the stream.
243	WriteCurrency	Write a currency-valued type to a stream
243	WriteDate	Writes a date type to the stream.
243	WriteFloat	Writes a float value to the stream.
243	WriteIdent	Writes an identifier to the stream.
243	WriteInteger	Writes an integer value to the stream.
244	WriteMethodName	Writes a methodname to the stream.
244	WriteSet	Writes a set value to the stream.
243	WriteSingle	Writes a single-type real value to the stream.
244	WriteString	Writes a string value to the stream.
244	WriteWideString	Write a widestring-valued type to a stream

2.33.3 TBinaryObjectWriter.Create

Synopsis: Creates a new instance of a binary object writer.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new instance of a binary object writer.

2.33.4 TBinaryObjectWriter.Destroy

Synopsis: Destroys an instance of the binary object writer.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys an instance of the binary object writer.

2.33.5 TBinaryObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Override`

Visibility: `public`

2.33.6 TBinaryObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent(Component: TComponent; Flags: TFileFlags;
ChildPos: Integer); Override`

Visibility: public

2.33.7 TBinaryObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Override`

Visibility: public

2.33.8 TBinaryObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Override`

Visibility: public

2.33.9 TBinaryObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: String); Override`

Visibility: public

2.33.10 TBinaryObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Override`

Visibility: public

2.33.11 TBinaryObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Override`

Visibility: public

2.33.12 TBinaryObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Override`

Visibility: public

2.33.13 TBinaryObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Override`

Visibility: `public`

2.33.14 TBinaryObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Override`

Visibility: `public`

2.33.15 TBinaryObjectWriter.WriteCurrency

Synopsis: Write a currency-valued type to a stream

Declaration: `procedure WriteCurrency(const Value: Currency); Override`

Visibility: `public`

Description: `WriteCurrency` writes a currency-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` ([224](#)).

See also: `TAbstractObjectWriter.WriteCurrency` ([227](#))

2.33.16 TBinaryObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Override`

Visibility: `public`

2.33.17 TBinaryObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: String); Override`

Visibility: `public`

2.33.18 TBinaryObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream.

Declaration: `procedure WriteInteger(Value: Int64); Override`

Visibility: `public`

2.33.19 TBinaryObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: String); Override`

Visibility: public

2.33.20 TBinaryObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Override`

Visibility: public

2.33.21 TBinaryObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: String); Override`

Visibility: public

2.33.22 TBinaryObjectWriter.WriteWideString

Synopsis: Write a widestring-valued type to a stream

Declaration: `procedure WriteWideString(const Value: WideString); Override`

Visibility: public

Description: `WriteWideString` writes a widestring-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` ([224](#)).

See also: `TAbstractObjectWriter.WriteString` ([228](#))

2.34 TBits

2.34.1 Description

`TBits` can be used to store collections of bits in an indexed array. This is especially useful for storing collections of booleans: Normally the size of a boolean is the size of the smallest enumerated type, i.e. 1 byte. Since a bit can take 2 values it can be used to store a boolean as well. Since `TBits` can store 8 bits in a byte, it takes 8 times less space to store an array of booleans in a `TBits` class than it would take to store them in a conventional array.

`TBits` introduces methods to store and retrieve bit values, apply masks, and search for bits.

2.34.2 Method overview

Page	Property	Description
247	AndBits	Performs an <code>and</code> operation on the bits.
246	Clear	Clears a particular bit.
246	Clearall	Clears all bits in the array.
245	Create	Creates a new bits collection.
245	Destroy	Destroys a bit collection
248	Equals	Determines whether the bits of 2 arrays are equal.
249	FindFirstBit	Find first bit with a particular value
249	FindNextBit	Searches the next bit with a particular value.
250	FindPrevBit	Searches the previous bit with a particular value.
248	Get	Retrieve the value of a particular bit
246	GetFSize	Returns the number of records used to store the bits.
248	Grow	Expands the bits array to the requested size.
248	NotBits	Performs a <code>not</code> operation on the bits.
250	OpenBit	Returns the position of the first bit that is set to <code>False</code> .
247	OrBits	Performs an <code>or</code> operation on the bits.
249	SetIndex	Sets the start position for FindNextBit (249) and FindPrevBit (250)
246	SetOn	Turn a particular bit on.
247	XorBits	Performs a <code>xor</code> operation on the bits.

2.34.3 Property overview

Page	Property	Access	Description
250	Bits	rw	Access to all bits in the array.
251	Size	rw	Current size of the array of bits.

2.34.4 TBits.Create

Synopsis: Creates a new bits collection.

Declaration: `constructor Create(TheSize: LongInt); Virtual`

Visibility: `public`

Description: `Create` creates a new bit collection with initial size `TheSize`. The size of the collection can be changed later on.

All bits are initially set to zero.

See also: [TBits.Destroy \(245\)](#)

2.34.5 TBits.Destroy

Synopsis: Destroys a bit collection

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys a previously created bit collection and releases all memory used to store the bit collection.

`Destroy` should never be called directly, `Free` should be used instead.

Errors: None.

See also: [TBits.Create \(245\)](#)

2.34.6 TBits.GetFSize

Synopsis: Returns the number of records used to store the bits.

Declaration: `function GetFSize : LongInt`

Visibility: `public`

Description: `GetFSize` returns the number of records used to store the current number of bits.

Errors: None.

See also: `TBits.Size` ([251](#))

2.34.7 TBits.SetOn

Synopsis: Turn a particular bit on.

Declaration: `procedure SetOn(Bit: LongInt)`

Visibility: `public`

Description: `SetOn` turns on the bit at position `bit`, i.e. sets it to 1. If `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` ([248](#)).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` ([206](#)) exception is raised.

See also: `TBits.Bits` ([250](#)), `TBits.clear` ([246](#))

2.34.8 TBits.Clear

Synopsis: Clears a particular bit.

Declaration: `procedure Clear(Bit: LongInt)`

Visibility: `public`

Description: `Clear` clears the bit at position `bit`. If the array `If bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` ([248](#)).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` ([206](#)) exception is raised.

See also: `TBits.Bits` ([250](#)), `TBits.clear` ([246](#))

2.34.9 TBits.Clearall

Synopsis: Clears all bits in the array.

Declaration: `procedure Clearall`

Visibility: `public`

Description: `ClearAll` clears all bits in the array, i.e. sets them to zero. `ClearAll` works faster than clearing all individual bits, since it uses the packed nature of the bits.

Errors: None.

See also: `TBits.Bits` ([250](#)), `TBits.clear` ([246](#))

2.34.10 TBits.AndBits

Synopsis: Performs an `and` operation on the bits.

Declaration: `procedure AndBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `and` operation on the bits in the array with the bits of array `BitSet`. If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are cleared.

Errors: None.

See also: `TBits.clearall` (246), `TBits.orbits` (247), `TBits.xorbits` (247), `TBits.notbits` (248)

2.34.11 TBits.OrBits

Synopsis: Performs an `or` operation on the bits.

Declaration: `procedure OrBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `or` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `or` operation is performed.

Errors: None.

See also: `TBits.clearall` (246), `TBits.andbits` (247), `TBits.xorbits` (247), `TBits.notbits` (248)

2.34.12 TBits.XorBits

Synopsis: Performs a `xor` operation on the bits.

Declaration: `procedure XorBits(BitSet: TBits)`

Visibility: `public`

Description: `XorBits` performs a `xor` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `xor` operation is performed.

Errors: None.

See also: `TBits.clearall` (246), `TBits.andbits` (247), `TBits.orbits` (247), `TBits.notbits` (248)

2.34.13 TBits.NotBits

Synopsis: Performs a not operation on the bits.

Declaration: `procedure NotBits (BitSet: TBits)`

Visibility: public

Description: `NotBits` performs a not operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

Errors: None.

See also: `TBits.clearall` (246), `TBits.andbits` (247), `TBits.orbits` (247), `TBits.xorbits` (247)

2.34.14 TBits.Get

Synopsis: Retrieve the value of a particular bit

Declaration: `function Get (Bit: LongInt) : Boolean`

Visibility: public

Description: `Get` returns `True` if the bit at position `bit` is set, or `False` if it is not set.

Errors: If `bit` is not a valid bit index then an `EBitsError` (206) exception is raised.

See also: `TBits.Bits` (250), `TBits.FindFirstBit` (249), `TBits.seton` (246)

2.34.15 TBits.Grow

Synopsis: Expands the bits array to the requested size.

Declaration: `procedure Grow (NBit: LongInt)`

Visibility: public

Description: `Grow` expands the bit array so it can at least contain `nbit` bits. If `nbit` is less than the current size, nothing happens.

Errors: If there is not enough memory to complete the operation, then an `EBitsError` (206) is raised.

See also: `TBits.Size` (251)

2.34.16 TBits.Equals

Synopsis: Determines whether the bits of 2 arrays are equal.

Declaration: `function Equals (BitSet: TBits) : Boolean`

Visibility: public

Description: `equals` returns `True` if all the bits in `BitSet` are the same as the ones in the current `BitSet`; if not, `False` is returned.

If the sizes of the two `BitSets` are different, the arrays are still reported equal when all the bits in the larger set, which are not present in the smaller set, are zero.

Errors: None.

See also: `TBits.clearall` (246), `TBits.andbits` (247), `TBits.orbits` (247), `TBits.xorbits` (247)

2.34.17 TBits.SetIndex

Synopsis: Sets the start position for FindNextBit (249) and FindPrevBit (250)

Declaration: `procedure SetIndex (Index: LongInt)`

Visibility: public

Description: `SetIndex` sets the search start position for `FindNextBit` (249) and `FindPrevBit` (250) to `Index`. This means that these calls will start searching from position `Index`.

This mechanism provides an alternative to `FindFirstBit` (249) which can also be used to position for the `FindNextBit` and `FindPrevBit` calls.

Errors: None.

See also: `TBits.FindNextBit` (249), `TBits.FindPrevBit` (250), `TBits.FindFirstBit` (249), `TBits.OpenBit` (250)

2.34.18 TBits.FindFirstBit

Synopsis: Find first bit with a particular value

Declaration: `function FindFirstBit (State: Boolean) : LongInt`

Visibility: public

Description: `FindFirstBit` searches for the first bit with value `State`. It returns the position of this bit, or `-1` if no such bit was found.

The search starts at position 0 in the array. If the first search returned a positive result, the found position is saved, and the `FindNextBit` (249) and `FindPrevBit` (250) will use this position to resume the search. To start a search from a certain position, the start position can be set with the `SetIndex` (249) instead.

Errors: None.

See also: `TBits.FindNextBit` (249), `TBits.FindPrevBit` (250), `TBits.OpenBit` (250), `TBits.SetIndex` (249)

2.34.19 TBits.FindNextBit

Synopsis: Searches the next bit with a particular value.

Declaration: `function FindNextBit : LongInt`

Visibility: public

Description: `FindNextBit` resumes a previously started search. It searches for the next bit with the value specified in the `FindFirstBit` (249). The search is done towards the end of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (249).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `TBits.FindFirstBit` (249), `TBits.FindPrevBit` (250), `TBits.OpenBit` (250), `TBits.SetIndex` (249)

2.34.20 TBits.FindPrevBit

Synopsis: Searches the previous bit with a particular value.

Declaration: `function FindPrevBit : LongInt`

Visibility: `public`

Description: `FindPrevBit` resumes a previously started search. It searches for the previous bit with the value specified in the `FindFirstBit` (249). The search is done towards the beginning of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (249).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `TBits.FindFirstBit` (249), `TBits.FindNextBit` (249), `TBits.OpenBit` (250), `TBits.SetIndex` (249)

2.34.21 TBits.OpenBit

Synopsis: Returns the position of the first bit that is set to `False`.

Declaration: `function OpenBit : LongInt`

Visibility: `public`

Description: `OpenBit` returns the position of the first bit whose value is `0` (`False`), or `-1` if no open bit was found. This call is equivalent to `FindFirstBit(False)`, except that it doesn't set the position for the next searches.

Errors: None.

See also: `TBits.FindFirstBit` (249), `TBits.FindPrevBit` (250), `TBits.FindFirstBit` (249), `TBits.SetIndex` (249)

2.34.22 TBits.Bits

Synopsis: Access to all bits in the array.

Declaration: `Property Bits[Bit: LongInt]: Boolean; default`

Visibility: `public`

Access: `Read, Write`

Description: `Bits` allows indexed access to all of the bits in the array. It gives `True` if the bit is `1`, `False` otherwise; Assigning to this property will set, respectively clear the bit.

Errors: If an index is specified which is out of the allowed range then an `EBitsError` (206) exception is raised.

See also: `TBits.Size` (251)

2.34.23 TBits.Size

Synopsis: Current size of the array of bits.

Declaration: `Property Size : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `Size` is the current size of the bit array. Setting this property will adjust the size; this is equivalent to calling `Grow(Value-1)`

Errors: If an invalid size (negative or too large) is specified, a `EBitsError` (206) exception is raised.

See also: `TBits.Bits` (250)

2.35 TCollection

2.35.1 Description

`TCollection` implements functionality to manage a collection of named objects. Each of these objects needs to be a descendent of the `TCollectionItem` (256) class. Exactly which type of object is managed can be seen from the `TCollection.ItemClass` (255) property.

Normally, no `TCollection` is created directly. Instead, a descendent of `TCollection` and `TCollectionItem` (256) are created as a pair.

2.35.2 Method overview

Page	Property	Description
252	Add	Creates and adds a new item to the collection.
252	Assign	Assigns one collection to another.
253	BeginUpdate	Start an update batch.
253	Clear	Removes all items from the collection.
251	Create	Creates a new collection.
254	Delete	Delete an item from the collection.
252	Destroy	Destroys the collection and frees all the objects it manages.
254	EndUpdate	Ends an update batch.
254	FindItemID	Searches for an Item in the collection, based on its <code>TCollectionItem.ID</code> (257) property.
254	Insert	Insert an item in the collection.
252	Owner	Owner of the collection.

2.35.3 Property overview

Page	Property	Access	Description
255	Count	r	Number of items in the collection.
255	ItemClass	r	Class pointer for each item in the collection.
255	Items	rw	Indexed array of items in the collection.

2.35.4 TCollection.Create

Synopsis: Creates a new collection.

Declaration: `constructor Create(AItemClass: TCollectionItemClass)`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TCollection` class which will manage objects of class `AItemClass`. It creates the list used to hold all objects, and stores the `AItemClass` for the adding of new objects to the collection.

See also: `TCollection.ItemClass` ([255](#)), `TCollection.Destroy` ([252](#))

2.35.5 TCollection.Destroy

Synopsis: Destroys the collection and frees all the objects it manages.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first clears the collection, and then frees all memory allocated to this instance. Don't call `Destroy` directly, call `Free` instead.

See also: `TCollection.Create` ([251](#))

2.35.6 TCollection.Owner

Synopsis: Owner of the collection.

Declaration: `function Owner : TPersistent`

Visibility: `public`

Description: `Owner` returns a reference to the owner of the collection. This property is required by the object inspector to be able to show the collection.

2.35.7 TCollection.Add

Synopsis: Creates and adds a new item to the collection.

Declaration: `function Add : TCollectionItem`

Visibility: `public`

Description: `Add` instantiates a new item of class `TCollection.ItemClass` ([255](#)) and adds it to the list. The newly created object is returned.

See also: `TCollection.ItemClass` ([255](#)), `TCollection.Clear` ([253](#))

2.35.8 TCollection.Assign

Synopsis: Assigns one collection to another.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` assigns the contents of one collection to another. It does this by clearing the items list, and adding as much elements as there are in the `Source` collection; it assigns to each created element the contents of it's counterpart in the `Source` element.

Two collections cannot be assigned to each other if instances of the `ItemClass` classes cannot be assigned to each other.

Errors: If the objects in the collections cannot be assigned to one another, then an `EConvertError` is raised.

See also: `TPersistent.Assign` (304), `TCollectionItem` (256)

2.35.9 TCollection.BeginUpdate

Synopsis: Start an update batch.

Declaration: `procedure BeginUpdate`

Visibility: `public`

Description: `BeginUpdate` is called at the beginning of a batch update. It raises the update count with 1.

Call `BeginUpdate` at the beginning of a series of operations that will change the state of the collection. This will avoid the call to `TCollection.Update` (251) for each operation. At the end of the operations, a corresponding call to `EndUpdate` must be made. It is best to do this in the context of a `Try ... finally` block:

```
With MyCollection Do
  try
    BeginUpdate;
    // Some Lengthy operations
  finally
    EndUpdate;
  end;
```

This insures that the number of calls to `BeginUpdate` always matches the number of calls to `TCollection.EndUpdate` (254), even in case of an exception.

See also: `TCollection.EndUpdate` (254), `TCollection.Changed` (251), `TCollection.Update` (251)

2.35.10 TCollection.Clear

Synopsis: Removes all items from the collection.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` will clear the collection, i.e. each item in the collection is destroyed and removed from memory. After a call to `Clear`, `Count` is zero.

See also: `TCollection.Add` (252), `TCollectionItem.Destroy` (256), `TCollection.Destroy` (252)

2.35.11 TCollection.EndUpdate

Synopsis: Ends an update batch.

Declaration: `procedure EndUpdate`

Visibility: `public`

Description: `EndUpdate` signals the end of a series of operations that change the state of the collection, possibly triggering an update event. It does this by decreasing the update count with 1 and calling `TCollection.Changed` (251) it should always be used in conjunction with `TCollection.BeginUpdate` (253), preferably in the `Finally` section of a `Try ... Finally` block.

See also: `TCollection.BeginUpdate` (253), `TCollection.Changed` (251), `TCollection.Update` (251)

2.35.12 TCollection.Delete

Synopsis: Delete an item from the collection.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at (zero based) position `Index` from the collection. This will result in a `cnDeleted` notification.

Errors: If an invalid index is specified, an exception is raised.

See also: `TCollection.Items` (255), `TCollection.Insert` (254), `TCollection.Clear` (253)

2.35.13 TCollection.Insert

Synopsis: Insert an item in the collection.

Declaration: `function Insert(Index: Integer) : TCollectionItem`

Visibility: `public`

Description: `Insert` creates a new item instance and inserts it in the collection at position `Index`, and returns the new instance.

In contrast, `TCollection.Add` (252) adds a new item at the end.

Errors: None.

See also: `TCollection.Add` (252), `TCollection.Delete` (254), `TCollection.Items` (255)

2.35.14 TCollection.FindItemID

Synopsis: Searches for an Item in the collection, based on its `TCollectionItem.ID` (257) property.

Declaration: `function FindItemID(ID: Integer) : TCollectionItem`

Visibility: `public`

Description: `FindItemID` searches through the collection for the item that has a value of `ID` for its `TCollectionItem.ID` (257) property, and returns the found item. If no such item is found in the collection, `Nil` is returned.

The routine performs a linear search, so this can be slow on very large collections.

See also: `TCollection.Items` (255), `TCollectionItem.ID` (257)

2.35.15 TCollection.Count

Synopsis: Number of items in the collection.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` contains the number of items in the collection.

Remark: The items in the collection are identified by their `TCollectionItem.Index` (257) property, which is a zero-based index, meaning that it can take values between 0 and `Count`.

See also: `TCollectionItem.Index` (257), `TCollection.Items` (255)

2.35.16 TCollection.ItemClass

Synopsis: Class pointer for each item in the collection.

Declaration: `Property ItemClass : TCollectionItemClass`

Visibility: public

Access: Read

Description: `ItemClass` is the class pointer with which each new item in the collection is created. It is the value that was passed to the collection's constructor when it was created, and does not change during the lifetime of the collection.

See also: `TCollectionItem` (256), `TCollection.Items` (255)

2.35.17 TCollection.Items

Synopsis: Indexed array of items in the collection.

Declaration: `Property Items[Index: Integer]: TCollectionItem`

Visibility: public

Access: Read, Write

Description: `Items` provides indexed access to the items in the collection. Since the array is zero-based, `Index` should be an integer between 0 and `Count-1`.

It is possible to set or retrieve an element in the array. When setting an element of the array, the object that is assigned should be compatible with the class of the objects in the collection, as given by the `TCollection.ItemClass` (255) property.

Adding an element to the array can be done with the `TCollection.Add` (252) method. The array can be cleared with the `TCollection.Clear` (253) method. Removing an element of the array should be done by freeing that element.

See also: `TCollection.Count` (255), `TCollection.ItemClass` (255), `TCollection.Clear` (253), `TCollection.Add` (252)

2.36 TCollectionItem

2.36.1 Description

TCollectionItem and TCollection (251) form a pair of base classes that manage a collection of named objects. The TCollectionItem is the named object that is managed, it represents one item in the collection. An item in the collection is represented by two properties: TCollectionItem.DisplayName (258), TCollection.Index (251) and TCollectionItem.ID (257).

A TCollectionItem object is never created directly. To manage a set of named items, it is necessary to make a descendant of TCollectionItem to which needed properties and methods are added. This descendant can then be managed with a TCollection (251) class. The managing collection will create and destroy it's items by itself, it should therefore never be necessary to create TCollectionItem descendants manually.

2.36.2 Method overview

Page	Property	Description
256	Create	Creates a new instance of this collection item.
256	Destroy	Destroys this collection item.

2.36.3 Property overview

Page	Property	Access	Description
257	Collection	rw	Pointer to the collection managing this item.
258	DisplayName	rw	Name of the item, displayed in the object inspector.
257	ID	r	Initial index of this item.
257	Index	rw	Index of the item in its managing collection TCollection.Items (255) property.

2.36.4 TCollectionItem.Create

Synopsis: Creates a new instance of this collection item.

Declaration: `constructor Create(ACollection: TCollection); Virtual`

Visibility: `public`

Description: `Create` instantiates a new item in a TCollection (251). It is called by the TCollection.Add (252) function and should under normal circumstances never be called directly. called

See also: TCollectionItem.Destroy (256)

2.36.5 TCollectionItem.Destroy

Synopsis: Destroys this collection item.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` removes the item from the managing collection and Destroys the item instance.

This is the only way to remove items from a collection;

See also: TCollectionItem.Create (256)

2.36.6 TCollectionItem.Collection

Synopsis: Pointer to the collection managing this item.

Declaration: `Property Collection : TCollection`

Visibility: `public`

Access: `Read, Write`

Description: `Collection` points to the collection managing this item. This property can be set to point to a new collection. If this is done, the old collection will be notified that the item should no longer be managed, and the new collection is notified that it should manage this item as well.

See also: `TCollection` ([251](#))

2.36.7 TCollectionItem.ID

Synopsis: Initial index of this item.

Declaration: `Property ID : Integer`

Visibility: `public`

Access: `Read`

Description: `ID` is the initial value of `TCollectionItem.Index` ([257](#)); it doesn't change after the index changes. It can be used to uniquely identify the item. The `ID` property doesn't change as items are added and removed from the collection.

While the `TCollectionItem.Index` ([257](#)) property forms a continuous series, `ID` does not. If items are removed from the collection, their `ID` is not used again, leaving gaps. Only when the collection is initially created, the `ID` and `Index` properties will be equal.

See also: `TCollection.Items` ([255](#)), `TCollectionItem.Index` ([257](#))

2.36.8 TCollectionItem.Index

Synopsis: Index of the item in its managing collection `TCollection.Items` ([255](#)) property.

Declaration: `Property Index : Integer`

Visibility: `public`

Access: `Read, Write`

Description: `Index` is the current index of the item in its managing collection's `TCollection.Items` ([255](#)) property. This property may change as items are added and removed from the collection.

The index of an item is zero-based, i.e. the first item has index zero. The last item has index `Count-1` where `Count` is the number of items in the collection.

The `Index` property of the items in a collection form a continuous series ranging from 0 to `Count-1`. The `TCollectionItem.ID` ([257](#)) property does not form a continuous series, but can also be used to identify an item.

See also: `TCollectionItem.ID` ([257](#)), `TCollection.Items` ([255](#))

2.36.9 TCollectionItem.DisplayName

Synopsis: Name of the item, displayed in the object inspector.

Declaration: `Property DisplayName : String`

Visibility: `public`

Access: `Read, Write`

Description: `DisplayName` contains the name of this item as shown in the object inspector. For `TCollectionItem` this returns always the class name of the managing collection, followed by the index of the item.

`TCollectionItem` does not implement any functionality to store the `DisplayName` property. The property can be set, but this will have no effect other than that the managing collection is notified of a change. The actual displayname will remain unchanged. To store the `DisplayName` property, `TCollectionItem` descendants should override the `TCollectionItem.SetDisplayName` (256) and `TCollectionItem.GetDisplayName` (256) to add storage functionality.

See also: `TCollectionItem.Index` (257), `TCollectionItem.ID` (257), `TCollectionItem.GetDisplayName` (256), `TCollectionItem.SetDisplayName` (256)

2.37 TComponent

2.37.1 Description

`TComponent` is the base class for any set of classes that needs owner-owned functionality, and which needs support for property streaming. All classes that should be handled by an IDE (Integrated Development Environment) must descend from `TComponent`, as it includes all support for streaming all its published properties.

Components can 'own' other components. `TComponent` introduces methods for enumerating the child components. It also allows to name the owned components with a unique name. Furthermore, functionality for sending notifications when a component is removed from the list or removed from memory altogether is also introduced in `TComponent`.

`TComponent` introduces a form of automatic memory management: When a component is destroyed, all its child components will be destroyed first.

2.37.2 Method overview

Page	Property	Description
260	BeforeDestruction	Overrides standard BeforeDestruction.
260	Create	Creates a new instance of the component.
260	Destroy	Destroys the instance of the component.
260	DestroyComponents	Destroy child components.
261	Destroying	Called when the component is being destroyed
261	ExecuteAction	Standard action execution method.
261	FindComponent	Finds and returns the named component in the owned components.
261	FreeNotification	Ask the component to notify called when it is being destroyed.
262	FreeOnRelease	Part of the <code>IVCLComObject</code> interface.
262	GetParentComponent	Returns the parent component.
262	HasParent	Does the component have a parent ?
263	InsertComponent	Insert the given component in the list of owned components.
263	RemoveComponent	Remove the given component from the list of owned components.
262	RemoveFreeNotification	Remove a component from the Free Notification list.
263	SafeCallException	Part of the <code>IVCLComObject</code> Interface.
263	SetSubComponent	Sets the <code>csSubComponent</code> style.
264	UpdateAction	Updates the state of an action.
259	WriteState	Writes the component to a stream.

2.37.3 Property overview

Page	Property	Access	Description
264	ComponentCount	r	Count of owned components
264	ComponentIndex	rw	Index of component in it's owner's list.
264	Components	r	Indexed list (zero-based) of all owned components.
265	ComponentState	r	Current component's state.
265	ComponentStyle	r	Current component's style.
265	DesignInfo	rw	Information for IDE designer.
266	Name	rws	Name of the component.
266	Owner	r	Owner of this component.
266	Tag	rw	Tag value of the component.
266	VCLComObject	rw	Not implemented.

2.37.4 TComponent.WriteState

Synopsis: Writes the component to a stream.

Declaration: `procedure WriteState(Writer: TWriter); Virtual`

Visibility: `public`

Description: `WriteState` writes the component's current state to a stream through the writer ([353](#)) object `writer`. Values for all published properties of the component can be written to the stream. Normally there is no need to call `WriteState` directly. The streaming system calls `WriteState` itself.

The `TComponent` ([258](#)) implementation of `WriteState` simply calls `TWriter.WriteData` ([353](#)). Descendent classes can, however, override `WriteState` to provide additional processing of stream data.

See also: `TComponent.ReadState` ([258](#)), `TStream.WriteComponent` ([322](#)), `TWriter.WriteData` ([353](#))

2.37.5 TComponent.Create

Synopsis: Creates a new instance of the component.

Declaration: `constructor Create(AOwner: TComponent); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a `TComponent` class. If `AOwner` is not `Nil`, the new component attempts to insert itself in the list of owned components of the owner.

See also: `TComponent.Insert` (258), `TComponent.Owner` (266)

2.37.6 TComponent.BeforeDestruction

Synopsis: Overrides standard `BeforeDestruction`.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` is overridden by `TComponent` to set the `csDestroying` flag in `ComponentState` (179)

See also: `ComponentState` (179)

2.37.7 TComponent.Destroy

Synopsis: Destroys the instance of the component.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` sends a `opRemove` notification to all components in the free-notification list. After that, all owned components are destroyed by calling `DestroyComponents` (260) (and hence removed from the list of owned components). When this is done, the component removes itself from its owner's child component list. After that, the parent's destroy method is called.

See also: `TComponent.Notification` (258), `TComponent.Owner` (266), `TComponent.DestroyComponents` (260), `TComponent.Components` (264)

2.37.8 TComponent.DestroyComponents

Synopsis: Destroy child components.

Declaration: `procedure DestroyComponents`

Visibility: `public`

Description: `DestroyComponents` calls the destructor of all owned components, till no more components are left in the `Components` (264) array.

Calling the destructor of an owned component has as the effect that the component will remove itself from the list of owned components, if nothing has disrupted the sequence of destructors.

Errors: If an overridden 'destroy' method does not call it's inherited destructor or raises an exception, it's `TComponent.Destroy` (260) destructor will not be called, which may result in an endless loop.

See also: `TComponent.Destroy` (260), `TComponent.Components` (264)

2.37.9 TComponent.Destroying

Synopsis: Called when the component is being destroyed

Declaration: `procedure Destroying`

Visibility: `public`

Description: `Destroying` sets the `csDestroying` flag in the component's state (258) property, and does the same for all owned components.

It is not necessary to call `Destroying` directly, the destructor `Destroy` (260) does this automatically.

See also: `TComponent.State` (258), `TComponent.Destroy` (260)

2.37.10 TComponent.ExecuteAction

Synopsis: Standard action execution method.

Declaration: `function ExecuteAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: `public`

Description: `ExecuteAction` checks whether `Action` handles the current component, and if yes, calls the `ExecuteAction` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (228), `TBasicAction.ExecuteAction` (228), `TBasicAction.HandlesTarget` (229), `UpdateAction` (179)

2.37.11 TComponent.FindComponent

Synopsis: Finds and returns the named component in the owned components.

Declaration: `function FindComponent(const AName: String) : TComponent`

Visibility: `public`

Description: `FindComponent` searches the component with name `AName` in the list of owned components. If `AName` is empty, then `Nil` is returned.

See also: `TComponent.Components` (264), `TComponent.Name` (266)

2.37.12 TComponent.FreeNotification

Synopsis: Ask the component to notify called when it is being destroyed.

Declaration: `procedure FreeNotification(AComponent: TComponent)`

Visibility: `public`

Description: `FreeNotification` inserts `AComponent` in the freenotification list. When the component is destroyed, the `Notification` (258) method is called for all components in the freenotification list.

See also: `TComponent.Components` (264), `TComponent.Notification` (258)

2.37.13 TComponent.RemoveFreeNotification

Synopsis: Remove a component from the Free Notification list.

Declaration: `procedure RemoveFreeNotification (AComponent: TComponent)`

Visibility: `public`

Description: `RemoveFreeNotification` removes `AComponent` from the `freenotification` list.

See also: `FreeNotification` ([179](#))

2.37.14 TComponent.FreeOnRelease

Synopsis: Part of the `IVCLComObject` interface.

Declaration: `procedure FreeOnRelease`

Visibility: `public`

Description: Provided for Delphi compatibility, but is not yet implemented.

2.37.15 TComponent.GetParentComponent

Synopsis: Returns the parent component.

Declaration: `function GetParentComponent : TComponent; Dynamic`

Visibility: `public`

Description: `GetParentComponent` can be implemented to return the parent component of this component. The implementation of this method in `TComponent` always returns `Nil`. Descendent classes must override this method to return the visual parent of the component.

See also: `TComponent.HasParent` ([262](#)), `TComponent.Owner` ([266](#))

2.37.16 TComponent.HasParent

Synopsis: Does the component have a parent ?

Declaration: `function HasParent : Boolean; Dynamic`

Visibility: `public`

Description: `HasParent` can be implemented to return whether the parent of the component exists. The implementation of this method in `TComponent` always returns `False`, and should be overridden by descendent classes to return `True` when a parent is available. If `HasParent` returns `True`, then `GetParentComponent` ([262](#)) will return the parent component.

See also: `TComponent.HasParent` ([262](#)), `TComponent.Owner` ([266](#))

2.37.17 TComponent.InsertComponent

Synopsis: Insert the given component in the list of owned components.

Declaration: `procedure InsertComponent (AComponent : TComponent)`

Visibility: public

Description: `InsertComponent` attempts to insert `AComponent` in the list with owned components. It first calls `ValidateComponent` (258) to see whether the component can be inserted. It then checks whether there are no name conflicts by calling `ValidateRename` (258). If neither of these checks have raised an exception the component is inserted, and notified of the insert.

See also: `TComponent.RemoveComponent` (263), `TComponent.Insert` (258), `TComponent.ValidateContainer` (258), `TComponent.ValidateRename` (258), `TComponent.Notification` (258)

2.37.18 TComponent.RemoveComponent

Synopsis: Remove the given component from the list of owned components.

Declaration: `procedure RemoveComponent (AComponent : TComponent)`

Visibility: public

Description: `RemoveComponent` will send an `opRemove` notification to `AComponent` and will then proceed to remove `AComponent` from the list of owned components.

See also: `TComponent.InsertComponent` (263), `TComponent.Remove` (258), `TComponent.ValidateRename` (258), `TComponent.Notification` (258)

2.37.19 TComponent.SafeCallException

Synopsis: Part of the `IVCLComObject` Interface.

Declaration: `function SafeCallException (ExceptObject : TObject; ExceptAddr : Pointer)
: Integer; Override`

Visibility: public

Description: Provided for Delphi compatibility, but not implemented.

2.37.20 TComponent.SetSubComponent

Synopsis: Sets the `csSubComponent` style.

Declaration: `procedure SetSubComponent (ASubComponent : Boolean)`

Visibility: public

Description: `SetSubComponent` includes `csSubComponent` in the `ComponentStyle` (265) property if `ASubComponent` is `True`, and excludes it again if `ASubComponent` is `False`.

See also: `TComponent.ComponentStyle` (265)

2.37.21 TComponent.UpdateAction

Synopsis: Updates the state of an action.

Declaration: `function UpdateAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: public

Description: `UpdateAction` checks whether `Action` handles the current component, and if yes, calls the `UpdateTarget` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (228), `TBasicAction.UpdateTarget` (230), `TBasicAction.HandlesTarget` (229), `ExecuteAction` (179)

2.37.22 TComponent.Components

Synopsis: Indexed list (zero-based) of all owned components.

Declaration: `Property Components[Index: Integer]: TComponent`

Visibility: public

Access: Read

Description: `Components` provides indexed access to the list of owned components. `Index` can range from 0 to `ComponentCount-1` (264).

See also: `TComponent.ComponentCount` (264), `TComponent.Owner` (266)

2.37.23 TComponent.ComponentCount

Synopsis: Count of owned components

Declaration: `Property ComponentCount : Integer`

Visibility: public

Access: Read

Description: `ComponentCount` returns the number of components that the current component owns. It can be used to determine the valid index range in the `Component` (264) array.

See also: `TComponent.Components` (264), `TComponent.Owner` (266)

2.37.24 TComponent.ComponentIndex

Synopsis: Index of component in it's owner's list.

Declaration: `Property ComponentIndex : Integer`

Visibility: public

Access: Read, Write

Description: `ComponentIndex` is the index of the current component in its owner's list of components. If the component has no owner, the value of this property is -1.

See also: `TComponent.Components` (264), `TComponent.ComponentCount` (264), `TComponent.Owner` (266)

2.37.25 TComponent.ComponentState

Synopsis: Current component's state.

Declaration: `Property ComponentState : TComponentState`

Visibility: `public`

Access: `Read`

Description: `ComponentState` indicates the current state of the component. It is a set of flags which indicate the various stages in the lifetime of a component. The following values can occur in this set:

Table 2.16: Component states

Flag	Meaning
<code>csLoading</code>	The component is being loaded from stream
<code>csReading</code>	Component properties are being read from stream.
<code>csWriting</code>	Component properties are being written to stream.
<code>csDestroying</code>	The component or one of its owners is being destroyed.
<code>csAncestor</code>	The component is being streamed as part of a frame
<code>csUpdating</code>	The component is being updated
<code>csFixups</code>	References to other components are being resolved
<code>csFreeNotification</code>	The component has free notifications.
<code>csInline</code>	The component is being loaded as part of a frame
<code>csDesignInstance</code>	? not used.

The component state is set by various actions such as reading it from stream, destroying it etc.

See also: `TComponent.SetAncestor` (258), `TComponent.SetDesigning` (258), `TComponent.SetInline` (258), `TComponent.SetDesignInstance` (258), `TComponent.Updating` (258), `TComponent.Updated` (258), `TComponent.Loaded` (258)

2.37.26 TComponent.ComponentStyle

Synopsis: Current component's style.

Declaration: `Property ComponentStyle : TComponentStyle`

Visibility: `public`

Access: `Read`

Description: Current component's style.

2.37.27 TComponent.DesignInfo

Synopsis: Information for IDE designer.

Declaration: `Property DesignInfo : LongInt`

Visibility: `public`

Access: `Read, Write`

Description: `DesignInformation` can be used by an IDE to store design information in the component. It should not be used by an application programmer.

See also: `TComponent.Tag` (266)

2.37.28 TComponent.Owner

Synopsis: Owner of this component.

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read`

Description: `Owner` returns the owner of this component. The owner cannot be set except by explicitly inserting the component in another component's owned components list using that component's `InsertComponent` (263) method, or by removing the component from it's owner's owned component list using the `RemoveComponent` (263) method.

See also: `TComponent.Components` (264), `TComponent.InsertComponent` (263), `TComponent.RemoveComponent` (263)

2.37.29 TComponent.VCLComObject

Synopsis: Not implemented.

Declaration: `Property VCLComObject : Pointer`

Visibility: `public`

Access: `Read,Write`

Description: `VCLComObject` is not yet implemented in Free Pascal.

2.37.30 TComponent.Name

Synopsis: Name of the component.

Declaration: `Property Name : TComponentName`

Visibility: `published`

Access: `Read,Write`

Description: `Name` is the name of the component. This name should be a valid identifier, i.e. must start with a letter, and can contain only letters, numbers and the underscore character. When attempting to set the name of a component, the name will be checked for validity. Furthermore, when a component is owned by another component, the name must be either empty or must be unique among the child component names.

Errors: Attempting to set the name to an invalid value will result in an exception being raised.

See also: `TComponent.ValidateRename` (258), `TComponent.Owner` (266)

2.37.31 TComponent.Tag

Synopsis: Tag value of the component.

Declaration: `Property Tag : LongInt`

Visibility: `published`

Access: `Read,Write`

Description: `Tag` can be used to store an integer value in the component. This value is streamed together with all other published properties. It can be used for instance to quickly identify a component in an event handler.

See also: `TComponent.Name` (266)

2.38 TCustomMemoryStream

2.38.1 Description

`TCustomMemoryStream` is the parent class for streams that stored their data in memory. It introduces all needed functions to handle reading from and navigating through the memory, and introduces a `Memory` (269) property which points to the memory area where the stream data is kept.

The only thing which `TCustomMemoryStream` does not do is obtain memory to store data when writing data or the writing of data. This functionality is implemented in descendent streams such as `TMemoryStream` (296). The reason for this approach is that this way it is possible to create e.g. read-only descendents of `TCustomMemoryStream` that point to a fixed part in memory which can be read from, but not written to.

Remark: Since `TCustomMemoryStream` is an abstract class, do not create instances of `TMemoryStream` directly. Instead, create instances of descendents such as `TMemoryStream` (296).

2.38.2 Method overview

Page	Property	Description
267	<code>GetSize</code>	return the size of the stream.
267	<code>Read</code>	Reads <code>Count</code> bytes from the stream into <code>buffer</code> .
269	<code>SaveToFile</code>	Writes the contents of the stream to a file.
268	<code>SaveToStream</code>	Writes the contents of the memory stream to another stream.
268	<code>Seek</code>	Sets a new position in the stream.

2.38.3 Property overview

Page	Property	Access	Description
269	<code>Memory</code>	r	Pointer to the data kept in the memory stream.

2.38.4 TCustomMemoryStream.GetSize

Synopsis: return the size of the stream.

Declaration: `function GetSize : Int64; Override`

Visibility: public

Description: `GetSize` returns the size of the reserved memory. It should not be used directly.

See also: `TStream.Size` (327)

2.38.5 TCustomMemoryStream.Read

Synopsis: Reads `Count` bytes from the stream into `buffer`.

Declaration: `function Read(var Buffer; Count : LongInt) : LongInt; Override`

Visibility: public

Description: `Read` reads `Count` bytes from the stream into the memory pointed to by `buffer`. It returns the number of bytes actually read.

This method overrides the abstract `TStream.Read` (319) method of `TStream` (318). It will read as much bytes as are still available in the memory area pointer to by `Memory` (269). After the bytes are read, the internal stream position is updated.

See also: `TCustomMemoryStream.Memory` (269), `TStream.Read` (319)

2.38.6 TCustomMemoryStream.Seek

Synopsis: Sets a new position in the stream.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` overrides the abstract `TStream.Seek` (320) method. It simply updates the internal stream position, and returns the new position.

Errors: No checking is done whether the new position is still a valid position, i.e. whether the position is still within the range `0..Size`. Attempting a seek outside the valid memory range of the stream may result in an exception at the next read or write operation.

See also: `TStream.Position` (327), `TStream.Size` (327), `TCustomMemoryStream.Memory` (269)

2.38.7 TCustomMemoryStream.SaveToStream

Synopsis: Writes the contents of the memory stream to another stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: public

Description: `SaveToStream` writes the contents of the memory stream to `Stream`. The content of `Stream` is not cleared first. The current position of the memory stream is not changed by this action.

Remark: This method will work much faster than the use of the `TStream.CopyFrom` (321) method:

```
Seek(0, soFromBeginning);
Stream.CopyFrom(Self, Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToStream` writes the contents of the memory as one big block.

Errors: If an error occurs when writing to `Stream` an `EStreamError` (209) exception will be raised.

See also: `TCustomMemoryStream.SaveToFile` (269), `TStream.CopyFrom` (321)

2.38.8 TCustomMemoryStream.SaveToFile

Synopsis: Writes the contents of the stream to a file.

Declaration: `procedure SaveToFile(const FileName: String)`

Visibility: public

Description: `SaveToFile` writes the contents of the stream to a file with name `FileName`. It simply creates a filestream and writes the contents of the memorystream to this file stream using `TCustomMemoryStream.SaveToStream` (268).

Remark: This method will work much faster than the use of the `TStream.CopyFrom` (321) method:

```
Stream:=TFileStream.Create(fmCreate,FileName);
Seek(0,soFromBeginning);
Stream.CopyFrom(Self,Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToFile` writes the contents of the memory as one big block.

Errors: If an error occurs when creating or writing to the file, an `EStreamError` (209) exception may occur.

See also: `TCustomMemoryStream.SaveToStream` (268), `TFileStream` (274), `TStream.CopyFrom` (321)

2.38.9 TCustomMemoryStream.Memory

Synopsis: Pointer to the data kept in the memory stream.

Declaration: `Property Memory : Pointer`

Visibility: public

Access: Read

Description: `Memory` points to the memory area where stream keeps it's data. The property is read-only, so the pointer cannot be set this way.

Remark: Do not write to the memory pointed to by `Memory`, since the memory content may be read-only, and thus writing to it may cause errors.

See also: `TStream.Size` (327)

2.39 TDataModule

2.39.1 Description

`TDataModule` is a container for non-visual objects which can be used in an IDE to group non-visual objects which can be used by various other containers (forms) in a project. Notably, data access components are typically stored on a datamodule. Web components and services can also be implemented as descendents of datamodules.

`TDataModule` introduces some events which make it easier to program, and provides the needed streaming capabilities for persistent storage.

An IDE will typically allow to create a descendent of `TDataModule` which contains non-visual components in it's published property list.

2.39.2 Method overview

Page	Property	Description
271	AfterConstruction	Overrides standard TObject (179) behaviour.
271	BeforeDestruction	
270	Create	Create a new instance of a TDataModule.
270	CreateNew	
270	Destroy	Destroys the TDataModule instance.

2.39.3 Property overview

Page	Property	Access	Description
271	DesignOffset	rw	Position property needed for manipulation in an IDE.
272	DesignSize	rw	Size property needed for manipulation in an IDE.
272	OldCreateOrder	rw	Determines when OnCreate and OnDestroy are triggered.
272	OnCreate	rw	Event handler, called when the datamodule is created.
272	OnDestroy	rw	Event handler, called when the datamodule is destroyed.

2.39.4 TDataModule.Create

Synopsis: Create a new instance of a TDataModule.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TDataModule` and calls `TDataModule.CreateNew` ([270](#)). After that it reads the published properties from a stream using `InitInheritedComponent` ([198](#)) if a descendent class is instantiated. If the `OldCreateOrder` ([272](#)) property is `True`, the `OnCreate` ([179](#)) event is called.

Errors: An exception can be raised during the streaming operation.

See also: `TDataModule.CreateNew` ([270](#))

2.39.5 TDataModule.CreateNew

Synopsis:

Declaration: `constructor CreateNew(AOwner: TComponent)`
`constructor CreateNew(AOwner: TComponent; CreateMode: Integer); Virtual`

Visibility: `public`

Description: `CreateNew` creates a new instance of the class, but bypasses the streaming mechanism. The `CreateMode` parameter (by default zero) is not used in `TDataModule`. If the `AddDataModule` ([191](#)) handler is set, then it is called, with the newly created instance as an argument.

See also: `TDataModule.Create` ([270](#)), `AddDataModule` ([191](#)), `TDataModule.OnCreate` ([272](#))

2.39.6 TDataModule.Destroy

Synopsis: Destroys the `TDataModule` instance.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` destroys the `TDataModule` instance. If the `OldCreateOrder` (272) property is `True` the `OnDestroy` (272) event handler is called prior to destroying the data module.

Before calling the inherited `destroy`, the `RemoveDataModule` (192) handler is called if it is set, and `Self` is passed as a parameter.

Errors: An event can be raised during the `OnDestroy` event handler.

See also: `TDataModule.OnDestroy` (272), `RemoveDataModule` (192)

2.39.7 TDataModule.AfterConstruction

Synopsis: Overrides standard `TObject` (179) behaviour.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: `AfterConstruction` calls the `OnCreate` (272) handler if the `OldCreateOrder` (272) property is `False`.

See also: `TDataModule.OldCreateOrder` (272), `TDataModule.OnCreate` (272)

2.39.8 TDataModule.BeforeDestruction

Synopsis:

Declaration: `procedure BeforeDestruction; Override`

Visibility: public

Description: `BeforeDestruction` calls the `OnDestroy` (272) handler if the `OldCreateOrder` (272) property is `False`.

See also: `TDataModule.OldCreateOrder` (272), `TDataModule.OnDestroy` (272)

2.39.9 TDataModule.DesignOffset

Synopsis: Position property needed for manipulation in an IDE.

Declaration: `Property DesignOffset : TPoint`

Visibility: public

Access: Read,Write

Description: `DesignOffset` is the position of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignSize` (272)

2.39.10 TDataModule.DesignSize

Synopsis: Size property needed for manipulation in an IDE.

Declaration: `Property DesignSize : TPoint`

Visibility: `public`

Access: `Read,Write`

Description: `DesignSize` is the size of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignOffset` ([271](#))

2.39.11 TDataModule.OnCreate

Synopsis: Event handler, called when the datamodule is created.

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnCreate` event is triggered when the datamodule is created and streamed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([272](#)) property.

See also: `TDataModule.Create` ([270](#)), `TDataModule.CreateNew` ([270](#)), `TDataModule.OldCreateOrder` ([272](#))

2.39.12 TDataModule.OnDestroy

Synopsis: Event handler, called when the datamodule is destroyed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnDestroy` event is triggered when the datamodule is destroyed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([272](#)) property.

See also: `TDataModule.Destroy` ([270](#)), `TDataModule.OnCreate` ([272](#)), `TDataModule.Create` ([270](#)), `TDataModule.CreateNew` ([270](#)), `TDataModule.OldCreateOrder` ([272](#))

2.39.13 TDataModule.OldCreateOrder

Synopsis: Determines when `OnCreate` and `OnDestroy` are triggered.

Declaration: `Property OldCreateOrder : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `OldCreateOrder` determines when exactly the `OnCreate` ([272](#)) and `OnDestroy` ([272](#)) event handlers are called:

See also: `TDataModule.OnDestroy` ([272](#)), `TDataModule.OnCreate` ([272](#)), `TDataModule.Destroy` ([270](#)), `TDataModule.Create` ([270](#)), `TDataModule.CreateNew` ([270](#)), `TDataModule.OldCreateOrder` ([272](#))

2.40 TFiler

2.40.1 Description

Class responsible for streaming of components.

2.40.2 Method overview

Page	Property	Description
273	DefineBinaryProperty	
273	DefineProperty	

2.40.3 Property overview

Page	Property	Access	Description
274	Ancestor	rw	Ancestor component from which an inherited component is streamed.
274	IgnoreChildren	rw	Determines whether children will be streamed as well.
274	LookupRoot	r	Component used to look up ancestor components.
273	Root	rw	The root component is the initial component which is being streamed.

2.40.4 TFiler.DefineProperty

Synopsis:

Declaration: `procedure DefineProperty(const Name: String; ReadData: TReaderProc;
WriteData: TWriterProc; HasData: Boolean)
; Virtual; Abstract`

Visibility: public

Description:

2.40.5 TFiler.DefineBinaryProperty

Synopsis:

Declaration: `procedure DefineBinaryProperty(const Name: String; ReadData: TStreamProc;
WriteData: TStreamProc; HasData: Boolean)
; Virtual; Abstract`

Visibility: public

Description:

2.40.6 TFiler.Root

Synopsis: The root component is the initial component which is being streamed.

Declaration: `Property Root : TComponent`

Visibility: public

Access: Read, Write

Description: The streaming process will stream a component and all the components which it owns. The `Root` component is the component which is initially streamed.

See also: `TFile.LookupRoot` ([274](#))

2.40.7 TFile.LookupRoot

Synopsis: Component used to look up ancestor components.

Declaration: `Property LookupRoot : TComponent`

Visibility: `public`

Access: `Read`

Description: When comparing inherited component's values against parent values, the values are compared with the component in `LookupRoot`. Initially, it is set to `Root` ([273](#)).

See also: `TFile.Root` ([273](#))

2.40.8 TFile.Ancestor

Synopsis: Ancestor component from which an inherited component is streamed.

Declaration: `Property Ancestor : TPersistent`

Visibility: `public`

Access: `Read,Write`

Description: When streaming a component, this is the parent component. Only properties that differ from the parent's property value will be streamed.

See also: `TFile.Root` ([273](#)), `TFile.LookupRoot` ([274](#))

2.40.9 TFile.IgnoreChildren

Synopsis: Determines whether children will be streamed as well.

Declaration: `Property IgnoreChildren : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: By default, all children (i.e. owned objects) will also be streamed when streaming a component. This property can be used to prevent owned objects from being streamed.

2.41 TFileStream

2.41.1 Description

`TFileStream` is a `TStream` ([318](#)) descendent that stores or reads it's data from a named file in the filesystem of the operating system.

To this end, it overrides some of the abstract methods in `TStream` and implements them for the case of files on disk, and it adds the `FileName` ([276](#)) property to the list of public properties.

2.41.2 Method overview

Page	Property	Description
275	Create	Creates a file stream.
275	Destroy	Destroys the file stream.

2.41.3 Property overview

Page	Property	Access	Description
276	FileName	r	The filename of the stream.

2.41.4 TFileStream.Create

Synopsis: Creates a file stream.

Declaration: `constructor Create(const AFileName: String; Mode: Word)`
`constructor Create(const AFileName: String; Mode: Word; Rights: Cardinal)`

Visibility: public

Description: `Create` creates a new instance of a `TFileStream` class. It opens the file `AFileName` with mode `Mode`, which can have one of the following values:

Table 2.17:

<code>fmCreate</code>	<code>TFileStream.Create</code> (275) creates a new file if needed.
<code>fmOpenRead</code>	<code>TFileStream.Create</code> (275) opens a file with read-only access.
<code>fmOpenWrite</code>	<code>TFileStream.Create</code> (275) opens a file with write-only access.
<code>fmOpenReadWrite</code>	<code>TFileStream.Create</code> (275) opens a file with read-write access.

After the file has been opened in the requested mode and a handle has been obtained from the operating system, the inherited constructor is called.

Errors: If the file could not be opened in the requested mode, an `EOpenError` ([207](#)) exception is raised.

See also: `TStream` ([318](#)), `TFileStream.FileName` ([276](#)), `THandleStream.Create` ([283](#))

2.41.5 TFileStream.Destroy

Synopsis: Destroys the file stream.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` closes the file (causing possible buffered data to be written to disk) and then calls the inherited destructor.

Do not call `destroy` directly, instead call the `Free` method. `Destroy` does not check whether `Self` is nil, while `Free` does.

See also: `TFileStream.Create` ([275](#))

2.41.6 TFileStream.FileName

Synopsis: The filename of the stream.

Declaration: `Property FileName : String`

Visibility: `public`

Access: `Read`

Description: `FileName` is the name of the file that the stream reads from or writes to. It is the name as passed in the constructor of the stream; it cannot be changed. To write to another file, the stream must be freed and created again with the new filename.

See also: `TFileStream.Create` (275)

2.42 TFPList

2.42.1 Description

`TFPList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. Contrary to `TList` (290), `TFPList` has no notification mechanism. If no notification mechanism is used, it is better to use `TFPList` instead of `TList`, as the performance of `TFPList` is much higher.

To manage collections of strings, it is better to use a `TStrings` (332) descendent such as `TStringList` (327). To manage general objects, a `TCollection` (251) class exists, from which a descendent can be made to manage collections of various kinds.

2.42.2 Method overview

Page	Property	Description
277	Add	Adds a new pointer to the list.
280	Assign	Assigns all items of a list to this list.
277	Clear	Clears the pointer list.
277	Delete	Removes a pointer from the list.
277	Destroy	Destroys the list and releases the memory used to store the list elements.
278	Error	Raises an <code>EListError</code> (208) exception.
278	Exchange	Exchanges two pointers in the list.
278	Expand	Increases the capacity of the list if needed.
278	Extract	Remove the first occurrence of a pointer from the list.
279	First	Returns the first non-nil pointer in the list.
281	ForEachCall	Call a procedure or method for each pointer in the list.
279	IndexOf	Returns the index of a given pointer.
279	Insert	Inserts a new pointer in the list at a given position.
279	Last	Returns the last non-nil pointer in the list.
280	Move	Moves a pointer from one position in the list to another.
280	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
280	Remove	Removes a value from the list.
281	Sort	Sorts the pointers in the list.

2.42.3 Property overview

Page	Property	Access	Description
281	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
282	Count	rw	Current number of pointers in the list.
282	Items	rw	Provides access to the pointers in the list.
282	List	r	Memory array where pointers are stored.

2.42.4 TFPList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

2.42.5 TFPList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add(Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Grow` ([276](#)) method.

To insert a pointer at a certain position in the list, use the `Insert` ([279](#)) method instead.

See also: `TFPList.Delete` ([277](#)), `TFPList.Grow` ([276](#)), `TFPList.Insert` ([279](#))

2.42.6 TFPList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `TFPList.Destroy` ([277](#))

2.42.7 TFPList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

2.42.8 TFPList.Error

Synopsis: Raises an `EListError` (208) exception.

Declaration: `procedure Error(const Msg: String; Data: PtrInt)`

Visibility: `public`

Description: `Error` raises an `EListError` (208) exception, with a message formatted with `Msg` and `Data`.

2.42.9 TFPList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (208) exception will be raised.

2.42.10 TFPList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TFPList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `TFPList.Capacity` (281)

2.42.11 TFPList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: `public`

Description: `Extract` searches for the first occurrence of `Item` in the list and deletes it from the list. If `Item` was found, it's value is returned. If `Item` was not found, `Nil` is returned.

See also: `TFPList.Delete` (277)

2.42.12 TFPList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: `public`

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TFPList.Last` ([279](#))

2.42.13 TFPList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: `public`

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

2.42.14 TFPList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: `public`

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` ([208](#)) exception is raised.

See also: `TFPList.Add` ([277](#)), `TFPList.Delete` ([277](#))

2.42.15 TFPList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: `public`

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TFPList.First` ([279](#))

2.42.16 TFPList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: `public`

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `NewIndex` are not inside the valid range of indices, an `EListError` (208) exception is raised.

See also: `TFPList.Exchange` (278)

2.42.17 TFPList.Assign

Synopsis: Assigns all items of a list to this list.

Declaration: `procedure Assign (Obj: TFPList)`

Visibility: `public`

Description: `Assign` clears the list and adds all pointers in `Obj` to the list.

See also: `TFPList.Add` (277), `TFPList.Clear` (277)

2.42.18 TFPList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: `public`

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `TFPList.Delete` (277), `TFPList.IndexOf` (279), `TFPList.Insert` (279)

2.42.19 TFPList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TFPList.Clear` (277)

2.42.20 TFPList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort (Compare: TListSortCompare)`

Visibility: public

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

2.42.21 TFPList.ForEachCall

Synopsis: Call a procedure or method for each pointer in the list.

Declaration: `procedure ForEachCall (proc2call: TListCallback; arg: pointer)`
`procedure ForEachCall (proc2call: TListStaticCallback; arg: pointer)`

Visibility: public

Description: `ForEachCall` iterates over all pointers in the list and calls `proc2call`, passing it the pointer and the additional `arg` data pointer. `Proc2Call` can be a method or a static procedure.

Errors: None.

See also: `TListStaticCallback` ([187](#)), `TListCallback` ([186](#))

2.42.22 TFPList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read, Write

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` ([277](#)) or `insert` ([279](#)), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `TFPList.SetCapacity` ([276](#)), `TFPList.Count` ([282](#))

2.42.23 TFPList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read, Write`

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

2.42.24 TFPList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TFPList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

2.42.25 TFPList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

2.43 THandleStream

2.43.1 Description

`THandleStream` is an abstract descendent of the `TStream` (318) class that provides methods for a stream to handle all reading and writing to and from a handle, provided by the underlying OS. To this end, it overrides the `Read` (283) and `Write` (283) methods of `TStream`.

Remark:

- `THandleStream` does not obtain a handle from the OS by itself, it just handles reading and writing to such a handle by wrapping the system calls for reading and writing; Descendent classes should obtain a handle from the OS by themselves and pass it on in the inherited constructor.
- Contrary to Delphi, no `seek` is implemented for `THandleStream`, since pipes and sockets do not support this. The `seek` is implemented in descendent methods that support it.

2.43.2 Method overview

Page	Property	Description
283	Create	Create a handlestream from an OS Handle.
283	Read	Overrides standard read method.
284	Seek	Overrides the Seek method.
283	Write	Overrides standard write method.

2.43.3 Property overview

Page	Property	Access	Description
284	Handle	r	The OS handle of the stream.

2.43.4 THandleStream.Create

Synopsis: Create a handlestream from an OS Handle.

Declaration: `constructor Create(AHandle: Integer)`

Visibility: `public`

Description: `Create` creates a new instance of a `THandleStream` class. It stores `AHandle` in an internal variable and then calls the inherited constructor.

See also: `TStream` ([318](#))

2.43.5 THandleStream.Read

Synopsis: Overrides standard read method.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` implements the abstract `Read` ([319](#)) method of `TStream`. It uses the `Handle` ([284](#)) property to read the `Count` bytes into `Buffer`.

If no error occurs while reading, the number of bytes actually read will be returned.

Errors: If the operating system reports an error while reading from the handle, -1 is returned.

See also: `TStream.Read` ([319](#)), `THandleStream.Write` ([283](#)), `THandleStream.Handle` ([284](#))

2.43.6 THandleStream.Write

Synopsis: Overrides standard write method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` implements the abstract `Write` ([320](#)) method of `TStream`. It uses the `Handle` ([284](#)) property to write the `Count` bytes from `Buffer`.

If no error occurs while writing, the number of bytes actually written will be returned.

Errors: If the operating system reports an error while writing to handle, -1 is returned.

See also: `TStream.Read` ([319](#)), `THandleStream.Write` ([283](#)), `THandleStream.Handle` ([284](#))

2.43.7 THandleStream.Seek

Synopsis: Overrides the Seek method.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64
; Override`

Visibility: public

Description: `seek` uses the `FileSeek` (1342) method to position the stream on the desired position. Note that handle stream descendents (notably pipes) can override the method to prevent the seek.

2.43.8 THandleStream.Handle

Synopsis: The OS handle of the stream.

Declaration: `Property Handle : Integer`

Visibility: public

Access: Read

Description: `Handle` represents the Operating system handle to which reading and writing is done. The handle can be read only, i.e. it cannot be set after the `THandleStream` instance was created. It should be passed to the constructor `THandleStream.Create` (283)

See also: `THandleStream` (282), `THandleStream.Create` (283)

2.44 TInterfacedPersistent

2.44.1 Description

`TInterfacedPersistent` is a direct descendent of `TPersistent` (304) which implements the `#rtl.system.IInterface` (1091) interface. In particular, it implements the `QueryInterface` as a public method.

2.44.2 Method overview

Page	Property	Description
285	<code>AfterConstruction</code>	Overrides the standard <code>AfterConstruction</code> method.
284	<code>QueryInterface</code>	Implementation of <code>IInterface.QueryInterface</code>

2.44.3 TInterfacedPersistent.QueryInterface

Synopsis: Implementation of `IInterface.QueryInterface`

Declaration: `function QueryInterface(const IID: TGUID; out Obj) : HRESULT; Virtual`

Visibility: public

Description: `QueryInterface` simply calls `GetInterface` using the specified IID, and returns the correct values.

See also: `#rtl.system.tobject.GetInterface` (1276)

2.44.4 TInterfacePersistent.AfterConstruction

Synopsis: Overrides the standard `AfterConstruction` method.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` is overridden to do some extra interface housekeeping: a reference to the `IInterface` interface of the owning class is obtained (if it exists).

2.45 TInterfaceList

2.45.1 Description

`TInterfaceList` is a standard implementation of the `IInterfaceList` (211) interface. It uses a `TThreadList` (351) instance to store the list of interfaces.

2.45.2 Method overview

Page	Property	Description
287	Add	Add an interface to the list
286	Clear	Removes all interfaces from the list.
285	Create	Create a new instance of <code>TInterfaceList</code>
286	Delete	Delete an interface from the list.
286	Destroy	Destroys the list of interfaces
286	Exchange	Exchange 2 interfaces in the list
289	Expand	Expands the list
287	First	Returns the first non- <code>Nil</code> element in the list.
287	IndexOf	Returns the index of an interface.
287	Insert	Insert an interface to the list
288	Last	Returns the last non- <code>Nil</code> element in the list.
288	Lock	Lock the list
288	Remove	Remove an interface from the list
288	Unlock	UnLocks a locked list

2.45.3 Property overview

Page	Property	Access	Description
289	Capacity	rw	The current capacity of the list.
289	Count	rw	The current number of elements in the list.
289	Items	rw	Array-based access to the list's items.

2.45.4 TInterfaceList.Create

Synopsis: Create a new instance of `TInterfaceList`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of the `TInterfaceList` class. It sets up the internal structures needed to store the list of interfaces.

See also: `TInterfaceList.Destroy` ([286](#))

2.45.5 TInterfaceList.Destroy

Synopsis: Destroys the list of interfaces

Declaration: `destructor Destroy`

Visibility: `public`

Description: `Destroy` first calls `Clear` (286) and then frees the `TInterfaceList` instance from memory.

Note that the `Clear` method decreases the reference count of all interfaces.

See also: `TInterfaceList.Create` (285), `TInterfaceList.Clear` (286)

2.45.6 TInterfaceList.Clear

Synopsis: Removes all interfaces from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` is the implementation of the `IInterfaceList.Clear` (213) method. It removes all interfaces from the list. It does this by setting each element in the list to `Nil`, in this way the reference count of each interface in the list is decreased.

See also: `IInterfaceList.Clear` (213), `TInterfaceList.Add` (287), `TInterfaceList.Destroy` (286), `TList.Clear` (291), `TFPList.Clear` (277)

2.45.7 TInterfaceList.Delete

Synopsis: Delete an interface from the list.

Declaration: `procedure Delete(index: Integer)`

Visibility: `public`

Description: `Delete` is the implementation of the `IInterfaceList.Delete` (213) method. It clears the slot first and then removes the element from the list.

See also: `IInterfaceList.Delete` (213), `TInterfaceList.Remove` (288), `TInterfaceList.Add` (287), `TList.Delete` (291), `TFPList.Delete` (277)

2.45.8 TInterfaceList.Exchange

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: `public`

Description: `Exchange` is the implementation of the `IInterfaceList.Exchange` (213) method. It exchanges the position of 2 interfaces in the list.

See also: `IInterfaceList.Exchange` (213), `TInterfaceList.Delete` (286), `TInterfaceList.Add` (287), `TList.Exchange` (292), `TFPList.Exchange` (278)

2.45.9 TInterfaceList.First

Synopsis: Returns the first non-`Nil` element in the list.

Declaration: `function First : IUnknown`

Visibility: `public`

Description: `First` is the implementation of the `IInterfaceList.First` (214) method. It returns the first non-`Nil` element from the list.

See also: `IInterfaceList.First` (214), `TList.First` (293)

2.45.10 TInterfaceList.IndexOf

Synopsis: Returns the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: `public`

Description: `IndexOf` is the implementation of the `IInterfaceList.IndexOf` (214) method. It returns the zero-based index in the list of the indicated interface, or -1 if the index is not in the list.

See also: `IInterfaceList.IndexOf` (214), `TList.IndexOf` (293)

2.45.11 TInterfaceList.Add

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: `public`

Description: `Add` is the implementation of the `IInterfaceList.Add` (214) method. It adds an interface to the list, and returns the location of the new element in the list. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Add` (214), `TInterfaceList.Delete` (286), `TInterfaceList.Insert` (287), `TList.Add` (291), `TFPList.Add` (277)

2.45.12 TInterfaceList.Insert

Synopsis: Insert an interface to the list

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: `public`

Description: `Insert` is the implementation of the `IInterfaceList.Insert` (214) method. It inserts an interface in the list at the indicated position. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Insert` (214), `TInterfaceList.Delete` (286), `TInterfaceList.Add` (287), `TList.Insert` (293), `TFPList.Insert` (279)

2.45.13 TInterfaceList.Last

Synopsis: Returns the last non-`Nil` element in the list.

Declaration: `function Last : IUnknown`

Visibility: `public`

Description: `Last` is the implementation of the `IInterfaceList.Last` (214) method. It returns the last non-`Nil` element from the list.

See also: `IInterfaceList.Last` (214), `TInterfaceList.First` (287), `TList.Last` (293), `TFPList.Last` (279)

2.45.14 TInterfaceList.Remove

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: `public`

Description: `Remove` is the implementation of the `IInterfaceList.Remove` (215) method. It removes the first occurrence of the interface from the list.

See also: `IInterfaceList.Remove` (215), `TInterfaceList.Delete` (286), `TInterfaceList.IndexOf` (287), `TList.Remove` (294), `TFList.Remove` (179)

2.45.15 TInterfaceList.Lock

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: `public`

Description: `Lock` locks the list. It is the implementation of the `IInterfaceList.Lock` (215) method. It limits access to the list to the current thread.

See also: `IInterfaceList.Lock` (215), `TInterfaceList.Unlock` (288), `TThreadList.LockList` (352)

2.45.16 TInterfaceList.Unlock

Synopsis: UnLocks a locked list

Declaration: `procedure Unlock`

Visibility: `public`

Description: `Unlock` unlocks the list. It is the implementation of the `IInterfaceList.Unlock` (215) method. After a call to unlock, the current thread releases the list for manipulation by other threads.

See also: `IInterfaceList.Unlock` (215), `TInterfaceList.Lock` (288), `TThreadList.UnlockList` (352)

2.45.17 TInterfaceList.Expand

Synopsis: Expands the list

Declaration: `function Expand : TInterfaceList`

Visibility: `public`

Description: `Expand` calls the `expand` method from the internally used list. It returns itself.

See also: `TList.Expand` ([292](#))

2.45.18 TInterfaceList.Capacity

Synopsis: The current capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of elements that the list can contain without needing to allocate more memory.

See also: `IInterfaceList.Capacity` ([215](#)), `TInterfaceList.Count` ([289](#)), `TList.Capacity` ([295](#)), `TFPList.Capacity` ([281](#))

2.45.19 TInterfaceList.Count

Synopsis: The current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the number of elements in the list. This can include `Nil` elements. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`.

See also: `IInterfaceList.Count` ([216](#)), `TInterfaceList.Items` ([289](#)), `TInterfaceList.Capacity` ([289](#)), `TList.Count` ([295](#)), `TFPList.Count` ([282](#))

2.45.20 TInterfaceList.Items

Synopsis: Array-based access to the list's items.

Declaration: `Property Items[Index: Integer]: IUnknown; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` provides indexed access to the elements in the list. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`. The items are read-write. It is not possible to add elements to the list by accessing an element with index larger or equal to `Count` ([289](#)).

See also: `IInterfaceList.Items` ([216](#)), `TInterfaceList.Count` ([289](#)), `TList.Items` ([296](#)), `TFPList.Items` ([282](#))

2.46 TList

2.46.1 Description

`TList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. It has an event notification mechanism which allows to notify of list changes. This slows down some of `TList` mechanisms, and if no notification is used, `TFPList` (276) may be used instead.

To manage collections of strings, it is better to use a `TStrings` (332) descendent such as `TStringList` (327). To manage general objects, a `TCollection` (251) class exists, from which a descendent can be made to manage collections of various kinds.

2.46.2 Method overview

Page	Property	Description
291	Add	Adds a new pointer to the list.
294	Assign	Copy the contents of another list.
291	Clear	Clears the pointer list.
290	Create	Class to manage collections of pointers.
291	Delete	Removes a pointer from the list.
291	Destroy	Destroys the list and releases the memory used to store the list elements.
292	Error	Raises an <code>EListError</code> (208) exception.
292	Exchange	Exchanges two pointers in the list.
292	Expand	Increases the capacity of the list if needed.
292	Extract	Remove the first occurrence of a pointer from the list.
293	First	Returns the first non-nil pointer in the list.
293	IndexOf	Returns the index of a given pointer.
293	Insert	Inserts a new pointer in the list at a given position.
293	Last	Returns the last non-nil pointer in the list.
294	Move	Moves a pointer from one position in the list to another.
294	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
294	Remove	Removes a value from the list.
295	Sort	Sorts the pointers in the list.

2.46.3 Property overview

Page	Property	Access	Description
295	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
295	Count	rw	Current number of pointers in the list.
296	Items	rw	Provides access to the pointers in the list.
296	List	r	Memory array where pointers are stored.

2.46.4 TList.Create

Synopsis: Class to manage collections of pointers.

Declaration: `constructor Create`

Visibility: `public`

Description: `TList.Create` creates a new instance of `TList`. It clears the list and prepares it for use.

See also: [TList \(290\)](#), [TList.Destroy \(291\)](#)

2.46.5 TList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

2.46.6 TList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add(Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the [Grow \(290\)](#) method.

To insert a pointer at a certain position in the list, use the [Insert \(293\)](#) method instead.

See also: [TList.Delete \(291\)](#), [TList.Grow \(290\)](#), [TList.Insert \(293\)](#)

2.46.7 TList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear; Virtual`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: [TList.Destroy \(291\)](#)

2.46.8 TList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

2.46.9 TList.Error

Synopsis: Raises an `EListError` (208) exception.

Declaration: `procedure Error(const Msg: String; Data: PtrInt); Virtual`

Visibility: `public`

Description: `Error` raises an `EListError` (208) exception, with a message formatted with `Msg` and `Data`.

2.46.10 TList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (208) exception will be raised.

2.46.11 TList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `TList.Capacity` (295)

2.46.12 TList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: `public`

Description: `Extract` searched for an occurrence of `item`, and if a match is found, the match is deleted from the list. If no match is found, nothing is deleted. If `Item` was found, the result is `Item`. If `Item` was not found, the result is `Nil`. A `lnExtracted` notification event is triggered if an element is extracted from the list. Note that a `lnDeleted` event will also occur.

See also: `TList.Delete` (291), `TList.IndexOf` (293), `TList.Remove` (294)

2.46.13 TList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: `public`

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TList.Last` ([293](#))

2.46.14 TList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: `public`

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

2.46.15 TList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: `public`

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` ([208](#)) exception is raised.

See also: `TList.Add` ([291](#)), `Tlist.Delete` ([291](#))

2.46.16 TList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: `public`

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TList.First` ([293](#))

2.46.17 TList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: `public`

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `NewIndex` are not inside the valid range of indices, an `EListError` (208) exception is raised.

See also: `TList.Exchange` (292)

2.46.18 TList.Assign

Synopsis: Copy the contents of another list.

Declaration: `procedure Assign (Obj: TList)`

Visibility: `public`

Description: `Assign` copies the pointers of the `Obj` list to the list. The list is cleared prior to copying.

See also: `TList.Clear` (291)

2.46.19 TList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: `public`

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `TList.Delete` (291), `TList.IndexOf` (293), `TList.Insert` (293)

2.46.20 TList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TList.Clear` (291)

2.46.21 TList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort (Compare: TListSortCompare)`

Visibility: `public`

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

2.46.22 TList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: Read, Write

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` (291) or `insert` (293), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `TList.SetCapacity` (290), `TList.Count` (295)

2.46.23 TList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: Read, Write

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

2.46.24 TList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

2.46.25 TList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

2.47 TMemoryStream

2.47.1 Description

`TMemoryStream` is a `TStream` (318) descendent that stores its data in memory. It descends directly from `TCustomMemoryStream` (267) and implements the necessary to allocate and de-allocate memory directly from the heap. It implements the `Write` (298) method which is missing in `TCustomMemoryStream`.

`TMemoryStream` also introduces methods to load the contents of another stream or a file into the memory stream.

It is not necessary to do any memory management manually, as the stream will allocate or de-allocate memory as needed. When the stream is freed, all allocated memory will be freed as well.

2.47.2 Method overview

Page	Property	Description
297	<code>Clear</code>	Zeroes the position, capacity and size of the stream.
296	<code>Destroy</code>	Frees any allocated memory and destroys the memory stream.
297	<code>LoadFromFile</code>	Loads the contents of a file into memory.
297	<code>LoadFromStream</code>	Loads the contents of a stream into memory.
298	<code>SetSize</code>	Sets the size for the memory stream.
298	<code>Write</code>	Writes data to the stream's memory.

2.47.3 TMemoryStream.Destroy

Synopsis: Frees any allocated memory and destroys the memory stream.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Free` clears the memory stream, thus in effect freeing any memory allocated for it, and then frees the memory stream.

2.47.4 TMemoryStream.Clear

Synopsis: Zeroes the position, capacity and size of the stream.

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` sets the position and size to 0, and sets the capacity of the stream to 0, thus freeing all memory allocated for the stream.

See also: `TStream.Size` (327), `TStream.Position` (327), `TCustomMemoryStream.Memory` (269)

2.47.5 TMemoryStream.LoadFromStream

Synopsis: Loads the contents of a stream into memory.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: public

Description: `LoadFromStream` loads the contents of `Stream` into the memorybuffer of the stream. Any previous contents of the memory stream are overwritten. Memory is allocated as needed.

Remark: The `LoadFromStream` uses the `Size` (327) property of `Stream` to determine how much memory must be allocated. Some streams do not allow the stream size to be determined, so care must be taken when using this method.

This method will work much faster than the use of the `TStream.CopyFrom` (321) method:

```
Seek(0, soFromBeginning);
CopyFrom(Stream, Stream.Size);
```

because the `CopyFrom` method copies the contents in blocks, while `LoadFromStream` reads the contents of the stream as one big block.

Errors: If an error occurs when reading from the stream, an `EStreamError` (209) may occur.

See also: `TStream.CopyFrom` (321), `TMemoryStream.LoadFromFile` (297)

2.47.6 TMemoryStream.LoadFromFile

Synopsis: Loads the contents of a file into memory.

Declaration: `procedure LoadFromFile(const FileName: String)`

Visibility: public

Description: `LoadFromFile` loads the contents of the file with name `FileName` into the memory stream. The current contents of the memory stream is replaced by the contents of the file. Memory is allocated as needed.

The `LoadFromFile` method simply creates a filestream and then calls the `TMemoryStream.LoadFromStream` (297) method.

See also: `TMemoryStream.LoadFromStream` (297)

2.47.7 TMemoryStream.SetSize

Synopsis: Sets the size for the memory stream.

Declaration: `procedure SetSize(NewSize: LongInt); Override`

Visibility: public

Description: `SetSize` sets the size of the memory stream to `NewSize`. This will set the capacity of the stream to `NewSize` and correct the current position in the stream when needed.

See also: `TStream.Position` (327), `TStream.Size` (327)

2.47.8 TMemoryStream.Write

Synopsis: Writes data to the stream's memory.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buffer` to the stream's memory, starting at the current position in the stream. If more memory is needed than currently allocated, more memory will be allocated. Any contents in the memory stream at the current position will be overwritten. The function returns the number of bytes actually written (which should under normal circumstances always equal `Count`).

This method overrides the abstract `TStream.Write` (320) method.

Errors: If no more memory could be allocated, then an exception will be raised.

See also: `TCustomMemoryStream.Read` (267)

2.48 TOwnedCollection

2.48.1 Description

`TOwnedCollection` automatically maintains owner information, so it can be displayed in an IDE. Collections that should be displayed in an IDE should descend from `TOwnedCollection` or must implement a `GetOwner` function.

2.48.2 Method overview

Page	Property	Description
298	Create	Create a new <code>TOwnerCollection</code> instance.

2.48.3 TOwnedCollection.Create

Synopsis: Create a new `TOwnerCollection` instance.

Declaration: `constructor Create(AOwner: TPersistent; AItemClass: TCollectionItemClass)`

Visibility: public

Description: `Create` creates a new instance of `TOwnedCollection` and stores the `AOwner` references. It will the value returned in the `TCollection.Owner` (252) property of the collection. The `ItemClass` class reference is passed on to the inherited constructor, and will be used to create new instances in the `Insert` (254) and `Add` (252) methods.

See also: `TCollection.Create` (251), `TCollection.Owner` (252)

2.49 TOwnerStream

2.49.1 Description

`TOwnerStream` can be used when creating stream chains such as when using encryption and compression streams. It keeps a reference to the source stream and will automatically free the source stream when ready (if the `SourceOwner` (300) property is set to `True`).

2.49.2 Method overview

Page	Property	Description
299	Create	Create a new instance of <code>TOwnerStream</code> .
299	Destroy	Destroys the <code>TOwnerStream</code> instance and the source stream.

2.49.3 Property overview

Page	Property	Access	Description
299	Source	r	Reference to the source stream.
300	SourceOwner	rw	Indicates whether the ownerstream owns it's source

2.49.4 TOwnerStream.Create

Synopsis: Create a new instance of `TOwnerStream`.

Declaration: constructor `Create (ASource: TStream)`

Visibility: public

Description: `Create` instantiates a new instance of `TOwnerStream` and stores the reference to `ASource`. If `SourceOwner` is `True`, the source stream will also be freed when the instance is destroyed.

See also: `TOwnerStream.Destroy` (299), `TOwnerStream.Source` (299), `TOwnerStream.SourceOwner` (300)

2.49.5 TOwnerStream.Destroy

Synopsis: Destroys the `TOwnerStream` instance and the source stream.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: `Destroy` frees the source stream if the `SourceOwner` property is `True`.

Errors:

See also: `TOwnerStream.Create` (299), `TOwnerStream.Source` (299), `TOwnerStream.SourceOwner` (300)

2.49.6 TOwnerStream.Source

Synopsis: Reference to the source stream.

Declaration: Property `Source` : `TStream`

Visibility: public

Access: Read

Description: `Source` is the source stream. It should be used by descendent streams to access the source stream to read from or write to.

Do not free the `Source` reference directly. Either the owner stream instance should free the source stream or

See also: `TOwnerStream.Create` ([299](#))

2.49.7 TOwnerStream.SourceOwner

Synopsis: Indicates whether the ownerstream owns its source

Declaration: `Property SourceOwner : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `SourceOwner` indicates whether the `TOwnerStream` owns its `Source` stream or not. If this property is `True` then the `Source` stream is freed when the `TOwnerStream` instance is freed.

See also: `TOwnerStream.Source` ([299](#)), `TOwnerStream.Destroy` ([299](#))

2.50 TParser

2.50.1 Description

Class to parse the contents of a stream containing text data.

2.50.2 Method overview

Page	Property	Description
301	<code>CheckToken</code>	Checks whether the token is of the given type.
301	<code>CheckTokenSymbol</code>	Checks whether the token equals the given symbol
301	<code>Create</code>	Creates a new parser instance.
301	<code>Destroy</code>	Destroys the parser instance.
301	<code>Error</code>	Raises an <code>EParserError</code> (208) exception with the given message
301	<code>ErrorFmt</code>	Raises an <code>EParserError</code> (208) exception and formats the message.
302	<code>ErrorStr</code>	Raises an <code>EParserError</code> (208) exception with the given message
302	<code>HexToBinary</code>	Writes hexadecimal data to the stream.
302	<code>NextToken</code>	Reads the next token and returns its type.
302	<code>SourcePos</code>	Returns the current position in the stream.
302	<code>TokenComponentIdent</code>	Checks whether the current token is a component identifier.
302	<code>TokenFloat</code>	Returns the current token as a float.
303	<code>TokenInt</code>	Returns the current token as an integer.
303	<code>TokenString</code>	Returns the current token as a string.
303	<code>TokenSymbolIs</code>	Returns <code>True</code> if the current token is a symbol.
303	<code>TokenWideString</code>	Token as widestring

2.50.3 Property overview

Page	Property	Access	Description
303	<code>SourceLine</code>	<code>r</code>	Current source linenumber.
304	<code>Token</code>	<code>r</code>	Contents of the current token.

2.50.4 TParser.Create

Synopsis: Creates a new parser instance.

Declaration: `constructor Create(Stream: TStream)`

Visibility: `public`

Description: Creates a new parser instance.

2.50.5 TParser.Destroy

Synopsis: Destroys the parser instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the parser instance.

2.50.6 TParser.CheckToken

Synopsis: Checks whether the token is of the given type.

Declaration: `procedure CheckToken(T: Char)`

Visibility: `public`

Description: Checks whether the token is of the given type.

2.50.7 TParser.CheckTokenSymbol

Synopsis: Checks whether the token equals the given symbol

Declaration: `procedure CheckTokenSymbol(const S: String)`

Visibility: `public`

Description: Checks whether the token equals the given symbol

2.50.8 TParser.Error

Synopsis: Raises an `EParserError` (208) exception with the given message

Declaration: `procedure Error(const Ident: String)`

Visibility: `public`

Description: Raises an `EParserError` (208) exception with the given message

2.50.9 TParser.ErrorFmt

Synopsis: Raises an `EParserError` (208) exception and formats the message.

Declaration: `procedure ErrorFmt(const Ident: String; const Args: Array[] of const)`

Visibility: `public`

Description: Raises an `EParserError` (208) exception and formats the message.

2.50.10 TParser.ErrorStr

Synopsis: Raises an EParserError (208) exception with the given message

Declaration: `procedure ErrorStr(const Message: String)`

Visibility: public

Description: Raises an EParserError (208) exception with the given message

2.50.11 TParser.HexToBinary

Synopsis: Writes hexadecimal data to the stream.

Declaration: `procedure HexToBinary(Stream: TStream)`

Visibility: public

Description: Writes hexadecimal data to the stream.

2.50.12 TParser.NextToken

Synopsis: Reads the next token and returns its type.

Declaration: `function NextToken : Char`

Visibility: public

Description: Reads the next token and returns its type.

2.50.13 TParser.SourcePos

Synopsis: Returns the current position in the stream.

Declaration: `function SourcePos : LongInt`

Visibility: public

Description: Returns the current position in the stream.

2.50.14 TParser.TokenComponentIdent

Synopsis: Checks whether the current token is a component identifier.

Declaration: `function TokenComponentIdent : String`

Visibility: public

Description: Checks whether the current token is a component identifier.

2.50.15 TParser.TokenFloat

Synopsis: Returns the current token as a float.

Declaration: `function TokenFloat : Extended`

Visibility: public

Description: Returns the current token as a float.

2.50.16 TParser.TokenInt

Synopsis: Returns the current token as an integer.

Declaration: `function TokenInt : LongInt`

Visibility: `public`

Description: Returns the current token as an integer.

2.50.17 TParser.TokenString

Synopsis: Returns the current token as a string.

Declaration: `function TokenString : String`

Visibility: `public`

Description: Returns the current token as a string.

2.50.18 TParser.TokenWideString

Synopsis: Token as widestring

Declaration: `function TokenWideString : widestring`

Visibility: `public`

Description: `TokenWideString` returns the current token as a widestring.

Errors: None.

See also: `TParser.TokenString` (303), `TParser.NextToken` (302)

2.50.19 TParser.TokenSymbols

Synopsis: Returns `True` if the current token is a symbol.

Declaration: `function TokenSymbolIs(const S: String) : Boolean`

Visibility: `public`

Description: Returns `True` if the current token is a symbol.

2.50.20 TParser.SourceLine

Synopsis: Current source linenumber.

Declaration: `Property SourceLine : Integer`

Visibility: `public`

Access: Read

Description: Current source linenumber.

2.50.21 TParser.Token

Synopsis: Contents of the current token.

Declaration: `Property Token : Char`

Visibility: `public`

Access: `Read`

Description: Contents of the current token.

2.51 TPersistent

2.51.1 Description

`TPersistent` is the basic class for the streaming system. Since it is compiled in the `{M+}` state, the compiler generates RTTI (Run-Time Type Information) for it and all classes that descend from it. This information can be used to stream all properties of classes.

It also introduces functionality to assign the contents of 2 classes to each other.

2.51.2 Method overview

Page	Property	Description
304	<code>Assign</code>	Assign the contents of one class to another.
304	<code>Destroy</code>	Destroys the <code>TPersistent</code> instance.
305	<code>GetNamePath</code>	Returns a string that can be used to identify the class instance.

2.51.3 TPersistent.Destroy

Synopsis: Destroys the `TPersistent` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` disposes of the persistent object. This method should never be called directly. Instead the `Free` method should be used.

2.51.4 TPersistent.Assign

Synopsis: Assign the contents of one class to another.

Declaration: `procedure Assign(Source: TPersistent); Virtual`

Visibility: `public`

Description: `Assign` copies the contents of `Source` to `Self`, if the classes of the destination and source classes are compatible.

The `TPersistent` implementation of `Assign` does nothing but calling the `AssignTo` ([304](#)) method of source. This means that if the destination class does not know how to assign the contents of the source class, the source class instance is asked to assign itself to the destination class. This means that it is necessary to implement only one of the two methods so that two classes can be assigned to one another.

Remark: In general, a statement of the form

```
Destination:=Source;
```

(where `Destination` and `Source` are classes) does not achieve the same as a statement of the form

```
Destination.Assign(Source);
```

After the former statement, both `Source` and `Destination` will point to the same object. The latter statement will copy the *contents* of the `Source` class to the `Destination` class.

See also: `TPersistent.AssignTo` ([304](#))

2.51.5 `TPersistent.GetNamePath`

Synopsis: Returns a string that can be used to identify the class instance.

Declaration: `function GetNamePath : String; Virtual`

Visibility: `public`

Description: `GetNamePath` returns a string that can be used to identify the class instance. This can be used to display a name for this instance in a Object designer.

`GetNamePath` constructs a name by recursively prepending the `Classname` of the `Owner` instance to the `Classname` of this instance, separated by a dot.

See also: `TPersistent.GetOwner` ([304](#))

2.52 `TReader`

2.52.1 Description

The `TReader` class is a reader class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectReader` ([217](#)) to do the actual reading of data. The interface of the `TReader` class should be identical to the interface in Delphi.

2.52.2 Method overview

Page	Property	Description
307	BeginReferences	Initializes the component referencing mechanism.
308	CheckValue	Raises an exception if the next value in the stream is not of type Value
312	CopyValue	Copy a value to a writer.
307	Create	Creates a new reader class
308	DefineBinaryProperty	Reads a user-defined binary property from the stream.
308	DefineProperty	Reads a user-defined property from the stream.
307	Destroy	Destroys a reader class.
308	EndOfList	Returns true if the stream contains an end-of-list marker.
308	EndReferences	Finalizes the component referencing mechanism.
309	FixupReferences	Tries to resolve all unresolved component references.
309	NextValue	Returns the type of the next value.
309	ReadBoolean	Reads a boolean from the stream.
309	ReadChar	Reads a character from the stream.
309	ReadCollection	Reads a collection from the stream.
309	ReadComponent	Starts reading a component from the stream.
310	ReadComponents	Starts reading child components from the stream.
310	ReadCurrency	Read a currency value from the stream.
310	ReadDate	Reads a date from the stream
310	ReadFloat	Reads a float from the stream.
311	ReadIdent	Reads an identifier from the stream.
311	ReadInt64	Reads a 64-bit integer from the stream.
311	ReadInteger	Reads an integer from the stream
311	ReadListBegin	Checks for the beginning of a list.
311	ReadListEnd	Checks for the end of a list.
311	ReadRootComponent	Starts reading a root component.
310	ReadSingle	Reads a single-type real from the stream.
312	ReadString	Reads a string from the stream.
312	ReadValue	Reads the next value type from the stream.
312	ReadWideString	Read a WideString value from the stream.

2.52.3 Property overview

Page	Property	Access	Description
312	Driver	r	The driver in use for streaming the data.
314	OnAncestorNotFound	rw	Handler called when the ancestor component cannot be found.
315	OnCreateComponent	rw	Handler called when a component needs to be created.
313	OnError	rw	Handler called when an error occurs.
315	OnFindComponentClass	rw	Handler called when a component class reference needs to be found.
314	OnFindMethod	rw	Handler to find or change a method address.
313	OnPropertyNotFound	rw	Handler for treating missing properties.
315	OnReadStringProperty	rw	Handler for translating strings when read from the stream.
314	OnReferenceName	rw	Handler called when another component is referenced.
314	OnSetMethodProperty	rw	Handler for setting method properties.
314	OnSetName	rw	Handler called when setting a component name.
313	Owner	rw	Owner of the component being read
313	Parent	rw	Parent of the component being read.

2.52.4 TReader.Create

Synopsis: Creates a new reader class

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new reader class

2.52.5 TReader.Destroy

Synopsis: Destroys a reader class.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys a reader class.

2.52.6 TReader.BeginReferences

Synopsis: Initializes the component referencing mechanism.

Declaration: `procedure BeginReferences`

Visibility: `public`

Description: Initializes the component referencing mechanism.

2.52.7 TReader.CheckValue

Synopsis: Raises an exception if the next value in the stream is not of type Value

Declaration: `procedure CheckValue(Value: TValueType)`

Visibility: public

Description: Raises an exception if the next value in the stream is not of type Value

2.52.8 TReader.DefineProperty

Synopsis: Reads a user-defined property from the stream.

Declaration: `procedure DefineProperty(const Name: String; AReadData: TReaderProc;
WriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: public

Description: Reads a user-defined property from the stream.

2.52.9 TReader.DefineBinaryProperty

Synopsis: Reads a user-defined binary property from the stream.

Declaration: `procedure DefineBinaryProperty(const Name: String;
AReadData: TStreamProc;
WriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: public

Description: Reads a user-defined binary property from the stream.

2.52.10 TReader.EndOfList

Synopsis: Returns true if the stream contains an end-of-list marker.

Declaration: `function EndOfList : Boolean`

Visibility: public

Description: Returns true if the stream contains an end-of-list marker.

2.52.11 TReader.EndReferences

Synopsis: Finalizes the component referencing mechanism.

Declaration: `procedure EndReferences`

Visibility: public

Description: Finalizes the component referencing mechanism.

2.52.12 TReader.FixupReferences

Synopsis: Tries to resolve all unresolved component references.

Declaration: `procedure FixupReferences`

Visibility: `public`

Description: Tries to resolve all unresolved component references.

2.52.13 TReader.NextValue

Synopsis: Returns the type of the next value.

Declaration: `function NextValue : TValueType`

Visibility: `public`

Description: Returns the type of the next value.

2.52.14 TReader.ReadBoolean

Synopsis: Reads a boolean from the stream.

Declaration: `function ReadBoolean : Boolean`

Visibility: `public`

Description: Reads a boolean from the stream.

2.52.15 TReader.ReadChar

Synopsis: Reads a character from the stream.

Declaration: `function ReadChar : Char`

Visibility: `public`

Description: Reads a character from the stream.

2.52.16 TReader.ReadCollection

Synopsis: Reads a collection from the stream.

Declaration: `procedure ReadCollection(Collection: TCollection)`

Visibility: `public`

Description: Reads a collection from the stream.

2.52.17 TReader.ReadComponent

Synopsis: Starts reading a component from the stream.

Declaration: `function ReadComponent(Component: TComponent) : TComponent`

Visibility: `public`

Description: Starts reading a component from the stream.

2.52.18 TReader.ReadComponents

Synopsis: Starts reading child components from the stream.

Declaration: `procedure ReadComponents (AOwner: TComponent; AParent: TComponent;
Proc: TReadComponentsProc)`

Visibility: public

Description: Starts reading child components from the stream.

2.52.19 TReader.ReadFloat

Synopsis: Reads a float from the stream.

Declaration: `function ReadFloat : Extended`

Visibility: public

Description: Reads a float from the stream.

2.52.20 TReader.ReadSingle

Synopsis: Reads a single-type real from the stream.

Declaration: `function ReadSingle : Single`

Visibility: public

Description: Reads a single-type real from the stream.

2.52.21 TReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency`

Visibility: public

Description: `ReadCurrency` reads a currency typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteCurrency` ([356](#))

2.52.22 TReader.ReadDate

Synopsis: Reads a date from the stream

Declaration: `function ReadDate : TDateTime`

Visibility: public

Description: Reads a date from the stream

2.52.23 TReader.ReadIdent

Synopsis: Reads an identifier from the stream.

Declaration: `function ReadIdent : String`

Visibility: `public`

Description: Reads an identifier from the stream.

2.52.24 TReader.ReadInteger

Synopsis: Reads an integer from the stream

Declaration: `function ReadInteger : LongInt`

Visibility: `public`

Description: Reads an integer from the stream

2.52.25 TReader.ReadInt64

Synopsis: Reads a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64`

Visibility: `public`

Description: Reads a 64-bit integer from the stream.

2.52.26 TReader.ReadListBegin

Synopsis: Checks for the beginning of a list.

Declaration: `procedure ReadListBegin`

Visibility: `public`

Description: Checks for the beginning of a list.

2.52.27 TReader.ReadListEnd

Synopsis: Checks for the end of a list.

Declaration: `procedure ReadListEnd`

Visibility: `public`

Description: Checks for the end of a list.

2.52.28 TReader.ReadRootComponent

Synopsis: Starts reading a root component.

Declaration: `function ReadRootComponent (ARoot : TComponent) : TComponent`

Visibility: `public`

Description: Starts reading a root component.

2.52.29 TReader.ReadString

Synopsis: Reads a string from the stream.

Declaration: `function ReadString : String`

Visibility: `public`

Description: Reads a string from the stream.

2.52.30 TReader.ReadWideString

Synopsis: Read a WideString value from the stream.

Declaration: `function ReadWideString : WideString`

Visibility: `public`

Description: `ReadWidestring` reads a widestring typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteWideString` ([357](#))

2.52.31 TReader.ReadValue

Synopsis: Reads the next value type from the stream.

Declaration: `function ReadValue : TValueType`

Visibility: `public`

Description: Reads the next value type from the stream.

2.52.32 TReader.CopyValue

Synopsis: Copy a value to a writer.

Declaration: `procedure CopyValue (Writer: TWriter)`

Visibility: `public`

Description: Copy a value to a writer.

2.52.33 TReader.Driver

Synopsis: The driver in use for streaming the data.

Declaration: `Property Driver : TAbstractObjectReader`

Visibility: `public`

Access: `Read`

Description: The driver in use for streaming the data.

2.52.34 TReader.Owner

Synopsis: Owner of the component being read

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Owner of the component being read

2.52.35 TReader.Parent

Synopsis: Parent of the component being read.

Declaration: `Property Parent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Parent of the component being read.

2.52.36 TReader.OnError

Synopsis: Handler called when an error occurs.

Declaration: `Property OnError : TReaderError`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when an error occurs.

2.52.37 TReader.OnPropertyNotFound

Synopsis: Handler for treating missing properties.

Declaration: `Property OnPropertyNotFound : TPropertyNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnPropertyNotFound` can be used to take appropriate action when a property is read from a stream and no such property is found in the RTTI information of the Instance that is being read from the stream. It can be set at runtime, or at design time by an IDE.

For more information about the meaning of the various arguments to the event handler, see `TPropertyNotFoundEvent` ([188](#)).

See also: `TPropertyNotFoundEvent` ([188](#)), `TReader.OnSetMethodProperty` ([314](#)), `TReader.OnReadStringProperty` ([315](#))

2.52.38 TReader.OnFindMethod

Synopsis: Handler to find or change a method address.

Declaration: `Property OnFindMethod : TFindMethodEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler to find or change a method address.

2.52.39 TReader.OnSetMethodProperty

Synopsis: Handler for setting method properties.

Declaration: `Property OnSetMethodProperty : TSetMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnSetMethodProperty` can be set to handle the setting of method properties. This handler can be used by an IDE to prevent methods from actually being when an object is being streamed in the designer.

See also: `TReader.OnReadStringProperty` ([315](#)), `TReader.OnPropertyNotFound` ([313](#))

2.52.40 TReader.OnSetName

Synopsis: Handler called when setting a component name.

Declaration: `Property OnSetName : TSetNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when setting a component name.

2.52.41 TReader.OnReferenceName

Synopsis: Handler called when another component is referenced.

Declaration: `Property OnReferenceName : TReferenceNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when another component is referenced.

2.52.42 TReader.OnAncestorNotFound

Synopsis: Handler called when the ancestor component cannot be found.

Declaration: `Property OnAncestorNotFound : TAncestorNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when the ancestor component cannot be found.

2.52.43 TReader.OnCreateComponent

Synopsis: Handler called when a component needs to be created.

Declaration: Property OnCreateComponent : TCreateComponentEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component needs to be created.

2.52.44 TReader.OnFindComponentClass

Synopsis: Handler called when a component class reference needs to be found.

Declaration: Property OnFindComponentClass : TFindComponentClassEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component class reference needs to be found.

2.52.45 TReader.OnReadStringProperty

Synopsis: Handler for translating strings when read from the stream.

Declaration: Property OnReadStringProperty : TReadWriteStringPropertyEvent

Visibility: public

Access: Read,Write

Description: OnReadStringProperty is called whenever a string property is read from the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is loaded. See TReadWriteStringPropertyEvent (188) for a description of the various parameters.

See also: TReader.OnPropertyNotFound (313), TReader.OnSetMethodProperty (314), TReadWriteStringPropertyEvent (188)

2.53 TRecall

2.53.1 Description

TRecall is a helper class used to copy published properties of a class (the reference object) in another class (the storage object). The reference object and storage object must be assignable to each other.

The TRecall can be used to store the state of a persistent class, and restore it at a later time.

When a TRecall object is created, it gets passed a reference instance and a storage instance. It immediately stores the properties of the reference object in the storage object.

The Store (316) method can be called throughout the lifetime of the reference object to update the stored properties.

When the TRecall instance is destroyed then the properties are copied from the storage object to the reference object. The storage object is freed automatically.

If the properties should not be copied back from the storage to the reference object, the Forget (317) can be called.

2.53.2 Method overview

Page	Property	Description
316	Create	Creates a new instance of <code>TRecall</code> .
316	Destroy	Copies the stored properties to the reference object and destroys the <code>TRecall</code> instance.
317	Forget	Clear the reference property.
316	Store	Assigns the reference instance to the storage instance.

2.53.3 Property overview

Page	Property	Access	Description
317	Reference	r	The reference object.

2.53.4 `TRecall.Create`

Synopsis: Creates a new instance of `TRecall`.

Declaration: `constructor Create(AStorage: TPersistent; AReference: TPersistent)`

Visibility: `public`

Description: `Create` creates a new instance of `TRecall` and initializes the Reference and Storage instances. It calls `Store` ([316](#)) to assign the reference object properties to the storage instance.

See also: `TRecall.Store` ([316](#)), `TRecall.Destroy` ([316](#))

2.53.5 `TRecall.Destroy`

Synopsis: Copies the stored properties to the reference object and destroys the `TRecall` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` assigns the storage instance to the reference instance, if the latter is still valid. After this, it frees the storage and calls the inherited `destroy`.

Errors: `Destroy` does not check whether the reference ([317](#)) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` ([317](#)) to clear the reference instance.

See also: `TRecall.Store` ([316](#)), `TRecall.Forget` ([317](#))

2.53.6 `TRecall.Store`

Synopsis: Assigns the reference instance to the storage instance.

Declaration: `procedure Store`

Visibility: `public`

Description: `Store` assigns the reference instance to the storage instance. This will only work if the two classes can be assigned to each other.

This method can be used to refresh the storage.

Errors: `Store` does not check whether the reference ([317](#)) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` ([317](#)) to clear the reference instance.

2.53.7 TRecall.Forget

Synopsis: Clear the reference property.

Declaration: `procedure Forget`

Visibility: `public`

Description: `Forget` sets the `Reference` (179) property to `Nil`. When the `TRecall` instance is destroyed, the reference instance will not be restored.

Note that after a call to `Forget`, a call to `Store` (316) has no effect.

Errors: None.

See also: `TRecall.Reference` (317), `TRecall.Store` (316), `TRecall.Destroy` (316)

2.53.8 TRecall.Reference

Synopsis: The reference object.

Declaration: `Property Reference : TPersistent`

Visibility: `public`

Access: `Read`

Description: `Reference` is the instance of the reference object. Do not free the reference directly. Call `Forget` (317) to clear the reference and then free the reference object.

See also: `TRecall.Forget` (317)

2.54 TResourceStream

2.54.1 Description

Stream that reads its data from a resource object.

2.54.2 Method overview

Page	Property	Description
317	<code>Create</code>	Creates a new instance of a resource stream.
318	<code>CreateFromID</code>	Creates a new instance of a resource stream with resource
318	<code>Destroy</code>	Destroys the instance of the resource stream.
318	<code>Write</code>	<code>Write</code> implements the abstract <code>TStream.Write</code> (320) method.

2.54.3 TResourceStream.Create

Synopsis: Creates a new instance of a resource stream.

Declaration: `constructor Create(Instance: THandle; const ResName: String;
ResType: PChar)`

Visibility: `public`

Description: Creates a new instance of a resource stream.

2.54.4 TResourceStream.CreateFromID

Synopsis: Creates a new instance of a resource stream with resource

Declaration: constructor `CreateFromID(Instance: THandle; ResID: Integer; ResType: PChar)`

Visibility: public

Description: Creates a new instance of a resource stream with resource

2.54.5 TResourceStream.Destroy

Synopsis: Destroys the instance of the resource stream.

Declaration: destructor `Destroy; Override`

Visibility: public

Description: Destroys the instance of the resource stream.

2.54.6 TResourceStream.Write

Synopsis: `Write` implements the abstract `TStream.Write` (320) method.

Declaration: function `Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` implements the abstract `TStream.Write` (320) method.

2.55 TStream

2.55.1 Description

`TStream` is the base class for all streaming classes. It defines abstract methods for reading (319), writing (320) from and to streams, as well as functions to determine the size of the stream as well as the current position of the stream.

Descendent classes such as `TMemoryStream` (296) or `TFileStream` (274) then implement these abstract methods to write streams to memory or file.

2.55.2 Method overview

Page	Property	Description
321	CopyFrom	Copy data from one stream to another
324	FixupResourceHeader	Not implemented in FPC
319	Read	Reads data from the stream to a buffer and returns the number of bytes read.
325	ReadAnsiString	Read an ansistring from the stream and return its value.
321	ReadBuffer	Reads data from the stream to a buffer
324	ReadByte	Read a byte from the stream and return its value.
322	ReadComponent	Reads component data from a stream
322	ReadComponentRes	Reads component data and resource header from a stream
325	ReadDWord	Read a DWord from the stream and return its value.
324	ReadResHeader	Read a resource header from the stream.
324	ReadWord	Read a word from the stream and return its value.
320	Seek	Sets the current position in the stream
320	Write	Writes data from a buffer to the stream and returns the number of bytes written.
326	WriteAnsiString	Write an ansistring to the stream.
321	WriteBuffer	Writes data from the stream to the buffer
325	WriteByte	Write a byte to the stream.
322	WriteComponent	Write component data to the stream
323	WriteComponentRes	Write resource header and component data to a stream
323	WriteDescendent	Write component data to a stream, relative to an ancestor
323	WriteDescendentRes	Write resource header and component data to a stream, relative to an ancestor
326	WriteDWord	Write a DWord to the stream.
323	WriteResourceHeader	Write resource header to the stream
326	WriteWord	Write a word to the stream.

2.55.3 Property overview

Page	Property	Access	Description
327	Position	rw	The current position in the stream.
327	Size	rw	The current size of the stream.

2.55.4 TStream.Read

Synopsis: Reads data from the stream to a buffer and returns the number of bytes read.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Virtual; Abstract`

Visibility: public

Description: Read attempts to read `Count` from the stream to `Buffer` and returns the number of bytes actually read.

This method should be used when the number of bytes is not determined. If a specific number of bytes is expected, use `TStream.ReadBuffer` ([321](#)) instead.

`Read` is an abstract method that is overridden by descendent classes to do the actual reading.

Errors: Descendent classes that do not allow reading from the stream may raise an exception when the `Read` is used.

See also: `TStream.Write` ([320](#)), `TStream.ReadBuffer` ([321](#))

2.55.5 TStream.Write

Synopsis: Writes data from a buffer to the stream and returns the number of bytes written.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Virtual
; Abstract`

Visibility: public

Description: `Write` attempts to write `Count` bytes from `Buffer` to the stream. It returns the actual number of bytes written to the stream.

This method should be used when the number of bytes that should be written is not determined. If a specific number of bytes should be written, use `TStream.WriteBuffer` (321) instead.

`Write` is an abstract method that is overridden by descendent classes to do the actual writing.

Errors: Descendent classes that do not allow writing to the stream may raise an exception when `Write` is used.

See also: `TStream.Read` (319), `TStream.WriteBuffer` (321)

2.55.6 TStream.Seek

Synopsis: Sets the current position in the stream

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Virtual
; Overload
function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Virtual
; Overload`

Visibility: public

Description: `Seek` sets the position of the stream to `Offset` bytes from `Origin`. `Origin` can have one of the following values:

Table 2.18:

Constant	Meaning
<code>soFromBeginning</code>	Set the position relative to the start of the stream.
<code>soFromCurrent</code>	Set the position relative to the beginning of the stream.
<code>soFromEnd</code>	Set the position relative to the end of the stream.

`Offset` should be negative when the origin is `SoFromEnd`. It should be positive for `soFromBeginning` and can have both signs for `soFromCurrent`

This is an abstract method, which must be overridden by descendent classes. They may choose not to implement this method for all values of `Origin` and `Offset`.

Errors: An exception may be raised if this method is called with an invalid pair of `Offset`, `Origin` values. e.g. a negative offset for `soFromBeginning`.

See also: `TStream.Position` (327)

2.55.7 TStream.ReadBuffer

Synopsis: Reads data from the stream to a buffer

Declaration: `procedure ReadBuffer (var Buffer; Count: LongInt)`

Visibility: public

Description: `ReadBuffer` reads `Count` bytes of the stream into `Buffer`. If the stream does not contain `Count` bytes, then an exception is raised.

`ReadBuffer` should be used to read in a fixed number of bytes, such as when reading structures or the content of variables. If the number of bytes is not determined, use `TStream.Read` (319) instead. `ReadBuffer` uses `Read` internally to do the actual reading.

Errors: If the stream does not allow to read `Count` bytes, then an exception is raised.

See also: `TStream.Read` (319), `TStream.WriteBuffer` (321)

2.55.8 TStream.WriteBuffer

Synopsis: Writes data from the stream to the buffer

Declaration: `procedure WriteBuffer (const Buffer; Count: LongInt)`

Visibility: public

Description: `WriteBuffer` writes `Count` bytes to the stream from `Buffer`. If the stream does not allow `Count` bytes to be written, then an exception is raised.

`WriteBuffer` should be used to read in a fixed number of bytes, such as when writing structures or the content of variables. If the number of bytes is not determined, use `TStream.Write` (320) instead. `WriteBuffer` uses `Write` internally to do the actual reading.

Errors: If the stream does not allow to write `Count` bytes, then an exception is raised.

See also: `TStream.Write` (320), `TStream.ReadBuffer` (321)

2.55.9 TStream.CopyFrom

Synopsis: Copy data from one stream to another

Declaration: `function CopyFrom (Source: TStream; Count: Int64) : Int64`

Visibility: public

Description: `CopyFrom` reads `Count` bytes from `Source` and writes them to the current stream. This updates the current position in the stream. After the action is completed, the number of bytes copied is returned.

This can be used to quickly copy data from one stream to another or to copy the whole contents of the stream.

See also: `TStream.Read` (319), `TStream.Write` (320)

2.55.10 TStream.ReadComponent

Synopsis: Reads component data from a stream

Declaration: `function ReadComponent (Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponent` reads a component state from the stream and transfers this state to `Instance`. If `Instance` is `nil`, then it is created first based on the type stored in the stream. `ReadComponent` returns the component as it is read from the stream.

`ReadComponent` simply creates a `TReader` (305) object and calls its `ReadRootComponent` (311) method.

Errors: If an error occurs during the reading of the component, an `EFileError` (207) exception is raised.

See also: `TStream.WriteComponent` (322), `TStream.ReadComponentRes` (322), `TReader.ReadRootComponent` (311)

2.55.11 TStream.ReadComponentRes

Synopsis: Reads component data and resource header from a stream

Declaration: `function ReadComponentRes (Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponentRes` reads a resource header from the stream, and then calls `ReadComponent` (322) to read the component state from the stream into `Instance`.

This method is usually called by the global streaming method when instantiating forms and datamodules as created by an IDE. It should be used mainly on Windows, to store components in Windows resources.

Errors: If an error occurs during the reading of the component, an `EFileError` (207) exception is raised.

See also: `TStream.ReadComponent` (322), `TStream.WriteComponentRes` (323)

2.55.12 TStream.WriteComponent

Synopsis: Write component data to the stream

Declaration: `procedure WriteComponent (Instance: TComponent)`

Visibility: public

Description: `WriteComponent` writes the published properties of `Instance` to the stream, so they can later be read with `TStream.ReadComponent` (322). This method is intended to be used by an IDE, to preserve the state of a form or datamodule as designed in the IDE.

`WriteComponent` simply calls `WriteDescendent` (323) with `Nil` ancestor.

See also: `TStream.ReadComponent` (322), `TStream.WriteComponentRes` (323)

2.55.13 TStream.WriteComponentRes

Synopsis: Write resource header and component data to a stream

Declaration: `procedure WriteComponentRes(const ResName: String; Instance: TComponent)`

Visibility: public

Description: `WriteComponentRes` writes a `ResName` resource header to the stream and then calls `WriteComponent` (322) to write the published properties of `Instance` to the stream.

This method is intended for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

See also: `TStream.WriteComponent` (322), `TStream.ReadComponentRes` (322)

2.55.14 TStream.WriteDescendent

Synopsis: Write component data to a stream, relative to an ancestor

Declaration: `procedure WriteDescendent(Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendent` writes the state of `Instance` to the stream where it differs from `Ancestor`, i.e. only the changed properties are written to the stream.

`WriteDescendent` creates a `TWriter` (353) object and calls its `WriteDescendent` (355) object. The writer is passed a binary driver object (240) by default.

2.55.15 TStream.WriteDescendentRes

Synopsis: Write resource header and component data to a stream, relative to an ancestor

Declaration: `procedure WriteDescendentRes(const ResName: String; Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendentRes` writes a `ResName` resource header, and then calls `WriteDescendent` (323) to write the state of `Instance` to the stream where it differs from `Ancestor`, i.e. only the changed properties are written to the stream.

This method is intended for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

2.55.16 TStream.WriteResourceHeader

Synopsis: Write resource header to the stream

Declaration: `procedure WriteResourceHeader(const ResName: String; var FixupInfo: Integer)`

Visibility: public

Description: `WriteResourceHeader` writes a resource-file header for a resource called `ResName`. It returns in `FixupInfo` the argument that should be passed on to `TStream.FixupResourceHeader` (324).

`WriteResourceHeader` should not be used directly. It is called by the `TStream.WriteComponentRes` (323) and `TStream.WriteDescendentRes` (323) methods.

See also: `TStream.FixupResourceHeader` (324), `TStream.WriteComponentRes` (323), `TStream.WriteDescendentRes` (323)

2.55.17 TStream.FixupResourceHeader

Synopsis: Not implemented in FPC

Declaration: `procedure FixupResourceHeader(FixupInfo: Integer)`

Visibility: `public`

Description: `FixupResourceHeader` is used to write the size of the resource after a component was written to stream. The size is determined from the current position, and it is written at position `FixupInfo`. After that the current position is restored.

`FixupResourceHeader` should never be called directly; it is handled by the streaming system.

See also: `TStream.WriteResourceHeader` (323), `TStream.WriteComponentRes` (323), `TStream.WriteDescendentRes` (323)

2.55.18 TStream.ReadResHeader

Synopsis: Read a resource header from the stream.

Declaration: `procedure ReadResHeader`

Visibility: `public`

Description: `ReadResourceHeader` reads a resource file header from the stream. It positions the stream just beyond the header.

`ReadResourceHeader` should not be called directly, it is called by the streaming system when needed.

Errors: If the resource header is invalid an `EInvalidImage` (207) exception is raised.

See also: `TStream.ReadComponentRes` (322), `EInvalidImage` (207)

2.55.19 TStream.ReadByte

Synopsis: Read a byte from the stream and return its value.

Declaration: `function ReadByte : Byte`

Visibility: `public`

Description: `ReadByte` reads one byte from the stream and returns its value.

Errors: If the byte cannot be read, an `EStreamError` (209) exception will be raised. This is a utility function which simply calls the `Read` (319) function.

See also: `TStream.Read` (319), `TStream.WriteByte` (325), `TStream.ReadWord` (324), `TStream.ReadDWord` (325), `TStream.ReadAnsiString` (325)

2.55.20 TStream.ReadWord

Synopsis: Read a word from the stream and return its value.

Declaration: `function ReadWord : Word`

Visibility: `public`

Description: `ReadWord` reads one Word (i.e. 2 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (319) function.

Errors: If the word cannot be read, a `EStreamError` (209) exception will be raised.

See also: `TStream.Read` (319), `TStream.WriteWord` (326), `TStream.ReadByte` (324), `TStream.ReadDWord` (325), `TStream.ReadAnsiString` (325)

2.55.21 TStream.ReadDWord

Synopsis: Read a DWord from the stream and return its value.

Declaration: `function ReadDWord : Cardinal`

Visibility: public

Description: `ReadDWord` reads one DWord (i.e. 4 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (319) function.

Errors: If the DWord cannot be read, a `EStreamError` (209) exception will be raised.

See also: `TStream.Read` (319), `TStream.WriteDWord` (326), `TStream.ReadByte` (324), `TStream.ReadWord` (324), `TStream.ReadAnsiString` (325)

2.55.22 TStream.ReadAnsiString

Synopsis: Read an ansistring from the stream and return its value.

Declaration: `function ReadAnsiString : String`

Visibility: public

Description: `ReadAnsiString` reads an ansistring from the stream and returns its value. This is a utility function which simply calls the `read` function several times. The Ansistring should be stored as 4 bytes (a DWord) representing the length of the string, and then the string value itself. The `WriteAnsiString` (326) function writes an ansistring in such a format.

Errors: If the AnsiString cannot be read, a `EStreamError` (209) exception will be raised.

See also: `TStream.Read` (319), `TStream.WriteAnsiString` (326), `TStream.ReadByte` (324), `TStream.ReadWord` (324), `TStream.ReadDWord` (325)

2.55.23 TStream.WriteByte

Synopsis: Write a byte to the stream.

Declaration: `procedure WriteByte(b: Byte)`

Visibility: public

Description: `WriteByte` writes the byte `B` to the stream. This is a utility function which simply calls the `Write` (320) function. The byte can be read from the stream using the `ReadByte` (324) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (209) exception will be raised.

See also: `TStream.Write` (320), `TStream.ReadByte` (324), `TStream.WriteWord` (326), `TStream.WriteDWord` (326), `TStream.WriteAnsiString` (326)

2.55.24 TStream.WriteWord

Synopsis: Write a word to the stream.

Declaration: `procedure WriteWord(w: Word)`

Visibility: `public`

Description: `WriteWord` writes the word `W` (i.e. 2 bytes) to the stream. This is a utility function which simply calls the `Write` (320) function. The word can be read from the stream using the `ReadWord` (324) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (209) exception will be raised.

See also: `TStream.Write` (320), `TStream.ReadWord` (324), `TStream.WriteByte` (325), `TStream.WriteDWord` (326), `TStream.WriteAnsiString` (326)

2.55.25 TStream.WriteDWord

Synopsis: Write a DWord to the stream.

Declaration: `procedure WriteDWord(d: Cardinal)`

Visibility: `public`

Description: `WriteDWord` writes the DWord `D` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (320) function. The DWord can be read from the stream using the `ReadDWord` (325) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (209) exception will be raised.

See also: `TStream.Write` (320), `TStream.ReadDWord` (325), `TStream.WriteByte` (325), `TStream.WriteWord` (326), `TStream.WriteAnsiString` (326)

2.55.26 TStream.WriteAnsiString

Synopsis: Write an ansistring to the stream.

Declaration: `procedure WriteAnsiString(S: String)`

Visibility: `public`

Description: `WriteAnsiString` writes the `AnsiString` `S` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (320) function. The ansistring is written as a 4 byte length specifier, followed by the ansistring's content. The ansistring can be read from the stream using the `ReadAnsiString` (325) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (209) exception will be raised.

See also: `TStream.Write` (320), `TStream.ReadAnsiString` (325), `TStream.WriteByte` (325), `TStream.WriteWord` (326), `TStream.WriteDWord` (326)

2.55.27 TStream.Position

Synopsis: The current position in the stream.

Declaration: `Property Position : Int64`

Visibility: `public`

Access: `Read, Write`

Description: `Position` can be read to determine the current position in the stream. It can be written to to set the (absolute) position in the stream. The position is zero-based, so to set the position at the beginning of the stream, the position must be set to zero.

Remark: Not all `TStream` descendants support setting the position in the stream, so this should be used with care.

Errors: Some descendents may raise an `EStreamError` (209) exception if they do not support setting the stream position.

See also: `TStream.Size` (327), `TStream.Seek` (320)

2.55.28 TStream.Size

Synopsis: The current size of the stream.

Declaration: `Property Size : Int64`

Visibility: `public`

Access: `Read, Write`

Description: `Size` can be read to determine the stream size or to set the stream size.

Remark: Not all descendents of `TStream` support getting or setting the stream size; they may raise an exception if the `Size` property is read or set.

See also: `TStream.Position` (327), `TStream.Seek` (320)

2.56 TStringList

2.56.1 Description

`TStringList` is a descendent class of `TStrings` (332) that implements all of the abstract methods introduced there. It also introduces some additional methods:

- Sort the list, or keep the list sorted at all times
- Special handling of duplicates in sorted lists
- Notification of changes in the list

2.56.2 Method overview

Page	Property	Description
328	Add	Implements the TStrings.Add (334) function.
329	Clear	Implements the TStrings.Clear (335) function.
330	CustomSort	
329	Delete	Implements the TStrings.Delete (336) function.
328	Destroy	Destroys the stringlist.
329	Exchange	Implements the TStrings.Exchange (337) function.
329	Find	Locates the index for a given string in sorted lists.
330	IndexOf	Overrides the TStrings.IndexOf (337) property.
330	Insert	Overrides the TStrings.Insert (338) method.
330	Sort	Sorts the strings in the list.

2.56.3 Property overview

Page	Property	Access	Description
331	CaseSensitive	rw	
331	Duplicates	rw	Describes the behaviour of a sorted list with respect to duplicate strings.
332	OnChange	rw	Event triggered after the list was modified.
332	OnChanging	rw	Event triggered when the list is about to be modified.
331	Sorted	rw	Determines whether the list is sorted or not.

2.56.4 TStringList.Destroy

Synopsis: Destroys the stringlist.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the stringlist, release all memory allocated for the storage of the strings, and then calls the inherited destroy method.

Remark: Any objects associated to strings in the list will *not* be destroyed; it is the responsibility of the caller to destroy all objects associated with strings in the list.

2.56.5 TStringList.Add

Synopsis: Implements the TStrings.Add ([334](#)) function.

Declaration: `function Add(const S: String) : Integer; Override`

Visibility: `public`

Description: `Add` will add `S` to the list. If the list is sorted and the string `S` is already present in the list and `TStringList.Duplicates` ([331](#)) is `dupError` then an `EStringListError` ([209](#)) exception is raised. If `Duplicates` is set to `dupIgnore` then the return value is undefined.

If the list is sorted, new strings will not necessarily be added to the end of the list, rather they will be inserted at their alphabetical position.

Errors: If the list is sorted and the string `S` is already present in the list and `TStringList.Duplicates` ([331](#)) is `dupError` then an `EStringListError` ([209](#)) exception is raised.

See also: `TStringList.Insert` ([330](#)), `TStringList.Duplicates` ([331](#))

2.56.6 TStringList.Clear

Synopsis: Implements the `TStrings.Clear` (335) function.

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: Implements the `TStrings.Clear` (335) function.

2.56.7 TStringList.Delete

Synopsis: Implements the `TStrings.Delete` (336) function.

Declaration: `procedure Delete(Index: Integer); Override`

Visibility: `public`

Description: Implements the `TStrings.Delete` (336) function.

2.56.8 TStringList.Exchange

Synopsis: Implements the `TStrings.Exchange` (337) function.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Override`

Visibility: `public`

Description: `Exchange` will exchange two items in the list as described in `TStrings.Exchange` (337).

Remark: `Exchange` will not check whether the list is sorted or not; if `Exchange` is called on a sorted list and the strings are not identical, the sort order of the list will be destroyed.

See also: `TStringList.Sorted` (331), `TStrings.Exchange` (337)

2.56.9 TStringList.Find

Synopsis: Locates the index for a given string in sorted lists.

Declaration: `function Find(const S: String; var Index: Integer) : Boolean; Virtual`

Visibility: `public`

Description: `Find` returns `True` if the string `S` is present in the list. Upon exit, the `Index` parameter will contain the position of the string in the list. If the string is not found, the function will return `False` and `Index` will contain the position where the string will be inserted if it is added to the list.

Remark:

1. Use this method only on sorted lists. For unsorted lists, use `TStringList.IndexOf` (330) instead.
2. `Find` uses a binary search method to locate the string

2.56.10 TStringList.IndexOf

Synopsis: Overrides the TStrings.IndexOf ([337](#)) property.

Declaration: `function IndexOf(const S: String) : Integer; Override`

Visibility: public

Description: `IndexOf` overrides the ancestor method `TStrings.indexOf` ([337](#)). It tries to optimize the search by executing a binary search if the list is sorted. The function returns the position of `S` if it is found in the list, or -1 if the string is not found in the list.

See also: `TStrings.IndexOf` ([337](#)), `TStringList.Find` ([329](#))

2.56.11 TStringList.Insert

Synopsis: Overrides the TStrings.Insert ([338](#)) method.

Declaration: `procedure Insert(Index: Integer; const S: String); Override`

Visibility: public

Description: `Insert` will insert the string `S` at position `Index` in the list. If the list is sorted, an `EStringListError` ([209](#)) exception will be raised instead. `Index` is a zero-based position.

Errors: If `Index` contains an invalid value (less than zero or larger than `Count`, or the list is sorted, an `EStringListError` ([209](#)) exception will be raised.

See also: `TStringList.Add` ([328](#)), `TStrings.Insert` ([338](#)), `TStringList.InsertObject` ([327](#))

2.56.12 TStringList.Sort

Synopsis: Sorts the strings in the list.

Declaration: `procedure Sort; Virtual`

Visibility: public

Description: `Sort` will sort the strings in the list using the quicksort algorithm. If the list has its `TStringList.Sorted` ([331](#)) property set to `True` then nothing will be done.

See also: `TStringList.Sorted` ([331](#))

2.56.13 TStringList.CustomSort

Synopsis:

Declaration: `procedure CustomSort(CompareFn: TStringListSortCompare)`

Visibility: public

Description:

2.56.14 TStringList.Duplicates

Synopsis: Describes the behaviour of a sorted list with respect to duplicate strings.

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what to do in case a duplicate value is added to the list:

Table 2.19:

<code>dupIgnore</code>	Duplicate values will not be added to the list, but no error will be triggered.
<code>dupError</code>	If an attempt is made to add a duplicate value to the list, an <code>EStringListError</code> (209) exception is raised.
<code>dupAccept</code>	Duplicate values can be added to the list.

If the stringlist is not sorted, the `Duplicates` setting is ignored.

2.56.15 TStringList.Sorted

Synopsis: Determines whether the list is sorted or not.

Declaration: `Property Sorted : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Sorted` can be set to `True` in order to cause the list of strings to be sorted. Further additions to the list will be inserted at the correct position so the list remains sorted at all times. Setting the property to `False` has no immediate effect, but will allow strings to be inserted at any position.

Remark:

1. When `Sorted` is `True`, `TStringList.Insert` (330) cannot be used. For sorted lists, `TStringList.Add` (328) should be used instead.
2. If `Sorted` is `True`, the `TStringList.Duplicates` (331) setting has effect. This setting is ignored when `Sorted` is `False`.

See also: `TStringList.Sort` (330), `TStringList.Duplicates` (331), `TStringList.Add` (328), `TstringList.Insert` (330)

2.56.16 TStringList.CaseSensitive

Synopsis:

Declaration: `Property CaseSensitive : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether locating strings happens in a case sensitive manner.

2.56.17 TStringList.OnChange

Synopsis: Event triggered after the list was modified.

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` can be assigned to respond to changes that have occurred in the list. The handler is called whenever strings are added, moved, modified or deleted from the list.

The `OnChange` event is triggered after the modification took place. When the modification is about to happen, an `TStringList.OnChanging` (332) event occurs.

See also: `TStringList.OnChanging` (332)

2.56.18 TStringList.OnChanging

Synopsis: Event triggered when the list is about to be modified.

Declaration: `Property OnChanging : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChanging` can be assigned to respond to changes that will occurred in the list. The handler is called whenever strings will be added, moved, modified or deleted from the list.

The `OnChanging` event is triggered before the modification will take place. When the modification has happened, an `TStringList.OnChange` (332) event occurs.

See also: `TStringList.OnChange` (332)

2.57 TStrings

2.57.1 Description

`TStrings` implements an abstract class to manage an array of strings. It introduces methods to set and retrieve strings in the array, searching for a particular string, concatenating the strings and so on. It also allows an arbitrary object to be associated with each string.

It also introduces methods to manage a series of `name=value` settings, as found in many configuration files.

An instance of `TStrings` is never created directly, instead a descendent class such as `TStringList` (327) should be created. This is because `TStrings` is an abstract class which does not implement all methods; `TStrings` also doesn't store any strings, this is the functionality introduced in descendents such as `TStringList` (327).

2.57.2 Method overview

Page	Property	Description
334	Add	Add a string to the list
334	AddObject	Add a string and associated object to the list.
334	AddStrings	Add contents of another stringlist to this list.
334	Append	Add a string to the list.
335	Assign	Assign the contents of another stringlist to this one.
335	BeginUpdate	Mark the beginning of an update batch.
335	Clear	Removes all strings and associated objects from the list.
336	Delete	Delete a string from the list.
333	Destroy	Frees all strings and objects, and removes the list from memory.
336	EndUpdate	Mark the end of an update batch.
336	Equals	Compares the contents of two stringlists.
337	Exchange	Exchanges two strings in the list.
341	GetNameValue	Return both name and value of a name,value pair based on it's index.
337	GetText	Returns the contents as a PChar
337	IndexOf	Find a string in the list and return its position.
337	IndexOfName	Finds the index of a name in the name-value pairs.
338	IndexOfObject	Finds an object in the list and returns its index.
338	Insert	Insert a string in the list.
338	InsertObject	Insert a string and associated object in the list.
339	LoadFromFile	Load the contents of a file as a series of strings.
339	LoadFromStream	Load the contents of a stream as a series of strings.
339	Move	Move a string from one place in the list to another.
340	SaveToFile	Save the contents of the list to a file.
340	SaveToStream	Save the contents of the string to a stream.
340	SetText	Set the contents of the list from a PChar.

2.57.3 Property overview

Page	Property	Access	Description
342	Capacity	rw	Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.
342	CommaText	rw	Contents of the list as a comma-separated string.
343	Count	r	Number of strings in the list.
341	DelimitedText	rw	Get or set all strings in the list in a delimited form.
341	Delimiter	rw	Delimiter character used in DelimitedText (341).
343	Names	r	Name parts of the name-value pairs in the list.
341	NameValueSeparator	rw	Value of the character used to separate name,value pairs
344	Objects	rw	Indexed access to the objects associated with the strings in the list.
341	QuoteChar	rw	Quote character used in DelimitedText (341).
344	Strings	rw	Indexed access to teh strings in the list.
345	StringsAdapter	rw	Not implemented in Free Pascal.
345	Text	rw	Contents of the list as one big string.
342	ValueFromIndex	rw	
344	Values	rw	Value parts of the name-value pairs in the list.

2.57.4 TStrings.Destroy

Synopsis: Frees all strings and objects, and removes the list from memory.

Declaration: `destructor Destroy;` `Override`

Visibility: public

Description: `Destroy` is the destructor of `TStrings` it does nothing except calling the inherited destructor.

2.57.5 TStrings.Add

Synopsis: Add a string to the list

Declaration: `function Add(const S: String) : Integer; Virtual`

Visibility: public

Description: `Add` adds `S` at the end of the list and returns the index of `S` in the list (which should equal `TStrings.Count` [\(343\)](#))

See also: `TStrings.Items` [\(332\)](#), `TStrings.AddObject` [\(334\)](#), `TStrings.Insert` [\(338\)](#), `TStrings.Delete` [\(336\)](#), `TStrings.Strings` [\(344\)](#), `TStrings.Count` [\(343\)](#)

2.57.6 TStrings.AddObject

Synopsis: Add a string and associated object to the list.

Declaration: `function AddObject(const S: String; AObject: TObject) : Integer; Virtual`

Visibility: public

Description: `AddObject` adds `S` to the list of strings, and associates `AObject` with it. It returns the index of `S`.

Remark: An object added to the list is not automatically destroyed by the list if the list is destroyed or the string it is associated with is deleted. It is the responsibility of the application to destroy any objects associated with strings.

See also: `TStrings.Add` [\(334\)](#), `TStrings.Items` [\(332\)](#), `TStrings.Objects` [\(344\)](#), `TStrings.InsertObject` [\(338\)](#)

2.57.7 TStrings.Append

Synopsis: Add a string to the list.

Declaration: `procedure Append(const S: String)`

Visibility: public

Description: `Append` does the same as `TStrings.Add` [\(334\)](#), only it does not return the index of the inserted string.

See also: `TStrings.Add` [\(334\)](#)

2.57.8 TStrings.AddStrings

Synopsis: Add contents of another stringlist to this list.

Declaration: `procedure AddStrings(TheStrings: TStrings); Virtual`

Visibility: public

Description: `AddStrings` adds the contents of `TheStrings` to the stringlist. Any associated objects are added as well.

See also: `TStrings.Add` [\(334\)](#), `TStrings.Assign` [\(335\)](#)

2.57.9 TStrings.Assign

Synopsis: Assign the contents of another stringlist to this one.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: public

Description: `Assign` replaces the contents of the stringlist with the contents of `Source` if `Source` is also of type `TStrings`. Any associated objects are copied as well.

See also: `TStrings.Add` (334), `TStrings.AddStrings` (334), `TPersistent.Assign` (304)

2.57.10 TStrings.BeginUpdate

Synopsis: Mark the beginning of an update batch.

Declaration: `procedure BeginUpdate`

Visibility: public

Description: `BeginUpdate` increases the update count by one. It is advisable to call `BeginUpdate` before lengthy operations on the stringlist. At the end of these operation, `TStrings.EndUpdate` (336) should be called to mark the end of the operation. Descendent classes may use this information to perform optimizations. e.g. updating the screen only once after many strings were added to the list.

All `TStrings` methods that modify the string list call `BeginUpdate` before the actual operation, and call `endUpdate` when the operation is finished. Descendent classes should also call these methods when modifying the string list.

Remark: Always put the corresponding call to `TStrings.EndUpdate` (336) in the context of a `Finally` block, to ensure that the update count is always decreased at the end of the operation, even if an exception occurred:

```
With MyStrings do
  try
    BeginUpdate;
    // Some lengthy operation.
  Finally
    EndUpdate
  end;
```

See also: `TStrings.EndUpdate` (336)

2.57.11 TStrings.Clear

Synopsis: Removes all strings and associated objects from the list.

Declaration: `procedure Clear; Virtual; Abstract`

Visibility: public

Description: `Clear` will remove all strings and their associated objects from the list. After a call to `clear`, `TStrings.Count` (343) is zero.

Since it is an abstract method, `TStrings` itself does not implement `Clear`. Descendent classes such as `TStringList` (327) implement this method.

See also: `TStrings.Items` (332), `TStrings.Delete` (336), `TStrings.Count` (343)

2.57.12 TStrings.Delete

Synopsis: Delete a string from the list.

Declaration: `procedure Delete(Index: Integer); Virtual; Abstract`

Visibility: `public`

Description: `Delete` deletes the string at position `Index` from the list. The associated object is also removed from the list, but not destroyed. `Index` is zero-based, and should be in the range 0 to `Count-1`.

Since it is an abstract method, `TStrings` itself does not implement `Delete`. Descendent classes such as `TStringList` (327) implement this method.

Errors: If `Index` is not in the allowed range, an `EStringListError` (209) is raised.

See also: `TStrings.Insert` (338), `TStrings.Items` (332), `TStrings.Clear` (335)

2.57.13 TStrings.EndUpdate

Synopsis: Mark the end of an update batch.

Declaration: `procedure EndUpdate`

Visibility: `public`

Description: `EndUpdate` should be called at the end of a lengthy operation on the stringlist, but only if there was a call to `BeginUpdate` before the operation was started. It is best to put the call to `EndUpdate` in the context of a `Finally` block, so it will be called even if an exception occurs.

For more information, see `TStrings.BeginUpdate` (335).

See also: `TStrings.BeginUpdate` (335)

2.57.14 TStrings.Equals

Synopsis: Compares the contents of two stringlists.

Declaration: `function Equals(TheStrings: TStrings) : Boolean`

Visibility: `public`

Description: `Equals` compares the contents of the stringlist with the contents of `TheStrings`. If the contents match, i.e. the stringlist contain an equal amount of strings, and all strings match, then `True` is returned. If the number of strings in the lists is unequal, or they contain one or more different strings, `False` is returned.

Remark:

- 1.The strings are compared case-insensitively.
- 2.The associated objects are not compared

See also: `Tstrings.Items` (332), `TStrings.Count` (343), `TStrings.Assign` (335)

2.57.15 TStrings.Exchange

Synopsis: Exchanges two strings in the list.

Declaration: `procedure Exchange (Index1: Integer; Index2: Integer); Virtual`

Visibility: public

Description: `Exchange` exchanges the strings at positions `Index1` and `Index2`. The associated objects are also exchanged.

Both indexes must be in the range of valid indexes, i.e. must have a value between 0 and `Count-1`.

Errors: If either `Index1` or `Index2` is not in the range of valid indexes, an `EStringListError` (209) exception is raised.

See also: `TStrings.Move` (339), `TStrings.Strings` (344), `TStrings.Count` (343)

2.57.16 TStrings.GetText

Synopsis: Returns the contents as a `PChar`

Declaration: `function GetText : PChar; Virtual`

Visibility: public

Description: `GetText` allocates a memory buffer and compies the contents of the stringlist to this buffer as a series of strings, separated by an end-of-line marker. The buffer is zero terminated.

Remark: The caller is responsible for freeing the returned memory buffer.

2.57.17 TStrings.IndexOf

Synopsis: Find a string in the list and return its position.

Declaration: `function IndexOf (const S: String) : Integer; Virtual`

Visibility: public

Description: `IndexOf` searches the list for `S`. The search is case-insensitive. If a matching entry is found, its position is returned. if no matching string is found, `-1` is returned.

Remark:

1. Only the first occurrence of the string is returned.

2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOfObject` (338), `TStrings.IndexOfName` (337), `TStrings.Strings` (344)

2.57.18 TStrings.IndexOfName

Synopsis: Finds the index of a name in the name-value pairs.

Declaration: `function IndexOfName (const Name: String) : Integer; Virtual`

Visibility: public

Description: `IndexOfName` searches in the list of strings for a name-value pair with name part `Name`. If such a pair is found, it returns the index of the pair in the stringlist. If no such pair is found, the function returns `-1`. The search is done case-insensitive.

Remark:

1. Only the first occurrence of a matching name-value pair is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOf` (337), `TStrings.IndexOfObject` (338), `TStrings.Strings` (344)

2.57.19 TStrings.IndexOfObject

Synopsis: Finds an object in the list and returns its index.

Declaration: `function IndexOfObject(AObject: TObject) : Integer; Virtual`

Visibility: public

Description: `IndexOfObject` searches through the list of strings till it find a string associated with `AObject`, and returns the index of this string. If no such string is found, -1 is returned.

Remark:

1. Only the first occurrence of a string with associated object `AObject` is returned; if more strings in the list can be associated with `AObject`, they will not be found by this routine.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

2.57.20 TStrings.Insert

Synopsis: Insert a string in the list.

Declaration: `procedure Insert(Index: Integer; const S: String); Virtual; Abstract`

Visibility: public

Description: `Insert` inserts the string `S` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Remark:

1. All methods that add strings to the list use `Insert` to add a string to the list.
2. If the string has an associated object, use `TStrings.InsertObject` (338) instead.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (209) exception is raised.

See also: `TStrings.Add` (334), `TStrings.InsertObject` (338), `TStrings.Append` (334), `TStrings.Delete` (336)

2.57.21 TStrings.InsertObject

Synopsis: Insert a string and associated object in the list.

Declaration: `procedure InsertObject(Index: Integer; const S: String; AObject: TObject)`

Visibility: public

Description: `InsertObject` inserts the string `S` and its associated object `AObject` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (209) exception is raised.

See also: `TStrings.Insert` (338), `TStrings.AddObject` (334), `TStrings.Append` (334), `TStrings.Delete` (336)

2.57.22 TStrings.LoadFromFile

Synopsis: Load the contents of a file as a series of strings.

Declaration: `procedure LoadFromFile(const FileName: String); Virtual`

Visibility: public

Description: `LoadFromFile` loads the contents of a file into the stringlist. Each line in the file (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

`LoadFromFile` simply creates a file stream (274) with the given filename, and then executes `TStrings.LoadfromStream` (339); after that the file stream object is destroyed again.

See also: `TStrings.LoadFromStream` (339), `TStrings.SaveToFile` (340), `Tstrings.SaveToStream` (340)

2.57.23 TStrings.LoadFromStream

Synopsis: Load the contents of a stream as a series of strings.

Declaration: `procedure LoadFromStream(Stream: TStream); Virtual`

Visibility: public

Description: `LoadFromStream` loads the contents of `Stream` into the stringlist. Each line in the stream (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

See also: `TStrings.LoadFromFile` (339), `TStrings.SaveToFile` (340), `Tstrings.SaveToStream` (340)

2.57.24 TStrings.Move

Synopsis: Move a string from one place in the list to another.

Declaration: `procedure Move(CurIndex: Integer; NewIndex: Integer); Virtual`

Visibility: public

Description: `Move` moves the string at position `CurIndex` so it has position `NewIndex` after the move operation. The object associated to the string is also moved. `CurIndex` and `NewIndex` should be in the range of 0 to `Count-1`.

Remark: `NewIndex` is *not* the position in the stringlist before the move operation starts. The move operation

- 1.removes the string from position `CurIndex`
- 2.inserts the string at position `NewIndex`

This may not lead to the desired result if `NewIndex` is bigger than `CurIndex`. Consider the following example:

```
With MyStrings do
begin
  Clear;
  Add('String 0');
  Add('String 1');
```



```

Add('String 2');
Add('String 3');
Add('String 4');
Move(1,3);
end;

```

After the `Move` operation has completed, 'String 1' will be between 'String 3' and 'String 4'.

Errors: If either `CurIndex` or `NewIndex` is outside the allowed range, an `EStringListError` (209) is raised.

See also: `TStrings.Exchange` (337)

2.57.25 TStrings.SaveToFile

Synopsis: Save the contents of the list to a file.

Declaration: `procedure SaveToFile(const FileName: String); Virtual`

Visibility: `public`

Description: `SaveToFile` saves the contents of the stringlist to the file with name `FileName`. It writes the strings to the file, separated by end-of-line markers, so each line in the file will contain 1 string from the stringlist.

`SaveToFile` creates a file stream (274) with name `FileName`, calls `TStrings.SaveToStream` (340) and then destroys the file stream object.

Errors: An `EStreamError` (209) exception can be raised if the file `FileName` cannot be opened, or if it cannot be written to.

See also: `TStrings.SaveToStream` (340), `Tstrings.LoadFromStream` (339), `TStrings.LoadFromFile` (339)

2.57.26 TStrings.SaveToStream

Synopsis: Save the contents of the string to a stream.

Declaration: `procedure SaveToStream(Stream: TStream); Virtual`

Visibility: `public`

Description: `SaveToStream` saves the contents of the stringlist to `Stream`. It writes the strings to the stream, separated by end-of-line markers, so each 'line' in the stream will contain 1 string from the stringlist.

Errors: An `EStreamError` (209) exception can be raised if the stream cannot be written to.

See also: `TStrings.SaveToFile` (340), `Tstrings.LoadFromStream` (339), `TStrings.LoadFromFile` (339)

2.57.27 TStrings.SetText

Synopsis: Set the contents of the list from a `PChar`.

Declaration: `procedure SetText(TheText: PChar); Virtual`

Visibility: `public`

Description: `SetText` parses the contents of `TheText` and fills the stringlist based on the contents. It regards `TheText` as a series of strings, separated by end-of-line markers. Each of these strings is added to the stringlist.

See also: `TStrings.Text` (345)

2.57.28 TStrings.GetNameValue

Synopsis: Return both name and value of a name,value pair based on it's index.

Declaration: `procedure GetNameValue(Index: Integer;var AName: String;
var AValue: String)`

Visibility: public

Description: Return both name and value of a name,value pair based on it's index.

2.57.29 TStrings.Delimiter

Synopsis: Delimiter character used in DelimitedText ([341](#)).

Declaration: `Property Delimiter : Char`

Visibility: public

Access: Read,Write

Description: Delimiter character used in DelimitedText ([341](#)).

2.57.30 TStrings.DelimitedText

Synopsis: Get or set all strings in the list in a delimited form.

Declaration: `Property DelimitedText : String`

Visibility: public

Access: Read,Write

Description: Get or set all strings in the list in a delimited form.

2.57.31 TStrings QuoteChar

Synopsis: Quote character used in DelimitedText ([341](#)).

Declaration: `Property QuoteChar : Char`

Visibility: public

Access: Read,Write

Description: Quote character used in DelimitedText ([341](#)).

2.57.32 TStrings.NameValueSeparator

Synopsis: Value of the character used to separate name,value pairs

Declaration: `Property NameValueSeparator : Char`

Visibility: public

Access: Read,Write

Description: Value of the character used to separate name,value pairs

2.57.33 TStrings.ValueFromIndex

Synopsis:

Declaration: `Property ValueFromIndex[Index: Integer]: String`

Visibility: `public`

Access: `Read,Write`

Description: Return the value part of a string based on it's index.

2.57.34 TStrings.Capacity

Synopsis: Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of strings that the list can hold before it tries to allocate more memory.

`TStrings` returns `TStrings.Count` (343) when read. Trying to set the capacity has no effect. Descendent classes such as `TStringlist` (327) can override this property such that it actually sets the new capacity.

See also: `TStringList` (327), `TStrings.Count` (343)

2.57.35 TStrings.CommaText

Synopsis: Contents of the list as a comma-separated string.

Declaration: `Property CommaText : String`

Visibility: `public`

Access: `Read,Write`

Description: `CommaText` represents the stringlist as a single string, consisting of a comma-separated concatenation of the strings in the list. If one of the strings contains spaces, comma's or quotes it will be enclosed by double quotes. Any double quotes in a string will be doubled. For instance the following strings:

```
Comma, string
Quote"string
Space string
NormalSttring
```

is converted to

```
"Comma, string", "Quote""String", "Space string", NormalString
```

Conversely, when setting the `CommaText` property, the text will be parsed according to the rules outlined above, and the strings will be set accordingly. Note that spaces will in this context be regarded as string separators, unless the string as a whole is contained in double quotes. Spaces that occur next to a delimiter will be ignored. The following string:

```
"Comma,string" , "Quote"String",Space string,, NormalString
```

Will be converted to

```
Comma,String
Quote"String
Space
String
```

```
NormalString
```

This is a special case of the `DelimitedText` (179) property where the quote character is always the double quote, and the delimiter is always the colon.

See also: `TStrings.Text` (345), `TStrings.SetText` (340)

2.57.36 TStrings.Count

Synopsis: Number of strings in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the current number of strings in the list. `TStrings` does not implement this property; descendent classes should override the property read handler to return the correct value.

Strings in the list are always uniquely identified by their `Index`; the index of a string is zero-based, i.e. it's supported range is 0 to `Count-1`. trying to access a string with an index larger than or equal to `Count` will result in an error. Code that iterates over the list in a stringlist should always take into account the zero-based character of the list index.

See also: `TStrings.Strings` (344), `TStrings.Objects` (344), `TStrings.Capacity` (342)

2.57.37 TStrings.Names

Synopsis: Name parts of the name-value pairs in the list.

Declaration: `Property Names[Index: Integer]: String`

Visibility: `public`

Access: `Read`

Description: `Names` provides indexed access to the names of the name-value pairs in the list. It returns the name part of the `Index`-th string in the list.

Remark: The index is not an index based on the number of name-value pairs in the list. It is the name part of the name-value pair a string `Index` in the list. If the string at position `Index` is not a name-value pair (i.e. does not contain the equal sign (=)), then an empty name is returned.

See also: `TStrings.Values` (344), `TStrings.IndexOfName` (337)

2.57.38 TStrings.Objects

Synopsis: Indexed access to the objects associated with the strings in the list.

Declaration: `Property Objects[Index: Integer]: TObject`

Visibility: public

Access: Read,Write

Description: `Objects` provides indexed access to the objects associated to the strings in the list. `Index` is a zero-based index and must be in the range of 0 to `Count-1`.

Setting the `objects` property will not free the previously associated object, if there was one. The caller is responsible for freeing the object that was previously associated to the string.

`TStrings` does not implement any storage for objects. Reading the `Objects` property will always return `Nil`. Setting the property will have no effect. It is the responsibility of the descendent classes to provide storage for the associated objects.

Errors: If an `Index` outside the valid range is specified, an `EStringListError` (209) exception will be raised.

See also: `TStrings.Strings` (344), `TStrings.IndexOfObject` (338), `TStrings.Names` (343), `TStrings.Values` (344)

2.57.39 TStrings.Values

Synopsis: Value parts of the name-value pairs in the list.

Declaration: `Property Values[Name: String]: String`

Visibility: public

Access: Read,Write

Description: `Values` represents the value parts of the name-value pairs in the list.

When reading this property, if there is a name-value pair in the list of strings that has name part `Name`, then the corresponding value is returned. If there is no such pair, an empty string is returned.

When writing this value, first it is checked whether there exists a name-value pair in the list with name `Name`. If such a pair is found, its value part is overwritten with the specified value. If no such pair is found, a new name-value pair is added with the specified `Name` and value.

Remark:

- 1.Names are compared case-insensitively.
- 2.Any character, including whitespace, up till the first equal (=) sign in a string is considered part of the name.

See also: `TStrings.Names` (343), `TStrings.Strings` (344), `TStrings.Objects` (344)

2.57.40 TStrings.Strings

Synopsis: Indexed access to the strings in the list.

Declaration: `Property Strings[Index: Integer]: String; default`

Visibility: public

Access: Read,Write

Description: `Strings` is the default property of `TStrings`. It provides indexed read-write access to the list of strings. Reading it will return the string at position `Index` in the list. Writing it will set the string at position `Index`.

`Index` is the position of the string in the list. It is zero-based, i.e. valid values range from 0 (the first string in the list) till `Count-1` (the last string in the list). When browsing through the strings in the list, this fact must be taken into account.

To access the objects associated with the strings in the list, use the `TStrings.Objects` (344) property. The name parts of name-value pairs can be accessed with the `TStrings.Names` (343) property, and the values can be set or read through the `TStrings.Values` (344) property.

Searching through the list can be done using the `TStrings.IndexOf` (337) method.

Errors: If `Index` is outside the allowed range, an `EStringListError` (209) exception is raised.

See also: `TStrings.Count` (343), `TStrings.Objects` (344), `TStrings.Names` (343), `TStrings.Values` (344), `TStrings.IndexOf` (337)

2.57.41 TStrings.Text

Synopsis: Contents of the list as one big string.

Declaration: `Property Text : String`

Visibility: public

Access: Read, Write

Description: `Text` returns, when read, the contents of the stringlist as one big string consisting of all strings in the list, separated by an end-of-line marker. When this property is set, the string will be cut into smaller strings, based on the positions of end-of-line markers in the string. Any previous content of the stringlist will be lost.

Remark: If any of the strings in the list contains an end-of-line marker, then the resulting string will appear to contain more strings than actually present in the list. To avoid this ambiguity, use the `TStrings.CommaText` (342) property instead.

See also: `TStrings.Strings` (344), `TStrings.Count` (343), `TStrings.CommaText` (342)

2.57.42 TStrings.StringsAdapter

Synopsis: Not implemented in Free Pascal.

Declaration: `Property StringsAdapter : IStringsAdapter`

Visibility: public

Access: Read, Write

Description: Not implemented in Free Pascal.

2.58 TStringStream

2.58.1 Description

`TStringStream` stores its data in an `ansistring`. The contents of this string is available as the `DataString` (347) property. It also introduces some methods to read or write parts of the stringstream's data as a string.

The main purpose of a `TStringStream` is to be able to treat a string as a stream from which can be read.

2.58.2 Method overview

Page	Property	Description
346	Create	Creates a new stringstream and sets its initial content.
346	Read	Reads from the stream.
346	ReadString	Reads a string of length <code>Count</code>
347	Seek	Sets the position in the stream.
347	Write	<code>Write</code> implements the abstract <code>TStream.Write</code> (320) method.
347	WriteString	<code>WriteString</code> writes a string to the stream.

2.58.3 Property overview

Page	Property	Access	Description
347	<code>DataStream</code>	<code>r</code>	Contains the contents of the stream in string form

2.58.4 TStringStream.Create

Synopsis: Creates a new stringstream and sets its initial content.

Declaration: `constructor Create(const AString: String)`

Visibility: `public`

Description: `Create` creates a new `TStringStream` instance and sets its initial content to `AString`. The position is still 0 but the size of the stream will equal the length of the string.

See also: `TStringStream.DataString` ([347](#))

2.58.5 TStringStream.Read

Synopsis: Reads from the stream.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` implements the abstract `Read` ([319](#)) from `TStream` ([318](#)). It tries to read `Count` bytes into `Buffer`. It returns the number of bytes actually read. The position of the stream is advanced with the number of bytes actually read; When the reading has reached the end of the `DataStream` ([347](#)), then the reading stops, i.e. it is not possible to read beyond the end of the datastring.

See also: `TStream.Read` ([319](#)), `TStringStream.Write` ([347](#)), `TStringStream.DataString` ([347](#))

2.58.6 TStringStream.ReadString

Synopsis: Reads a string of length `Count`

Declaration: `function ReadString(Count: LongInt) : String`

Visibility: `public`

Description: `ReadString` reads `Count` bytes from the stream and returns the read bytes as a string. If less than `Count` bytes were available, the string has as many characters as bytes could be read.

The `ReadString` method is a wrapper around the `Read` (346) method. It does not do the same string as the `TStream.ReadAnsiString` (325) method, which first reads a length integer to determine the length of the string to be read.

See also: `TStringStream.Read` (346), `TStream.ReadAnsiString` (325)

2.58.7 TStringStream.Seek

Synopsis: Sets the position in the stream.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` implements the abstract `Seek` (320) method.

2.58.8 TStringStream.Write

Synopsis: `Write` implements the abstract `TStream.Write` (320) method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` implements the abstract `TStream.Write` (320) method.

2.58.9 TStringStream.WriteString

Synopsis: `WriteString` writes a string to the stream.

Declaration: `procedure WriteString(const AString: String)`

Visibility: `public`

Description: `WriteString` writes a string to the stream.

2.58.10 TStringStream.DataString

Synopsis: Contains the contents of the stream in string form

Declaration: `Property DataString : String`

Visibility: `public`

Access: `Read`

Description: Contains the contents of the stream in string form

2.59 TTextObjectWriter

2.59.1 Description

Not yet implemented.

2.60 TThread

2.60.1 Description

The `TThread` class encapsulates the native thread support of the operating system. To create a thread, declare a descendent of the `TThread` object and override the `Execute` (348) method. In this method, the `tthread`'s code should be executed. To run a thread, create an instance of the `tthread` descendent, and call its `execute` method.

2.60.2 Method overview

Page	Property	Description
348	Create	Creates a new thread.
348	Destroy	Destroys the thread object.
349	Resume	Resumes the thread's execution.
349	Suspend	Suspends the thread's execution.
349	Terminate	Signals the thread it should terminate.
349	WaitFor	Waits for the thread to terminate and returns the exit status.

2.60.3 Property overview

Page	Property	Access	Description
351	FatalException	r	Exception that occurred during thread execution
349	FreeOnTerminate	rw	Indicates whether the thread should free itself when it stops executing.
350	Handle	r	Returns the thread handle.
350	OnTerminate	rw	Event called when the thread terminates.
350	Priority	rw	Returns the thread priority.
350	Suspended	rw	Indicates whether the thread is suspended.
350	ThreadID	r	Returns the thread ID.

2.60.4 TThread.Create

Synopsis: Creates a new thread.

Declaration: `constructor Create(CreateSuspended: Boolean; const StackSize: SizeUInt)`

Visibility: `public`

Description: Creates a new thread.

2.60.5 TThread.Destroy

Synopsis: Destroys the thread object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the thread object.

2.60.6 TThread.Resume

Synopsis: Resumes the thread's execution.

Declaration: `procedure Resume`

Visibility: `public`

Description: Resumes the thread's execution.

2.60.7 TThread.Suspend

Synopsis: Suspends the thread's execution.

Declaration: `procedure Suspend`

Visibility: `public`

Description: Suspends the thread's execution.

2.60.8 TThread.Terminate

Synopsis: Signals the thread it should terminate.

Declaration: `procedure Terminate`

Visibility: `public`

Description: Signals the thread it should terminate.

2.60.9 TThread.WaitFor

Synopsis: Waits for the thread to terminate and returns the exit status.

Declaration: `function WaitFor : Integer`

Visibility: `public`

Description: Waits for the thread to terminate and returns the exit status.

2.60.10 TThread.FreeOnTerminate

Synopsis: Indicates whether the thread should free itself when it stops executing.

Declaration: `Property FreeOnTerminate : Boolean`

Visibility: `public`

Access: Read, Write

Description: Indicates whether the thread should free itself when it stops executing.

2.60.11 TThread.Handle

Synopsis: Returns the thread handle.

Declaration: `Property Handle : TThreadID`

Visibility: public

Access: Read

Description: Returns the thread handle.

2.60.12 TThread.Priority

Synopsis: Returns the thread priority.

Declaration: `Property Priority : TThreadPriority`

Visibility: public

Access: Read,Write

Description: Returns the thread priority.

2.60.13 TThread.Suspended

Synopsis: Indicates whether the thread is suspended.

Declaration: `Property Suspended : Boolean`

Visibility: public

Access: Read,Write

Description: Indicates whether the thread is suspended.

2.60.14 TThread.ThreadID

Synopsis: Returns the thread ID.

Declaration: `Property ThreadID : TThreadID`

Visibility: public

Access: Read

Description: Returns the thread ID.

2.60.15 TThread.OnTerminate

Synopsis: Event called when the thread terminates.

Declaration: `Property OnTerminate : TNotifyEvent`

Visibility: public

Access: Read,Write

Description: Event called when the thread terminates.

2.60.16 TThread.FatalException

Synopsis: Exception that occurred during thread execution

Declaration: `Property FatalException : TObject`

Visibility: `public`

Access: `Read`

Description: `FatalException` contains the exception that occurred during the thread's execution.

2.61 TThreadList

2.61.1 Description

This class is not yet implemented in Free Pascal.

2.61.2 Method overview

Page	Property	Description
352	Add	Adds an element to the list.
352	Clear	Removes all emements from the list.
351	Create	Creates a new thread-safe list.
351	Destroy	Destroys the list instance.
352	LockList	Locks the list for exclusive access.
352	Remove	Removes an item from the list.
352	UnlockList	Unlocks the list after it was locked.

2.61.3 Property overview

Page	Property	Access	Description
353	Duplicates	<code>rw</code>	Describes what to do with duplicates

2.61.4 TThreadList.Create

Synopsis: Creates a new thread-safe list.

Declaration: `constructor Create`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.5 TThreadList.Destroy

Synopsis: Destroys the list instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.6 TThreadList.Add

Synopsis: Adds an element to the list.

Declaration: `procedure Add(Item: Pointer)`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.7 TThreadList.Clear

Synopsis: Removes all emements from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.8 TThreadList.LockList

Synopsis: Locks the list for exclusive access.

Declaration: `function LockList : TList`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.9 TThreadList.Remove

Synopsis: Removes an item from the list.

Declaration: `procedure Remove(Item: Pointer)`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.10 TThreadList.UnlockList

Synopsis: Unlocks the list after it was locked.

Declaration: `procedure UnlockList`

Visibility: `public`

Description: This class is not yet implemented in Free Pascal.

Errors:

2.61.11 TThreadList.Duplicates

Synopsis: Describes what to do with duplicates

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what the threadlist should do when a duplicate pointer is added to the list. It is identical in behaviour to the `Duplicates` (331) property of `TStringList` (327).

See also: `TDuplicates` (184)

2.62 TWriter

2.62.1 Description

Object to write component data to an arbitrary format.

2.62.2 Method overview

Page	Property	Description
354	Create	Creates a new Writer with a stream and bufsize.
354	DefineBinaryProperty	Callback used when defining and streaming custom properties.
354	DefineProperty	Callback used when defining and streaming custom properties.
354	Destroy	Destroys the writer instance.
354	WriteBoolean	Write boolean value to the stream.
355	WriteChar	Write a character to the stream.
355	WriteCollection	Write a collection to the stream.
355	WriteComponent	Stream a component to the stream.
356	WriteCurrency	Write a currency value to the stream
356	WriteDate	Write a date to the stream.
355	WriteDescendent	Write a descendent component to the stream.
355	WriteFloat	Write a float to the stream.
356	WriteIdent	Write an identifier to the stream.
356	WriteInteger	Write an integer to the stream.
356	WriteListBegin	Write a start-of-list marker to the stream.
357	WriteListEnd	Write an end-of-list marker to the stream.
357	WriteRootComponent	Write a root component to the stream.
355	WriteSingle	Write a single-type real to the stream.
357	WriteString	Write a string to the stream.
357	WriteWideString	Write a widestring value to the stream

2.62.3 Property overview

Page	Property	Access	Description
358	Driver	r	Driver used when writing to the stream.
358	OnFindAncestor	rw	Event occurring when an ancestor component must be found.
358	OnWriteMethodProperty	rw	Handler from writing method properties.
358	OnWriteStringProperty	rw	Event handler for translating strings written to stream.
357	RootAncestor	rw	Ancestor of root component.

2.62.4 TWriter.Create

Synopsis: Creates a new Writer with a stream and bufsize.

Declaration: `constructor Create(ADriver: TAbstractObjectWriter)`
`constructor Create(Stream: TStream;BufSize: Integer)`

Visibility: public

Description: Creates a new Writer with a stream and bufsize.

2.62.5 TWriter.Destroy

Synopsis: Destroys the writer instance.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: Destroys the writer instance.

2.62.6 TWriter.DefineProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineProperty(const Name: String;ReadData: TReaderProc;`
`AWriteData: TWriterProc;HasData: Boolean)`
`; Override`

Visibility: public

Description: Callback used when defining and streaming custom properties.

2.62.7 TWriter.DefineBinaryProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineBinaryProperty(const Name: String;ReadData: TStreamProc;`
`AWriteData: TStreamProc;HasData: Boolean)`
`; Override`

Visibility: public

Description: Callback used when defining and streaming custom properties.

2.62.8 TWriter.WriteBoolean

Synopsis: Write boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean)`

Visibility: public

Description: Write boolean value to the stream.

2.62.9 TWriter.WriteCollection

Synopsis: Write a collection to the stream.

Declaration: `procedure WriteCollection(Value: TCollection)`

Visibility: `public`

Description: Write a collection to the stream.

2.62.10 TWriter.WriteComponent

Synopsis: Stream a component to the stream.

Declaration: `procedure WriteComponent(Component: TComponent)`

Visibility: `public`

Description: Stream a component to the stream.

2.62.11 TWriter.WriteChar

Synopsis: Write a character to the stream.

Declaration: `procedure WriteChar(Value: Char)`

Visibility: `public`

Description: Write a character to the stream.

2.62.12 TWriter.WriteDescendent

Synopsis: Write a descendent component to the stream.

Declaration: `procedure WriteDescendent(ARoot: TComponent; AAncessor: TComponent)`

Visibility: `public`

Description: Write a descendent component to the stream.

2.62.13 TWriter.WriteFloat

Synopsis: Write a float to the stream.

Declaration: `procedure WriteFloat(const Value: Extended)`

Visibility: `public`

Description: Write a float to the stream.

2.62.14 TWriter.WriteSingle

Synopsis: Write a single-type real to the stream.

Declaration: `procedure WriteSingle(const Value: Single)`

Visibility: `public`

Description: Write a single-type real to the stream.

2.62.15 TWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency)`

Visibility: `public`

Description: `WriteCurrency` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadCurrency` ([310](#))

2.62.16 TWriter.WriteDate

Synopsis: Write a date to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime)`

Visibility: `public`

Description: Write a date to the stream.

2.62.17 TWriter.WriteIdent

Synopsis: Write an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: String)`

Visibility: `public`

Description: Write an identifier to the stream.

2.62.18 TWriter.WriteInteger

Synopsis: Write an integer to the stream.

Declaration: `procedure WriteInteger(Value: LongInt); Overload`
`procedure WriteInteger(Value: Int64); Overload`

Visibility: `public`

Description: Write an integer to the stream.

2.62.19 TWriter.WriteListBegin

Synopsis: Write a start-of-list marker to the stream.

Declaration: `procedure WriteListBegin`

Visibility: `public`

Description: Write a start-of-list marker to the stream.

2.62.20 TWriter.WriteListEnd

Synopsis: Write an end-of-list marker to the stream.

Declaration: `procedure WriteListEnd`

Visibility: `public`

Description: Write an end-of-list marker to the stream.

2.62.21 TWriter.WriteRootComponent

Synopsis: Write a root component to the stream.

Declaration: `procedure WriteRootComponent (ARoot: TComponent)`

Visibility: `public`

Description: Write a root component to the stream.

2.62.22 TWriter.WriteString

Synopsis: Write a string to the stream.

Declaration: `procedure WriteString(const Value: String)`

Visibility: `public`

Description: Write a string to the stream.

2.62.23 TWriter.WriteString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString)`

Visibility: `public`

Description: `WriteWidestring` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadWideString` ([312](#))

2.62.24 TWriter.RootAncestor

Synopsis: Ancestor of root component.

Declaration: `Property RootAncestor : TComponent`

Visibility: `public`

Access: `Read, Write`

Description: Ancestor of root component.

2.62.25 TWriter.OnFindAncestor

Synopsis: Event occurring when an ancestor component must be found.

Declaration: `Property OnFindAncestor : TFindAncestorEvent`

Visibility: `public`

Access: `Read,Write`

Description: Event occurring when an ancestor component must be found.

2.62.26 TWriter.OnWriteMethodProperty

Synopsis: Handler from writing method properties.

Declaration: `Property OnWriteMethodProperty : TWriteMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnWriteMethodProperty` can be set by an IDE or some streaming mechanism which handles dummy values for method properties; It can be used to write a real value to the stream which will be interpreted correctly when the stream is read. See `TWriteMethodPropertyEvent` (191) for a description of the arguments.

See also: `TWriteMethodPropertyEvent` (191), `TReader.OnSetMethodProperty` (314)

2.62.27 TWriter.OnWriteStringProperty

Synopsis: Event handler for translating strings written to stream.

Declaration: `Property OnWriteStringProperty : TReadWriteStringPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnWriteStringProperty` is called whenever a string property is written to the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is written. See `TReadWriteStringPropertyEvent` (188) for a description of the various parameters.

See also: `TReader.OnPropertyNotFound` (313), `TReader.OnSetMethodProperty` (314), `TReadWriteStringPropertyEvent` (188)

2.62.28 TWriter.Driver

Synopsis: Driver used when writing to the stream.

Declaration: `Property Driver : TAbstractObjectWriter`

Visibility: `public`

Access: `Read`

Description: Driver used when writing to the stream.

Chapter 3

Reference for unit 'Crt'

3.1 Overview

This chapter describes the CRT unit for Free Pascal, both under dos linux and Windows. The unit was first written for dos by Florian klaempfl. The unit was ported to linux by Mark May and enhanced by Michael Van Canneyt and Peter Vreman. It works on the linux console, and in xterm and rxvt windows under X-Windows. The functionality for both is the same, except that under linux the use of an early implementation (versions 0.9.1 and earlier of the compiler) the crt unit automatically cleared the screen at program startup.

There are some caveats when using the CRT unit:

- Programs using the CRT unit will *not* be usable when input/output is being redirected on the command-line.
- For similar reasons they are not usable as CGI-scripts for use with a webserver.
- The use of the CRT unit and the graph unit may not always be supported.
- On linux or other unix OSes , executing other programs that expect special terminal behaviour (using one of the special functions in the linux unit) will not work. The terminal is set in RAW mode, which will destroy most terminal emulation settings.

3.2 Constants, types and variables

3.2.1 Constants

`Black = 0`

Black color attribute

`Blink = 128`

Blink attribute

`Blue = 1`

Blue color attribute

Brown = 6

Brown color attribute

BW40 = 0

40 columns black and white screen mode.

BW80 = 2

80 columns black and white screen mode.

C40 = CO40

40 columns color screen mode.

C80 = CO80

80 columns color screen mode.

CO40 = 1

40 columns color screen mode.

CO80 = 3

80 columns color screen mode.

ConsoleMaxX = 1024

ConsoleMaxY = 1024

Cyan = 3

Cyan color attribute

DarkGray = 8

Dark gray color attribute

Flushing = false

Font8x8 = 256

Internal ROM font mode

Green = 2

Green color attribute

LightBlue = 9

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

Magenta = 5

Magenta color attribute

Mono = 7

Monochrome screen mode (hercules screens)

Red = 4

Red color attribute

ScreenHeight : LongInt = 25

Current screen height.

ScreenWidth : LongInt = 80

Current screen width

White = 15

White color attribute

Yellow = 14

Yellow color attribute

3.2.2 Types

```
PConsoleBuf = ^TConsoleBuf
```

```
TCharAttr = packed record
  ch : Char;
  attr : Byte;
end
```

```
TConsoleBuf = Array[0..ConsoleMaxX*ConsoleMaxY-1] of TCharAttr
```

3.2.3 Variables

```
CheckBreak : Boolean
```

Check for CTRL-Break keystroke. Not used.

```
CheckEOF : Boolean
```

Check for EOF on standard input. Not used.

```
CheckSnow : Boolean
```

Check snow on CGA screens. Not used.

```
ConsoleBuf : PConsoleBuf
```

```
DirectVideo : Boolean
```

The `DirectVideo` variable controls the writing to the screen. If it is `True`, the the cursor is set via direct port access. If `False`, then the BIOS is used. This is defined under dos only.

```
LastMode : Word = 3
```

The `Lastmode` variable tells you which mode was last selected for the screen. It is defined on DOS only.

```
TextAttr : Byte = $07
```

The `TextAttr` variable controls the attributes with which characters are written to screen.

```
WindMax : Word = $184f
```

The upper byte of `WindMax` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMaxX` and `WindMaxY` instead.

```
WindMaxX : DWord
```

X coordinate of lower right corner of the defined window

`WindMaxY : DWord`

Y coordinate of lower right corner of the defined window

`WindMin : Word = $0`

The upper byte of `WindMin` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMinX` and `WindMinY` instead.

`WindMinX : DWord`

X coordinate of upper left corner of the defined window

`WindMinY : DWord`

Y coordinate of upper left corner of the defined window

3.3 Procedures and functions

3.3.1 AssignCrt

Synopsis: Assign file to CRT.

Declaration: `procedure AssignCrt (var F: Text)`

Visibility: default

Description: `AssignCrt` Assigns a file `F` to the console. Everything written to the file `F` goes to the console instead. If the console contains a window, everything is written to the window instead.

Errors: None.

See also: [Window \(374\)](#)

Listing: `./crtex/ex1.pp`

```

Program Example1;
uses Crt;

{ Program to demonstrate the AssignCrt function. }

var
  F : Text;
begin
  AssignCrt(F);
  Rewrite(F); { Don't forget to open for output! }
  WriteLn(F, 'This is written to the Assigned File');
  Close(F);
end.

```

3.3.2 ClrEol

Synopsis: Clear from cursor position till end of line.

Declaration: `procedure ClrEol`

Visibility: default

Description: `ClrEol` clears the current line, starting from the cursor position, to the end of the window. The cursor doesn't move

Errors: None.

See also: `DelLine` ([366](#)), `InsLine` ([368](#)), `ClrScr` ([364](#))

Listing: `./crtex/ex9.pp`

```

Program Example9;
uses Crt;

{ Program to demonstrate the ClrEol function. }
var
  I,J : integer;

begin
  For I:=1 to 15 do
    For J:=1 to 80 do
      begin
        gotoxy(j,i);
        Write(j mod 10);
      end;
  Window(5,5,75,12);
  Write('This line will be cleared from',
    ' here till the right of the window');
  GotoXY(27,WhereY);
  ReadKey;
  ClrEol;
  WriteLn;
end.

```

3.3.3 ClrScr

Synopsis: Clear current window.

Declaration: `procedure ClrScr`

Visibility: default

Description: `ClrScr` clears the current window (using the current colors), and sets the cursor in the top left corner of the current window.

Errors: None.

See also: `Window` ([374](#))

Listing: `./crtex/ex8.pp`

```
Program Example8;  
uses Crt;  
  
{ Program to demonstrate the ClrScr function. }  
  
begin  
  WriteLn('Press any key to clear the screen');  
  ReadKey;  
  ClrScr;  
  WriteLn('Have fun with the cleared screen');  
end.
```

3.3.4 cursorbig

Synopsis: Show big cursor

Declaration: `procedure cursorbig`

Visibility: default

Description: `CursorBig` makes the cursor a big rectangle. Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([365](#)), `CursorOff` ([365](#))

3.3.5 cursoroff

Synopsis: Hide cursor

Declaration: `procedure cursoroff`

Visibility: default

Description: `CursorOff` switches the cursor off (i.e. the cursor is no longer visible). Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([365](#)), `CursorBig` ([365](#))

3.3.6 cursoron

Synopsis: Display cursor

Declaration: `procedure cursoron`

Visibility: default

Description: `CursorOn` switches the cursor on. Not implemented on unixes.

Errors: None.

See also: `CursorBig` ([365](#)), `CursorOff` ([365](#))

3.3.7 Delay

Synopsis: Delay program execution.

Declaration: `procedure Delay (MS: Word)`

Visibility: default

Description: `Delay` waits a specified number of milliseconds. The number of specified seconds is an approximation, and may be off a lot, if system load is high.

Errors: None

See also: [Sound \(371\)](#), [NoSound \(370\)](#)

Listing: `./crtex/ex15.pp`

```

Program Example15;
uses Crt;

{ Program to demonstrate the Delay function. }
var
  i : longint;
begin
  WriteLn( 'Counting Down' );
  for i:=10 downto 1 do
    begin
      WriteLn(i);
      Delay(1000); { Wait one second }
    end;
  WriteLn( 'BOOM!!! ' );
end.

```

3.3.8 DelLine

Synopsis: Delete line at cursor position.

Declaration: `procedure DelLine`

Visibility: default

Description: `DelLine` removes the current line. Lines following the current line are scrolled 1 line up, and an empty line is inserted at the bottom of the current window. The cursor doesn't move.

Errors: None.

See also: [ClrEol \(364\)](#), [InsLine \(368\)](#), [ClrScr \(364\)](#)

Listing: `./crtex/ex11.pp`

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn( 'Line 1 ' );

```

```

WriteLn('Line 2');
WriteLn('Line 2');
WriteLn('Line 3');
WriteLn;
WriteLn('Oops, Line 2 is listed twice,',
        ' let''s delete the line at the cursor postion');
GotoXY(1,3);
ReadKey;
DelLine;
GotoXY(1,10);
end.

```

3.3.9 GotoXY

Synopsis: Set cursor position on screen.

Declaration: `procedure GotoXY(X: Byte; Y: Byte)`

Visibility: default

Description: `GotoXY` positions the cursor at (X, Y), X in horizontal, Y in vertical direction relative to the origin of the current window. The origin is located at (1, 1), the upper-left corner of the window.

Errors: None.

See also: [WhereX \(373\)](#), [WhereY \(373\)](#), [Window \(374\)](#)

Listing: `./crtex/ex6.pp`

```

Program Example6;
uses Crt;

{ Program to demonstrate the GotoXY function. }

begin
  ClrScr;
  GotoXY(10,10);
  Write('10,10');
  GotoXY(70,20);
  Write('70,20');
  GotoXY(1,22);
end.

```

3.3.10 HighVideo

Synopsis: Switch to highlighted text mode

Declaration: `procedure HighVideo`

Visibility: default

Description: `HighVideo` switches the output to highlighted text. (It sets the high intensity bit of the video attribute)

Errors: None.

See also: [TextColor \(372\)](#), [TextBackground \(371\)](#), [LowVideo \(369\)](#), [NormVideo \(369\)](#)

Listing: ./crtex/ex14.pp

```

Program Example14;
uses Crt;

{ Program to demonstrate the LowVideo, HighVideo, NormVideo functions. }

begin
  LowVideo;
  WriteLn( 'This is written with LowVideo' );
  HighVideo;
  WriteLn( 'This is written with HighVideo' );
  NormVideo;
  WriteLn( 'This is written with NormVideo' );
end.

```

3.3.11 InsLine

Synopsis: Insert an empty line at cursor position

Declaration: `procedure InsLine`

Visibility: default

Description: `InsLine` inserts an empty line at the current cursor position. Lines following the current line are scrolled 1 line down, causing the last line to disappear from the window. The cursor doesn't move.

Errors: None.

See also: `ClrEol` ([364](#)), `DelLine` ([366](#)), `ClrScr` ([364](#))

Listing: ./crtex/ex10.pp

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn( 'Line 1 ' );
  WriteLn( 'Line 3 ' );
  WriteLn;
  WriteLn( 'Oops, forgot Line 2, let''s insert at the cursor postion' );
  GotoXY(1,3);
  ReadKey;
  InsLine;
  Write( 'Line 2 ' );
  GotoXY(1,10);
end.

```

3.3.12 KeyPressed

Synopsis: Check if there is a keypress in the keybuffer

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` scans the keyboard buffer and sees if a key has been pressed. If this is the case, `True` is returned. If not, `False` is returned. The `Shift`, `Alt`, `Ctrl` keys are not reported. The key is not removed from the buffer, and can hence still be read after the `KeyPressed` function has been called.

Errors: None.

See also: `ReadKey` ([370](#))

Listing: `./crtex/ex2.pp`

```
Program Example2;
uses Crt;

{ Program to demonstrate the KeyPressed function. }

begin
  WriteLn('Waiting until a key is pressed');
  repeat
    until KeyPressed;
  { The key is not Read,
    so it should also be outputted at the commandline}
end.
```

3.3.13 LowVideo

Synopsis: Switch to low intensity colors.

Declaration: `procedure LowVideo`

Visibility: default

Description: `LowVideo` switches the output to non-highlighted text. (It clears the high intensity bit of the video attribute)

For an example, see `HighVideo` ([367](#))

Errors: None.

See also: `TextColor` ([372](#)), `TextBackground` ([371](#)), `HighVideo` ([367](#)), `NormVideo` ([369](#))

3.3.14 NormVideo

Synopsis: Return to normal (startup) modus

Declaration: `procedure NormVideo`

Visibility: default

Description: `NormVideo` switches the output to the defaults, read at startup. (The defaults are read from the cursor position at startup)

For an example, see `HighVideo` ([367](#))

Errors: None.

See also: `TextColor` ([372](#)), `TextBackground` ([371](#)), `LowVideo` ([369](#)), `HighVideo` ([367](#))

3.3.15 NoSound

Synopsis: Stop system speaker

Declaration: `procedure NoSound`

Visibility: default

Description: `NoSound` stops the speaker sound. This call is not supported on all operating systems.

Errors: None.

See also: `Sound` ([371](#))

Listing: `./crtex/ex16.pp`

```

Program Example16;
uses Crt;

{ Program to demonstrate the Sound and NoSound function. }

var
  i : longint;
begin
  WriteLn('You will hear some tones from your speaker');
  while (i < 15000) do
    begin
      inc(i, 500);
      Sound(i);
      Delay(100);
    end;
  WriteLn('Quiet now!');
  NoSound; { Stop noise }
end.
```

3.3.16 ReadKey

Synopsis: Read key from keybuffer

Declaration: `function ReadKey : Char`

Visibility: default

Description: `ReadKey` reads 1 key from the keyboard buffer, and returns this. If an extended or function key has been pressed, then the zero ASCII code is returned. You can then read the scan code of the key with a second `ReadKey` call.

Key mappings under Linux can cause the wrong key to be reported by `ReadKey`, so caution is needed when using `ReadKey`.

Errors: None.

See also: `KeyPressed` ([368](#))

Listing: `./crtex/ex3.pp`

```

Program Example3;
uses Crt;

{ Program to demonstrate the ReadKey function. }
```

```

var
  ch : char;
begin
  writeln( 'Press Left/Right , Esc=Quit' );
  repeat
    ch:=ReadKey;
    case ch of
      #0 : begin
        ch:=ReadKey; {Read ScanCode}
        case ch of
          #75 : WriteLn( 'Left' );
          #77 : WriteLn( 'Right' );
        end;
      end;
      #27 : WriteLn( 'ESC' );
    end;
  until ch=#27 {Esc}
end.

```

3.3.17 Sound

Synopsis: Sound system speaker

Declaration: `procedure Sound(Hz: Word)`

Visibility: default

Description: Sound sounds the speaker at a frequency of hz. Under Windows, a system sound is played and the frequency parameter is ignored. On other operating systems, this routine may not be implemented.

Errors: None.

See also: NoSound ([370](#))

3.3.18 TextBackground

Synopsis: Set text background

Declaration: `procedure TextBackground(Color: Byte)`

Visibility: default

Description: TextBackground sets the background color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: TextColor ([372](#)), HighVideo ([367](#)), LowVideo ([369](#)), NormVideo ([369](#))

Listing: ./crtex/ex13.pp

```

Program Example13;
uses Crt;

```

```

{ Program to demonstrate the TextBackground function. }

```

```

begin

```

```

    TextColor(White);
    WriteLn('This is written in with the default background color');
    TextBackground(Green);
    WriteLn('This is written in with a Green background');
    TextBackground(Brown);
    WriteLn('This is written in with a Brown background');
    TextBackground(Black);
    WriteLn('Back with a black background');
end.

```

3.3.19 TextColor

Synopsis: Set text color

Declaration: `procedure TextColor(Color: Byte)`

Visibility: default

Description: `TextColor` sets the foreground color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextBackground` ([371](#)), `HighVideo` ([367](#)), `LowVideo` ([369](#)), `NormVideo` ([369](#))

Listing: `./crtex/ex12.pp`

```

Program Example12;
uses Crt;

{ Program to demonstrate the TextColor function. }

begin
    WriteLn('This is written in the default color');
    TextColor(Red);
    WriteLn('This is written in Red');
    TextColor(White);
    WriteLn('This is written in White');
    TextColor(LightBlue);
    WriteLn('This is written in Light Blue');
end.

```

3.3.20 TextMode

Synopsis: Set screen mode.

Declaration: `procedure TextMode(Mode: Word)`

Visibility: default

Description: `TextMode` sets the textmode of the screen (i.e. the number of lines and columns of the screen). The lower byte is use to set the VGA text mode.

This procedure is only implemented on dos.

Errors: None.

See also: `Window` ([374](#))

3.3.21 WhereX

Synopsis: Return X (horizontal) cursor position

Declaration: `function WhereX : Byte`

Visibility: default

Description: `WhereX` returns the current X-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` (367), `WhereY` (373), `Window` (374)

Listing: `./crtex/ex7.pp`

```
Program Example7;  
uses Crt;  
  
{ Program to demonstrate the WhereX and WhereY functions. }  
  
begin  
  WriteLn( 'Cursor position: X= ', WhereX, ' Y= ', WhereY );  
end.
```

3.3.22 WhereY

Synopsis: Return Y (vertical) cursor position

Declaration: `function WhereY : Byte`

Visibility: default

Description: `WhereY` returns the current Y-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` (367), `WhereX` (373), `Window` (374)

Listing: `./crtex/ex7.pp`

```
Program Example7;  
uses Crt;  
  
{ Program to demonstrate the WhereX and WhereY functions. }  
  
begin  
  WriteLn( 'Cursor position: X= ', WhereX, ' Y= ', WhereY );  
end.
```

3.3.23 Window

Synopsis: Create new window on screen.

Declaration: `procedure Window(X1: Byte;Y1: Byte;X2: Byte;Y2: Byte)`

Visibility: default

Description: `Window` creates a window on the screen, to which output will be sent. $(X1, Y1)$ are the coordinates of the upper left corner of the window, $(X2, Y2)$ are the coordinates of the bottom right corner of the window. These coordinates are relative to the entire screen, with the top left corner equal to $(1, 1)$. Further coordinate operations, except for the next `Window` call, are relative to the window's top left corner.

Errors: None.

See also: [GotoXY \(367\)](#), [WhereX \(373\)](#), [WhereY \(373\)](#), [ClrScr \(364\)](#)

Listing: `./crtex/ex5.pp`

```

Program Example5;
uses Crt;

{ Program to demonstrate the Window function. }

begin
  ClrScr;
  WriteLn('Creating a window from 30,10 to 50,20');
  Window(30,10,50,20);
  WriteLn('We are now writing in this small window we just created, we '+
    'can''t get outside it when writing long lines like this one');
  Write('Press any key to clear the window');
  ReadKey;
  ClrScr;
  Write('The window is cleared, press any key to restore to fullscreen');
  ReadKey;
  { Full Screen is 80x25 }
  Window(1,1,80,25);
  Clrscr;
  WriteLn('Back in Full Screen');
end.

```

Chapter 4

Reference for unit 'dateutils'

4.1 Used units

Table 4.1: Used units by unit 'dateutils'

Name	Page
math	655
sysutils	1278
Types	375

4.2 Overview

`DateUtils` contains a large number of date/time manipulation routines, all based on the `TDateTime` type. There are routines for date/time math, for comparing dates and times, for composing dates and decomposing dates in their constituent parts.

4.3 Constants, types and variables

4.3.1 Constants

`ApproxDaysPerMonth : Double = 30.4375`

Average number of days in a month, measured over a year. Used in `MonthsBetween` ([421](#)).

`ApproxDaysPerYear : Double = 365.25`

Average number of days in a year, measured over 4 years. Used in `YearsBetween` ([461](#)).

`DayFriday = 5`

ISO day number for Friday

`DayMonday = 1`

ISO day number for Monday

DaySaturday = 6

ISO day number for Saturday

DaysPerWeek = 7

Number of days in a week.

DaysPerYear : Array[Boolean] of Word = (365,366)

Array with number of days in a year. The boolean index indicates whether it is a leap year or not.

DaySunday = 7

ISO day number for Sunday

DayThursday = 4

ISO day number for Thursday

DayTuesday = 2

ISO day number for Tuesday

DayWednesday = 3

ISO day number for Wednesday

MonthsPerYear = 12

Number of months in a year

OneHour = 1 / HoursPerDay

One hour as a fraction of a day (suitable for TDateTime)

OneMillisecond = 1 / MSecsPerDay

One millisecond as a fraction of a day (suitable for TDateTime)

OneMinute = 1 / MinsPerDay

One minute as a fraction of a day (suitable for TDateTime)

OneSecond = 1 / SecsPerDay

One second as a fraction of a day (suitable for TDateTime)

RecodeLeaveFieldAsIs = High (Word)

Bitmask deciding what to do with each TDateTime field in recode routines

`WeeksPerFortnight = 2`

Number of weeks in fortnight

`YearsPerCentury = 100`

Number of years in a century

`YearsPerDecade = 10`

Number of years in a decade

`YearsPerMillennium = 1000`

Number of years in a millenium

4.4 Procedures and functions

4.4.1 CompareDate

Synopsis: Compare 2 dates, disregarding the time of day

Declaration: `function CompareDate(const A: TDateTime;const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareDate` compares the date parts of two timestamps A and B and returns the following results:

< 0 if the day part of A is earlier than the day part of B.

0 if A and B are the on same day (times may differ) .

> 0 if the day part of A is later than the day part of B.

See also: `CompareTime` (379), `CompareDateTime` (378), `SameDate` (430), `SameTime` (432), `SameDateTime` (431)

Listing: `./datutex/ex99.pp`

Program `Example99;`

`{ This program demonstrates the CompareDate function }`

Uses `SysUtils, DateUtils;`

Const

`Fmt = 'dddd dd mmm yyyy';`

Procedure `Test(D1,D2 : TDateTime);`

Var

`Cmp : Integer;`

```

Procedure Test(D1,D2 : TDateTime);

Var
  Cmp : Integer;

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDateTime(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

4.4.3 CompareTime

Synopsis: Compares two times of the day, disregarding the date part.

Declaration: `function CompareTime(const A: TDateTime;const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareTime` compares the time parts of two timestamps A and B and returns the following results:

< 0 if the time part of A is earlier than the time part of B.

0 if A and B have the same time part (dates may differ) .

> 0 if the time part of A is later than the time part of B.

See also: `CompareDateTime` (378), `CompareDate` (377), `SameDate` (430), `SameTime` (432), `SameDateTime` (431)

Listing: ./datutex/ex100.pp

```

Program Example100;

{ This program demonstrates the CompareTime function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

Var
    Cmp : Integer;

begin
    Write(FormatDateTime(Fmt,D1), ' has ');
    Cmp:=CompareDateTime(D1,D2);
    If Cmp<0 then
        write('earlier time than ')
    else if Cmp>0 then
        Write('later time than ')
    else
        Write('equal time with ');
    WriteIn(FormatDateTime(Fmt,D2));
end;

Var
    D,N : TDateTime;

Begin
    D:=Today;
    N:=Now;
    Test(D,D);
    Test(N,N);
    Test(N+1,N);
    Test(N-1,N);
    Test(N+OneSecond,N);
    Test(N-OneSecond,N);
End.

```

4.4.4 DateOf

Synopsis: Extract the date part from a DateTime indication.

Declaration: `function DateOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: DateOf extracts the date part from AValue and returns the result.

Since the TDateTime is actually a double with the date part encoded in the integer part, this operation corresponds to a call to Trunc.

See also: TimeOf ([441](#)), YearOf ([460](#)), MonthOf ([420](#)), DayOf ([382](#)), HourOf ([397](#)), MinuteOf ([416](#)), SecondOf ([433](#)), MilliSecondOf ([412](#))

Listing: ./datutex/ex1.pp

Program Example1;

{ This program demonstrates the DateOf function }

Uses SysUtils, DateUtils;

Begin

 WriteLn('Date is : ', DateTimeToStr(DateOf(Now)));

End.

4.4.5 DateTimeToJulianDate

Synopsis: Converts a TDateTime value to a Julian date representation

Declaration: function DateTimeToJulianDate(const AValue: TDateTime) : Double

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: JulianDateToDateTime ([411](#)), TryJulianDateToDateTime ([446](#)), DateTimeToModifiedJulianDate ([381](#)), TryModifiedJulianDateToDateTime ([446](#))

4.4.6 DateTimeToMac

Synopsis: Convert a TDateTime timestamp to a Mac timestamp

Declaration: function DateTimeToMac(const AValue: TDateTime) : Int64

Visibility: default

Description: DateTimeToMac converts the TDateTime value AValue to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: UnixTimeStampToMac ([448](#)), MacToDateTime ([412](#)), MacTimeStampToUnix ([412](#))

4.4.7 DateTimeToModifiedJulianDate

Synopsis: Convert a TDateTime value to a modified Julian date representation

Declaration: function DateTimeToModifiedJulianDate(const AValue: TDateTime) : Double

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: DateTimeToJulianDate ([381](#)), JulianDateToDateTime ([411](#)), TryJulianDateToDateTime ([446](#)), TryModifiedJulianDateToDateTime ([446](#))

4.4.8 DateTimeToUnix

Synopsis: Convert a `TDateTime` value to Unix epoch time

Declaration: `function DateTimeToUnix(const AValue: TDateTime) : Int64`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [UnixToDateTime \(448\)](#)

4.4.9 DayOf

Synopsis: Extract the day (of month) part from a `DateTime` value

Declaration: `function DayOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOf` returns the day of the month part of the `AValue` date/time indication. It is a number between 1 and 31.

For an example, see [YearOf \(460\)](#)

See also: [YearOf \(460\)](#), [WeekOf \(448\)](#), [MonthOf \(420\)](#), [HourOf \(397\)](#), [MinuteOf \(416\)](#), [SecondOf \(433\)](#), [MilliSecondOf \(412\)](#)

4.4.10 DayOfTheMonth

Synopsis: Extract the day (of month) part of a `DateTime` value

Declaration: `function DayOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheMonth` returns the number of days that have passed since the start of the month till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the month will return 1.

For an example, see the [WeekOfTheMonth \(448\)](#) function.

See also: [DayOfTheYear \(383\)](#), [WeekOfTheMonth \(448\)](#), [HourOfTheMonth \(397\)](#), [MinuteOfTheMonth \(417\)](#), [SecondOfTheMonth \(434\)](#), [MilliSecondOfTheMonth \(413\)](#)

4.4.11 DayOfTheWeek

Synopsis: Extracts the day of the week from a `DateTime` value

Declaration: `function DayOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheWeek` returns the number of days that have passed since the start of the week till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the week will return 1.

See also: [DayOfTheYear \(383\)](#), [DayOfTheMonth \(382\)](#), [HourOfTheWeek \(398\)](#), [MinuteOfTheWeek \(418\)](#), [SecondOfTheWeek \(434\)](#), [MilliSecondOfTheWeek \(414\)](#)

Listing: ./datutex/ex42.pp

Program Example42;

{ This program demonstrates the WeekOfTheMonth function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Day of the Week : ', DayOfTheWeek(N));

WriteLn('Hour of the Week : ', HourOfTheWeek(N));

WriteLn('Minute of the Week : ', MinuteOfTheWeek(N));

WriteLn('Second of the Week : ', SecondOfTheWeek(N));

WriteLn('MilliSecond of the Week : ',
MilliSecondOfTheWeek(N));

End.

4.4.12 DayOfTheYear

Synopsis: Extracts the day of the year from a TDateTime value

Declaration: function DayOfTheYear(const AValue: TDateTime) : Word

Visibility: default

Description: DayOfTheYear returns the number of days that have passed since the start of the year till the moment indicated by AValue. This is a one-based number, i.e. January 1 will return 1.

For an example, see the WeekOfTheYear ([449](#)) function.

See also: [WeekOfTheYear \(449\)](#), [HourOfTheYear \(398\)](#), [MinuteOfTheYear \(418\)](#), [SecondOfTheYear \(435\)](#), [MilliSecondOfTheYear \(414\)](#)

4.4.13 DaysBetween

Synopsis: Number of whole days between two DateTime values.

Declaration: function DaysBetween(const ANow: TDateTime; const AThen: TDateTime)
: Integer

Visibility: default

Description: DaysBetween returns the number of whole days between ANow and AThen. This means the fractional part of a day (hours, minutes, etc.) is dropped.

See also: [YearsBetween \(461\)](#), [MonthsBetween \(421\)](#), [WeeksBetween \(450\)](#), [HoursBetween \(398\)](#), [MinutesBetween \(418\)](#), [SecondsBetween \(435\)](#), [MilliSecondsBetween \(415\)](#)

Listing: ./datutex/ex58.pp

Program Example58;

{ This program demonstrates the DaysBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of days between ');

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 WriteLn(' : ', DaysBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Now;

 D2 := Today - 23/24;

 Test(D1, D2);

 D2 := Today - 1;

 Test(D1, D2);

 D2 := Today - 25/24;

 Test(D1, D2);

 D2 := Today - 26/24;

 Test(D1, D2);

 D2 := Today - 5.4;

 Test(D1, D2);

 D2 := Today - 2.5;

 Test(D1, D2);

End.

4.4.14 DaysInAMonth

Synopsis: Number of days in a month of a certain year.

Declaration: function DaysInAMonth(const AYear: Word; const AMonth: Word) : Word

Visibility: default

Description: DaysInMonth returns the number of days in the month AMonth in the year AYear. The return value takes leap years into account.

See also: WeeksInAYear ([451](#)), WeeksInYear ([451](#)), DaysInYear ([386](#)), DaysInAYear ([385](#)), DaysInMonth ([385](#))

Listing: ./datutex/ex17.pp

Program Example17;

{ This program demonstrates the DaysInAMonth function }

Uses SysUtils, DateUtils;

Var

 Y, M : Word;

```

Begin
  For Y:=1992 to 2010 do
    For M:=1 to 12 do
      WriteLn (LongMonthNames[m], ' ', Y, ' has ', DaysInAMonth(Y,M), ' days. ');
End.

```

4.4.15 DaysInAYear

Synopsis: Number of days in a particular year.

Declaration: `function DaysInAYear(const AYear: Word) : Word`

Visibility: default

Description: `DaysInAYear` returns the number of weeks in the year `AYear`. The return value is either 365 or 366.

See also: `WeeksInAYear` ([451](#)), `WeeksInYear` ([451](#)), `DaysInYear` ([386](#)), `DaysInMonth` ([385](#)), `DaysInAMonth` ([384](#))

Listing: ./datutex/ex15.pp

Program Example15;

{ This program demonstrates the DaysInAYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 **to** 2010 **do**

WriteLn (Y, ' has ', DaysInAYear(Y), ' days. ');

End.

4.4.16 DaysInMonth

Synopsis: Return the number of days in the month in which a date occurs.

Declaration: `function DaysInMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DaysInMonth` returns the number of days in the month in which `AValue` falls. The return value takes leap years into account.

See also: `WeeksInAYear` ([451](#)), `WeeksInYear` ([451](#)), `DaysInYear` ([386](#)), `DaysInAYear` ([385](#)), `DaysInAMonth` ([384](#))

Listing: ./datutex/ex16.pp

Program Example16;

{ This program demonstrates the DaysInMonth function }

Uses SysUtils, DateUtils;

Var
Y, M : Word;

Begin
 For Y:=1992 **to** 2010 **do**
 For M:=1 **to** 12 **do**
 WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInMonth(**EncodeDate**(Y, M, 1)), ' days. ');
End.

4.4.17 DaysInYear

Synopsis: Return the number of days in the year in which a date occurs.

Declaration: `function DaysInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `daysInYear` returns the number of days in the year part of `AValue`. The return value is either 365 or 366.

See also: [WeeksInAYear \(451\)](#), [WeeksInYear \(451\)](#), [DaysInAYear \(385\)](#), [DaysInMonth \(385\)](#), [DaysInAMonth \(384\)](#)

Listing: ./datutex/ex14.pp

Program Example14;

{ This program demonstrates the DaysInYear function }

Uses SysUtils, DateUtils;

Var
Y : Word;

Begin
 For Y:=1992 **to** 2010 **do**
 WriteLn(Y, ' has ', DaysInYear(**EncodeDate**(Y, 1, 1)), ' days. ');
End.

4.4.18 DaySpan

Synopsis: Calculate the approximate number of days between two `DateTime` values.

Declaration: `function DaySpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: `DaySpan` returns the number of Days between `ANow` and `AThen`, including any fractional parts of a Day.

See also: [YearSpan \(462\)](#), [MonthSpan \(422\)](#), [WeekSpan \(452\)](#), [HourSpan \(399\)](#), [MinuteSpan \(419\)](#), [SecondSpan \(436\)](#), [MilliSecondSpan \(415\)](#), [DaysBetween \(383\)](#)

Listing: ./datutex/ex66.pp

Program Example66;

{ This program demonstrates the DaySpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of days between ');

Write(**DateTimeToStr**(AThen), ' and ', **DateTimeToStr**(ANow));

WriteLn(' : ', DaySpan(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := **Now**;

 D2 := Today - 23/24;

 Test(D1, D2);

 D2 := Today - 1;

 Test(D1, D2);

 D2 := Today - 25/24;

 Test(D1, D2);

 D2 := Today - 26/24;

 Test(D1, D2);

 D2 := Today - 5.4;

 Test(D1, D2);

 D2 := Today - 2.5;

 Test(D1, D2);

End.

4.4.19 DecodeDateDay

Synopsis: Decode a DateTime value in year and year of day.

Declaration: procedure DecodeDateDay(const AValue: TDateTime; var AYear: Word;
 var ADayOfYear: Word)

Visibility: default

Description: DecodeDateDay decomposes the date indication in AValue and returns the various components in AYear, ADayOfYear.

See also: EncodeDateTime (391), EncodeDateMonthWeek (391), EncodeDateWeek (391), EncodeDateDay (390), DecodeDateTime (388), DecodeDateWeek (389), DecodeDateMonthWeek (388)

Listing: ./datutex/ex83.pp

Program Example83;

{ This program demonstrates the DecodeDateDay function }

Uses SysUtils, DateUtils;

```

Var
  Y,DoY : Word;
  TS : TDateTime;

Begin
  DecodeDateDay(Now,Y,DoY);
  TS:=EncodeDateDay(Y,DoY);
  WriteLn('Today is : ',DateToStr(TS));
End.

```

4.4.20 DecodeDateMonthWeek

Synopsis: Decode a DateTime value in a month, week of month and day of week

Declaration: `procedure DecodeDateMonthWeek(const AValue: TDateTime; var AYear: Word; var AMonth: Word; var AWeekOfMonth: Word; var ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDateMonthWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

See also: [EncodeDateTime \(391\)](#), [EncodeDateMonthWeek \(391\)](#), [EncodeDateWeek \(391\)](#), [EncodeDateDay \(390\)](#), [DecodeDateTime \(388\)](#), [DecodeDateWeek \(389\)](#), [DecodeDateDay \(387\)](#)

Listing: ./datutex/ex85.pp

Program Example85;

{ This program demonstrates the DecodeDateMonthWeek function }

Uses SysUtils, DateUtils;

Var
 Y,M,Wom,Dow : Word;
 TS : TDateTime;

Begin
 DecodeDateMonthWeek(**Now**,Y,M,WoM,DoW);
 TS:=EncodeDateMonthWeek(Y,M,WoM,Dow);
WriteLn('Today is : ',**DateToStr**(TS));
End.

4.4.21 DecodeDateTime

Synopsis: Decode a datetime value in a date and time value

Declaration: `procedure DecodeDateTime(const AValue: TDateTime; var AYear: Word; var AMonth: Word; var ADay: Word; var AHour: Word; var AMinute: Word; var ASecond: Word; var AMilliSecond: Word)`

Visibility: default

Description: `DecodeDateTime` decomposes the date/time indication in `AValue` and returns the various components in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond`, `AMilliSecond`

See also: `EncodeDateTime` (391), `EncodeDateMonthWeek` (391), `EncodeDateWeek` (391), `EncodeDateDay` (390), `DecodeDateWeek` (389), `DecodeDateDay` (387), `DecodeDateMonthWeek` (388)

Listing: `./datutex/ex79.pp`

Program `Example79`;

{ This program demonstrates the DecodeDateTime function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, Mo, D, H, Mi, S, MS` : `Word`;
`TS` : `TDateTime`;

Begin

`DecodeDateTime(Now, Y, Mo, D, H, Mi, S, MS)`;
`TS := EncodeDateTime(Y, Mo, D, H, Mi, S, MS)`;
`WriteLn('Now is : ', DateTimeToStr(TS))`;

End.

4.4.22 DecodeDateWeek

Synopsis: Decode a `DateTime` value in a week of year and day of week.

Declaration: `procedure DecodeDateWeek(const AValue: TDateTime; var AYear: Word;`
`var AWeekOfYear: Word; var ADayOfWeek: Word)`

Visibility: `default`

Description: `DecodeDateWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AWeekOfYear`, `ADayOfWeek`.

See also: `EncodeDateTime` (391), `EncodeDateMonthWeek` (391), `EncodeDateWeek` (391), `EncodeDateDay` (390), `DecodeDateTime` (388), `DecodeDateDay` (387), `DecodeDateMonthWeek` (388)

Listing: `./datutex/ex81.pp`

Program `Example81`;

{ This program demonstrates the DecodeDateWeek function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, W, Dow` : `Word`;
`TS` : `TDateTime`;

Begin

`DecodeDateWeek(Now, Y, W, Dow)`;
`TS := EncodeDateWeek(Y, W, Dow)`;
`WriteLn('Today is : ', DateTimeToStr(TS))`;

End.

4.4.23 DecodeDayOfWeekInMonth

Synopsis: Decode a DateTime value in year, month, day of week parts

Declaration: `procedure DecodeDayOfWeekInMonth(const AValue: TDateTime;
var AYear: Word; var AMonth: Word;
var ANthDayOfWeek: Word;
var ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDayOfWeekInMonth` decodes the date `AValue` in a `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek`. (This is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.)

See also: `NthDayOfWeek` (422), `EncodeDateMonthWeek` (391), `#rtl.sysutils.DayOfWeek` (1324), `EncodeDayOfWeekInMonth` (392), `TryEncodeDayOfWeekInMonth` (445)

Listing: ./datutex/ex105.pp

Program Example105;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses SysUtils, DateUtils;

Var

Y,M,NDoW,DoW : Word;

D : TDateTime;

Begin

`DecodeDayOfWeekInMonth (Date, Y, M, NDoW, DoW);`

`D := EncodeDayOfWeekInMonth (Y, M, NDoW, DoW);`

`Write (DateToStr (D), ' is the ', NDoW, '-th ');`

`WriteLn (formatdateTime ('dddd', D), ' of the month. ');`

End.

4.4.24 EncodeDateDay

Synopsis: Encodes a year and day of year to a DateTime value

Declaration: `function EncodeDateDay(const AYear: Word; const ADayOfYear: Word)
: TDateTime`

Visibility: default

Description: `EncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value.

For an example, see `DecodeDateDay` (387).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `EncodeDateMonthWeek` (391), `DecodeDateDay` (387), `EncodeDateTime` (391), `EncodeDateWeek` (391), `TryEncodeDateTime` (444), `TryEncodeDateMonthWeek` (443), `TryEncodeDateWeek` (445)

4.4.25 EncodeDateMonthWeek

Synopsis: Encodes a year, month, week of month and day of week to a `DateTime` value

Declaration:

```
function EncodeDateMonthWeek(const AYear: Word;const AMonth: Word;
                             const AWeekOfMonth: Word;
                             const ADayOfWeek: Word) : TDateTime
```

Visibility: default

Description: `EncodeDateTime` encodes the values `AYear`, `AMonth`, `WeekOfMonth`, `ADayOfWeek`, to a date value and returns this value.

For an example, see `DecodeDateMonthWeek` (388).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `DecodeDateMonthWeek` (388), `EncodeDateTime` (391), `EncodeDateWeek` (391), `EncodeDateDay` (390), `TryEncodeDateTime` (444), `TryEncodeDateWeek` (445), `TryEncodeDateMonthWeek` (443), `TryEncodeDateDay` (443), `NthDayOfWeek` (422)

4.4.26 EncodeDateTime

Synopsis: Encodes a `DateTime` value from all its parts

Declaration:

```
function EncodeDateTime(const AYear: Word;const AMonth: Word;
                        const ADay: Word;const AHour: Word;
                        const AMinute: Word;const ASecond: Word;
                        const AMilliSecond: Word) : TDateTime
```

Visibility: default

Description: `EncodeDateTime` encodes the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` to a date/time value and returns this value.

For an example, see `DecodeDateTime` (388).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `DecodeDateTime` (388), `EncodeDateMonthWeek` (391), `EncodeDateWeek` (391), `EncodeDateDay` (390), `TryEncodeDateTime` (444), `TryEncodeDateWeek` (445), `TryEncodeDateDay` (443), `TryEncodeDateMonthWeek` (443)

4.4.27 EncodeDateWeek

Synopsis: Encode a `TDateTime` value from a year, week and day of week triplet

Declaration:

```
function EncodeDateWeek(const AYear: Word;const AWeekOfYear: Word;
                        const ADayOfWeek: Word) : TDateTime
function EncodeDateWeek(const AYear: Word;const AWeekOfYear: Word)
                        : TDateTime
```

Visibility: default

Description: `EncodeDateWeek` encodes the values `AYear`, `AWeekOfYear` and `ADayOfWeek` to a date value and returns this value.

For an example, see `DecodeDateWeek` (389).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `EncodeDateMonthWeek` (391), `DecodeDateWeek` (389), `EncodeDateTime` (391), `EncodeDateDay` (390), `TryEncodeDateTime` (444), `TryEncodeDateWeek` (445), `TryEncodeDateMonthWeek` (443)

4.4.28 EncodeDayOfWeekInMonth

Synopsis: Encodes a year, month, week, day of week specification to a `TDateTime` value

Declaration:

```
function EncodeDayOfWeekInMonth(const AYear: Word;const AMonth: Word;
                                const ANthDayOfWeek: Word;
                                const ADayOfWeek: Word) : TDateTime
```

Visibility: default

Description: `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

For an example, see `DecodeDayOfWeekInMonth` (390).

Errors: If any of the values is not in range, then an `EConvertError` exception will be raised.

See also: `NthDayOfWeek` (422), `EncodeDateMonthWeek` (391), `#rtl.sysutils.DayOfWeek` (1324), `DecodeDayOfWeekInMonth` (390), `TryEncodeDayOfWeekInMonth` (445)

4.4.29 EndOfDay

Synopsis: Calculates a `DateTime` value representing the end of a specified day

Declaration:

```
function EndOfDay(const AYear: Word;const AMonth: Word;
                  const ADay: Word) : TDateTime; Overload
function EndOfDay(const AYear: Word;const ADayOfYear: Word) : TDateTime
; Overload
```

Visibility: default

Description: `EndOfDay` returns a `TDateTime` value with the date/time indication of the last moment (23:59:59.999) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: `StartOfDay` (439), `StartOfDay` (437), `StartOfTheWeek` (440), `StartOfAWeek` (438), `StartOfAMonth` (438), `StartOfTheMonth` (440), `EndOfTheWeek` (396), `EndOfAWeek` (393), `EndOfTheYear` (396), `EndOfAYear` (394), `EndOfTheMonth` (395), `EndOfAMonth` (393), `EndOfTheDay` (394)

Listing: `./datutex/ex39.pp`

Program Example39;

{ This program demonstrates the EndOfDay function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss';

Var

 Y,M,D : Word;

Begin

 Y:=YearOf(Today);

 M:=MonthOf(Today);

```
D:=DayOf(Today);
WriteIn(FormatDateTime(Fmt, EndOfADay(Y,M,D)));
DecodeDateDay(Today,Y,D);
WriteIn(FormatDateTime(Fmt, EndOfADay(Y,D)));
End.
```

4.4.30 EndOfAMonth

Synopsis: Calculate a datetime value representing the last day of the indicated month

Declaration: `function EndOfAMonth(const AYear: Word;const AMonth: Word) : TDateTime`

Visibility: default

Description: `EndOfAMonth` returns a `TDateTime` value with the date of the last day of the month indicated by the `AYear`, `AMonth` pair.

See also: [StartOfTheMonth \(440\)](#), [StartOfAMonth \(438\)](#), [EndOfTheMonth \(395\)](#), [EndOfTheYear \(396\)](#), [End-OfAYear \(394\)](#), [StartOfAWeek \(438\)](#), [StartOfTheWeek \(440\)](#)

Listing: `./datutex/ex31.pp`

Program Example31;

{ This program demonstrates the EndOfAMonth function }

Uses SysUtils, DateUtils;

Const

Fmt = 'Last day of this month : "dd mmm yyyy';

Var

Y,M : Word;

Begin

Y:=YearOf(Today);

M:=MonthOf(Today);

WriteIn(FormatDateTime(Fmt, EndOfAMonth(Y,M)));

End.

4.4.31 EndOfAWeek

Synopsis: Return the last moment of day of the week, given a year and a week in the year.

Declaration: `function EndOfAWeek(const AYear: Word;const AWeekOfYear: Word;
const ADayOfWeek: Word) : TDateTime`
`function EndOfAWeek(const AYear: Word;const AWeekOfYear: Word)
: TDateTime`

Visibility: default

Description: `EndOfAWeek` returns a `TDateTime` value with the date of the last moment (23:59:59:999) on the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 7.

See also: [StartOfTheWeek \(440\)](#), [EndOfTheWeek \(396\)](#), [EndOfAWeek \(393\)](#), [StartOfAMonth \(438\)](#), [End-OfTheYear \(396\)](#), [EndOfAYear \(394\)](#), [EndOfTheMonth \(395\)](#), [EndOfAMonth \(393\)](#)

Listing: ./datutex/ex35.pp

Program Example35;

{ This program demonstrates the EndOfAWeek function }

Uses SysUtils, DateUtils;

Const

 Fmt = '"Last day of this week : "dd mmm yyyy hh:nn:ss';
 Fmt2 = '"Last-1 day of this week : "dd mmm yyyy hh:nn:ss';

Var

 Y,W : Word;

Begin

 Y:=YearOf(Today);
 W:=WeekOf(Today);
 WriteIn (FormatDateTime (Fmt, EndOfAWeek(Y,W)));
 WriteIn (FormatDateTime (Fmt2, EndOfAWeek(Y,W,6)));

End.

4.4.32 EndOfAYear

Synopsis: Calculate a DateTime value representing the last day of a year

Declaration: function EndOfAYear(const AYear: Word) : TDateTime

Visibility: default

Description: StartOfAYear returns a TDateTime value with the date of the last day of the year AYear (December 31).

See also: StartOfTheYear ([441](#)), EndOfTheYear ([396](#)), EndOfAYear ([394](#)), EndOfTheMonth ([395](#)), EndOfA-Month ([393](#)), StartOfAWeek ([438](#)), StartOfTheWeek ([440](#))

Listing: ./datutex/ex27.pp

Program Example27;

{ This program demonstrates the EndOfAYear function }

Uses SysUtils, DateUtils;

Const

 Fmt = '"Last day of this year : "dd mmm yyyy';

Begin

WriteIn (FormatDateTime (Fmt, EndOfAYear (YearOf (Today))));

End.

4.4.33 EndOfTheDay

Synopsis: Calculate a datetime value that represents the end of a given day.

Declaration: function EndOfTheDay(const AValue: TDateTime) : TDateTime

Visibility: default

Description: `EndOfDay` extracts the date part of `AValue` and returns a `TDateTime` value with the date/-time indication of the last moment (23:59:59.999) of this day.

See also: `StartOfDay` (439), `StartOfDay` (437), `StartOfTheWeek` (440), `StartOfAWeek` (438), `StartOfAMonth` (438), `StartOfTheMonth` (440), `EndOfTheWeek` (396), `EndOfAWeek` (393), `EndOfTheYear` (396), `EndOfAYear` (394), `EndOfTheMonth` (395), `EndOfAMonth` (393), `EndOfDay` (392)

Listing: `./datutex/ex37.pp`

Program `Example37`;

{ This program demonstrates the EndOfDay function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss';`

Begin

`WriteLn (FormatDateTime (Fmt, EndOfDay (Today)));`

End.

4.4.34 EndOfTheMonth

Synopsis: Calculate a `DateTime` value representing the last day of the month, given a day in that month.

Declaration: `function EndOfTheMonth(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheMonth` extracts the year and month parts of `AValue` and returns a `TDateTime` value with the date of the first day of that year and month as the `EndOfAMonth` (393) function.

See also: `StartOfAMonth` (438), `StartOfTheMonth` (440), `EndOfAMonth` (393), `EndOfTheYear` (396), `EndOfAYear` (394), `StartOfAWeek` (438), `StartOfTheWeek` (440)

Listing: `./datutex/ex29.pp`

Program `Example29`;

{ This program demonstrates the EndOfTheMonth function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = 'last day of this month : "dd mmm yyyy';`

Begin

`WriteLn (FormatDateTime (Fmt, EndOfTheMonth (Today)));`

End.

4.4.35 EndOfTheWeek

Synopsis: Calculate a `DateTime` value which represents the end of a week, given a date in that week.

Declaration: `function EndOfTheWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the last day of that week as the `EndOfAWeek` (393) function.

See also: `StartOfAWeek` (438), `StartOfTheWeek` (440), `EndOfAWeek` (393), `StartOfAMonth` (438), `EndOfTheYear` (396), `EndOfAYear` (394), `EndOfTheMonth` (395), `EndOfAMonth` (393)

Listing: `./datutex/ex33.pp`

Program Example33;

{ This program demonstrates the EndOfTheWeek function }

Uses SysUtils, DateUtils;

Const

Fmt = ' "last day of this week : " dd mmm yyyy ';

Begin

WriteLn (FormatDateTime (Fmt, EndOfTheWeek (Today)));

End.

4.4.36 EndOfTheYear

Synopsis: Calculate a `DateTime` value representing the last day of a year, given a date in that year.

Declaration: `function EndOfTheYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the last day of that year (December 31), as the `EndOfAYear` (394) function.

See also: `StartOfAYear` (439), `StartOfTheYear` (441), `EndOfTheMonth` (395), `EndOfAMonth` (393), `StartOfAWeek` (438), `StartOfTheWeek` (440), `EndOfAYear` (394)

Listing: `./datutex/ex25.pp`

Program Example25;

{ This program demonstrates the EndOfTheYear function }

Uses SysUtils, DateUtils;

Const

Fmt = ' "Last day of this year : " dd mmm yyyy ';

Begin

WriteLn (FormatDateTime (Fmt, EndOfTheYear (Today)));

End.

4.4.37 HourOf

Synopsis: Extract the hour part from a DateTime value.

Declaration: `function HourOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOf` returns the hour of the day part of the `AValue` date/time indication. It is a number between 0 and 23.

For an example, see `YearOf` (460)

See also: `YearOf` (460), `WeekOf` (448), `MonthOf` (420), `DayOf` (382), `MinuteOf` (416), `SecondOf` (433), `MilliSecondOf` (412)

4.4.38 HourOfDay

Synopsis: Calculate the hour of a given DateTime value

Declaration: `function HourOfDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfDay` returns the number of hours that have passed since the start of the day till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 will return 0.

See also: `HourOfTheYear` (398), `HourOfTheMonth` (397), `HourOfTheWeek` (398), `MinuteOfDay` (416), `SecondOfDay` (433), `MilliSecondOfDay` (412)

Listing: `./datutex/ex43.pp`

Program `Example43;`

`{ This program demonstrates the HourOfDay function }`

Uses `SysUtils, DateUtils;`

Var

`N : TDateTime;`

Begin

`N:=Now;`

`WriteLn('Hour of the Day : ',HourOfDay(N));`

`WriteLn('Minute of the Day : ',MinuteOfDay(N));`

`WriteLn('Second of the Day : ',SecondOfDay(N));`

`WriteLn('MilliSecond of the Day : ',
MilliSecondOfDay(N));`

End.

4.4.39 HourOfTheMonth

Synopsis: Calculate the number of hours passed since the start of the month.

Declaration: `function HourOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheMonth` returns the number of hours that have passed since the start of the month till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (448) function.

See also: `WeekOfTheMonth` (448), `DayOfTheMonth` (382), `MinuteOfTheMonth` (417), `SecondOfTheMonth` (434), `MilliSecondOfTheMonth` (413)

4.4.40 HourOfTheWeek

Synopsis: Calculate the number of hours elapsed since the start of the week.

Declaration: `function HourOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheWeek` returns the number of hours that have passed since the start of the Week till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (382) function.

See also: `HourOfTheYear` (398), `HourOfTheMonth` (397), `HourOfTheDay` (397), `DayOfTheWeek` (382), `MinuteOfTheWeek` (418), `SecondOfTheWeek` (434), `MilliSecondOfTheWeek` (414)

4.4.41 HourOfTheYear

Synopsis: Calculate the number of hours passed since the start of the year.

Declaration: `function HourOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheYear` returns the number of hours that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:59:59 will return 0.

For an example, see the `WeekOfTheYear` (449) function.

See also: `WeekOfTheYear` (449), `DayOfTheYear` (383), `MinuteOfTheYear` (418), `SecondOfTheYear` (435), `MilliSecondOfTheYear` (414)

4.4.42 HoursBetween

Synopsis: Calculate the number of whole hours between two `DateTime` values.

Declaration: `function HoursBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `HoursBetween` returns the number of whole hours between `ANow` and `AThen`. This means the fractional part of an hour (minutes, seconds etc.) is dropped.

See also: `YearsBetween` (461), `MonthsBetween` (421), `WeeksBetween` (450), `DaysBetween` (383), `MinutesBetween` (418), `SecondsBetween` (435), `MillisecondsBetween` (415)

Listing: `./datutex/ex59.pp`

Program Example59;

{ This program demonstrates the HoursBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of hours between ');

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 WriteLn(' : ', HoursBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;

 D2:=D1-(59*OneMinute);

 Test(D1, D2);

 D2:=D1-(61*OneMinute);

 Test(D1, D2);

 D2:=D1-(122*OneMinute);

 Test(D1, D2);

 D2:=D1-(306*OneMinute);

 Test(D1, D2);

 D2:=D1-(5.4*OneHour);

 Test(D1, D2);

 D2:=D1-(2.5*OneHour);

 Test(D1, D2);

End.

4.4.43 HourSpan

Synopsis: Calculate the approximate number of hours between two DateTime values.

Declaration: function HourSpan(const ANow: TDateTime; const AThen: TDateTime) : Double

Visibility: default

Description: HourSpan returns the number of Hours between ANow and AThen, including any fractional parts of a Hour.

See also: YearSpan ([462](#)), MonthSpan ([422](#)), WeekSpan ([452](#)), DaySpan ([386](#)), MinuteSpan ([419](#)), SecondSpan ([436](#)), MilliSecondSpan ([415](#)), HoursBetween ([398](#))

Listing: ./datutex/ex67.pp

Program Example67;

{ This program demonstrates the HourSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

```

begin
  Write( 'Number of hours between ');
  Write( DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  WriteLn( ' : ', HourSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Now;
  D2 := D1 - (59 * OneMinute);
  Test(D1, D2);
  D2 := D1 - (61 * OneMinute);
  Test(D1, D2);
  D2 := D1 - (122 * OneMinute);
  Test(D1, D2);
  D2 := D1 - (306 * OneMinute);
  Test(D1, D2);
  D2 := D1 - (5.4 * OneHour);
  Test(D1, D2);
  D2 := D1 - (2.5 * OneHour);
  Test(D1, D2);
End.

```

4.4.44 IncDay

Synopsis: Increase a DateTime value with a number of days.

Declaration: `function IncDay(const AValue: TDateTime; const ANumberOfDays: Integer) : TDateTime`
`function IncDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncDay` adds `ANumberOfDays` days to `AValue` and returns the resulting date/time. `ANumberOfDays` can be positive or negative.

See also: `IncYear` ([403](#)), `#rtl.sysutils.IncMonth` ([1366](#)), `IncWeek` ([403](#)), `IncHour` ([401](#)), `IncMinute` ([402](#)), `IncSecond` ([402](#)), `IncMilliSecond` ([401](#))

Listing: `./datutex/ex74.pp`

Program Example74;

{ This program demonstrates the IncDay function }

Uses SysUtils, DateUtils;

```

Begin
  WriteLn( 'One Day from today is ', DateToStr(IncDay(Today, 1)));
  WriteLn( 'One Day ago from today is ', DateToStr(IncDay(Today, -1)));
End.

```

4.4.45 IncHour

Synopsis: Increase a DateTime value with a number of hours.

Declaration: `function IncHour(const AValue: TDateTime; const ANumberOfHours: Int64) : TDateTime`
`function IncHour(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncHour` adds `ANumberOfHours` hours to `AValue` and returns the resulting date/time. `ANumberOfHours` can be positive or negative.

See also: `IncYear` (403), `#rtl.sysutils.IncMonth` (1366), `IncWeek` (403), `IncDay` (400), `IncMinute` (402), `IncSecond` (402), `IncMilliSecond` (401)

Listing: `./datutex/ex75.pp`

Program Example75

;

{ This program demonstrates the IncHour function }

Uses SysUtils, DateUtils;

Begin

`WriteLn('One Hour from now is ', DateTimeToStr(IncHour(Now, 1)));`

`WriteLn('One Hour ago from now is ', DateTimeToStr(IncHour(Now, -1)));`

End.

4.4.46 IncMilliSecond

Synopsis: Increase a DateTime value with a number of milliseconds.

Declaration: `function IncMilliSecond(const AValue: TDateTime; const ANumberOfMilliseconds: Int64) : TDateTime`
`function IncMilliSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMilliSecond` adds `ANumberOfMilliseconds` milliseconds to `AValue` and returns the resulting date/time. `ANumberOfMilliseconds` can be positive or negative.

See also: `IncYear` (403), `#rtl.sysutils.IncMonth` (1366), `IncWeek` (403), `IncDay` (400), `IncHour` (401), `IncSecond` (402), `IncMilliSecond` (401)

Listing: `./datutex/ex78.pp`

Program Example78;

{ This program demonstrates the IncMilliSecond function }

Uses SysUtils, DateUtils;

Begin

`WriteLn('One MilliSecond from now is ', TimeToStr(IncMilliSecond(Now, 1)));`

`WriteLn('One MilliSecond ago from now is ', TimeToStr(IncMilliSecond(Now, -1)));`

End.

4.4.47 IncMinute

Synopsis: Increase a DateTime value with a number of minutes.

Declaration: `function IncMinute(const AValue: TDateTime;
const ANumberOfMinutes: Int64) : TDateTime
function IncMinute(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMinute` adds `ANumberOfMinutes` minutes to `AValue` and returns the resulting date/-time. `ANumberOfMinutes` can be positive or negative.

See also: `IncYear` (403), `#rtl.sysutils.IncMonth` (1366), `IncWeek` (403), `IncDay` (400), `IncHour` (401), `IncSecond` (402), `IncMilliSecond` (401)

Listing: `./datutex/ex76.pp`

Program `Example76;`

{ This program demonstrates the IncMinute function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Minute from now is ', TimeToStr(IncMinute(Time, 1)));`

`WriteLn('One Minute ago from now is ', TimeToStr(IncMinute(Time, -1)));`

End.

4.4.48 IncSecond

Synopsis: Increase a DateTime value with a number of seconds.

Declaration: `function IncSecond(const AValue: TDateTime;
const ANumberOfSeconds: Int64) : TDateTime
function IncSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncSecond` adds `ANumberOfSeconds` seconds to `AValue` and returns the resulting date/-time. `ANumberOfSeconds` can be positive or negative.

See also: `IncYear` (403), `#rtl.sysutils.IncMonth` (1366), `IncWeek` (403), `IncDay` (400), `IncHour` (401), `IncSecond` (402), `IncMilliSecond` (401)

Listing: `./datutex/ex77.pp`

Program `Example77;`

{ This program demonstrates the IncSecond function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Second from now is ', TimeToStr(IncSecond(Time, 1)));`

`WriteLn('One Second ago from now is ', TimeToStr(IncSecond(Time, -1)));`

End.

4.4.49 IncWeek

Synopsis: Increase a DateTime value with a number of weeks.

Declaration: `function IncWeek(const AValue: TDateTime;const ANumberOfWeeks: Integer)
: TDateTime
function IncWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: IncWeek adds ANumberOfWeeks weeks to AValue and returns the resulting date/time. ANumberOfWeeks can be positive or negative.

See also: IncYear (403), #rtl.sysutils.IncMonth (1366), IncDay (400), IncHour (401), IncMinute (402), IncSecond (402), IncMilliSecond (401)

Listing: ./datutex/ex73.pp

Program Example73;

{ This program demonstrates the IncWeek function }

Uses SysUtils, DateUtils;

Begin

WriteIn ('One Week from today is ', **DateToStr** (IncWeek (Today, 1)));

WriteIn ('One Week ago from today is ', **DateToStr** (IncWeek (Today, -1)));

End.

4.4.50 IncYear

Synopsis: Increase a DateTime value with a number of years.

Declaration: `function IncYear(const AValue: TDateTime;const ANumberOfYears: Integer)
: TDateTime
function IncYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: IncYear adds ANumberOfYears years to AValue and returns the resulting date/time. ANumberOfYears can be positive or negative.

See also: #rtl.sysutils.IncMonth (1366), IncWeek (403), IncDay (400), IncHour (401), IncMinute (402), IncSecond (402), IncMilliSecond (401)

Listing: ./datutex/ex71.pp

Program Example71;

{ This program demonstrates the IncYear function }

Uses SysUtils, DateUtils;

Begin

WriteIn ('One year from today is ', **DateToStr** (IncYear (Today, 1)));

WriteIn ('One year ago from today is ', **DateToStr** (IncYear (Today, -1)));

End.

4.4.51 InvalidDateDayError

Synopsis: Raise an `EConvertError` exception when a day is not a valid day of a year.

Declaration: `procedure InvalidDateDayError(const AYear: Word; const ADayOfYear: Word)`

Visibility: `default`

Description: `InvalidDateDayError` raises an `EConvertError` (1413) exception and formats the error message with an appropriate description made up from the parts `AYear` and `ADayOfYear`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (405), `InvalidDateTimeError` (404), `InvalidDateMonthWeekError` (404), `InvalidDayOfWeekInMonthError` (405)

4.4.52 InvalidDateMonthWeekError

Synopsis: Raise an `EConvertError` exception when a `Year, Month, WeekOfMonth, DayOfWeek` is invalid.

Declaration: `procedure InvalidDateMonthWeekError(const AYear: Word;
const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word)`

Visibility: `default`

Description: `InvalidDateMonthWeekError` raises an `EConvertError` (1413) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (405), `InvalidDateTimeError` (404), `InvalidDateDayError` (404), `InvalidDayOfWeekInMonthError` (405)

4.4.53 InvalidDateTimeError

Synopsis: Raise an `EConvertError` about an invalid date-time specification.

Declaration: `procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word;
const ABaseDate: TDateTime)
procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word)`

Visibility: `default`

Description: `InvalidDateTimeError` raises an `EConvertError` (1413) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: [InvalidDateWeekError \(405\)](#), [InvalidDateDayError \(404\)](#), [InvalidDateMonthWeekError \(404\)](#), [InvalidDayOfWeekInMonthError \(405\)](#)

4.4.54 InvalidDateWeekError

Synopsis: Raise an `EConvertError` with an invalid Year, WeekOfyear and DayOfWeek specification

Declaration:

```
procedure InvalidDateWeekError(const AYear: Word;
                                const AWeekOfYear: Word;
                                const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDateWeekError` raises an `EConvertError` ([1413](#)) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AWeek`, `ADayOfWeek`

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: [InvalidDateTimeError \(404\)](#), [InvalidDateDayError \(404\)](#), [InvalidDateMonthWeekError \(404\)](#), [InvalidDayOfWeekInMonthError \(405\)](#)

4.4.55 InvalidDayOfWeekInMonthError

Synopsis: Raise an `EConvertError` exception when a Year,Month,NthDayOfWeek,DayOfWeek is invalid.

Declaration:

```
procedure InvalidDayOfWeekInMonthError(const AYear: Word;
                                       const AMonth: Word;
                                       const ANthDayOfWeek: Word;
                                       const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDayOfWeekInMonthError` raises an `EConvertError` ([1413](#)) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ANthDayOfWeek` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: [InvalidDateWeekError \(405\)](#), [InvalidDateTimeError \(404\)](#), [InvalidDateDayError \(404\)](#), [InvalidDateMonthWeekError \(404\)](#)

4.4.56 IsInLeapYear

Synopsis: Determine whether a date is in a leap year.

Declaration:

```
function IsInLeapYear(const AValue: TDateTime) : Boolean
```

Visibility: default

Description: `IsInLeapYear` returns `True` if the year part of `AValue` is leap year, or `False` if not.

See also: [YearOf \(460\)](#), [IsPM \(406\)](#), [IsToday \(407\)](#), [IsSameDay \(406\)](#)

Listing: ./datutex/ex3.pp

Program Example3;

```
{ This program demonstrates the IsInLeapYear function }
```

Uses SysUtils , DateUtils ;

Begin

```
WriteLn( 'Current year is leap year: ', IsInLeapYear(Date));
```

End .

4.4.57 IsPM

Synopsis: Determine whether a time is PM or AM.

Declaration: `function IsPM(const AValue: TDateTime) : Boolean`

Visibility: default

Description: IsPM returns True if the time part of AValue is later then 12:00 (PM, or afternoon).

See also: YearOf (460), IsInLeapYear (405), IsToday (407), IsSameDay (406)

Listing: ./datutex/ex4.pp

Program Example4;

```
{ This program demonstrates the lsPM function }
```

Uses SysUtils , DateUtils ;

Begin

```
WriteLn( 'Current time is PM : ',IsPM(Now));
```

End .

4.4.58 IsSameDay

Synopsis: Check if two date/time indications are the same day.

```
Declaration: function IsSameDay(const AValue: TDateTime; const ABasis: TDateTime)
                : Boolean
```

Visibility: default

Description: `IsSameDay` checks whether `AValue` and `ABasis` have the same date part, and returns `True` if they do, `False` if not.

See also: Today (442), Yesterday (463), Tomorrow (442), IsToday (407)

Listing: ./datutex/ex21.pp

Program Example21 ;

```
{ This program demonstrates the IsSameDay function }
```

Uses SysUtils , DateUtils ;

```

Var
  I : Integer;
  D : TDateTime;

Begin
  For I:=1 to 3 do
    begin
      D:=Today+Random(3)-1;
      Write(FormatDateTime('dd mmm yyyy "is today : "',D));
      WriteLn(IsSameDay(D,Today));
    end;
End.

```

4.4.59 IsToday

Synopsis: Check whether a given date is today.

Declaration: `function IsToday(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsToday` returns `True` if `AValue` is today's date, and `False` otherwise.

See also: `Today` (442), `Yesterday` (463), `Tomorrow` (442), `IsSameDay` (406)

Listing: ./datutex/ex20.pp

```

Program Example20;

{ This program demonstrates the IsToday function }

Uses SysUtils, DateUtils;

Begin
  WriteLn('Today      : ',IsToday(Today));
  WriteLn('Tomorrow   : ',IsToday(Tomorrow));
  WriteLn('Yesterday  : ',IsToday(Yesterday));
End.

```

4.4.60 IsValidDate

Synopsis: Check whether a set of values is a valid date indication.

Declaration: `function IsValidDate(const AYear: Word;const AMonth: Word;
const ADay: Word) : Boolean`

Visibility: default

Description: `IsValidDate` returns `True` when the values `AYear`, `AMonth`, `ADay` form a valid date indication. If one of the values is not valid (e.g. the day is invalid or does not exist in that particular month), `False` is returned.

`AYear` must be in the range 1..9999 to be valid.

See also: `IsValidTime` (411), `IsValidDateTime` (409), `IsValidDateDay` (408), `IsValidDateWeek` (410), `IsValidDateMonthWeek` (409)

Listing: ./datutex/ex5.pp

Program Example5;

{ This program demonstrates the IsValidDate function }

Uses SysUtils, DateUtils;

Var

Y,M,D : Word;

Begin

For Y:=2000 to 2004 do

For M:=1 to 12 do

For D:=1 to 31 do

If Not IsValidDate(Y,M,D) then

WriteLn(D, ' is not a valid day in ',Y,'/',M);

End.

4.4.61 IsValidDateDay

Synopsis: Check whether a given year/day of year combination is a valid date.

Declaration: function IsValidDateDay(const AYear: Word;const ADayOfYear: Word)
: Boolean

Visibility: default

Description: IsValidDateDay returns True if AYear and ADayOfYear form a valid date indication, or False otherwise.

AYear must be in the range 1..9999 to be valid.

The ADayOfYear value is checked to see whether it falls within the valid range of dates for AYear.

See also: IsValidDate (407), IsValidTime (411), IsValidDateTime (409), IsValidDateWeek (410), IsValidDate-MonthWeek (409)

Listing: ./datutex/ex9.pp

Program Example9;

{ This program demonstrates the IsValidDateDay function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1996 to 2004 do

if IsValidDateDay(Y,366) then

WriteLn(Y, ' is a leap year');

End.

4.4.62 IsValidDateMonthWeek

Synopsis: Check whether a given year/month/week/day of the week combination is a valid day

Declaration: `function IsValidDateMonthWeek(const AYear: Word;const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word) : Boolean`

Visibility: default

Description: IsValidDateMonthWeek returns True if AYear, AMonth, AWeekOfMonth and ADayOfWeek form a valid date indication, or False otherwise.

AYear must be in the range 1..9999 to be valid.

The AWeekOfMonth, ADayOfWeek values are checked to see whether the combination falls within the valid range of weeks for the AYear, AMonth combination.

See also: IsValidDate (407), IsValidTime (411), IsValidDateTime (409), IsValidDateDay (408), IsValidDate-Week (410)

Listing: ./datutex/ex11.pp

Program Example11;

{ This program demonstrates the IsValidDateMonthWeek function }

Uses SysUtils, DateUtils;

Var

Y, W, D : Word;
B : Boolean;

Begin

For Y:=2000 to 2004 do

begin

B:=True;

For W:=4 to 6 do

For D:=1 to 7 do

If B then

begin

B:=IsValidDateMonthWeek(Y, 12, W, D);

If Not B then

if (D=1) then

Writeln('December ', Y, ' has exactly ', W, ' weeks.')

else

Writeln('December ', Y, ' has ', W, ' weeks and ', D-1, ' days.');

end;

end;

End.

4.4.63 IsValidDateTime

Synopsis: Check whether a set of values is a valid date and time indication.

Declaration: `function IsValidDateTime(const AYear: Word;const AMonth: Word;
const ADay: Word;const AHour: Word;
const AMinute: Word;const ASecond: Word;
const AMilliSecond: Word) : Boolean`

Visibility: default

Description: `IsValidTime` returns `True` when the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` form a valid date and time indication. If one of the values is not valid (e.g. the seconds are larger than 60), `False` is returned.

`AYear` must be in the range 1..9999 to be valid.

See also: `IsValidDate` (407), `IsValidTime` (411), `IsValidDateDay` (408), `IsValidDateWeek` (410), `IsValidDate-MonthWeek` (409)

Listing: `./datutex/ex7.pp`

Program `Example7`;

{ This program demonstrates the IsValidDateTime function }

Uses `SysUtils`, `DateUtils`;

Var

`Y,Mo,D` : `Word`;
`H,M,S,MS` : `Word`;
`I` : `Integer`;

Begin

For `I:=1 to 10 do`

begin

`Y:=2000+Random(5)`;

`Mo:=Random(15)`;

`D:=Random(40)`;

`H:=Random(32)`;

`M:=Random(90)`;

`S:=Random(90)`;

`MS:=Random(1500)`;

If Not `IsValidDateTime(Y,Mo,D,H,M,S,MS)` **then**

`WriteLn(Y,'-',Mo,'-',D,' ',H,':',M,':',S,'.',MS,' is not a valid date/time.');`

end;

End.

4.4.64 IsValidDateWeek

Synopsis: Check whether a given year/week/day of the week combination is a valid day.

Declaration: `function IsValidDateWeek(const AYear: Word;const AWeekOfYear: Word;
const ADayOfWeek: Word) : Boolean`

Visibility: default

Description: `IsValidDateWeek` returns `True` if `AYear`, `AWeekOfYear` and `ADayOfWeek` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfWeek`, `ADayOfWeek` values are checked to see whether the combination falls within the valid range of weeks for `AYear`.

See also: `IsValidDate` (407), `IsValidTime` (411), `IsValidDateTime` (409), `IsValidDateDay` (408), `IsValidDate-MonthWeek` (409)

Listing: ./datutex/ex10.pp

Program Example10;

{ This program demonstrates the IsValidDateWeek function }

Uses SysUtils, DateUtils;

Var

Y,W,D : Word;
B : Boolean;

Begin

For Y:=2000 to 2004 do

begin

B:=True;

For W:=51 to 54 do

For D:=1 to 7 do

If B then

begin

B:=IsValidDateWeek(Y,W,D);

If Not B then

if (D=1) then

WriteLn(Y, ' has exactly ',W, ' weeks. ')

else

WriteLn(Y, ' has ',W, ' weeks and ',D-1, ' days. ');

end;

end;

End.

4.4.65 IsValidTime

Synopsis: Check whether a set of values is a valid time indication.

Declaration: function IsValidTime(const AHour: Word;const AMinute: Word;
const ASecond: Word;const AMilliSecond: Word)
: Boolean

Visibility: default

Description: Check whether a set of values is a valid time indication.

4.4.66 JulianDateToDateTime

Synopsis: Convert a Julian date representation to a TDateTime value.

Declaration: function JulianDateToDateTime(const AValue: Double) : TDateTime

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: DateTimeToJulianDate ([381](#)), TryJulianDateToDateTime ([446](#)), DateTimeToModifiedJulianDate ([381](#)), TryModifiedJulianDateToDateTime ([446](#))

4.4.67 MacTimeStampToUnix

Synopsis: Convert a Mac timestamp to a Unix timestamp

Declaration: `function MacTimeStampToUnix(const AValue: Int64) : Int64`

Visibility: default

Description: `MacTimeStampToUnix` converts the Mac timestamp indication in `AValue` to a unix timestamp indication (epoch time)

Errors: None.

See also: `UnixTimeStampToMac` (448), `DateTimeToMac` (381), `MacToDateTime` (412)

4.4.68 MacToDateTime

Synopsis: Convert a Mac timestamp to a TDateTime timestamp

Declaration: `function MacToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `MacToDateTime` converts the Mac timestamp indication in `AValue` to a valid `TDateTime` indication.

Errors: None.

See also: `UnixTimeStampToMac` (448), `DateTimeToMac` (381), `MacTimeStampToUnix` (412)

4.4.69 MilliSecondOf

Synopsis: Extract the millisecond part from a DateTime value.

Declaration: `function MilliSecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 999.

For an example, see `YearOf` (460)

See also: `YearOf` (460), `WeekOf` (448), `MonthOf` (420), `DayOf` (382), `HourOf` (397), `MinuteOf` (416), `MilliSecondOf` (412)

4.4.70 MilliSecondOfDay

Synopsis: Calculate the number of milliseconds elapsed since the start of the day

Declaration: `function MilliSecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfDay` returns the number of milliseconds that have passed since the start of the Day (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 will return 0.

For an example, see the `HourOfDay` (397) function.

See also: `MilliSecondOfTheYear` (414), `MilliSecondOfTheMonth` (413), `MilliSecondOfTheWeek` (414), `MilliSecondOfTheHour` (413), `MilliSecondOfTheMinute` (413), `MilliSecondOfTheSecond` (413), `HourOfTheDay` (397), `MinuteOfDay` (416), `SecondOfDay` (433)

4.4.71 MilliSecondOfTheHour

Synopsis: Calculate the number of milliseconds elapsed since the start of the hour

Declaration: `function MilliSecondOfTheHour(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheHour` returns the number of milliseconds that have passed since the start of the Hour (HH:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.000 will return 0.

For an example, see the `MinuteOfTheHour` (417) function.

See also: `MilliSecondOfTheYear` (414), `MilliSecondOfTheMonth` (413), `MilliSecondOfTheWeek` (414), `MilliSecondOfTheDay` (412), `MilliSecondOfTheMinute` (413), `MilliSecondOfTheSecond` (413), `MinuteOfTheHour` (417), `SecondOfTheHour` (433)

4.4.72 MilliSecondOfTheMinute

Synopsis: Calculate the number of milliseconds elapsed since the start of the minute

Declaration: `function MilliSecondOfTheMinute(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMinute` returns the number of milliseconds that have passed since the start of the Minute (HH:MM:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.000 will return 0.

For an example, see the `SecondOfTheMinute` (434) function.

See also: `MilliSecondOfTheYear` (414), `MilliSecondOfTheMonth` (413), `MilliSecondOfTheWeek` (414), `MilliSecondOfTheDay` (412), `MilliSecondOfTheHour` (413), `MilliSecondOfTheMinute` (413), `MilliSecondOfTheSecond` (413), `SecondOfTheMinute` (434)

4.4.73 MilliSecondOfTheMonth

Synopsis: Calculate number of milliseconds elapsed since the start of the month.

Declaration: `function MilliSecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMonth` returns the number of milliseconds that have passed since the start of the month (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the month will return 0.

For an example, see the `WeekOfTheMonth` (448) function.

See also: `WeekOfTheMonth` (448), `DayOfTheMonth` (382), `HourOfTheMonth` (397), `MinuteOfTheMonth` (417), `SecondOfTheMonth` (434), `MilliSecondOfTheMonth` (413)

4.4.74 MilliSecondOfTheSecond

Synopsis: Calculate the number of milliseconds elapsed since the start of the second

Declaration: `function MilliSecondOfTheSecond(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOfTheSecond` returns the number of milliseconds that have passed since the start of the second (HH:MM:SS.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:SS.000 will return 0.

See also: `MilliSecondOfTheYear` (414), `MilliSecondOfTheMonth` (413), `MilliSecondOfTheWeek` (414), `MilliSecondOfTheDay` (412), `MilliSecondOfTheHour` (413), `MilliSecondOfTheMinute` (413), `SecondOfTheMinute` (434)

Listing: `./datutex/ex46.pp`

Program `Example46`;

{ This program demonstrates the MilliSecondOfTheSecond function }

Uses `SysUtils` , `DateUtils` ;

Var

`N` : `TDateTime` ;

Begin

`N:=Now`;

`WriteLn` ('MilliSecond of the Second : ',
 `MilliSecondOfTheSecond` (N));

End.

4.4.75 MilliSecondOfTheWeek

Synopsis: Calculate the number of milliseconds elapsed since the start of the week

Declaration: `function MilliSecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: `default`

Description: `MilliSecondOfTheWeek` returns the number of milliseconds that have passed since the start of the Week (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the Week will return 0.

For an example, see the `DayOfTheWeek` (382) function.

See also: `MilliSecondOfTheYear` (414), `MilliSecondOfTheMonth` (413), `MilliSecondOfTheDay` (412), `MilliSecondOfTheHour` (413), `MilliSecondOfTheMinute` (413), `MilliSecondOfTheSecond` (413), `DayOfTheWeek` (382), `HourOfTheWeek` (398), `MinuteOfTheWeek` (418), `SecondOfTheWeek` (434)

4.4.76 MilliSecondOfTheYear

Synopsis: Calculate the number of milliseconds elapsed since the start of the year.

Declaration: `function MilliSecondOfTheYear(const AValue: TDateTime) : Int64`

Visibility: `default`

Description: `MilliSecondOfTheYear` returns the number of milliseconds that have passed since the start of the year (January 1, 00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.000 will return 0.

For an example, see the `WeekOfTheYear` (449) function.

See also: `WeekOfTheYear` (449), `DayOfTheYear` (383), `HourOfTheYear` (398), `MinuteOfTheYear` (418), `SecondOfTheYear` (435), `MilliSecondOfTheYear` (414)

4.4.77 MilliSecondsBetween

Synopsis: Calculate the number of whole milliseconds between two `DateTime` values.

Declaration: `function MilliSecondsBetween(const ANow: TDateTime;
const AThen: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondsBetween` returns the number of whole milliseconds between `ANow` and `AThen`. This means a fractional part of a millisecond is dropped.

See also: `YearsBetween` ([461](#)), `MonthsBetween` ([421](#)), `WeeksBetween` ([450](#)), `DaysBetween` ([383](#)), `HoursBetween` ([398](#)), `MinutesBetween` ([418](#)), `SecondsBetween` ([435](#))

Listing: `./datutex/ex62.pp`

Program Example62;

{ This program demonstrates the MilliSecondsBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of milliseconds between ');
 Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
 WriteLn(' : ', MilliSecondsBetween(ANow, AThen));
end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;
 D2:=D1-(0.9*OneMilliSecond);
 Test(D1,D2);
 D2:=D1-(1.0*OneMilliSecond);
 Test(D1,D2);
 D2:=D1-(1.1*OneMilliSecond);
 Test(D1,D2);
 D2:=D1-(2.5*OneMilliSecond);
 Test(D1,D2);

End.

4.4.78 MilliSecondSpan

Synopsis: Calculate the approximate number of milliseconds between two `DateTime` values.

Declaration: `function MilliSecondSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: `MilliSecondSpan` returns the number of milliseconds between `ANow` and `AThen`. Since millisecond is the smallest fraction of a `TDateTime` indication, the returned number will always be an integer value.

See also: [YearSpan \(462\)](#), [MonthSpan \(422\)](#), [WeekSpan \(452\)](#), [DaySpan \(386\)](#), [HourSpan \(399\)](#), [MinuteSpan \(419\)](#), [SecondSpan \(436\)](#), [MillisecondsBetween \(415\)](#)

Listing: ./datutex/ex70.pp

Program Example70;

{ This program demonstrates the MilliSecondSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of milliseconds between ');
 Write(**TimeToStr**(AThen), ' and ', **TimeToStr**(ANow));
 WriteLn(' : ', MilliSecondSpan(ANow, AThen));
end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=**Now**;
 D2:=D1-(0.9*OneMilliSecond);
 Test(D1,D2);
 D2:=D1-(1.0*OneMilliSecond);
 Test(D1,D2);
 D2:=D1-(1.1*OneMilliSecond);
 Test(D1,D2);
 D2:=D1-(2.5*OneMilliSecond);
 Test(D1,D2);

End.

4.4.79 MinuteOf

Synopsis: Extract the minute part from a DateTime value.

Declaration: function MinuteOf(const AValue: TDateTime) : Word

Visibility: default

Description: MinuteOf returns the minute of the hour part of the AValue date/time indication. It is a number between 0 and 59.

For an example, see YearOf ([460](#))

See also: YearOf ([460](#)), WeekOf ([448](#)), MonthOf ([420](#)), DayOf ([382](#)), HourOf ([397](#)), SecondOf ([433](#)), MilliSecondOf ([412](#))

4.4.80 MinuteOfTheDay

Synopsis: Calculate the number of minutes elapsed since the start of the day

Declaration: function MinuteOfTheDay(const AValue: TDateTime) : Word

Visibility: default

Description: `MinuteOfDay` returns the number of minutes that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 will return 0.

For an example, see the `HourOfDay` (397) function.

See also: `MinuteOfYear` (418), `MinuteOfMonth` (417), `MinuteOfWeek` (418), `MinuteOfTheHour` (417), `HourOfDay` (397), `SecondOfDay` (433), `MilliSecondOfDay` (412)

4.4.81 MinuteOfTheHour

Synopsis: Calculate the number of minutes elapsed since the start of the hour

Declaration: `function MinuteOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheHour` returns the number of minutes that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:59 will return 0.

See also: `MinuteOfYear` (418), `MinuteOfMonth` (417), `MinuteOfWeek` (418), `MinuteOfDay` (416), `SecondOfTheHour` (433), `MilliSecondOfTheHour` (413)

Listing: `./datutex/ex44.pp`

Program Example44 ;

{ This program demonstrates the MinuteOfTheHour function }

Uses SysUtils , DateUtils ;

Var

N : TDateTime ;

Begin

N:=Now;

WriteLn('Minute of the Hour : ',MinuteOfTheHour(N));

WriteLn('Second of the Hour : ',SecondOfTheHour(N));

WriteLn('MilliSecond of the Hour : ',
MilliSecondOfTheHour(N));

End.

4.4.82 MinuteOfTheMonth

Synopsis: Calculate number of minutes elapsed since the start of the month.

Declaration: `function MinuteOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheMonth` returns the number of minutes that have passed since the start of the Month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (448) function.

See also: `WeekOfTheMonth` (448), `DayOfTheMonth` (382), `HourOfTheMonth` (397), `MinuteOfTheMonth` (417), `SecondOfTheMonth` (434), `MilliSecondOfTheMonth` (413)

4.4.83 MinuteOfTheWeek

Synopsis: Calculate the number of minutes elapsed since the start of the week

Declaration: `function MinuteOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheWeek` returns the number of minutes that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (382) function.

See also: `MinuteOfTheYear` (418), `MinuteOfTheMonth` (417), `MinuteOfTheDay` (416), `MinuteOfTheHour` (417), `DayOfTheWeek` (382), `HourOfTheWeek` (398), `SecondOfTheWeek` (434), `MilliSecondOfTheWeek` (414)

4.4.84 MinuteOfTheYear

Synopsis: Calculate the number of minutes elapsed since the start of the year

Declaration: `function MinuteOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MinuteOfTheYear` returns the number of minutes that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:59 will return 0.

For an example, see the `WeekOfTheYear` (449) function.

See also: `WeekOfTheYear` (449), `DayOfTheYear` (383), `HourOfTheYear` (398), `MinuteOfTheYear` (418), `SecondOfTheYear` (435), `MilliSecondOfTheYear` (414)

4.4.85 MinutesBetween

Synopsis: Calculate the number of whole minutes between two `DateTime` values.

Declaration: `function MinutesBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `MinutesBetween` returns the number of whole minutes between `ANow` and `AThen`. This means the fractional part of a minute (seconds, milliseconds etc.) is dropped.

See also: `YearsBetween` (461), `MonthsBetween` (421), `WeeksBetween` (450), `DaysBetween` (383), `HoursBetween` (398), `SecondsBetween` (435), `MillisecondsBetween` (415)

Listing: `./datutex/ex60.pp`

Program Example60;

{ This program demonstrates the MinutesBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

```

begin
  Write('Number of minutes between ');
  Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
  WriteLn(' : ', MinutesBetween(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Now;
  D2 := D1 - (59 * OneSecond);
  Test(D1, D2);
  D2 := D1 - (61 * OneSecond);
  Test(D1, D2);
  D2 := D1 - (122 * OneSecond);
  Test(D1, D2);
  D2 := D1 - (306 * OneSecond);
  Test(D1, D2);
  D2 := D1 - (5.4 * OneMinute);
  Test(D1, D2);
  D2 := D1 - (2.5 * OneMinute);
  Test(D1, D2);
End.

```

4.4.86 MinuteSpan

Synopsis: Calculate the approximate number of minutes between two DateTime values.

Declaration: `function MinuteSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: `MinuteSpan` returns the number of minutes between `ANow` and `AThen`, including any fractional parts of a minute.

See also: [YearSpan \(462\)](#), [MonthSpan \(422\)](#), [WeekSpan \(452\)](#), [DaySpan \(386\)](#), [HourSpan \(399\)](#), [SecondSpan \(436\)](#), [MilliSecondSpan \(415\)](#), [MinutesBetween \(418\)](#)

Listing: `./datutex/ex68.pp`

Program Example68;

{ This program demonstrates the MinuteSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

```

begin
  Write('Number of minutes between ');
  Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
  WriteLn(' : ', MinuteSpan(ANow, AThen));
end;

```

Var

D1,D2 : TDateTime;

Begin

```
D1:=Now;
D2:=D1-(59*OneSecond);
Test(D1,D2);
D2:=D1-(61*OneSecond);
Test(D1,D2);
D2:=D1-(122*OneSecond);
Test(D1,D2);
D2:=D1-(306*OneSecond);
Test(D1,D2);
D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);
```

End.

4.4.87 ModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a TDateTime value.

Declaration: `function ModifiedJulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(381\)](#), [JulianDateToDateTime \(411\)](#), [TryJulianDateToDateTime \(446\)](#), [DateTimeToModifiedJulianDate \(381\)](#), [TryModifiedJulianDateToDateTime \(446\)](#)

4.4.88 MonthOf

Synopsis: Extract the month from a given date.

Declaration: `function MonthOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOf` returns the month part of the `AValue` date/time indication. It is a number between 1 and 12.

For an example, see [YearOf \(460\)](#)

See also: [YearOf \(460\)](#), [DayOf \(382\)](#), [WeekOf \(448\)](#), [HourOf \(397\)](#), [MinuteOf \(416\)](#), [SecondOf \(433\)](#), [MilliSecondOf \(412\)](#)

4.4.89 MonthOfTheYear

Synopsis: Extract the month of a DateTime indication.

Declaration: `function MonthOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOfTheYear` extracts the month part of `Avalue` and returns it. It is an alias for `MonthOf` (420), and is provided for completeness only, corresponding to the other `PartOfTheYear` functions.

For an example, see the `WeekOfTheYear` (449) function.

See also: `MonthOf` (420), `WeekOfTheYear` (449), `DayOfTheYear` (383), `HourOfTheYear` (398), `MinuteOfTheYear` (418), `SecondOfTheYear` (435), `MilliSecondOfTheYear` (414)

4.4.90 MonthsBetween

Synopsis: Calculate the number of whole months between two `DateTime` values

Declaration: `function MonthsBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

Visibility: default

Description: `MonthsBetween` returns the number of whole months between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years). This means the fractional part of a month is dropped.

See also: `YearsBetween` (461), `WeeksBetween` (450), `DaysBetween` (383), `HoursBetween` (398), `MinutesBetween` (418), `SecondsBetween` (435), `MillisecondsBetween` (415)

Listing: `./datutex/ex56.pp`

Program `Example56`;

{ This program demonstrates the MonthsBetween function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime);`

begin

`Write('Number of months between ');`
`Write(DateToStr(AThen), ' and ', DateToStr(ANow));`
`WriteLn(' : ', MonthsBetween(ANow, AThen));`
end;

Var

`D1, D2 : TDateTime;`

Begin

`D1 := Today;`
`D2 := Today - 364;`
`Test(D1, D2);`
`D2 := Today - 365;`
`Test(D1, D2);`
`D2 := Today - 366;`
`Test(D1, D2);`
`D2 := Today - 390;`
`Test(D1, D2);`
`D2 := Today - 368;`
`Test(D1, D2);`
`D2 := Today - 1000;`
`Test(D1, D2);`

End.

4.4.91 MonthSpan

Synopsis: Calculate the approximate number of months between two `DateTime` values.

Declaration: `function MonthSpan(const ANow: TDateTime;const AThen: TDateTime)
: Double`

Visibility: default

Description: `MonthSpan` returns the number of month between `ANow` and `AThen`, including any fractional parts of a month. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years).

See also: `YearSpan` (462), `WeekSpan` (452), `DaySpan` (386), `HourSpan` (399), `MinuteSpan` (419), `SecondSpan` (436), `MilliSecondSpan` (415), `MonthsBetween` (421)

Listing: `./datutex/ex64.pp`

Program Example64;

{ This program demonstrates the MonthSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of months between ');

Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

WriteLn(' : ', MonthSpan(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Today;

 D2 := Today - 364;

 Test(D1, D2);

 D2 := Today - 365;

 Test(D1, D2);

 D2 := Today - 366;

 Test(D1, D2);

 D2 := Today - 390;

 Test(D1, D2);

 D2 := Today - 368;

 Test(D1, D2);

 D2 := Today - 1000;

 Test(D1, D2);

End.

4.4.92 NthDayOfWeek

Synopsis: Calculate which occurrence of weekday in the month a given day represents

Declaration: `function NthDayOfWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `NthDayOfWeek` returns the occurrence of the weekday of `AValue` in the month. This is the N-th time that this weekday occurs in the month (e.g. the third saturday of the month).

See also: `EncodeDateMonthWeek` ([391](#)), `#rtl.sysutils.DayOfWeek` ([1324](#)), `DecodeDayOfWeekInMonth` ([390](#)), `EncodeDayOfWeekInMonth` ([392](#)), `TryEncodeDayOfWeekInMonth` ([445](#))

Listing: `./datutex/ex104.pp`

Program `Example104`;

{ This program demonstrates the NthDayOfWeek function }

Uses `SysUtils` , `DateUtils` ;

Begin

`Write('Today is the ',NthDayOfWeek(Today),'-th ');`

`WriteLn(formatdateTime('dddd',Today),' of the month.');`

End.

4.4.93 PreviousDayOfWeek

Synopsis: Given a day of the week, return the previous day of the week.

Declaration: `function PreviousDayOfWeek(DayOfWeek: Word) : Word`

Visibility: `default`

Description: `PreviousDayOfWeek` returns the previous day of the week. If the current day is the first day of the week (1) then the last day will be returned (7).

Remark: Note that the days of the week are in ISO notation, i.e. 1-based.

See also: `Yesterday` ([463](#))

Listing: `./datutex/ex22.pp`

Program `Example22`;

{ This program demonstrates the PreviousDayOfWeek function }

Uses `SysUtils` , `DateUtils` ;

Var

`D : Word;`

Begin

`For D:=1 to 7 do`

`WriteLn('Previous day of ',D,' is : ',PreviousDayOfWeek(D));`

End.

4.4.94 RecodeDate

Synopsis: Replace date part of a `TDateTime` value with another date.

Declaration: `function RecodeDate(const AValue: TDateTime;const AYear: Word;
const AMonth: Word;const ADay: Word) : TDateTime`

Visibility: default

Description: `RecodeDate` replaces the date part of the timestamp `AValue` with the date specified in `AYear`, `AMonth`, `ADay`. All other parts (the time part) of the date/time stamp are left untouched.

Errors: If one of the `AYear`, `AMonth`, `ADay` values is not within a valid range then an `EConvertError` exception is raised.

See also: `RecodeYear` (430), `RecodeMonth` (428), `RecodeDay` (425), `RecodeHour` (426), `RecodeMinute` (427), `RecodeSecond` (428), `RecodeDate` (423), `RecodeTime` (429), `RecodeDateTime` (424)

Listing: `./datutex/ex94.pp`

Program `Example94`;

{ This program demonstrates the RecodeDate function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = 'dddd dd mmmm yyyy hh:nn:ss';`

Var

`S : AnsiString;`

Begin

`S:=FormatDateTime(Fmt,RecodeDate(Now,2001,1,1));`

`WriteLn('This moment on the first of the millenium : ',S);`

End.

4.4.95 RecodeDateTime

Synopsis: Replace selected parts of a `TDateTime` value with other values

Declaration: `function RecodeDateTime(const AValue: TDateTime;const AYear: Word;
const AMonth: Word;const ADay: Word;
const AHour: Word;const AMinute: Word;
const ASecond: Word;const AMilliSecond: Word)
: TDateTime`

Visibility: default

Description: `RecodeDateTime` replaces selected parts of the timestamp `AValue` with the date/time values specified in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`. If any of these values equals the pre-defined constant `RecodeLeaveFieldAsIs` (377), then the corresponding part of the date/time stamp is left untouched.

Errors: If one of the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond`, `AMilliSecond` is not within a valid range (`RecodeLeaveFieldAsIs` excepted) then an `EConvertError` exception is raised.

See also: `RecodeYear` (430), `RecodeMonth` (428), `RecodeDay` (425), `RecodeHour` (426), `RecodeMinute` (427), `RecodeSecond` (428), `RecodeMilliSecond` (426), `RecodeDate` (423), `RecodeTime` (429), `TryRecodeDateTime` (447)

Listing: `./datutex/ex96.pp`

Program Example96;

{ This program demonstrates the RecodeDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

D : TDateTime;

Begin

D:=Now;

D:=RecodeDateTime(D,2000,2,RecodeLeaveFieldAsIs,0,0,0,0);

S:=FormatDateTime(Fmt,D);

WriteIn('This moment in februari 2000 : ',S);

End.

4.4.96 RecodeDay

Synopsis: Replace day part of a TDateTime value with another day.

Declaration: function RecodeDay(const AValue: TDateTime;const ADay: Word) : TDateTime

Visibility: default

Description: RecodeDay replaces the Day part of the timestamp AValue with ADay. All other parts of the date/time stamp are left untouched.

Errors: If the ADay value is not within a valid range (1..12) then an EConvertError exception is raised.

See also: RecodeYear (430), RecodeMonth (428), RecodeHour (426), RecodeMinute (427), RecodeSecond (428), RecodeMilliSecond (426), RecodeDate (423), RecodeTime (429), RecodeDateTime (424)

Listing: ./datutex/ex89.pp

Program Example89;

{ This program demonstrates the RecodeDay function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

Begin

S:=FormatDateTime(Fmt,RecodeDay(Now,1));

WriteIn('This moment on the first of the month : ',S);

End.

4.4.97 RecodeHour

Synopsis: Replace hours part of a `TDateTime` value with another hour.

Declaration: `function RecodeHour(const AValue: TDateTime; const AHour: Word)
: TDateTime`

Visibility: default

Description: `RecodeHour` replaces the Hour part of the timestamp `AValue` with `AHour`. All other parts of the date/time stamp are left untouched.

Errors: If the `AHour` value is not within a valid range (0..23) then an `EConvertError` exception is raised.

See also: `RecodeYear` (430), `RecodeMonth` (428), `RecodeDay` (425), `RecodeMinute` (427), `RecodeSecond` (428), `RecodeMilliSecond` (426), `RecodeDate` (423), `RecodeTime` (429), `RecodeDateTime` (424)

Listing: `./datutex/ex90.pp`

Program Example90;

{ This program demonstrates the RecodeHour function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, **RecodeHour**(**Now**, 0));

WriteLn('Today, in the first hour : ', S);

End.

4.4.98 RecodeMilliSecond

Synopsis: Replace milliseconds part of a `TDateTime` value with another millisecond.

Declaration: `function RecodeMilliSecond(const AValue: TDateTime;
const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: `RecodeMilliSecond` replaces the millisecond part of the timestamp `AValue` with `AMilliSecond`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMilliSecond` value is not within a valid range (0..999) then an `EConvertError` exception is raised.

See also: `RecodeYear` (430), `RecodeMonth` (428), `RecodeDay` (425), `RecodeHour` (426), `RecodeMinute` (427), `RecodeSecond` (428), `RecodeDate` (423), `RecodeTime` (429), `RecodeDateTime` (424)

Listing: `./datutex/ex93.pp`

Program Example93;

{ This program demonstrates the RecodeMilliSecond function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Var

S : AnsiString;

Begin

S := **FormatDateTime**(Fmt, RecodeMilliSecond(**Now**, 0));

WriteIn('This moment, milliseconds stripped : ', S);

End.

4.4.99 RecodeMinute

Synopsis: Replace minutse part of a TDateTime value with another minute.

Declaration: function RecodeMinute(const AValue: TDateTime; const AMinute: Word)
: TDateTime

Visibility: default

Description: RecodeMinute replaces the Minute part of the timestamp AValue with AMinute. All other parts of the date/time stamp are left untouched.

Errors: If the AMinute value is not within a valid range (0..59) then an EConvertError exception is raised.

See also: RecodeYear (430), RecodeMonth (428), RecodeDay (425), RecodeHour (426), RecodeSecond (428), RecodeMilliSecond (426), RecodeDate (423), RecodeTime (429), RecodeDateTime (424)

Listing: ./datutex/ex91.pp

Program Example91;

{ This program demonstrates the RecodeMinute function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

Begin

S := **FormatDateTime**(Fmt, RecodeMinute(**Now**, 0));

WriteIn('This moment in the first minute of the hour : ', S);

End.

4.4.100 RecodeMonth

Synopsis: Replace month part of a `TDateTime` value with another month.

Declaration: `function RecodeMonth(const AValue: TDateTime; const AMonth: Word): TDateTime`

Visibility: default

Description: `RecodeMonth` replaces the Month part of the timestamp `AValue` with `AMonth`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMonth` value is not within a valid range (1..12) then an `EConvertError` exception is raised.

See also: `RecodeYear` (430), `RecodeDay` (425), `RecodeHour` (426), `RecodeMinute` (427), `RecodeSecond` (428), `RecodeMilliSecond` (426), `RecodeDate` (423), `RecodeTime` (429), `RecodeDateTime` (424)

Listing: `./datutex/ex88.pp`

Program Example88;

{ This program demonstrates the RecodeMonth function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, `RecodeMonth`(**Now**, 5));

WriteLn('This moment in May : ', S);

End.

4.4.101 RecodeSecond

Synopsis: Replace seconds part of a `TDateTime` value with another second.

Declaration: `function RecodeSecond(const AValue: TDateTime; const ASecond: Word): TDateTime`

Visibility: default

Description: `RecodeSecond` replaces the Second part of the timestamp `AValue` with `ASecond`. All other parts of the date/time stamp are left untouched.

Errors: If the `ASecond` value is not within a valid range (0..59) then an `EConvertError` exception is raised.

See also: `RecodeYear` (430), `RecodeMonth` (428), `RecodeDay` (425), `RecodeHour` (426), `RecodeMinute` (427), `RecodeMilliSecond` (426), `RecodeDate` (423), `RecodeTime` (429), `RecodeDateTime` (424)

Listing: `./datutex/ex92.pp`

Program Example92;

{ This program demonstrates the RecodeSecond function }

Uses SysUtils , DateUtils ;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss' ;

Var

 S : AnsiString ;

Begin

 S:=**FormatDateTime**(Fmt,RecodeSecond(**Now**,0));

WriteIn('This moment, seconds stripped : ',S);

End.

4.4.102 RecodeTime

Synopsis: Replace time part of a TDateTime value with another time.

Declaration: function RecodeTime(const AValue: TDateTime;const AHour: Word;
 const AMinute: Word;const ASecond: Word;
 const AMilliSecond: Word) : TDateTime

Visibility: default

Description: RecodeTime replaces the time part of the timestamp AValue with the date specified in AHour, AMinute, ASecond and AMilliSecond. All other parts (the date part) of the date/time stamp are left untouched.

Errors: If one of the values AHour, AMinute, ASecondAMilliSecond is not within a valid range then an EConvertError exception is raised.

See also: RecodeYear (430), RecodeMonth (428), RecodeDay (425), RecodeHour (426), RecodeMinute (427), RecodeSecond (428), RecodeMilliSecond (426), RecodeDate (423), RecodeDateTime (424)

Listing: ./datutex/ex95.pp

Program Example95;

{ This program demonstrates the RecodeTime function }

Uses SysUtils , DateUtils ;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss' ;

Var

 S : AnsiString ;

Begin

 S:=**FormatDateTime**(Fmt,RecodeTime(**Now**,8,0,0,0));

WriteIn('Today, 8 AM : ',S);

End.

4.4.103 RecodeYear

Synopsis: Replace year part of a `TDateTime` value with another year.

Declaration: `function RecodeYear(const AValue: TDateTime; const AYear: Word) : TDateTime`

Visibility: default

Description: `RecodeYear` replaces the year part of the timestamp `AValue` with `AYear`. All other parts of the date/time stamp are left untouched.

Errors: If the `AYear` value is not within a valid range (1..9999) then an `EConvertError` exception is raised.

See also: `RecodeMonth` (428), `RecodeDay` (425), `RecodeHour` (426), `RecodeMinute` (427), `RecodeSecond` (428), `RecodeMilliSecond` (426), `RecodeDate` (423), `RecodeTime` (429), `RecodeDateTime` (424)

Listing: `./datutex/ex87.pp`

Program Example87;

{ This program demonstrates the RecodeYear function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, **RecodeYear**(**Now**, 1999));

WriteIn('This moment in 1999 : ', S);

End.

4.4.104 SameDate

Synopsis: Check whether two `TDateTime` values have the same date part.

Declaration: `function SameDate(const A: TDateTime; const B: TDateTime) : Boolean`

Visibility: default

Description: `SameDate` compares the date parts of two timestamps `A` and `B` and returns `True` if they are equal, `False` if they are not.

The function simply checks whether `CompareDate` (377) returns zero.

See also: `CompareDateTime` (378), `CompareDate` (377), `CompareTime` (379), `SameDateTime` (431), `SameTime` (432)

Listing: `./datutex/ex102.pp`

Program Example102;

{ This program demonstrates the SameDate function }

Uses SysUtils , DateUtils ;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz' ;

Procedure Test(D1,D2 : TDateTime);

begin

 Write(FormatDateTime(Fmt,D1), ' is the same date as ');

 WriteIn(FormatDateTime(Fmt,D2), ' : ', SameDate(D1,D2));

end;

Var

 D,N : TDateTime;

Begin

 D:=Today;

 N:=Now;

 Test(D,D);

 Test(N,N);

 Test(N+1,N);

 Test(N-1,N);

 Test(N+OneSecond,N);

 Test(N-OneSecond,N);

End.

4.4.105 SameDateTime

Synopsis: Check whether two TDateTime values have the same date and time parts.

Declaration: function SameDateTime(const A: TDateTime;const B: TDateTime) : Boolean

Visibility: default

Description: SameDateTime compares the date/time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDateTime (378) returns zero.

See also: CompareDateTime (378), CompareDate (377), CompareTime (379), SameDate (430), SameTime (432)

Listing: ./datutex/ex101.pp

Program Example101;

{ This program demonstrates the SameDateTime function }

Uses SysUtils , DateUtils ;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz' ;

Procedure Test(D1,D2 : TDateTime);

begin

 Write(FormatDateTime(Fmt,D1), ' is the same datetime as ');

 WriteIn(FormatDateTime(Fmt,D2), ' : ', SameDateTime(D1,D2));

```

end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(N+1,N);
  Test(N-1,N);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

4.4.106 SameTime

Synopsis: Check whether two TDateTime values have the same time part.

Declaration: `function SameTime(const A: TDateTime;const B: TDateTime) : Boolean`

Visibility: default

Description: SameTime compares the time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareTime (379) returns zero.

See also: CompareDateTime (378), CompareDate (377), CompareTime (379), SameDateTime (431), SameDate (430)

Listing: ./datutex/ex103.pp

Program Example102;

{ This program demonstrates the SameTime function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

begin

 Write(FormatDateTime(Fmt,D1), ' is the same time as ');

 WriteLn(FormatDateTime(Fmt,D2), ' : ', SameTime(D1,D2));

end;

Var

 D,N : TDateTime;

Begin

 D:=Today;

 N:=Now;

 Test(D,D);

 Test(N,N);

```

Test(N+1,N);
Test(N-1,N);
Test(N+OneSecond,N);
Test(N-OneSecond,N);
End.
```

4.4.107 SecondOf

Synopsis: Extract the second part from a DateTime value.

Declaration: `function SecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see `YearOf` (460)

See also: `YearOf` (460), `WeekOf` (448), `MonthOf` (420), `DayOf` (382), `HourOf` (397), `MinuteOf` (416), `MilliSecondOf` (412)

4.4.108 SecondOfDay

Synopsis: Calculate the number of seconds elapsed since the start of the day

Declaration: `function SecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfDay` returns the number of seconds that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 return 0.

For an example, see the `HourOfDay` (397) function.

See also: `SecondOfTheYear` (435), `SecondOfTheMonth` (434), `SecondOfTheWeek` (434), `SecondOfTheHour` (433), `SecondOfTheMinute` (434), `HourOfDay` (397), `MinuteOfDay` (416), `MilliSecondOfTheDay` (412)

4.4.109 SecondOfTheHour

Synopsis: Calculate the number of seconds elapsed since the start of the hour

Declaration: `function SecondOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheHour` returns the number of seconds that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.999 return 0.

For an example, see the `MinuteOfTheHour` (417) function.

See also: `SecondOfTheYear` (435), `SecondOfTheMonth` (434), `SecondOfTheWeek` (434), `SecondOfTheDay` (433), `SecondOfTheMinute` (434), `MinuteOfTheHour` (417), `MilliSecondOfTheHour` (413)

4.4.110 SecondOfTheMinute

Synopsis: Calculate the number of seconds elapsed since the start of the minute

Declaration: `function SecondOfTheMinute(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheMinute` returns the number of seconds that have passed since the start of the minute (HH:MM:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.999 return 0.

See also: `SecondOfTheYear` (435), `SecondOfTheMonth` (434), `SecondOfTheWeek` (434), `SecondOfTheDay` (433), `SecondOfTheHour` (433), `MilliSecondOfTheMinute` (413)

Listing: `./datutex/ex45.pp`

Program Example45;

{ This program demonstrates the SecondOfTheMinute function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Second of the Minute : ',SecondOfTheMinute(N));

WriteLn('MilliSecond of the Minute : ',
MilliSecondOfTheMinute(N));

End.

4.4.111 SecondOfTheMonth

Synopsis: Calculate number of seconds elapsed since the start of the month.

Declaration: `function SecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheMonth` returns the number of seconds that have passed since the start of the month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (448) function.

See also: `WeekOfTheMonth` (448), `DayOfTheMonth` (382), `HourOfTheMonth` (397), `MinuteOfTheMonth` (417), `MilliSecondOfTheMonth` (413)

4.4.112 SecondOfTheWeek

Synopsis: Calculate the number of seconds elapsed since the start of the week

Declaration: `function SecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheWeek` returns the number of seconds that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (382) function.

See also: `SecondOfTheYear` (435), `SecondOfTheMonth` (434), `SecondOfTheDay` (433), `SecondOfTheHour` (433), `SecondOfTheMinute` (434), `DayOfTheWeek` (382), `HourOfTheWeek` (398), `MinuteOfTheWeek` (418), `MilliSecondOfTheWeek` (414)

4.4.113 `SecondOfTheYear`

Synopsis: Calculate the number of seconds elapsed since the start of the year.

Declaration: `function SecondOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheYear` returns the number of seconds that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.999 will return 0.

For an example, see the `WeekOfTheYear` (449) function.

See also: `WeekOfTheYear` (449), `DayOfTheYear` (383), `HourOfTheYear` (398), `MinuteOfTheYear` (418), `SecondOfTheYear` (435), `MilliSecondOfTheYear` (414)

4.4.114 `SecondsBetween`

Synopsis: Calculate the number of whole seconds between two `DateTime` values.

Declaration: `function SecondsBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `SecondsBetween` returns the number of whole seconds between `ANow` and `AThen`. This means the fractional part of a second (milliseconds etc.) is dropped.

See also: `YearsBetween` (461), `MonthsBetween` (421), `WeeksBetween` (450), `DaysBetween` (383), `HoursBetween` (398), `MinutesBetween` (418), `MilliSecondsBetween` (415)

Listing: `./datutex/ex61.pp`

Program `Example61` ;

{ This program demonstrates the SecondsBetween function }

Uses `SysUtils` , `DateUtils` ;

Procedure `Test` (`ANow`, `AThen` : `TDateTime`) ;

begin

Write ('Number of seconds between ');
 Write (`TimeToStr` (`AThen`) , ' and ' , `TimeToStr` (`ANow`));
 WriteLn (' : ' , `SecondsBetween` (`ANow`, `AThen`));
end ;

Var


```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(999*OneMilliSecond);
Test(D1,D2);
D2:=D1-(1001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(2001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5.4*OneSecond);
Test(D1,D2);
D2:=D1-(2.5*OneSecond);
Test(D1,D2);
```

End.

4.4.115 SecondSpan

Synopsis: Calculate the approximate number of seconds between two DateTime values.

Declaration: `function SecondSpan(const ANow: TDateTime;const AThen: TDateTime)
: Double`

Visibility: default

Description: `SecondSpan` returns the number of seconds between `ANow` and `AThen`, including any fractional parts of a second.

See also: `YearSpan` ([462](#)), `MonthSpan` ([422](#)), `WeekSpan` ([452](#)), `DaySpan` ([386](#)), `HourSpan` ([399](#)), `MinuteSpan` ([419](#)), `MilliSecondSpan` ([415](#)), `SecondsBetween` ([435](#))

Listing: ./datutex/ex69.pp

Program Example69;

```
{ This program demonstrates the SecondSpan function }
```

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```
Write('Number of seconds between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', SecondSpan(ANow, AThen));
end;
```

Var

```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(999*OneMilliSecond);
Test(D1,D2);
D2:=D1-(1001*OneMilliSecond);
```

```

Test(D1,D2);
D2:=D1-(2001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5.4*OneSecond);
Test(D1,D2);
D2:=D1-(2.5*OneSecond);
Test(D1,D2);
End.

```

4.4.116 StartOfDay

Synopsis: Return the start of a day as a DateTime value, given a day indication

Declaration:

```

function StartOfDay(const AYear: Word;const AMonth: Word;
                    const ADay: Word) : TDateTime; Overload
function StartOfDay(const AYear: Word;const ADayOfYear: Word)
                    : TDateTime; Overload

```

Visibility: default

Description: StartOfDay returns a TDateTime value with the date/time indication of the start (0:0:0.000) of the day given by AYear, AMonth, ADay.

The day may also be indicated with a AYear, ADayOfYear pair.

See also: StartOfDay (439), StartOfTheWeek (440), StartOfAWeek (438), StartOfAMonth (438), StartOfTheMonth (440), EndOfTheWeek (396), EndOfAWeek (393), EndOfTheYear (396), EndOfAYear (394), EndOfTheMonth (395), EndOfAMonth (393), EndOfTheDay (394), EndOfDay (392)

Listing: ./datutex/ex38.pp

Program Example38;

```
{ This program demonstrates the StartOfDay function }
```

Uses SysUtils, DateUtils;

Const

```
Fmt = ' "Start of the day : " dd mmm yyyy hh:nn:ss ';
```

Var

```
Y,M,D : Word;
```

Begin

```
Y:=YearOf(Today);
```

```
M:=MonthOf(Today);
```

```
D:=DayOf(Today);
```

```
WriteLn(FormatDateTime(Fmt, StartOfDay(Y,M,D)));
```

```
DecodeDateDay(Today,Y,D);
```

```
WriteLn(FormatDateTime(Fmt, StartOfDay(Y,D)));
```

End.

4.4.117 StartOfAMonth

Synopsis: Return first date of month, given a year/month pair.

Declaration: `function StartOfAMonth(const AYear: Word;const AMonth: Word) : TDateTime`

Visibility: default

Description: `StartOfAMonth` returns a `TDateTime` value with the date of the first day of the month indicated by the `AYear`, `AMonth` pair.

See also: `StartOfTheMonth` (440), `EndOfTheMonth` (395), `EndOfAMonth` (393), `EndOfTheYear` (396), `EndOfAYear` (394), `StartOfAWeek` (438), `StartOfTheWeek` (440)

Listing: `./datutex/ex30.pp`

Program Example30;

{ This program demonstrates the StartOfAMonth function }

Uses SysUtils, DateUtils;

Const

 Fmt = ' "First day of this month : "dd mmm yyyy ';

Var

 Y,M : Word;

Begin

 Y:=YearOf(Today);

 M:=MonthOf(Today);

 WriteLn(FormatDateTime(Fmt, StartOfAMonth(Y,M)));

End.

4.4.118 StartOfAWeek

Synopsis: Return a day of the week, given a year, week and day in the week.

Declaration: `function StartOfAWeek(const AYear: Word;const AWeekOfYear: Word;
 const ADayOfWeek: Word) : TDateTime`
`function StartOfAWeek(const AYear: Word;const AWeekOfYear: Word)
 : TDateTime`

Visibility: default

Description: `StartOfAWeek` returns a `TDateTime` value with the date of the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 1.

See also: `StartOfTheWeek` (440), `EndOfTheWeek` (396), `EndOfAWeek` (393), `StartOfAMonth` (438), `EndOfTheYear` (396), `EndOfAYear` (394), `EndOfTheMonth` (395), `EndOfAMonth` (393)

Listing: `./datutex/ex34.pp`

Program Example34;

{ This program demonstrates the StartOfAWeek function }

Uses SysUtils, DateUtils;

```

Const
  Fmt = '"First day of this week : "dd mmm yyyy hh:nn:ss';
  Fmt2 = '"Second day of this week : "dd mmm yyyy hh:nn:ss';

Var
  Y,W : Word;

Begin
  Y:=YearOf(Today);
  W:=WeekOf(Today);
  WriteIn (FormatDateTime (Fmt , StartOfAWeek (Y,W) ));
  WriteIn (FormatDateTime (Fmt2 , StartOfAWeek (Y,W,2) ));
End.

```

4.4.119 StartOfAYear

Synopsis: Return the first day of a given year.

Declaration: `function StartOfAYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAYear` returns a `TDateTime` value with the date of the first day of the year `AYear` (January 1).

See also: `StartOfTheYear` ([441](#)), `EndOfTheYear` ([396](#)), `EndOfAYear` ([394](#)), `EndOfTheMonth` ([395](#)), `EndOfA-Month` ([393](#)), `StartOfAWeek` ([438](#)), `StartOfTheWeek` ([440](#))

Listing: `./datutex/ex26.pp`

Program Example26;

{ This program demonstrates the StartOfAYear function }

Uses SysUtils , DateUtils ;

```

Const
  Fmt = '"First day of this year : "dd mmm yyyy';

Begin
  WriteIn (FormatDateTime (Fmt , StartOfAYear (YearOf(Today) )));
End.

```

4.4.120 StartOfTheDay

Synopsis: Calculate the start of the day as a `DateTime` value, given a moment in the day.

Declaration: `function StartOfTheDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `StartOfTheDay` extracts the date part of `AValue` and returns a `TDateTime` value with the date/time indication of the start (0:0:0.000) of this day.

See also: [StartOfADay \(437\)](#), [StartOfTheWeek \(440\)](#), [StartOfAWeek \(438\)](#), [StartOfAMonth \(438\)](#), [StartOfTheMonth \(440\)](#), [EndOfTheWeek \(396\)](#), [EndOfAWeek \(393\)](#), [EndOfTheYear \(396\)](#), [EndOfAYear \(394\)](#), [EndOfTheMonth \(395\)](#), [EndOfAMonth \(393\)](#), [EndOftheDay \(394\)](#), [EndOfADay \(392\)](#)

Listing: ./datutex/ex36.pp

Program Example36;

{ This program demonstrates the StartOfTheDay function }

Uses SysUtils, DateUtils;

Const

Fmt = 'Start of the day : "dd mmm yyyy hh:nn:ss';

Begin

WriteIn (FormatDateTime (Fmt, StartOfTheDay (Today)));

End.

4.4.121 StartOfTheMonth

Synopsis: Calculate the first day of the month, given a date in that month.

Declaration: function StartOfTheMonth(const AValue: TDateTime) : TDateTime

Visibility: default

Description: StartOfTheMonth extracts the year and month parts of AValue and returns a TDateTime value with the date of the first day of that year and month as the StartOfAMonth ([438](#)) function.

See also: [StartOfAMonth \(438\)](#), [EndOfTheYear \(396\)](#), [EndOfAYear \(394\)](#), [EndOfTheMonth \(395\)](#), [EndOfAMonth \(393\)](#), [StartOfAWeek \(438\)](#), [StartOfTheWeek \(440\)](#)

Listing: ./datutex/ex28.pp

Program Example28;

{ This program demonstrates the StartOfTheMonth function }

Uses SysUtils, DateUtils;

Const

Fmt = 'First day of this month : "dd mmm yyyy';

Begin

WriteIn (FormatDateTime (Fmt, StartOfTheMonth (Today)));

End.

4.4.122 StartOfTheWeek

Synopsis: Return the first day of the week, given a date.

Declaration: function StartOfTheWeek(const AValue: TDateTime) : TDateTime

Visibility: default

Description: `StartOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the first day of that week as the `StartOfAWeek` (438) function.

See also: `StartOfAWeek` (438), `EndOfTheWeek` (396), `EndOfAWeek` (393), `StartOfAMonth` (438), `EndOfTheYear` (396), `EndOfAYear` (394), `EndOfTheMonth` (395), `EndOfAMonth` (393)

Listing: `./datutex/ex32.pp`

Program `Example32`;

{ This program demonstrates the StartOfTheWeek function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = ' "First day of this week : "dd mmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, StartOfTheWeek (Today)));`

End.

4.4.123 StartOfTheYear

Synopsis: Return the first day of the year, given a date in this year.

Declaration: `function StartOfTheYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `StartOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the first day of that year (January 1), as the `StartOfAYear` (439) function.

See also: `StartOfAYear` (439), `EndOfTheYear` (396), `EndOfAYear` (394)

Listing: `./datutex/ex24.pp`

Program `Example24`;

{ This program demonstrates the StartOfTheYear function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = ' "First day of this year : "dd mmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, StartOfTheYear (Today)));`

End.

4.4.124 TimeOf

Synopsis: Extract the time part from a `DateTime` indication.

Declaration: `function TimeOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `TimeOf` extracts the time part from `AValue` and returns the result.

Since the `TDateTime` is actually a double with the time part encoded in the fractional part, this operation corresponds to a call to `Frac`.

See also: `DateOf` ([380](#)), `YearOf` ([460](#)), `MonthOf` ([420](#)), `DayOf` ([382](#)), `HourOf` ([397](#)), `MinuteOf` ([416](#)), `SecondOf` ([433](#)), `MillisecondOf` ([412](#))

Listing: `./datutex/ex2.pp`

Program `Example2`;

{ This program demonstrates the TimeOf function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('Time is : ', TimeToStr(TimeOf(Now)));`
End.

4.4.125 Today

Synopsis: Return the current date

Declaration: `function Today : TDateTime`

Visibility: `default`

Description: `Today` is an alias for the `Date` ([1320](#)) function in the `sysutils` ([1278](#)) unit.

For an example, see `Yesterday` ([463](#))

See also: `#rtl.sysutils.Date` ([1320](#)), `Yesterday` ([463](#)), `Tomorrow` ([442](#))

4.4.126 Tomorrow

Synopsis: Return the next day

Declaration: `function Tomorrow : TDateTime`

Visibility: `default`

Description: `Tomorrow` returns tomorrow's date. `Tomorrow` is determined from the system clock, i.e. it is `Today` ([442](#)) +1.

See also: `Today` ([442](#)), `Yesterday` ([463](#))

Listing: `./datutex/ex19.pp`

Program `Example19`;

{ This program demonstrates the Tomorrow function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn(FormatDateTime('"Today is" dd mmm yyyy', Today));`
`WriteLn(FormatDateTime('"Tomorrow will be" dd mmm yyyy', Tomorrow));`
End.

4.4.127 TryEncodeDateDay

Synopsis: Encode a year and day of year to a TDateTime value

Declaration: `function TryEncodeDateDay(const AYear: Word;const ADayOfYear: Word;
var AValue: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeDateDay encodes the values AYear and ADayOfYear to a date value and returns this value in AValue.

If the encoding was successful, True is returned. False is returned if any of the arguments is not valid.

See also: EncodeDateDay (390), EncodeDateTime (391), EncodeDateMonthWeek (391), EncodeDateWeek (391), TryEncodeDateTime (444), TryEncodeDateMonthWeek (443), TryEncodeDateWeek (445)

Listing: ./datutex/ex84.pp

Program Example84;

{ This program demonstrates the TryEncodeDateDay function }

Uses SysUtils, DateUtils;

Var

Y, DoY : Word;
TS : TDateTime;

Begin

DecodeDateDay(**Now**, Y, DoY);
If TryEncodeDateDay(Y, DoY, TS) **then**
 WriteLn('Today is : ', **DateToStr**(TS))
else
 WriteLn('Wrong year/day of year indication ');

End.

4.4.128 TryEncodeDateMonthWeek

Synopsis: Encode a year, month, week of month and day of week to a TDateTime value

Declaration: `function TryEncodeDateMonthWeek(const AYear: Word;const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word;
var AValue: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeDateMonthWeek encodes the values AYear, AMonth, AWeekOfMonth, ADayOfWeek, to a date value and returns this value in AValue.

If the encoding was successful, True is returned, False if any of the arguments is not valid.

See also: DecodeDateMonthWeek (388), EncodeDateTime (391), EncodeDateWeek (391), EncodeDateDay (390), EncodeDateMonthWeek (391), TryEncodeDateTime (444), TryEncodeDateWeek (445), TryEncodeDateDay (443), NthDayOfWeek (422)

Listing: ./datutex/ex86.pp

Program Example86;

{ This program demonstrates the TryEncodeDateMonthWeek function }

Uses SysUtils, DateUtils;

Var

Y,M,WoM,Dow : Word;
TS : TDateTime;

Begin

DecodeDateMonthWeek(**Now**,Y,M,WoM,Dow);
If TryEncodeDateMonthWeek(Y,M,WoM,Dow,TS) **then**
 WriteLn('Today is : ',**DateToStr**(TS))
else
 WriteLn('Invalid year/month/week/dow indication');

End.

4.4.129 TryEncodeDateTime

Synopsis: Encode a Year, Month, Day, Hour, minute, seconds, milliseconds tuple to a TDateTime value

Declaration: function TryEncodeDateTime(const AYear: Word;const AMonth: Word;
 const ADay: Word;const AHour: Word;
 const AMinute: Word;const ASecond: Word;
 const AMilliSecond: Word;
 var AValue: TDateTime) : Boolean

Visibility: default

Description: EncodeDateTime encodes the values AYearAMonth, ADay,AHour, AMinute,ASecond and AMilliSecond to a date/time value and returns this value in AValue.

If the date was encoded successfully, True is returned, False is returned if one of the arguments is not valid.

See also: EncodeDateTime (391), EncodeDateMonthWeek (391), EncodeDateWeek (391), EncodeDateDay (390), TryEncodeDateDay (443), TryEncodeDateWeek (445), TryEncodeDateMonthWeek (443)

Listing: ./datutex/ex80.pp

Program Example79;

{ This program demonstrates the TryEncodeDateTime function }

Uses SysUtils, DateUtils;

Var

Y,Mo,D,H,Mi,S,MS : Word;
TS : TDateTime;

Begin

DecodeDateTime(**Now**,Y,Mo,D,H,Mi,S,MS);
If TryEncodeDateTime(Y,Mo,D,H,Mi,S,MS,TS) **then**
 WriteLn('Now is : ',**DateTimeToStr**(TS))
else
 WriteLn('Wrong date/time indication');

End.

4.4.130 TryEncodeDateWeek

Synopsis: Encode a year, week and day of week triplet to a TDateTime value

Declaration:

```
function TryEncodeDateWeek(const AYear: Word;const AWeekOfYear: Word;
                           var AValue: TDateTime;const ADayOfWeek: Word)
                           : Boolean
function TryEncodeDateWeek(const AYear: Word;const AWeekOfYear: Word;
                           var AValue: TDateTime) : Boolean
```

Visibility: default

Description: TryEncodeDateWeek encodes the values AYear, AWeekOfYear and ADayOfWeek to a date value and returns this value in AValue.

If the encoding was successful, True is returned. False is returned if any of the arguments is not valid.

See also: EncodeDateMonthWeek (391), EncodeDateWeek (391), EncodeDateTime (391), EncodeDateDay (390), TryEncodeDateTime (444), TryEncodeDateMonthWeek (443), TryEncodeDateDay (443)

Listing: ./datutex/ex82.pp

Program Example82;

{ This program demonstrates the TryEncodeDateWeek function }

Uses SysUtils , DateUtils ;

Var

Y,W,Dow : Word;
TS : TDateTime;

Begin

DecodeDateWeek(**Now**,Y,W,Dow);
If TryEncodeDateWeek(Y,W,TS,Dow) **then**
 WriteLn('Today is : ',DateToStr(TS))
else
 WriteLn('Invalid date/week indication');

End.

4.4.131 TryEncodeDayOfWeekInMonth

Synopsis: Encode a year, month, week, day of week triplet to a TDateTime value

Declaration:

```
function TryEncodeDayOfWeekInMonth(const AYear: Word;const AMonth: Word;
                                   const ANthDayOfWeek: Word;
                                   const ADayOfWeek: Word;
                                   var AValue: TDateTime) : Boolean
```

Visibility: default

Description: `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result in `AValue`.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

The function returns `True` if the encoding was succesful, `False` if any of the values is not in range.

See also: `NthDayOfWeek` (422), `EncodeDateMonthWeek` (391), `#rtl.sysutils.DayOfWeek` (1324), `DecodeDayOfWeekInMonth` (390), `EncodeDayOfWeekInMonth` (392)

Listing: `./datutex/ex106.pp`

Program `Example105`;

{ This program demonstrates the `DecodeDayOfWeekInMonth` function }

Uses `SysUtils`, `DateUtils`;

Var

`Y,M,NDoW,DoW` : `Word`;

`D` : `TDateTime`;

Begin

`DecodeDayOfWeekInMonth (Date , Y,M,NDoW,DoW)` ;

If `TryEncodeDayOfWeekInMonth (Y,M,NDoW,DoW,D)` **then**

begin

Write (`DateToStr(D)` , ' is the ', `NDoW`, ' -th ');

WriteLn (`formatdateTime ('dddd',D)` , ' of the month. ');

end

else

WriteLn ('Invalid year/month/NthDayOfWeek combination');

End.

4.4.132 TryJulianDateToDateTime

Synopsis: Convert a Julian date representation to a `TDateTime` value.

Declaration: `function TryJulianDateToDateTime(const AValue: Double;`
`var ADateTime: TDateTime)` : `Boolean`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: `DateTimeToJulianDate` (381), `JulianDateToDateTime` (411), `DateTimeToModifiedJulianDate` (381), `TryModifiedJulianDateToDateTime` (446)

4.4.133 TryModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a `TDateTime` value.

Declaration: `function TryModifiedJulianDateToDateTime(const AValue: Double;`
`var ADateTime: TDateTime)`
: `Boolean`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(381\)](#), [JulianDateToDateTime \(411\)](#), [TryJulianDateToDateTime \(446\)](#), [DateTimeToModifiedJulianDate \(381\)](#), [ModifiedJulianDateToDateTime \(420\)](#)

4.4.134 TryRecodeDateTime

Synopsis: Replace selected parts of a `TDateTime` value with other values

Declaration:

```
function TryRecodeDateTime(const AValue: TDateTime; const AYear: Word;
                           const AMonth: Word; const ADay: Word;
                           const AHour: Word; const AMinute: Word;
                           const ASecond: Word; const AMilliSecond: Word;
                           var AResult: TDateTime) : Boolean
```

Visibility: default

Description: `TryRecodeDateTime` replaces selected parts of the timestamp `AValue` with the date/time values specified in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`. If any of these values equals the pre-defined constant `RecodeLeaveFieldAsIs (377)`, then the corresponding part of the date/time stamp is left untouched.

The resulting date/time is returned in `AValue`.

The function returns `True` if the encoding was succesful. It returns `False` if one of the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` or `AMilliSecond` is not within a valid range.

See also: [RecodeYear \(430\)](#), [RecodeMonth \(428\)](#), [RecodeDay \(425\)](#), [RecodeHour \(426\)](#), [RecodeMinute \(427\)](#), [RecodeSecond \(428\)](#), [RecodeMilliSecond \(426\)](#), [RecodeDate \(423\)](#), [RecodeTime \(429\)](#), [RecodeDateTime \(424\)](#)

Listing: `./datutex/ex97.pp`

Program `Example97`;

{ This program demonstrates the TryRecodeDateTime function }

Uses `SysUtils, DateUtils`;

Const

`Fmt = 'dddd dd mmm yyyy hh:nn:ss';`

Var

`S : AnsiString;`

`D : TDateTime;`

Begin

`If TryRecodeDateTime(Now, 2000, 2, RecodeLeaveFieldAsIs, 0, 0, 0, 0, D) then`
`begin`
`S := FormatDateTime(Fmt, D);`
`WriteLn('This moment in february 2000 : ', S);`
`end`

`else`

`WriteLn('This moment did/does not exist in february 2000');`

End.

4.4.135 UnixTimeStampToMac

Synopsis: Convert Unix Timestamp to a Mac Timestamp

Declaration: `function UnixTimeStampToMac(const AValue: Int64) : Int64`

Visibility: default

Description: `UnixTimeStampToMac` converts the unix epoch time in `AValue` to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: `DateTimeToMac` ([381](#)), `MacToDateTime` ([412](#)), `MacTimeStampToUnix` ([412](#))

4.4.136 UnixToDateTime

Synopsis: Convert Unix epoch time to a `TDateTime` value

Declaration: `function UnixToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: `DateTimeToUnix` ([382](#))

4.4.137 WeekOf

Synopsis: Extract week (of the year) from a given date.

Declaration: `function WeekOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeekOf` returns the week-of-the-year part of the `AValue` date/time indication. It is a number between 1 and 53.

For an example, see `YearOf` ([460](#))

See also: `YearOf` ([460](#)), `DayOf` ([382](#)), `MonthOf` ([420](#)), `HourOf` ([397](#)), `MinuteOf` ([416](#)), `SecondOf` ([433](#)), `MilliSecondOf` ([412](#))

4.4.138 WeekOfTheMonth

Synopsis: Extract the week of the month (and optionally month and year) from a `DateTime` value

Declaration: `function WeekOfTheMonth(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheMonth(const AValue: TDateTime; var AYear: Word;`
`var AMonth: Word) : Word; Overload`

Visibility: default

Description: `WeekOfTheMonth` extracts the week of the month from `AValue` and returns it, and optionally returns the year and month as well (in `AYear`, `AMonth` respectively).

Remark: Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year and month may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: [WeekOfTheYear \(449\)](#), [DayOfTheMonth \(382\)](#), [HourOfTheMonth \(397\)](#), [MinuteOfTheMonth \(417\)](#), [SecondOfTheMonth \(434\)](#), [MilliSecondOfTheMonth \(413\)](#)

Listing: ./datutex/ex41.pp

Program Example41 ;

{ This program demonstrates the WeekOfTheMonth function }

Uses SysUtils , DateUtils ;

Var

N : TDateTime ;

Begin

N:=Now;

WriteLn ('Week of the Month : ', WeekOfTheMonth(N));

WriteLn ('Day of the Month : ', DayOfTheMonth(N));

WriteLn ('Hour of the Month : ', HourOfTheMonth(N));

WriteLn ('Minute of the Month : ', MinuteOfTheMonth(N));

WriteLn ('Second of the Month : ', SecondOfTheMonth(N));

WriteLn ('MilliSecond of the Month : ',
MilliSecondOfTheMonth(N));

End.

4.4.139 WeekOfTheYear

Synopsis: Extract the week of the year (and optionally year) of a DateTime indication.

Declaration: function WeekOfTheYear(const AValue: TDateTime) : Word; Overload
function WeekOfTheYear(const AValue: TDateTime; var AYear: Word) : Word
; Overload

Visibility: default

Description: WeekOfTheYear extracts the week of the year from AValue and returns it, and optionally returns the year as well. It returns the same value as WeekOf ([448](#)).

Remark: Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: [WeekOf \(448\)](#), [MonthOfTheYear \(420\)](#), [DayOfTheYear \(383\)](#), [HourOfTheYear \(398\)](#), [MinuteOfTheYear \(418\)](#), [SecondOfTheYear \(435\)](#), [MilliSecondOfTheYear \(414\)](#)

Listing: ./datutex/ex40.pp

Program Example40 ;

{ This program demonstrates the WeekOfTheYear function }

Uses SysUtils , DateUtils ;

Var

N : TDateTime ;

Begin

N:=Now;

```

WriteLn ( 'Month of the year      : ', MonthOfTheYear(N));
WriteLn ( 'Week of the year       : ', WeekOfTheYear(N));
WriteLn ( 'Day of the year        : ', DayOfTheYear(N));
WriteLn ( 'Hour of the year       : ', HourOfTheYear(N));
WriteLn ( 'Minute of the year     : ', MinuteOfTheYear(N));
WriteLn ( 'Second of the year    : ', SecondOfTheYear(N));
WriteLn ( 'MilliSecond of the year : ',
          MilliSecondOfTheYear(N));
End.

```

4.4.140 WeeksBetween

Synopsis: Calculate the number of whole weeks between two `DateTime` values

Declaration: `function WeeksBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

Visibility: default

Description: `WeeksBetween` returns the number of whole weeks between `ANow` and `AThen`. This means the fractional part of a Week is dropped.

See also: `YearsBetween` (461), `MonthsBetween` (421), `DaysBetween` (383), `HoursBetween` (398), `MinutesBetween` (418), `SecondsBetween` (435), `MillisecondsBetween` (415)

Listing: `./datutex/ex57.pp`

Program Example57;

{ This program demonstrates the WeeksBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write ('Number of weeks between ');

Write (**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

WriteLn (' : ', WeeksBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Today;

 D2 := Today - 7;

 Test(D1, D2);

 D2 := Today - 8;

 Test(D1, D2);

 D2 := Today - 14;

 Test(D1, D2);

 D2 := Today - 35;

 Test(D1, D2);

 D2 := Today - 36;

 Test(D1, D2);

 D2 := Today - 17;

```
Test(D1,D2);
End.
```

4.4.141 WeeksInAYear

Synopsis: Return the number of weeks in a given year

Declaration: `function WeeksInAYear(const AYear: Word) : Word`

Visibility: default

Description: `WeeksInAYear` returns the number of weeks in the year `AYear`. The return value is either 52 or 53.

Remark: The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: `WeeksInYear` ([451](#)), `DaysInYear` ([386](#)), `DaysInAYear` ([385](#)), `DaysInMonth` ([385](#)), `DaysInAMonth` ([384](#))

Listing: `./datutex/ex13.pp`

Program `Example13;`

{ This program demonstrates the WeeksInAYear function }

Uses `SysUtils, DateUtils;`

Var
`Y : Word;`

Begin
`For Y:=1992 to 2010 do`
`Writeln(Y, ' has ', WeeksInAYear(Y), ' weeks. ');`
End.

4.4.142 WeeksInYear

Synopsis: return the number of weeks in the year, given a date

Declaration: `function WeeksInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeeksInYear` returns the number of weeks in the year part of `AValue`. The return value is either 52 or 53.

Remark: The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: `WeeksInAYear` ([451](#)), `DaysInYear` ([386](#)), `DaysInAYear` ([385](#)), `DaysInMonth` ([385](#)), `DaysInAMonth` ([384](#))

Listing: `./datutex/ex12.pp`

```

Program Example12;

{ This program demonstrates the WeeksInYear function }

Uses SysUtils, DateUtils;

Var
    Y : Word;

Begin
    For Y:=1992 to 2010 do
        WriteLn(Y, ' has ', WeeksInYear(EncodeDate(Y,2,1)), ' weeks. ');
End.

```

4.4.143 WeekSpan

Synopsis: Calculate the approximate number of weeks between two `DateTime` values.

Declaration: `function WeekSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: `WeekSpan` returns the number of weeks between `ANow` and `AThen`, including any fractional parts of a week.

See also: `YearSpan` ([462](#)), `MonthSpan` ([422](#)), `DaySpan` ([386](#)), `HourSpan` ([399](#)), `MinuteSpan` ([419](#)), `SecondSpan` ([436](#)), `MilliSecondSpan` ([415](#)), `WeeksBetween` ([450](#))

Listing: `./datutex/ex65.pp`

```

Program Example57;

{ This program demonstrates the WeekSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin
    Write( 'Number of weeks between ');
    Write( DateToStr(AThen), ' and ', DateToStr(ANow));
    WriteLn( ' : ', WeekSpan(ANow, AThen));
end;

Var
    D1, D2 : TDateTime;

Begin
    D1:=Today;
    D2:=Today-7;
    Test(D1,D2);
    D2:=Today-8;
    Test(D1,D2);
    D2:=Today-14;
    Test(D1,D2);
    D2:=Today-35;
    Test(D1,D2);

```

```

D2:=Today-36;
Test(D1,D2);
D2:=Today-17;
Test(D1,D2);
End.

```

4.4.144 WithinPastDays

Synopsis: Check whether two datetimes are only a number of days apart

Declaration: `function WithinPastDays(const ANow: TDateTime; const AThen: TDateTime;
const ADays: Integer) : Boolean`

Visibility: default

Description: `WithinPastDays` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ADays` days apart, or `False` if they are further apart.

Remark: Since this function uses the `DaysBetween` (383) function to calculate the difference in days, this means that fractional days do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half days apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastMonths` (456), `WithinPastWeeks` (458), `WithinPastHours` (454), `WithinPastMinutes` (456), `WithinPastSeconds` (457), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex50.pp`

Program Example50;

{ This program demonstrates the WithinPastDays function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; ADays : Integer);

begin

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 Write(' are within ', ADays, ' days: ');

 WriteLn(WithinPastDays(ANow, AThen, ADays));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;

 D2:=Today-23/24;

 Test(D1,D2,1);

 D2:=Today-1;

 Test(D1,D2,1);

 D2:=Today-25/24;

 Test(D1,D2,1);

 D2:=Today-26/24;

 Test(D1,D2,5);

 D2:=Today-5.4;

 Test(D1,D2,5);

 D2:=Today-2.5;

 Test(D1,D2,1);

```

    Test(D1,D2,2);
    Test(D1,D2,3);
End.

```

4.4.145 WithinPastHours

Synopsis: Check whether two datetimes are only a number of hours apart

Declaration: `function WithinPastHours(const ANow: TDateTime;const AThen: TDateTime;
const AHours: Int64) : Boolean`

Visibility: default

Description: `WithinPastHours` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AHours` hours apart, or `False` if they are further apart.

Remark: Since this function uses the `HoursBetween` (398) function to calculate the difference in Hours, this means that fractional hours do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half hours apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastMonths` (456), `WithinPastWeeks` (458), `WithinPastDays` (453), `WithinPastMinutes` (456), `WithinPastSeconds` (457), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex51.pp`

Program Example51 ;

{ This program demonstrates the WithinPastHours function }

Uses SysUtils , DateUtils ;

Procedure Test(ANow,AThen : TDateTime; AHours : Integer);

begin

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 Write(' are within ',AHours, ' hours: ');

 WriteLn (WithinPastHours(ANow,AThen,AHours));

end;

Var

 D1,D2 : TDateTime;

Begin

 D1:=Now;

 D2:=D1-(59*OneMinute);

 Test(D1,D2,1);

 D2:=D1-(61*OneMinute);

 Test(D1,D2,1);

 D2:=D1-(122*OneMinute);

 Test(D1,D2,1);

 D2:=D1-(306*OneMinute);

 Test(D1,D2,5);

 D2:=D1-(5.4*OneHour);

 Test(D1,D2,5);

 D2:=D1-(2.5*OneHour);

 Test(D1,D2,1);

 Test(D1,D2,2);

 Test(D1,D2,3);

End.

4.4.146 WithinPastMilliseconds

Synopsis: Check whether two datetimes are only a number of milliseconds apart

Declaration: `function WithinPastMilliseconds(const ANow: TDateTime;
const AThen: TDateTime;
const AMilliSeconds: Int64) : Boolean`

Visibility: default

Description: `WithinPastMilliseconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMilliSeconds` milliseconds apart, or `False` if they are further apart.

Remark: Since this function uses the `MillisecondsBetween` (415) function to calculate the difference in milliseconds, this means that fractional milliseconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half milliseconds apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastMonths` (456), `WithinPastWeeks` (458), `WithinPastDays` (453), `WithinPastHours` (454), `WithinPastMinutes` (456), `WithinPastSeconds` (457)

Listing: `./datutex/ex54.pp`

Program Example54;

{ This program demonstrates the WithinPastMilliseconds function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMilliSeconds : Integer);

begin
 Write(**TimeToStr**(AThen), ' and ', **TimeToStr**(ANow));
 Write(' are within ', AMilliSeconds, ' milliseconds: ');
 WriteLn(WithinPastMilliseconds(ANow, AThen, AMilliSeconds));
end;

Var
 D1, D2 : TDateTime;

Begin
 D1:=**Now**;
 D2:=D1-(0.9*OneMilliSecond);
 Test(D1,D2,1);
 D2:=D1-(1.0*OneMilliSecond);
 Test(D1,D2,1);
 D2:=D1-(1.1*OneMilliSecond);
 Test(D1,D2,1);
 D2:=D1-(2.5*OneMilliSecond);
 Test(D1,D2,1);
 Test(D1,D2,2);
 Test(D1,D2,3);

End.

4.4.147 WithinPastMinutes

Synopsis: Check whether two datetimes are only a number of minutes apart

Declaration: `function WithinPastMinutes(const ANow: TDateTime; const AThen: TDateTime;
const AMinutes: Int64) : Boolean`

Visibility: default

Description: `WithinPastMinutes` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMinutes` minutes apart, or `False` if they are further apart.

Remark: Since this function uses the `MinutesBetween` (418) function to calculate the difference in Minutes, this means that fractional minutes do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half minutes apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastMonths` (456), `WithinPastWeeks` (458), `WithinPastDays` (453), `WithinPastHours` (454), `WithinPastSeconds` (457), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex52.pp`

Program Example52;

{ This program demonstrates the WithinPastMinutes function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMinutes : Integer);

begin

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 Write(' are within ', AMinutes, ' Minutes: ');

 WriteLn(WithinPastMinutes(ANow, AThen, AMinutes));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;

 D2:=D1-(59*OneSecond);

 Test(D1, D2, 1);

 D2:=D1-(61*OneSecond);

 Test(D1, D2, 1);

 D2:=D1-(122*OneSecond);

 Test(D1, D2, 1);

 D2:=D1-(306*OneSecond);

 Test(D1, D2, 5);

 D2:=D1-(5.4*OneMinute);

 Test(D1, D2, 5);

 D2:=D1-(2.5*OneMinute);

 Test(D1, D2, 1);

 Test(D1, D2, 2);

 Test(D1, D2, 3);

End.

4.4.148 WithinPastMonths

Synopsis: Check whether two datetimes are only a number of months apart

Declaration: `function WithinPastMonths(const ANow: TDateTime; const AThen: TDateTime;
const AMonths: Integer) : Boolean`

Visibility: default

Description: `WithinPastMonths` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMonths` months apart, or `False` if they are further apart.

Remark: Since this function uses the `MonthsBetween` (421) function to calculate the difference in Months, this means that fractional months do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half months apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastWeeks` (458), `WithinPastDays` (453), `WithinPastHours` (454), `WithinPastMinutes` (456), `WithinPastSeconds` (457), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex48.pp`

Program Example48;

{ This program demonstrates the WithinPastMonths function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMonths : Integer);

begin

Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

Write(' are within ', AMonths, ' months: ');

WriteLn(WithinPastMonths(ANow, AThen, AMonths));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Today;

 D2 := Today - 364;

 Test(D1, D2, 12);

 D2 := Today - 365;

 Test(D1, D2, 12);

 D2 := Today - 366;

 Test(D1, D2, 12);

 D2 := Today - 390;

 Test(D1, D2, 12);

 D2 := Today - 368;

 Test(D1, D2, 11);

 D2 := Today - 1000;

 Test(D1, D2, 31);

 Test(D1, D2, 32);

 Test(D1, D2, 33);

End.

4.4.149 WithinPastSeconds

Synopsis: Check whether two datetimes are only a number of seconds apart

Declaration: `function WithinPastSeconds(const ANow: TDateTime; const AThen: TDateTime;
const ASeconds: Int64) : Boolean`

Visibility: default

Description: `WithinPastSeconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ASeconds` seconds apart, or `False` if they are further apart.

Remark: Since this function uses the `SecondsBetween` (435) function to calculate the difference in seconds, this means that fractional seconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half seconds apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastMonths` (456), `WithinPastWeeks` (458), `WithinPastDays` (453), `WithinPastHours` (454), `WithinPastMinutes` (456), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex53.pp`

Program `Example53`;

{ This program demonstrates the WithinPastSeconds function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow,AThen : TDateTime; ASeconds : Integer);`

begin

`Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));`

`Write(' are within ',ASeconds,' seconds: ');`

`WriteLn(WithinPastSeconds(ANow,AThen,ASeconds));`

end;

Var

`D1,D2 : TDateTime;`

Begin

`D1:=Now;`

`D2:=D1-(999*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(1001*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(2001*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(5001*OneMilliSecond);`

`Test(D1,D2,5);`

`D2:=D1-(5.4*OneSecond);`

`Test(D1,D2,5);`

`D2:=D1-(2.5*OneSecond);`

`Test(D1,D2,1);`

`Test(D1,D2,2);`

`Test(D1,D2,3);`

End.

4.4.150 WithinPastWeeks

Synopsis: Check whether two datetimes are only a number of weeks apart

Declaration: `function WithinPastWeeks(const ANow: TDateTime;const AThen: TDateTime;
const AWeeks: Integer) : Boolean`

Visibility: default

Description: `WithinPastWeeks` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AWeeks` weeks apart, or `False` if they are further apart.

Remark: Since this function uses the `WeeksBetween` (450) function to calculate the difference in Weeks, this means that fractional Weeks do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half weeks apart, the result will also be `True`

See also: `WithinPastYears` (459), `WithinPastMonths` (456), `WithinPastDays` (453), `WithinPastHours` (454), `WithinPastMinutes` (456), `WithinPastSeconds` (457), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex49.pp`

Program `Example49`;

{ This program demonstrates the WithinPastWeeks function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime; AWeeks : Integer);`

```
begin
  Write( DateToStr(AThen), ' and ', DateToStr(ANow));
  Write( ' are within ', AWeeks, ' weeks: ');
  WriteLn( WithinPastWeeks(ANow, AThen, AWeeks));
end;
```

Var
 `D1, D2 : TDateTime;`

```
Begin
  D1:=Today;
  D2:=Today-7;
  Test(D1,D2,1);
  D2:=Today-8;
  Test(D1,D2,1);
  D2:=Today-14;
  Test(D1,D2,1);
  D2:=Today-35;
  Test(D1,D2,5);
  D2:=Today-36;
  Test(D1,D2,5);
  D2:=Today-17;
  Test(D1,D2,1);
  Test(D1,D2,2);
  Test(D1,D2,3);
```

End.

4.4.151 WithinPastYears

Synopsis: Check whether two datetimes are only a number of years apart

Declaration: `function WithinPastYears(const ANow: TDateTime; const AThen: TDateTime;
 const AYears: Integer) : Boolean`

Visibility: `default`

Description: `WithinPastYears` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AYears` years apart, or `False` if they are further apart.

Remark: Since this function uses the `YearsBetween` (461) function to calculate the difference in years, this means that fractional years do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half years apart, the result will also be `True`

See also: `WithinPastMonths` (456), `WithinPastWeeks` (458), `WithinPastDays` (453), `WithinPastHours` (454), `WithinPastMinutes` (456), `WithinPastSeconds` (457), `WithinPastMilliseconds` (455)

Listing: `./datutex/ex47.pp`

Program `Example47`;

{ This program demonstrates the WithinPastYears function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test`(`ANow`, `AThen` : `TDateTime`; `AYears` : `Integer`);

begin
 `Write`(`DateToStr`(`AThen`), ' and ', `DateToStr`(`ANow`));
 `Write`(' are within ', `AYears`, ' years: ');
 `WriteLn`(`WithinPastYears`(`ANow`, `AThen`, `AYears`));
end;

Var
 `D1`, `D2` : `TDateTime`;

Begin
 `D1` := `Today`;
 `D2` := `Today` - 364;
 `Test`(`D1`, `D2`, 1);
 `D2` := `Today` - 365;
 `Test`(`D1`, `D2`, 1);
 `D2` := `Today` - 366;
 `Test`(`D1`, `D2`, 1);
 `D2` := `Today` - 390;
 `Test`(`D1`, `D2`, 1);
 `D2` := `Today` - 368;
 `Test`(`D1`, `D2`, 1);
 `D2` := `Today` - 1000;
 `Test`(`D1`, `D2`, 1);
 `Test`(`D1`, `D2`, 2);
 `Test`(`D1`, `D2`, 3);
End.

4.4.152 YearOf

Synopsis: Extract the year from a given date.

Declaration: `function YearOf(const AValue: TDateTime) : Word`

Visibility: `default`

Description: `YearOf` returns the year part of the `AValue` date/time indication. It is a number between 1 and 9999.

See also: `MonthOf` (420), `DayOf` (382), `WeekOf` (448), `HourOf` (397), `MinuteOf` (416), `SecondOf` (433), `MilliSecondOf` (412)

Listing: ./datutex/ex23.pp

Program Example23;

{ This program demonstrates the YearOf function }

Uses SysUtils, DateUtils;

Var

D : TDateTime;

Begin

D:=Now;

WriteLn('Year : ', YearOf(D));

WriteLn('Month : ', MonthOf(D));

WriteLn('Day : ', DayOf(D));

WriteLn('Week : ', WeekOf(D));

WriteLn('Hour : ', HourOf(D));

WriteLn('Minute : ', MinuteOf(D));

WriteLn('Second : ', SecondOf(D));

WriteLn('MilliSecond : ', MilliSecondOf(D));

End.

4.4.153 YearsBetween

Synopsis: Calculate the number of whole years between two DateTime values

Declaration: function YearsBetween(const ANow: TDateTime; const AThen: TDateTime)
: Integer

Visibility: default

Description: YearsBetween returns the number of whole years between ANow and AThen. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years). This means the fractional part of a year is dropped.

See also: MonthsBetween (421), WeeksBetween (450), DaysBetween (383), HoursBetween (398), MinutesBetween (418), SecondsBetween (435), MilliSecondsBetween (415), YearSpan (462)

Listing: ./datutex/ex55.pp

Program Example55;

{ This program demonstrates the YearsBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of years between ');

Write(DateToStr(AThen), ' and ', DateToStr(ANow));

WriteLn(' : ', YearsBetween(ANow, AThen));

end;

Var

D1, D2 : TDateTime;

Begin

```

D1:=Today;
D2:=Today-364;
Test(D1,D2);
D2:=Today-365;
Test(D1,D2);
D2:=Today-366;
Test(D1,D2);
D2:=Today-390;
Test(D1,D2);
D2:=Today-368;
Test(D1,D2);
D2:=Today-1000;
Test(D1,D2);

```

End.**4.4.154 YearSpan**

Synopsis: Calculate the approximate number of years between two DateTime values.

Declaration: `function YearSpan(const ANow: TDateTime;const AThen: TDateTime) : Double`

Visibility: default

Description: `YearSpan` returns the number of years between `ANow` and `AThen`, including any fractional parts of a year. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years).

See also: `MonthSpan` ([422](#)), `WeekSpan` ([452](#)), `DaySpan` ([386](#)), `HourSpan` ([399](#)), `MinuteSpan` ([419](#)), `SecondSpan` ([436](#)), `MilliSecondSpan` ([415](#)), `YearsBetween` ([461](#))

Listing: `./datutex/ex63.pp`

Program Example63;

{ This program demonstrates the YearSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```

Write('Number of years between ');
Write(DateToStr(AThen), ' and ', DateToStr(ANow));
WriteLn(' : ', YearSpan(ANow, AThen));
end;

```

Var

```

D1, D2 : TDateTime;

```

Begin

```

D1:=Today;
D2:=Today-364;
Test(D1,D2);
D2:=Today-365;
Test(D1,D2);
D2:=Today-366;

```

```

Test(D1,D2);
D2:=Today-390;
Test(D1,D2);
D2:=Today-368;
Test(D1,D2);
D2:=Today-1000;
Test(D1,D2);
End.
```

4.4.155 Yesterday

Synopsis: Return the previous day.

Declaration: `function Yesterday : TDateTime`

Visibility: default

Description: `Yesterday` returns yesterday's date. `Yesterday` is determined from the system clock, i.e. it is `Today` (442) -1.

See also: `Today` (442), `Tomorrow` (442)

Listing: `./datutex/ex18.pp`

Program `Example18;`

{ This program demonstrates the Yesterday function }

Uses `SysUtils, DateUtils;`

Begin

```

  WriteLn(FormatDateTime('"Today is " dd mmm yyyy ',Today));
  WriteLn(FormatDateTime('"Yesterday was " dd mmm yyyy ',Yesterday));
End.
```

Chapter 5

Reference for unit 'Dos'

5.1 System information

Functions for retrieving and setting general system information such as date and time.

Table 5.1:

Name	Description
DosVersion (473)	Get OS version
GetCBreak (479)	Get setting of control-break handling flag
GetDate (479)	Get system date
GetIntVec (482)	Get interrupt vector status
GetTime (483)	Get system time
GetVerify (484)	Get verify flag
Intr (484)	Execute an interrupt
Keep (484)	Keep process in memory and exit
MSDos (485)	Execute MS-dos function call
PackTime (485)	Pack time for file time
SetCBreak (486)	Set control-break handling flag
SetDate (486)	Set system date
SetIntVec (487)	Set interrupt vectors
SetTime (488)	Set system time
SetVerify (488)	Set verify flag
SwapVectors (488)	Swap interrupt vectors
UnPackTime (489)	Unpack file time

5.2 Process handling

Functions to handle process information and starting new processes.

5.3 Directory and disk handling

Routines to handle disk information.

Table 5.2:

Name	Description
DosExitCode (473)	Exit code of last executed program
EnvCount (474)	Return number of environment variables
EnvStr (475)	Return environment string pair
Exec (475)	Execute program
GetEnv (480)	Return specified environment string

Table 5.3:

Name	Description
AddDisk (470)	Add disk to list of disks (UNIX only)
DiskFree (471)	Return size of free disk space
DiskSize (472)	Return total disk size

5.4 File handling

Routines to handle files on disk.

Table 5.4:

Name	Description
FExpand (475)	Expand filename to full path
FindClose (476)	Close finfirst/findnext session
FindFirst (476)	Start find of file
FindNext (477)	Find next file
FSearch (477)	Search for file in a path
FSplit (478)	Split filename in parts
GetFAttr (480)	Return file attributes
GetFTime (481)	Return file time
GetLongName (482)	Convert short filename to long filename (DOS only)
GetShortName (483)	Convert long filename to short filename (DOS only)
SetFAttr (486)	Set file attributes
SetFTime (487)	Set file time

5.5 File open mode constants.

These constants are used in the `Mode` field of the `TextRec` record. Gives information on the file-mode of the text I/O. For their definitions consult the following table:

5.6 File attributes

The File Attribute constants are used in `FindFirst` (476), `FindNext` (477) to determine what type of special file to search for in addition to normal files. These flags are also used in the `SetFAttr` (486) and

Table 5.5: Possible mode constants

Constant	Description	Value
<code>fmclosed</code>	File is closed	<code>\$D7B0</code>
<code>fminput</code>	File is read only	<code>\$D7B1</code>
<code>fmoutput</code>	File is write only	<code>\$D7B2</code>
<code>fminout</code>	File is read and write	<code>\$D7B3</code>

`GetFAttr` ([480](#)) routines to set and retrieve attributes of files. For their definitions consult `fileattributes` ([465](#)).

Table 5.6: Possible file attributes

Constant	Description	Value
<code>readonly</code>	Read-Only file attribute	<code>\$01</code>
<code>hidden</code>	Hidden file attribute	<code>\$02</code>
<code>sysfile</code>	System file attribute	<code>\$04</code>
<code>volumeid</code>	Volumd ID file attribute	<code>\$08</code>
<code>directory</code>	Directory file attribute	<code>\$10</code>
<code>archive</code>	Archive file attribute	<code>\$20</code>
<code>anyfile</code>	Match any file attribute	<code>\$3F</code>

5.7 Used units

Table 5.7: Used units by unit 'Dos'

Name	Page
<code>baseunix</code>	464

5.8 Overview

The DOS unit gives access to some operating system calls related to files, the file system, date and time. Except for the PalmOS target, this unit is available to all supported platforms.

The unit was first written for dos by Florian Klaempfl. It was ported to linux by Mark May and enhanced by Michael Van Canneyt. The Amiga version was ported by Nils Sjöholm.

Under non-DOS systems, some of the functionality is lost, as it is either impossible or meaningless to implement it. Other than that, the functionality for all operating systems is the same.

5.9 Constants, types and variables

5.9.1 Constants

`anyfile` = `$3F`

Match any file attribute

archive = \$20

Archive file attribute

directory = \$10

Directory file attribute

fauxiliary = \$0010

CPU auxiliary flag. Not used.

fcarry = \$0001

CPU carry flag. Not used.

FileNameLen = 255

Maximum length of a filename

filerecnamelength = 255

Maximum length of FileName part in FileRec ([469](#))

fmclosed = \$D7B0

File is closed

fminout = \$D7B3

File is read and write

fminput = \$D7B1

File is read only

fmoutput = \$D7B2

File is write only

foverflow = \$0800

CPU overflow flag. Not used.

fparity = \$0004

CPU parity flag. Not used.

fsign = \$0080

CPU sign flag. Not used.

`fzero = $0040`

CPU zero flag. Not used.

`hidden = $02`

Hidden file attribute

`readonly = $01`

Read-Only file attribute

`sysfile = $04`

System file attribute

`TextRecBufSize = 256`

Size of default buffer in `TextRec` ([470](#))

`TextRecNameLength = 256`

Maximum length of filename in `TextRec` ([470](#))

`volumeid = $08`

Volumd ID file attribute

5.9.2 Types

`ComStr =`

Command-line string type

```
DateTime = packed record
  Year : Word;
  Month : Word;
  Day : Word;
  Hour : Word;
  Min : Word;
  Sec : Word;
end
```

The `DateTime` type is used in `PackTime` ([485](#)) and `UnPackTime` ([489](#)) for setting/reading file times with `GetFTime` ([481](#)) and `SetFTime` ([487](#)).

`DirStr =`

Full directory string type.

ExtStr =

Filename extension string type.

```
FileRec = packed record
  Handle : THandle;
  Mode : LongInt;
  RecSize : SizeInt;
  _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer)] of Byte;
  UserData : Array[1..32] of Byte;
  name : Array[0..filerecnamelength] of Char;
end
```

FileRec is used for internal representation of typed and untyped files.

NameStr =

Fill filename string type.

PathStr =

Full File path string type.

```
Registers = packed record
end
```

Record to keep CPU registers for MSDos (485) call. Unused.

```
SearchRec = packed record
  SearchPos : TOff;
  SearchNum : LongInt;
  DirPtr : Pointer;
  SearchType : Byte;
  SearchAttr : Byte;
  Fill : Array[1..03] of Byte;
  Attr : Byte;
  Time : LongInt;
  Size : LongInt;
  Reserved : Word;
  Name : String;
  SearchSpec : String;
  NamePos : Word;
end
```

SearchRec is filled by the FindFirst (476) call and can be used in subsequent FindNext (477) calls to search for files. The structure of this record depends on the platform. Only the following fields are present on all platforms:

Attr File attributes.

Time File modification time.

Size File size

Name File name (name part only, no path)

```
TextBuf = Array[0..TextRecBufSize-1] of Char
```

Type for default buffer in TextRec (470)

```
TextRec = packed record
  Handle : THandle;
  Mode : LongInt;
  bufsize : SizeInt;
  _private : SizeInt;
  bufpos : SizeInt;
  bufend : SizeInt;
  bufptr : ^TextBuf;
  openfunc : pointer;
  inoutfunc : pointer;
  flushfunc : pointer;
  closefunc : pointer;
  UserData : Array[1..32] of Byte;
  name : Array[0..textreclenlength-1] of Char;
  LineEnd : TLineEndStr;
  buffer : TextBuf;
end
```

TextRec describes the internal working of a Text file.

Remark that this is not binary compatible with the Turbo Pascal definition of TextRec, since the sizes of the different fields are different.

```
TLineEndStr =
```

TLineEndStr is used in the TextRec (470) record to indicate the end-of-line sequence for a text file.

5.9.3 Variables

```
DosError : Integer
```

The DosError variable is used by the procedures in the dos unit to report errors. It can have the following values :

Other values are possible, but are not documented.

5.10 Procedures and functions

5.10.1 AddDisk

Synopsis: Add disk definition to list if drives (Unix only)

Table 5.8: Dos error codes

Value	Meaning
2	File not found.
3	path not found.
5	Access denied.
6	Invalid handle.
8	Not enough memory.
10	Invalid environment.
11	Invalid format.
18	No more files.

Declaration: `function AddDisk(const path: String) : Byte`

Visibility: default

Description: `AddDisk` adds a filename `S` to the internal list of disks. It is implemented for systems which do not use DOS type drive letters. This list is used to determine which disks to use in the `DiskFree` (471) and `DiskSize` (472) calls. The `DiskFree` (471) and `DiskSize` (472) functions need a file on the specified drive, since this is required for the `statfs` system call. The names are added sequentially. The dos initialization code presets the first three disks to:

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (linux only).
- `'/fd1/.'` for the second floppy-drive (linux only).
- `''` for the first hard disk.

The first call to `AddDisk` will therefore add a name for the second harddisk, The second call for the third drive, and so on until 23 drives have been added (corresponding to drives '`D:`' to '`Z:`')

Errors: None

See also: `DiskFree` (471), `DiskSize` (472)

5.10.2 DiskFree

Synopsis: Get free size on Disk.

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the number of free bytes on a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy `a:`, 2 for floppy `b:`, etc. A value of 0 returns the free space on the current drive.

Remark: For Unices: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (linux only).
- `'/fd1/.'` for the second floppy-drive (linux only).

- ' / ' for the first hard disk.

There is room for 1-26 drives. You can add a drive with the AddDisk (470) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: DiskSize (472), AddDisk (470)

Listing: `./dosex/ex6.pp`

```

Program Example6;
uses Dos;

{ Program to demonstrate the DiskSize and DiskFree function. }

begin
  WriteLn('This partition size has ', DiskSize(0), ' bytes');
  WriteLn('Currently ', DiskFree(0), ' bytes are free');
end.

```

5.10.3 DiskSize

Synopsis: Get total size of disk.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the total size (in bytes) of a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the size of the current drive.

Remark: For unix only: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the `dos` unit, and have been preset to :

- ' . ' for the current drive,
- ' /fd0/ . ' for the first floppy-drive (linux only).
- ' /fd1/ . ' for the second floppy-drive (linux only).
- ' / ' for the first hard disk.

There is room for 1-26 drives. You can add a drive with the AddDisk (470) procedure. These settings can be coded in `dos.pp`, in the initialization part.

For an example, see DiskFree (471).

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: DiskFree (471), AddDisk (470)

5.10.4 DosExitCode

Synopsis: Exit code of last executed program.

Declaration: `function DosExitCode : Word`

Visibility: default

Description: `DosExitCode` contains (in the low byte) the exit-code of a program executed with the `Exec` call.

Errors: None.

See also: `Exec` ([475](#))

Listing: `./dosex/ex5.pp`

```

Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function. }

begin
  {$IFDEF Unix}
    WriteLn('Executing /bin/ls -la');
    Exec('/bin/ls', '-la');
  {$ELSE}
    WriteLn('Executing Dir');
    Exec(GetEnv('COMSPEC'), '/C dir');
  {$ENDIF}
  WriteLn('Program returned with ExitCode ', Lo(DosExitCode));
end.

```

5.10.5 DosVersion

Synopsis: Current OS version

Declaration: `function DosVersion : Word`

Visibility: default

Description: `DosVersion` returns the operating system or kernel version. The low byte contains the major version number, while the high byte contains the minor version number.

Remark: On systems where versions consists of more then two numbers, only the first two numbers will be returned. For example Linux version 2.1.76 will give you `DosVersion` 2.1. Some operating systems, such as FreeBSD, do not have system calls to return the kernel version, in that case a value of 0 will be returned.

Errors: None.

Listing: `./dosex/ex1.pp`

```

Program Example1;
uses Dos;

{ Program to demonstrate the DosVersion function. }

var
  OS      : string[32];

```

```

    Version : word;
begin
{$IFDEF LINUX}
    OS:= 'Linux';
{$ENDIF}
{$IFDEF FreeBSD}
    OS:= 'FreeBSD';
{$endif}
{$IFDEF NetBSD}
    OS:= 'NetBSD';
{$endif}
{$IFDEF Solaris}
    OS:= 'Solaris';
{$endif}
{$IFDEF QNX}
    OS:= 'QNX';
{$endif}

{$IFDEF DOS}
    OS:= 'Dos';
{$ENDIF}
    Version:=DosVersion;
    WriteLn('Current ',OS,' version is ',Lo(Version),'. ',Hi(Version));
end.

```

5.10.6 DTToUnixDate

Synopsis: Convert a DateTime to unix timestamp

Declaration: `function DTToUnixDate(DT: DateTime) : LongInt`

Visibility: default

Description: `DTToUnixDate` converts the `DateTime` value in `DT` to a unix timestamp. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `UnixDateToDT` ([489](#)), `PackTime` ([485](#)), `UnpackTime` ([489](#)), `GetTime` ([483](#)), `SetTime` ([488](#))

5.10.7 EnvCount

Synopsis: Return the number of environment variables

Declaration: `function EnvCount : LongInt`

Visibility: default

Description: `EnvCount` returns the number of environment variables.

Errors: None.

See also: `EnvStr` ([475](#)), `GetEnv` ([480](#))

5.10.8 EnvStr

Synopsis: Return environment variable by index

Declaration: `function EnvStr(Index: LongInt) : String`

Visibility: default

Description: `EnvStr` returns the `Index`-th Name=Value pair from the list of environment variables. The index of the first pair is zero.

Errors: The length is limited to 255 characters.

See also: `EnvCount` ([474](#)), `GetEnv` ([480](#))

Listing: `./dosex/ex13.pp`

Program `Example13;`
uses `Dos;`

{ Program to demonstrate the EnvCount and EnvStr function. }

```
var
  i : Longint;
begin
  WriteLn('Current Environment is:');
  for i:=1 to EnvCount do
    WriteLn(EnvStr(i));
end.
```

5.10.9 Exec

Synopsis: Execute another program, and wait for it to finish.

Declaration: `procedure Exec(const path: PathStr; const comline: ComStr)`

Visibility: default

Description: `Exec` executes the program in `Path`, with the options given by `ComLine`. The program name should *not* appear again in `ComLine`, it is specified in `Path`. `Comline` contains only the parameters that are passed to the program.

After the program has terminated, the procedure returns. The Exit value of the program can be consulted with the `DosExitCode` function.

For an example, see `DosExitCode` ([473](#))

Errors: Errors are reported in `DosError`.

See also: `DosExitCode` ([473](#))

5.10.10 FExpand

Synopsis: Expand a relative path to an absolute path

Declaration: `function FExpand(const path: PathStr) : PathStr`

Visibility: default

Description: `FExpand` takes its argument and expands it to a complete filename, i.e. a filename starting from the root directory of the current drive, prepended with the drive-letter or volume name (when supported).

Remark: On case sensitive file systems (such as unix and linux), the resulting name is left as it is, otherwise it is converted to uppercase.

Errors: `FSplit` (478)

Listing: `./dosex/ex11.pp`

Program `Example11`;
uses `Dos`;

{ Program to demonstrate the FExpand function. }

begin
 WriteLn('Expanded Name of this program is ', `FExpand(ParamStr(0))`);
end.

5.10.11 FindClose

Synopsis: Dispose resources allocated by a `FindFirst` (476)/`FindNext` (477) sequence.

Declaration: `procedure FindClose(var f: SearchRec)`

Visibility: `default`

Description: `FindClose` frees any resources associated with the search record `F`.

This call is needed to free any internal resources allocated by the `FindFirst` (476) or `FindNext` (477) calls.

The unix implementation of the `dos` unit therefore keeps a table of open directories, and when the table is full, closes one of the directories, and reopens another. This system is adequate but slow if you use a lot of `searchrecs`.

So, to speed up the `findfirst/findnext` system, the `FindClose` call was implemented. When you don't need a `searchrec` any more, you can tell this to the `dos` unit by issuing a `FindClose` call. The directory which is kept open for this `searchrec` is then closed, and the table slot freed.

Remark: It is recommended to use the linux call `Glob` when looking for files on linux.

Errors: Errors are reported in `DosError`.

See also: `FindFirst` (476), `FindNext` (477)

5.10.12 FindFirst

Synopsis: Start search for one or more files.

Declaration: `procedure FindFirst(const path: PathStr; attr: Word; var f: SearchRec)`

Visibility: `default`

Description: `FindFirst` searches the file specified in `Path`. Normal files, as well as all special files which have the attributes specified in `Attr` will be returned.

It returns a `SearchRec` record for further searching in `F`. `Path` can contain the wildcard characters `?` (matches any single character) and `*` (matches 0 ore more arbitrary characters). In this case

`FindFirst` will return the first file which matches the specified criteria. If `DosError` is different from zero, no file(s) matching the criteria was(were) found.

Remark: On os/2, you cannot issue two different `FindFirst` calls. That is, you must close any previous search operation with `FindClose` (476) before starting a new one. Failure to do so will end in a Run-Time Error 6 (Invalid file handle)

Errors: Errors are reported in `DosError`.

See also: `FindNext` (477), `FindClose` (476)

Listing: `./dosex/ex7.pp`

```

Program Example7;
uses Dos;

{ Program to demonstrate the FindFirst and FindNext function. }

var
  Dir : SearchRec;
begin
  FindFirst( ' *.* ', archive , Dir );
  WriteLn( 'FileName '+Space(32), 'FileSize ':9);
  while ( DosError=0) do
    begin
      WriteLn( Dir.Name+Space(40-Length( Dir.Name)) , Dir.Size :9);
      FindNext(Dir);
    end;
  FindClose( Dir );
end.

```

5.10.13 FindNext

Synopsis: Find next matching file after `FindFirst` (476)

Declaration: `procedure FindNext (var f: SearchRec)`

Visibility: default

Description: `FindNext` takes as an argument a `SearchRec` from a previous `FindNext` call, or a `FindFirst` call, and tries to find another file which matches the criteria, specified in the `FindFirst` call. If `DosError` is different from zero, no more files matching the criteria were found.

For an example, see `FindFirst` (476).

Errors: `DosError` is used to report errors.

See also: `FindFirst` (476), `FindClose` (476)

5.10.14 FSearch

Synopsis: Search a file in searchpath

Declaration: `function FSearch(path: PathStr;dirlist: String) : PathStr`

Visibility: default

Description: `FSearch` searches the file `Path` in all directories listed in `DirList`. The full name of the found file is returned. `DirList` must be a list of directories, separated by semi-colons. When no file is found, an empty string is returned.

Remark: On unix systems, `DirList` can also be separated by colons, as is customary on those environments.

Errors: None.

See also: `FExpand` ([475](#))

Listing: `./dosex/ex10.pp`

```

program Example10;

uses Dos;

{ Program to demonstrate the FSearch function. }

var s:pathstr;

begin
  s:=FSearch(ParamStr(1),GetEnv('PATH'));
  if s='' then
    WriteLn(ParamStr(1),' not Found in PATH')
  else
    WriteLn(ParamStr(1),' Found in PATH at ',s);
end.

```

5.10.15 FSplit

Synopsis: Split a full-path filename in parts.

Declaration: `procedure FSplit(path: PathStr; var dir: DirStr; var name: NameStr; var ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A `Path`, a `Name` and an extension (in `ext`.) The extension is taken to be all letters after the *last* dot (.). For dos, however, an exception is made when `LFNSupport=False`, then the extension is defined as all characters after the *first* dot.

Errors: None.

See also: `FSearch` ([477](#))

Listing: `./dosex/ex12.pp`

```

program Example12;

uses Dos;

{ Program to demonstrate the FSplit function. }

var dir:dirstr;
    name:namestr;
    ext:extstr;

begin

```

```

FSplit(ParamStr(1),dir,name,ext);
WriteLn('Splitted ',ParamStr(1),' in:');
WriteLn('Path      : ',dir);
WriteLn('Name       : ',name);
WriteLn('Extension : ',ext);
end.

```

5.10.16 GetCBreak

Synopsis: Get control-Break flag

Declaration: `procedure GetCBreak(var breakvalue: Boolean)`

Visibility: default

Description: `GetCBreak` gets the status of CTRL-Break checking under dos and Amiga. When `BreakValue` is `false`, then dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to `True`, then a check is done at every system call.

Remark: Under non-dos and non-Amiga operating systems, `BreakValue` always returns `True`.

Errors: None

See also: `SetCBreak` ([486](#))

5.10.17 GetDate

Synopsis: Get the current date

Declaration: `procedure GetDate(var year: Word;var month: Word;var mday: Word;
var wday: Word)`

Visibility: default

Description: `GetDate` returns the system's date. `Year` is a number in the range 1980..2099. `mday` is the day of the month, `wday` is the day of the week, starting with Sunday as day 0.

Errors: None.

See also: `GetTime` ([483](#)), `SetDate` ([486](#))

Listing: `./dosex/ex2.pp`

Program Example2;

uses Dos;

{ Program to demonstrate the GetDate function. }

const

DayStr:array[0..6] of string[3]=('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat');

MonthStr:array[1..12] of string[3]=('Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun',
'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');

var

Year, Month, Day, WDay : word;

begin

GetDate(Year, Month, Day, WDay);

WriteLn('Current date');

WriteLn(DayStr[WDay], ' ', ' ', Day, ' ', ' ', MonthStr[Month], ' ', ' ', Year, ' ');

end.

5.10.18 GetEnv

Synopsis: Get environment variable by name.

Declaration: `function GetEnv(envvar: String) : String`

Visibility: default

Description: `Getenv` returns the value of the environment variable `EnvVar`. When there is no environment variable `EnvVar` defined, an empty string is returned.

Remark: Under some operating systems (such as unix), case is important when looking for `EnvVar`.

Errors: None.

See also: `EnvCount` ([474](#)), `EnvStr` ([475](#))

Listing: `./dosex/ex14.pp`

```

Program Example14;
uses Dos;

{ Program to demonstrate the GetEnv function. }

begin
  WriteLn('Current PATH is ',GetEnv('PATH'));
end.
```

5.10.19 GetFAttr

Synopsis: Get file attributes

Declaration: `procedure GetFAttr(var f;var attr: Word)`

Visibility: default

Description: `GetFAttr` returns the file attributes of the file-variable `f`. `F` can be a untyped or typed file, or of type `Text`. `f` must have been assigned, but not opened. The attributes can be examined with the following constants :

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Under linux, supported attributes are:

- `Directory`
- `ReadOnly` if the current process doesn't have access to the file.
- `Hidden` for files whose name starts with a dot (`'.'`).

Errors: Errors are reported in `DosError`

See also: `SetFAttr` ([486](#))

Listing: ./dosex/ex8.pp

```

Program Example8;
uses Dos;

{ Program to demonstrate the GetFAttr function. }

var
  Attr : Word;
  f    : File;
begin
  Assign(f, ParamStr(1));
  GetFAttr(f, Attr);
  WriteLn('File ', ParamStr(1), ' has attribute ', Attr);
  if (Attr and archive) <> 0 then WriteLn(' - Archive');
  if (Attr and directory) <> 0 then WriteLn(' - Directory');
  if (Attr and readonly) <> 0 then WriteLn(' - Read-Only');
  if (Attr and sysfile) <> 0 then WriteLn(' - System');
  if (Attr and hidden) <> 0 then WriteLn(' - Hidden');
end.

```

5.10.20 GetFTime

Synopsis: Get file last modification time.

Declaration: `procedure GetFTime(var f; var time: LongInt)`

Visibility: default

Description: `GetFTime` returns the modification time of a file. This time is encoded and must be decoded with `UnPackTime`. `F` must be a file type, which has been assigned, and opened.

Errors: Errors are reported in `DosError`

See also: `SetFTime` ([487](#)), `PackTime` ([485](#)), `UnPackTime` ([489](#))

Listing: ./dosex/ex9.pp

```

Program Example9;
uses Dos;

{ Program to demonstrate the GetFTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w, s);
  if w < 10 then
    L0 := '0' + s
  else
    L0 := s;
end;

var
  f    : File;
  Time : Longint;
  DT   : DateTime;

```

```

begin
  if Paramcount>0 then
    Assign(f, ParamStr(1))
  else
    Assign(f, 'ex9.pp' );
  Reset(f);
  GetFTime(f, Time);
  Close(f);
  UnPackTime(Time, DT);
  Write ('File ', ParamStr(1), ' is last modified on ');
  WriteLn (L0(DT.Month), '-', L0(DT.Day), '-', DT.Year,
           ' at ', L0(DT.Hour), ': ', L0(DT.Min));
end.

```

5.10.21 GetIntVec

Synopsis: Get interrupt vector

Declaration: `procedure GetIntVec(intno: Byte; var vector: pointer)`

Visibility: default

Description: `GetIntVec` returns the address of interrupt vector `IntNo`.

Remark: This call does nothing, it is present for compatibility only. Modern systems do not allow low level access to the hardware.

Errors: None.

See also: `SetIntVec` ([487](#))

5.10.22 GetLongName

Synopsis: Get the long filename of a DOS 8.3 filename.

Declaration: `function GetLongName(var p: String) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetLongName` changes the filename `p` to a long filename if the API call to do this is successful. The resulting string is the long file name corresponding to the short filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetShortName` ([483](#))

5.10.23 GetMsCount

Synopsis: Number of milliseconds since a starting point.

Declaration: `function GetMsCount : Int64`

Visibility: default

Description: `GetMSCount` returns a number of milliseconds elapsed since a certain moment in time. This moment in time is implementation dependent. This function is used for timing purposes: Subtracting the results of 2 subsequent calls to this function returns the number of milliseconds elapsed between the two calls.

This call is not very reliable, it is recommended to use some system specific calls for timings.

See also: `GetTime` ([483](#))

5.10.24 GetShortName

Synopsis: Get the short (8.3) filename of a long filename.

Declaration: `function GetShortName(var p: String) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetShortName` changes the filename `p` to a short filename if the API call to do this is successful. The resulting string is the short file name corresponding to the long filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetLongName` ([482](#))

5.10.25 GetTime

Synopsis: Return the current time

Declaration: `procedure GetTime(var hour: Word; var minute: Word; var second: Word; var sec100: Word)`

Visibility: default

Description: `GetTime` returns the system's time. `Hour` is on a 24-hour time scale. `sec100` is in hundredth of a second.

Remark: Certain operating systems (such as Amiga), always set the `sec100` field to zero.

Errors: None.

See also: `GetDate` ([479](#)), `SetTime` ([488](#))

Listing: `./dosex/ex3.pp`

```

Program Example3;
uses Dos;

{ Program to demonstrate the GetTime function. }

Function L0(w: word): string;
var
    s : string;
begin
    Str(w,s);
    if w<10 then

```

```

    L0:= '0'+s
  else
    L0:=s;
end;

var
  Hour, Min, Sec, HSec : word;
begin
  GetTime(Hour, Min, Sec, HSec);
  WriteLn('Current time');
  WriteLn(L0(Hour), ': ', L0(Min), ': ', L0(Sec));
end.

```

5.10.26 GetVerify

Synopsis: Get verify flag

Declaration: `procedure GetVerify(var verify: Boolean)`

Visibility: default

Description: `GetVerify` returns the status of the verify flag under dos. When `Verify` is `True`, then dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark: Under non-dos systems (excluding os/2 applications running under vanilla DOS), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([488](#))

5.10.27 Intr

Synopsis: Execute interrupt

Declaration: `procedure Intr(intno: Byte; var regs: Registers)`

Visibility: default

Description: `Intr` executes a software interrupt number `IntNo` (must be between 0 and 255), with processor registers set to `Regs`. After the interrupt call returned, the processor registers are saved in `Regs`.

Remark: Under non-dos operating systems, this call does nothing.

Errors: None.

See also: `MSDos` ([485](#))

5.10.28 Keep

Synopsis: Terminate and stay resident.

Declaration: `procedure Keep(exitcode: Word)`

Visibility: default

Description: `Keep` terminates the program, but stays in memory. This is used for TSR (Terminate Stay Resident) programs which catch some interrupt. `ExitCode` is the same parameter as the `Halt` function takes.

Remark: This call does nothing, it is present for compatibility only.

Errors: None.

5.10.29 MSDos

Synopsis: Execute MS-DOS system call

Declaration: `procedure MSDos (var regs: Registers)`

Visibility: default

Description: `MSDos` executes an operating system call. This is the same as doing a `Intr` call with the interrupt number for an os call.

Remark: Under non-dos operating systems, this call does nothing. On DOS systems, this calls interrupt \$21.

Errors: None.

See also: `Intr` ([484](#))

5.10.30 PackTime

Synopsis: Pack `DateTime` value to a packed-time format.

Declaration: `procedure PackTime (var t: DateTime; var p: LongInt)`

Visibility: default

Description: `UnPackTime` converts the date and time specified in `T` to a packed-time format which can be fed to `SetFTime`.

Errors: None.

See also: `SetFTime` ([487](#)), `FindFirst` ([476](#)), `FindNext` ([477](#)), `UnPackTime` ([489](#))

Listing: `./dosex/ex4.pp`

```

Program Example4;
uses Dos;

{ Program to demonstrate the PackTime and UnPackTime functions. }

var
  DT    : DateTime;
  Time  : longint;
begin
  with DT do
    begin
      Year:=1998;
      Month:=11;
      Day:=11;
      Hour:=11;
      Min:=11;
      Sec:=11;
    end;
  PackTime (DT, Time);

```

```

WriteLn( 'Packed Time : ',Time);
UnPackTime(Time,DT);
WriteLn( 'Unpacked Again: ');
with DT do
  begin
    WriteLn( 'Year   ',Year);
    WriteLn( 'Month  ',Month);
    WriteLn( 'Day    ',Day);
    WriteLn( 'Hour   ',Hour);
    WriteLn( 'Min    ',Min);
    WriteLn( 'Sec    ',Sec);
  end;
end.

```

5.10.31 SetCBreak

Synopsis: Set Control-Break flag status

Declaration: `procedure SetCBreak(breakvalue: Boolean)`

Visibility: default

Description: `SetCBreak` sets the status of CTRL-Break checking. When `BreakValue` is false, then dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to `True`, then a check is done at every system call.

Remark: Under non-dos and non-Amiga operating systems, this call does nothing.

Errors: None.

See also: `GetCBreak` ([479](#))

5.10.32 SetDate

Synopsis: Set system date

Declaration: `procedure SetDate(year: Word;month: Word;day: Word)`

Visibility: default

Description: `SetDate` sets the system's internal date. `Year` is a number between 1980 and 2099.

Remark: On a unix machine, there must be root privileges, otherwise this routine will do nothing. On other unix systems, this call currently does nothing.

Errors: None.

See also: `GetDate` ([479](#)), `SetTime` ([488](#))

5.10.33 SetFAttr

Synopsis: Set file attributes

Declaration: `procedure SetFAttr(var f;attr: Word)`

Visibility: default

Description: `SetFAttr` sets the file attributes of the file-variable `F`. `F` can be a untyped or typed file, or of type `Text`. `F` must have been assigned, but not opened. The attributes can be a sum of the following constants:

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Remark: Under unix like systems (such as linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`.

See also: `GetFAttr` ([480](#))

5.10.34 SetFTime

Synopsis: Set file modification time.

Declaration: `procedure SetFTime(var f; time: LongInt)`

Visibility: default

Description: `SetFTime` sets the modification time of a file, this time is encoded and must be encoded with `PackTime`. `F` must be a file type, which has been assigned, and opened.

Remark: Under unix like systems (such as linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`

See also: `GetFTime` ([481](#)), `PackTime` ([485](#)), `UnPackTime` ([489](#))

5.10.35 SetIntVec

Synopsis: Set interrupt vector

Declaration: `procedure SetIntVec(intno: Byte; vector: pointer)`

Visibility: default

Description: `SetIntVec` sets interrupt vector `IntNo` to `Vector`. `Vector` should point to an interrupt procedure.

Remark: This call does nothing, it is present for compatibility only.

Errors: None.

See also: `GetIntVec` ([482](#))

5.10.36 SetTime

Synopsis: Set system time

Declaration: `procedure SetTime(hour: Word; minute: Word; second: Word; sec100: Word)`

Visibility: default

Description: `SetTime` sets the system's internal clock. The `Hour` parameter is on a 24-hour time scale.

Remark: On a linux machine, there must be root privileges, otherwise this routine will do nothing. On other unix systems, this call currently does nothing.

Errors: None.

See also: `GetTime` ([483](#)), `SetDate` ([486](#))

5.10.37 SetVerify

Synopsis: Set verify flag

Declaration: `procedure SetVerify(verify: Boolean)`

Visibility: default

Description: `SetVerify` sets the status of the verify flag under dos. When `Verify` is `True`, then dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark: Under non-dos operating systems (excluding os/2 applications running under vanilla dos), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([488](#))

5.10.38 SwapVectors

Synopsis: Swap interrupt vectors

Declaration: `procedure SwapVectors`

Visibility: default

Description: `SwapVectors` swaps the contents of the internal table of interrupt vectors with the current contents of the interrupt vectors. This is called typically in before and after an `Exec` call.

Remark: Under certain operating systems, this routine may be implemented as an empty stub.

Errors: None.

See also: `Exec` ([475](#)), `SetIntVec` ([487](#))

5.10.39 UnixDateToDt

Synopsis: Convert a unix timestamp to a DateTime record

Declaration: `procedure UnixDateToDt (SecsPast: LongInt; var Dt: DateTime)`

Visibility: default

Description: `DTToUnixDate` converts the unix timestamp value in `SecsPast` to a `DateTime` representation in `DT`. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `DTToUnixDate` (474), `PackTime` (485), `UnpackTime` (489), `GetTime` (483), `SetTime` (488)

5.10.40 UnpackTime

Synopsis: Unpack packed file time to a DateTime value

Declaration: `procedure UnpackTime (p: LongInt; var t: DateTime)`

Visibility: default

Description: `UnPackTime` converts the file-modification time in `p` to a `DateTime` record. The file-modification time can be returned by `GetFTime`, `FindFirst` or `FindNext` calls.

For an example, see `PackTime` (485).

Errors: None.

See also: `GetFTime` (481), `FindFirst` (476), `FindNext` (477), `PackTime` (485)

5.10.41 weekday

Synopsis: Return the day of the week

Declaration: `function weekday (y: LongInt; m: LongInt; d: LongInt) : LongInt`

Visibility: default

Description: `WeekDay` returns the day of the week on which the day `Y/M/D` falls. Sunday is represented by 0, Saturday is 6.

Errors: On error, -1 is returned.

See also: `PackTime` (485), `UnpackTime` (489), `GetTime` (483), `SetTime` (488)

Chapter 6

Reference for unit 'dxeload'

6.1 Overview

The `dxeload` unit was implemented by Pierre Mueller for dos, it allows to load a DXE file (an object file with 1 entry point) into memory and return a pointer to the entry point.

It exists only for dos.

6.2 Procedures and functions

6.2.1 `dxeload`

Synopsis: Load DXE file in memory

Declaration: `function dxeload(filename: String) : pointer`

Visibility: `default`

Description: `dxeload` loads the contents of the file `filename` into memory. It performs the necessary relocations in the object code, and returns then a pointer to the entry point of the code.

For an example, see the `emu387` ([494](#)) unit in the RTL.

Errors: If an error occurs during the load or relocations, `Nil` is returned.

Chapter 7

Reference for unit 'dynlibs'

7.1 Overview

The Dynlibs unit provides support for dynamically loading shared libraries. It is available only on those platforms that support shared libraries. The functionality available here may only be a part of the functionality available on each separate platform, in the interest of portability.

On unix platforms, using this unit will cause the program to be linked to the C library, as most shared libraries are implemented in C and the dynamical linker too.

7.2 Constants, types and variables

7.2.1 Constants

```
NilHandle = TLibHandle ( 0 )
```

Correctly typed Nil handle - returned on error by LoadLibrary ([492](#))

7.2.2 Types

```
HModule = TLibHandle
```

Alias for TLibHandle ([491](#)) type.

```
TLibHandle = PtrInt
```

TLibHandle should be considered an opaque type. It is defined differently on various platforms. The definition shown here depends on the platform for which the documentation was generated.

7.3 Procedures and functions

7.3.1 FreeLibrary

Synopsis: For compatibility with Delphi/Windows: Unload a library

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `FreeLibrary` provides the same functionality as `UnloadLibrary` (493), and is provided for compatibility with Delphi.

See also: `UnloadLibrary` (493)

7.3.2 GetProcAddress

Synopsis: For compatibility with Delphi/Windows: Get the address of a procedure

Declaration: `function GetProcAddress(Lib: TLibHandle; ProcName: AnsiString) : Pointer`

Visibility: default

Description: `GetProcAddress` provides the same functionality as `GetProcedureAddress` (492), and is provided for compatibility with Delphi.

See also: `GetProcedureAddress` (492)

7.3.3 GetProcedureAddress

Synopsis: Get the address of a procedure or symbol in a dynamic library.

Declaration: `function GetProcedureAddress(Lib: TLibHandle; ProcName: AnsiString)
: Pointer`

Visibility: default

Description: `GetProcedureAddress` returns a pointer to the location in memory of the symbol `ProcName` in the dynamically loaded library specified by its handle `lib`. If the symbol cannot be found or the handle is invalid, `Nil` is returned.

On Windows, only an exported procedure or function can be searched this way. On Unix platforms the location of any exported symbol can be retrieved this way.

Errors: If the symbol cannot be found, `Nil` is returned.

See also: `LoadLibrary` (492), `UnLoadLibrary` (493)

7.3.4 LoadLibrary

Synopsis: Load a dynamic library and return a handle to it.

Declaration: `function LoadLibrary(Name: AnsiString) : TLibHandle`

Visibility: default

Description: `LoadLibrary` loads a dynamic library in file `Name` and returns a handle to it. If the library cannot be loaded, `NilHandle` (491) is returned.

No assumptions should be made about the location of the loaded library if a relative pathname is specified. The behaviour is dependent on the platform. Therefore it is best to specify an absolute pathname if possible.

Errors: On error, `NilHandle` (491) is returned.

See also: `UnloadLibrary` (493), `GetProcedureAddress` (492)

7.3.5 UnloadLibrary

Synopsis: Unload a previously loaded library

Declaration: `function UnloadLibrary(Lib: TLibHandle) : Boolean`

Visibility: `default`

Description: `UnloadLibrary` unloads a previously loaded library (specified by the handle `lib`). The call returns `True` if succesful, `False` otherwisa.

Errors: On error, `False` is returned.

See also: `LoadLibrary` ([492](#)), `GetProcAddress` ([492](#))

Chapter 8

Reference for unit 'emu387'

8.1 Overview

The `emu387` unit was written by Pierre Mueller for dos. It sets up the coprocessor emulation for FPC under dos. It is not necessary to use this unit on other OS platforms because they either simply do not run on a machine without coprocessor, or they provide the coprocessor emulation themselves.

It shouldn't be necessary to use the function in this unit, it should be enough to place this unit in the `uses` clause of your program to enable the coprocessor emulation under dos. The unit initialization code will try and load the coprocessor emulation code and initialize it.

8.2 Procedures and functions

8.2.1 `npxsetup`

Synopsis: Set up coprocessor emulation.

Declaration: `procedure npxsetup(prog_name: String)`

Visibility: `default`

Description: `npxsetup` checks whether a coprocessor is found. If not, it loads the file `wmemu387.dxe` into memory and initializes the code in it.

If the environment variable `387` is set to `N`, then the emulation will be loaded, even if there is a coprocessor present. If the variable doesn't exist, or is set to any other value, the unit will try to detect the presence of a coprocessor unit.

The function searches the file `wmemu387.dxe` in the following way:

- 1.If the environment variable `EMU387` is set, then it is assumed to point at the `wmemu387.dxe` file.
- 2.if the environment variable `EMU387` does not exist, then the function will take the path part of `prog_name` and look in that directory for the file `wmemu387.dxe`.

It should never be necessary to call this function, because the initialization code of the unit contains a call to the function with as an argument `paramstr(0)`. This means that you should deliver the file `wmemu387.dxe` together with your program.

Errors: If there is an error, an error message is printed to standard error, and the program is halted, since any floating-point code is bound to fail anyhow.

Chapter 9

Reference for unit 'getopts'

9.1 Overview

This document describes the GETOPTS unit for Free Pascal. It was written for linux by Michael Van Canneyt. It now also works for all supported platforms.

The getopts unit provides a mechanism to handle command-line options in a structured way, much like the GNU getopts mechanism. It allows you to define the valid options for your program, and the unit will then parse the command-line options for you, and inform you of any errors.

9.2 Constants, types and variables

9.2.1 Constants

`EndOfOptions = #255`

Returned by `getopt` ([497](#)), `getlongopts` ([497](#)) to indicate that there are no more options.

`No_Argument = 0`

Specifies that a long option does not take an argument.

`Optional_Argument = 2`

Specifies that a long option optionally takes an argument.

`OptSpecifier : Set of Char = [' - ']`

Character indicating an option on the command-line.

`Required_Argument = 1`

Specifies that a long option needs an argument.

Table 9.1: Enumeration values for type Orderings

Value	Explanation
permute	Change command-line options.
require_order	Don't touch the ordering of the command-line options
return_in_order	Return options in the correct order.

9.2.2 Types

Orderings = (require_order, permute, return_in_order)

Command-line ordering options.

POption = ^TOption

Pointer to TOption ([496](#)) record.

```
TOption = record
  Name : String;
  Has_arg : Integer;
  Flag : PChar;
  Value : Char;
end
```

The TOption type is used to communicate the long options to GetLongOpts ([497](#)). The Name field is the name of the option. Has_arg specifies if the option wants an argument, Flag is a pointer to a char, which is set to Value, if it is non-nil.

9.2.3 Variables

OptArg : String

Set to the argument of an option, if the option needs one.

OptErr : Boolean

Indicates whether getopt() prints error messages.

OptInd : LongInt

when all options have been processed, optind is the index of the first non-option parameter. This is a read-only variable. Note that it can become equal to paramcount+1.

OptOpt : Char

In case of an error, contains the character causing the error.

9.3 Procedures and functions

9.3.1 GetLongOpts

Synopsis: Return next long option.

Declaration: `function GetLongOpts (ShortOpts: String; LongOpts: POption;
var Longind: LongInt) : Char`

Visibility: default

Description: Returns the next option found on the command-line, taking into account long options as well. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. (see [Getopt \(497\)](#) for its description and use) `LongOpts` is a pointer to the first element of an array of `Option` records, the last of which needs a name of zero length.

The function tries to match the names even partially (i.e. `-app` will match e.g. the append option), but will report an error in case of ambiguity. If the option needs an argument, set `Has_arg` to `Required_argument`, if the option optionally has an argument, set `Has_arg` to `Optional_argument`. If the option needs no argument, set `Has_arg` to zero.

Required arguments can be specified in two ways :

1. Pasted to the option : `-option=value`
2. As a separate argument : `-option value`

Optional arguments can only be specified through the first method.

Errors: see [Getopt \(497\)](#).

See also: [Getopt \(497\)](#)

9.3.2 GetOpt

Synopsis: Get next short option.

Declaration: `function GetOpt (ShortOpts: String) : Char`

Visibility: default

Description: Returns the next option found on the command-line. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. If a letter is followed by a colon (:), then that option needs an argument. If a letter is followed by 2 colons, the option has an optional argument. If the first character of `shortoptions` is a '+' then options following a non-option are regarded as non-options (standard Unix behavior). If it is a '-', then all non-options are treated as arguments of a option with character #0. This is useful for applications that require their options in the exact order as they appear on the command-line. If the first character of `shortoptions` is none of the above, options and non-options are permuted, so all non-options are behind all options. This allows options and non-options to be in random order on the command line.

Errors: Errors are reported through giving back a '?' character. `OptOpt` then gives the character which caused the error. If `OptErr` is `True` then `getopt` prints an error-message to `stdout`.

See also: [GetLongOpts \(497\)](#)

Listing: ./optex/optex.pp

```

program testopt;

{ Program to depmonstrate the getopt function. }

{
  Valid calls to this program are
  optex --verbose --add me --delete you
  optex --append --create child
  optex -ab -c me -d you
  and so on
}
uses getopt;

var c : char;
    optionindex : Longint;
    theopts : array[1..7] of TOption;

begin
  with theopts[1] do
    begin
      name := 'add';
      has_arg := 1;
      flag := nil;
      value := #0;
    end;
  with theopts[2] do
    begin
      name := 'append';
      has_arg := 0;
      flag := nil;
      value := #0;
    end;
  with theopts[3] do
    begin
      name := 'delete';
      has_arg := 1;
      flag := nil;
      value := #0;
    end;
  with theopts[4] do
    begin
      name := 'verbose';
      has_arg := 0;
      flag := nil;
      value := #0;
    end;
  with theopts[5] do
    begin
      name := 'create';
      has_arg := 1;
      flag := nil;
      value := 'c';
    end;
  with theopts[6] do
    begin
      name := 'file';
      has_arg := 1;

```

```

    flag:=nil;
    value:=#0;
end;
with theopts[7] do
    begin
        name:='';
        has_arg:=0;
        flag:=nil;
    end;
c:=#0;
repeat
    c:=getlongopts('abc:d:012',@theo[1],optionindex);
    case c of
        '1','2','3','4','5','6','7','8','9' :
            begin
                writeln('Got optind : ',c)
            end;
        #0 : begin
                write('Long option : ',theo[optionindex].name);
                if theopts[optionindex].has_arg>0 then
                    writeln(' With value : ',optarg)
                else
                    writeln
                end;
            'a' : writeln('Option a. ');
            'b' : writeln('Option b. ');
            'c' : writeln('Option c : ',optarg);
            'd' : writeln('Option d : ',optarg);
            '?' : writeln('Error with opt : ',optopt);
        end; { case }
    until c=endofoptions;
    if optind<=paramcount then
        begin
            write('Non options : ');
            while optind<=paramcount do
                begin
                    write(paramstr(optind),' ');
                    inc(optind)
                end;
            writeln
        end
    end.
end.

```

Chapter 10

Reference for unit 'go32'

10.1 Real mode callbacks

The callback mechanism can be thought of as the converse of calling a real mode procedure (i.e. interrupt), which allows your program to pass information to a real mode program, or obtain services from it in a manner that's transparent to the real mode program. In order to make a real mode callback available, you must first get the real mode callback address of your procedure and the selector and offset of a register data structure. This real mode callback address (this is a segment:offset address) can be passed to a real mode program via a software interrupt, a dos memory block or any other convenient mechanism. When the real mode program calls the callback (via a far call), the DPMI host saves the registers contents in the supplied register data structure, switches into protected mode, and enters the callback routine with the following settings:

- interrupts disabled
- `%CS : %EIP` = 48 bit pointer specified in the original call to `get_rm_callback` ([518](#))
- `%DS : %ESI` = 48 bit pointer to real mode `SS : SP`
- `%ES : %EDI` = 48 bit pointer of real mode register data structure.
- `%SS : %ESP` = locked protected mode stack
- All other registers undefined

The callback procedure can then extract its parameters from the real mode register data structure and/or copy parameters from the real mode stack to the protected mode stack. Recall that the segment register fields of the real mode register data structure contain segment or paragraph addresses that are not valid in protected mode. Far pointers passed in the real mode register data structure must be translated to virtual addresses before they can be used with a protected mode program. The callback procedure exits by executing an `IRET` with the address of the real mode register data structure in `%ES : %EDI`, passing information back to the real mode caller by modifying the contents of the real mode register data structure and/or manipulating the contents of the real mode stack. The callback procedure is responsible for setting the proper address for resumption of real mode execution into the real mode register data structure; typically, this is accomplished by extracting the return address from the real mode stack and placing it into the `%CS : %EIP` fields of the real mode register data structure. After the `IRET`, the DPMI host switches the CPU back into real mode, loads ALL registers with the contents of the real mode register data structure, and finally returns control to the real mode program. All variables and code touched by the callback procedure **MUST** be locked to prevent page faults.

See also: `get_rm_callback` ([518](#)), `free_rm_callback` ([514](#)), `lock_code` ([526](#)), `lock_data` ([527](#))

10.2 Executing software interrupts

Simply execute a `realintr()` call with the desired interrupt number and the supplied register data structure. But some of these interrupts require you to supply them a pointer to a buffer where they can store data to or obtain data from in memory. These interrupts are real mode functions and so they only can access the first Mb of linear address space, not FPC's data segment. For this reason FPC supplies a pre-initialized dos memory location within the GO32 unit. This buffer is internally used for dos functions too and so it's contents may change when calling other procedures. It's size can be obtained with `tb_size` (536) and it's linear address via `transfer_buffer` (536). Another way is to allocate a completely new dos memory area via the `global_dos_alloc` (523) function for your use and supply its real mode address.

See also: `tb_size` (536), `transfer_buffer` (536), `global_dos_alloc` (523), `global_dos_free` (525), `realintr` (529)

10.3 Software interrupts

Ordinarily, a handler installed with `set_pm_interrupt` (533) only services software interrupts that are executed in protected mode; real mode software interrupts can be redirected by `set_rm_interrupt` (534).

See also: `set_rm_interrupt` (534), `get_rm_interrupt` (521), `set_pm_interrupt` (533), `get_pm_interrupt` (518), `lock_data` (527), `lock_code` (526), `enable` (513), `disable` (511), `outportb` (528)

10.4 Hardware interrupts

Hardware interrupts are generated by hardware devices when something unusual happens; this could be a keypress or a mouse move or any other action. This is done to minimize CPU time, else the CPU would have to check all installed hardware for data in a big loop (this method is called 'polling') and this would take much time. A standard IBM-PC has two interrupt controllers, that are responsible for these hardware interrupts: both allow up to 8 different interrupt sources (IRQs, interrupt requests). The second controller is connected to the first through IRQ 2 for compatibility reasons, e.g. if controller 1 gets an IRQ 2, he hands the IRQ over to controller 2. Because of this up to 15 different hardware interrupt sources can be handled. IRQ 0 through IRQ 7 are mapped to interrupts 8h to Fh and the second controller (IRQ 8 to 15) is mapped to interrupt 70h to 77h. All of the code and data touched by these handlers MUST be locked (via the various locking functions) to avoid page faults at interrupt time. Because hardware interrupts are called (as in real mode) with interrupts disabled, the handler has to enable them before it returns to normal program execution. Additionally a hardware interrupt must send an EOI (end of interrupt) command to the responsible controller; this is accomplished by sending the value 20h to port 20h (for the first controller) or A0h (for the second controller). The following example shows how to redirect the keyboard interrupt.

10.5 Disabling interrupts

The GO32 unit provides the two procedures `disable()` and `enable()` to disable and enable all interrupts.

10.6 Creating your own interrupt handlers

Interrupt redirection with FPC pascal is done via the `set_pm_interrupt()` for protected mode interrupts or via the `set_rm_interrupt()` for real mode interrupts.

10.7 Protected mode interrupts vs. Real mode interrupts

As mentioned before, there's a distinction between real mode interrupts and protected mode interrupts; the latter are protected mode programs, while the former must be real mode programs. To call a protected mode interrupt handler, an assembly 'int' call must be issued, while the other is called via the `realintr()` or `intr()` function. Consequently, a real mode interrupt then must either reside in dos memory (<1MB) or the application must allocate a real mode callback address via the `get_rm_callback()` function.

10.8 Handling interrupts with DPMI

The interrupt functions are real-mode procedures; they normally can't be called in protected mode without the risk of an protection fault. So the DPMI host creates an interrupt descriptor table for the application. Initially all software interrupts (except for int 31h, 2Fh and 21h function 4Ch) or external hardware interrupts are simply directed to a handler that reflects the interrupt in real-mode, i.e. the DPMI host's default handlers switch the CPU to real-mode, issue the interrupt and switch back to protected mode. The contents of general registers and flags are passed to the real mode handler and the modified registers and flags are returned to the protected mode handler. Segment registers and stack pointer are not passed between modes.

10.9 Interrupt redirection

Interrupts are program interruption requests, which in one or another way get to the processor; there's a distinction between software and hardware interrupts. The former are explicitly called by an 'int' instruction and are a bit comparable to normal functions. Hardware interrupts come from external devices like the keyboard or mouse. Functions that handle hardware interrupts are called handlers.

10.10 Processor access

These are some functions to access various segment registers (`%cs`, `%ds`, `%ss`) which makes your work a bit easier.

See also: `get_cs` ([514](#)), `get_ds` ([515](#)), `get_ss` ([523](#))

10.11 I/O port access

The I/O port access is done via the various `inportb` ([525](#)), `outportb` ([528](#)) functions which are available. Additionally Free Pascal supports the Turbo Pascal `PORT[]`-arrays but it is by no means recommended to use them, because they're only for compatibility purposes.

See also: `outportb` ([528](#)), `inportb` ([525](#))

10.12 dos memory access

Dos memory is accessed by the predefined `dosmemselector` selector; the GO32 unit additionally provides some functions to help you with standard tasks, like copying memory from heap to dos memory and the likes. Because of this it is strongly recommended to use them, but you are still free

to use the provided standard memory accessing functions which use 48 bit pointers. The third, but only thought for compatibility purposes, is using the `mem[]`-arrays. These arrays map the whole 1 Mb dos space. They shouldn't be used within new programs. To convert a segment:offset real mode address to a protected mode linear address you have to multiply the segment by 16 and add its offset. This linear address can be used in combination with the `DOSMEMSELECTOR` variable.

See also: `dosmemget` (505), `dosmempnt` (505), `dosmemmove` (505), `dosmemfillchar` (504), `dosmemfillword` (504), `seg_move` (532), `seg_fillchar` (530), `seg_fillword` (531)

10.13 FPC specialities

The `%ds` and `%es` selector MUST always contain the same value or some system routines may crash when called. The `%fs` selector is preloaded with the `DOSMEMSELECTOR` variable at startup, and it MUST be restored after use, because again FPC relies on this for some functions. Luckily we asm programmers can still use the `%gs` selector for our own purposes, but for how long ?

See also: `get_cs` (514), `get_ds` (515), `get_ss` (523), `allocate_ldt_descriptors` (507), `free_ldt_descriptor` (513), `segment_to_descriptor` (530), `get_next_selector_increment_value` (517), `get_segment_base_address` (522), `set_segment_base_address` (534), `set_segment_limit` (535), `create_code_segment_alias_descriptor` (511)

10.14 Selectors and descriptors

Descriptors are a bit like real mode segments; they describe (as the name implies) a memory area in protected mode. A descriptor contains information about segment length, its base address and the attributes of it (i.e. type, access rights, ...). These descriptors are stored internally in a so-called descriptor table, which is basically an array of such descriptors. Selectors are roughly an index into this table. Because these 'segments' can be up to 4 GB in size, 32 bits aren't sufficient anymore to describe a single memory location like in real mode. 48 bits are now needed to do this, a 32 bit address and a 16 bit sized selector. The GO32 unit provides the `tseginfo` record to store such a pointer. But due to the fact that most of the time data is stored and accessed in the `%ds` selector, FPC assumes that all pointers point to a memory location of this selector. So a single pointer is still only 32 bits in size. This value represents the offset from the data segment base address to this memory location.

10.15 What is DPMI

The dos Protected Mode Interface helps you with various aspects of protected mode programming. These are roughly divided into descriptor handling, access to dos memory, management of interrupts and exceptions, calls to real mode functions and other stuff. Additionally it automatically provides swapping to disk for memory intensive applications. A DPMI host (either a Windows dos box or `CWSDPMI.EXE`) provides these functions for your programs.

10.16 Overview

This document describes the GO32 unit for the Free Pascal compiler under dos. It was donated by Thomas Schatzl (`tom_at_work@geocities.com`), for which my thanks. This unit was first written for dos by Florian Klaempfl.

Only the GO32V2 DPMI mode is discussed by me here due to the fact that new applications shouldn't be created with the older GO32V1 model. The go32v2 version is much more advanced and better. Additionally a lot of functions only work in DPMI mode anyway. I hope the following explanations and introductions aren't too confusing at all. If you notice an error or bug send it to the FPC mailing list or directly to me. So let's get started and happy and error free coding I wish you.... Thomas Schatzl, 25. August 1998

10.17 Constants, types and variables

10.17.1 Constants

```
auxcarryflag = $010
```

Check for auxiliary carry flag in `trealregs` ([507](#))

```
carryflag = $001
```

Check for carry flag in `trealregs` ([507](#))

```
directionflag = $400
```

Check for direction flag in `trealregs` ([507](#))

```
dosmemfillchar : procedure(seg: Word;ofs: Word;count: LongInt;c: Char) = @dpmi_dosmemfillchar
```

Sets a region of dos memory to a specific byte value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of bytes to set.

c value to set memory to.

Notes: No range check is performed.

```
dosmemfillword : procedure(seg: Word;ofs: Word;count: LongInt;w: Word) = @dpmi_dosmemfillword
```

Sets a region of dos memory to a specific word value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of words to set.

w value to set memory to.

Notes: No range check is performed.

```
dosmemget : procedure(seg: Word;ofs: Word;var data;count: LongInt) = @dpmi_dosmemget
```

Copies data from the dos memory onto the heap.

Parameters:

seg source real mode segment.

ofs source real mode offset.

data destination.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see [global_dos_alloc \(523\)](#).

```
dosmemmove : procedure(sseg: Word;sofs: Word;dseg: Word;dofs: Word;count: LongInt) =
```

Copies count bytes of data between two dos real mode memory locations.

Parameters:

sseg source real mode segment.

sofs source real mode offset.

dseg destination real mode segment.

dofs destination real mode offset.

count number of bytes to copy.

Notes: No range check is performed in any way.

```
dosmempout : procedure(seg: Word;ofs: Word;var data;count: LongInt) = @dpmi_dosmempout
```

Copies heap data to dos real mode memory.

Parameters:

seg destination real mode segment.

ofs destination real mode offset.

data source.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see [global_dos_alloc \(523\)](#).

```
interruptflag = $200
```

Check for interrupt flag in [trealregs \(507\)](#)

```
overflowflag = $800
```

Check for overflow flag in `trealregs` (507)

```
parityflag = $004
```

Check for parity flag in `trealregs` (507)

```
rm_dpml = 4
```

`get_run_mode` (522) return value: DPMI (e.g. dos box or 386Max)

```
rm_raw = 1
```

`get_run_mode` (522) return value: raw (without HIMEM)

```
rm_unknown = 0
```

`get_run_mode` (522) return value: Unknown runmode

```
rm_vcpi = 3
```

`get_run_mode` (522) return value: VCPI (with HIMEM and EMM386)

```
rm_xms = 2
```

`get_run_mode` (522) return value: XMS (with HIMEM, without EMM386)

```
signflag = $080
```

Check for sign flag in `trealregs` (507)

```
trapflag = $100
```

Check for trap flag in `trealregs` (507)

```
zeroflag = $040
```

Check for zero flag in `trealregs` (507)

10.17.2 Types

```
registers = trealregs
```

Alias for `trealregs` (507)

```
tmeminfo = record
  available_memory : LongInt;
  available_pages : LongInt;
  available_lockable_pages : LongInt;
  linear_space : LongInt;
  unlocked_pages : LongInt;
  available_physical_pages : LongInt;
```

```

total_physical_pages : LongInt;
free_linear_space : LongInt;
max_pages_in_paging_file : LongInt;
reserved0 : LongInt;
reserved1 : LongInt;
reserved2 : LongInt;
end

```

`tmeminfo` Holds information about the memory allocation, etc.

NOTE: The value of a field is -1 (0ffffffh) if the value is unknown, it's only guaranteed, that `available_memory` contains a valid value. The size of the pages can be determined by the `get_page_size()` function.

```

trealregs = record
end

```

The `trealregs` type contains the data structure to pass register values to a interrupt handler or real mode callback.

```

tseginfo = record
    offset : pointer;
    segment : Word;
end

```

This record is used to store a full 48-bit pointer. This may be either a protected mode selector:offset address or in real mode a segment:offset address, depending on application.

See also: Selectors and descriptors, dos memory access, Interrupt redirection

10.17.3 Variables

```
dosmemselector : Word
```

Selector to the dos memory. The whole dos memory is automatically mapped to this single descriptor at startup. This selector is the recommended way to access dos memory.

```
int31error : Word
```

This variable holds the result of a DPMI interrupt call. Any nonzero value must be treated as a critical failure.

10.18 Procedures and functions

10.18.1 `allocate_ldt_descriptors`

Synopsis: Allocate a number of descriptors

Declaration: `function allocate_ldt_descriptors(count: Word) : Word`

Visibility: default

Description: Allocates a number of new descriptors.

Parameters:

count: \ specifies the number of requested unique descriptors.

Return value: The base selector.

Remark: Notes: The descriptors allocated must be initialized by the application with other function calls. This function returns descriptors with a limit and size value set to zero. If more than one descriptor was requested, the function returns a base selector referencing the first of a contiguous array of descriptors. The selector values for subsequent descriptors in the array can be calculated by adding the value returned by the `get_next_selector_increment_value` (517) function.

Errors: Check the `int31error` (507) variable.

See also: `free_ldt_descriptor` (513), `get_next_selector_increment_value` (517), `segment_to_descriptor` (530), `create_code_segment_alias_descriptor` (511), `set_segment_limit` (535), `set_segment_base_address` (534)

Listing: `./go32ex/seldes.pp`

```
{ $mode delphi }
uses
    crt ,
    go32;

const
    maxx = 80;
    maxy = 25;
    bytespercell = 2;
    screensize = maxx * maxy * bytespercell;

    linB8000 = $B800 * 16;

type
    string80 = string[80];

var
    text_save : array[0..screensize-1] of byte;
    text_oldx , text_oldy : Word;

    text_sel : Word;

procedure status(s : string80);
begin
    gotoxy(1, 1); clreol; write(s); readkey;
end;

procedure selinfo(sel : Word);
begin
    gotoxy(1, 24);
    clreol; writeln('Descriptor base address : $',
        hexstr(get_segment_base_address(sel), 8));
    clreol; write('Descriptor limit : ', get_segment_limit(sel));
end;

function makechar(ch : char; color : byte) : Word;
```

```

begin
    result := byte(ch) or (color shl 8);
end;

begin
    seg_move(dosmemselector, linB8000, get_ds, longint(@text_save),
        screensize);
    text_oldx := wherex; text_oldy := wherey;
    seg_fillword(dosmemselector, linB8000, screensize div 2,
        makechar(' ', Black or (Black shl 4)));
    status('Creating selector ''text_sel'' to a part of ' +
        'text screen memory');
    text_sel := allocate_ldt_descriptors(1);
    set_segment_base_address(text_sel,
        linB8000 + bytespercell * maxx * 1);
    set_segment_limit(text_sel, screensize - 1 - bytespercell *
        maxx * 3);
    selinfo(text_sel);

    status('and clearing entire memory selected by ''text_sel'' +
        ' descriptor');
    seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
        makechar(' ', LightBlue shl 4));

    status('Notice that only the memory described by the ' +
        ' descriptor changed, nothing else');

    status('Now reducing it''s limit and base and setting it''s ' +
        'described memory');
    set_segment_base_address(text_sel,
        get_segment_base_address(text_sel) + bytespercell * maxx);
    set_segment_limit(text_sel,
        get_segment_limit(text_sel) - bytespercell * maxx * 2);
    selinfo(text_sel);
    status('Notice that the base addr increased by one line but ' +
        'the limit decreased by 2 lines');
    status('This should give you the hint that the limit is ' +
        'relative to the base');
    seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
        makechar(#176, LightMagenta or Brown shl 4));

    status('Now let''s get crazy and copy 10 lines of data from ' +
        'the previously saved screen');
    seg_move(get_ds, longint(@text_save), text_sel,
        maxx * bytespercell * 2, maxx * bytespercell * 10);

    status('At last freeing the descriptor and restoring the old ' +
        'screen contents..');
    status('I hope this little program may give you some hints on ' +
        'working with descriptors');
    free_ldt_descriptor(text_sel);
    seg_move(get_ds, longint(@text_save), dosmemselector,
        linB8000, screensize);
    gotoxy(text_oldx, text_oldy);
end.

```

10.18.2 allocate_memory_block

Synopsis: Allocate a block of linear memory

Declaration: `function allocate_memory_block(size: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of linear memory.

Parameters:

size:Size of requested linear memory block in bytes.

Returned values: blockhandle - the memory handle to this memory block. Linear address of the requested memory.

Remark: *warning* According to my DPMI docs this function is not implemented correctly. Normally you should also get a blockhandle to this block after successful operation. This handle can then be used to free the memory block afterwards or use this handle for other purposes. Since the function isn't implemented correctly, and doesn't return a blockhandle, the block can't be deallocated and is hence unusable ! This function doesn't allocate any descriptors for this block, it's the applications responsibility to allocate and initialize for accessing this memory.

Errors: Check the `int31error` ([507](#)) variable.

See also: `free_memory_block` ([513](#))

10.18.3 copyfromdos

Synopsis: Copy data from DOS to to heap

Declaration: `procedure copyfromdos(var addr;len: LongInt)`

Visibility: default

Description: Copies data from the pre-allocated dos memory transfer buffer to the heap.

Parameters:

addrdata to copy to.

lennumber of bytes to copy to heap.

Notes: Can only be used in conjunction with the dos memory transfer buffer.

Errors: Check the `int31error` ([507](#)) variable.

See also: `tb_size` ([536](#)), `transfer_buffer` ([536](#)), `copytodos` ([510](#))

10.18.4 copytodos

Synopsis: Copy data from heap to DOS memory

Declaration: `procedure copytodos(var addr;len: LongInt)`

Visibility: default

Description: Copies data from heap to the pre-allocated dos memory buffer.

Parameters:

addrdata to copy from.

lennumber of bytes to copy to dos memory buffer.

Notes: This function fails if you try to copy more bytes than the transfer buffer is in size. It can only be used in conjunction with the transfer buffer.

Errors: Check the `int31error` (507) variable.

See also: `tb_size` (536), `transfer_buffer` (536), `copyfromdos` (510)

10.18.5 `create_code_segment_alias_descriptor`

Synopsis: Create new descriptor from existing descriptor

Declaration: `function create_code_segment_alias_descriptor(seg: Word) : Word`

Visibility: default

Description: Creates a new descriptor that has the same base and limit as the specified descriptor.

Parameters:

segDescriptor.

Return values: The data selector (alias).

Notes: In effect, the function returns a copy of the descriptor. The descriptor alias returned by this function will not track changes to the original descriptor. In other words, if an alias is created with this function, and the base or limit of the original segment is then changed, the two descriptors will no longer map the same memory.

Errors: Check the `int31error` (507) variable.

See also: `allocate_ldt_descriptors` (507), `set_segment_limit` (535), `set_segment_base_address` (534)

10.18.6 `disable`

Synopsis: Disable hardware interrupts

Declaration: `procedure disable`

Visibility: default

Description: Disables all hardware interrupts by execution a CLI instruction.

Errors: None.

See also: `enable` (513)

10.18.7 `dpmi_dosmemfillchar`

Synopsis: Fill DOS memory with a character

Declaration: `procedure dpmi_dosmemfillchar(seg: Word; ofs: Word; count: LongInt; c: Char)`

Visibility: default

Description: `dpmi_dosmemfillchar` fills the DOS memory region indicated by `seg,ofs` with `count` characters `c`.

See also: `dpmi_dosmempur` (512), `dpmi_dosmemget` (512), `dpmi_dosmemmove` (512), `dpmi_dosmemfillword` (512)

10.18.8 dpmi_dosmemfillword

Synopsis: Fill DOS memory with a word value

Declaration: `procedure dpmi_dosmemfillword(seg: Word; ofs: Word; count: LongInt;
w: Word)`

Visibility: default

Description: `dpmi_dosmemfillword` fills the DOS memory region indicated by `seg,ofs` with `count` words `W`.

See also: `dpmi_dosmempout` (512), `dpmi_dosmemget` (512), `dpmi_dosmemfillchar` (511), `dpmi_dosmemmove` (512)

10.18.9 dpmi_dosmemget

Synopsis: Move data from DOS memory to DPMI memory

Declaration: `procedure dpmi_dosmemget(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from the DOS memory location indicated by `seg` and `ofs` to DPMI memory indicated by `data`.

See also: `dpmi_dosmempout` (512), `dpmi_dosmemmove` (512), `dpmi_dosmemfillchar` (511), `dpmi_dosmemfillword` (512)

10.18.10 dpmi_dosmemmove

Synopsis: Move DOS memory

Declaration: `procedure dpmi_dosmemmove(sseg: Word; sofs: Word; dseg: Word; dofs: Word;
count: LongInt)`

Visibility: default

Description: `dpmi_dosmemmove` moves `count` bytes from DOS memory `sseg,sofs` to `dseg,dofs`.

See also: `dpmi_dosmempout` (512), `dpmi_dosmemget` (512), `dpmi_dosmemfillchar` (511), `dpmi_dosmemfillword` (512)

10.18.11 dpmi_dosmempout

Synopsis: Move data from DPMI memory to DOS memory.

Declaration: `procedure dpmi_dosmempout(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from `data` to the DOS memory location indicated by `seg` and `ofs`.

See also: `dpmi_dosmemget` (512), `dpmi_dosmemmove` (512), `dpmi_dosmemfillchar` (511), `dpmi_dosmemfillword` (512)

10.18.12 enable

Synopsis: Enable hardware interrupts

Declaration: `procedure enable`

Visibility: default

Description: Enables all hardware interrupts by executing a STI instruction.

Errors: None.

See also: `disable` ([511](#))

10.18.13 free_ldt_descriptor

Synopsis: Free a descriptor

Declaration: `function free_ldt_descriptor(d: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated descriptor.

Parameters:

desThe descriptor to be freed.

Return value: `True` if successful, `False` otherwise. Notes: After this call this selector is invalid and must not be used for any memory operations anymore. Each descriptor allocated with `allocate_ldt_descriptors` ([507](#)) must be freed individually with this function, even if it was previously allocated as a part of a contiguous array of descriptors.

For an example, see `allocate_ldt_descriptors` ([507](#)).

Errors: Check the `int31error` ([507](#)) variable.

See also: `allocate_ldt_descriptors` ([507](#)), `get_next_selector_increment_value` ([517](#))

10.18.14 free_memory_block

Synopsis: Free allocated memory block

Declaration: `function free_memory_block(blockhandle: LongInt) : Boolean`

Visibility: default

Description: Frees a previously allocated memory block.

Parameters:

blockhandlethe handle to the memory area to free.

Return value: `True` if successful, `false` otherwise. Notes: Frees memory that was previously allocated with `allocate_memory_block` ([510](#)) . This function doesn't free any descriptors mapped to this block, it's the application's responsibility.

Errors: Check `int31error` ([507](#)) variable.

See also: `allocate_memory_block` ([510](#))

10.18.15 free_rm_callback

Synopsis: Release real mode callback.

Declaration: `function free_rm_callback(var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Releases a real mode callback address that was previously allocated with the `get_rm_callback` (518) function.

Parameters:

intaddr real mode address buffer returned by `get_rm_callback` (518) .

Return values: True if successful, False if not

For an example, see `get_rm_callback` (518).

Errors: Check the `int31error` (507) variable.

See also: `set_rm_interrupt` (534), `get_rm_callback` (518)

10.18.16 get_cs

Synopsis: Get CS selector

Declaration: `function get_cs : Word`

Visibility: default

Description: Returns the cs selector.

Return value: The content of the cs segment register.

For an example, see `set_pm_interrupt` (533).

Errors: None.

See also: `get_ds` (515), `get_ss` (523)

10.18.17 get_descriptor_access_right

Synopsis: Get descriptor's access rights

Declaration: `function get_descriptor_access_right(d: Word) : LongInt`

Visibility: default

Description: Gets the access rights of a descriptor.

Parameters:

d selector to descriptor.

Return value: Access rights bit field.

Errors: Check the `int31error` (507) variable.

See also: `set_descriptor_access_right` (532)

10.18.18 get_ds

Synopsis: Get DS Selector

Declaration: `function get_ds : Word`

Visibility: default

Description: Returns the ds selector.

Return values: The content of the ds segment register.

Errors: None.

See also: `get_cs` ([514](#)), `get_ss` ([523](#))

10.18.19 get_exception_handler

Synopsis: Return current exception handler

Declaration: `function get_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_exception_handler` returns the exception handler for exception E in intaddr. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` ([532](#)), `get_pm_exception_handler` ([518](#))

10.18.20 get_linear_addr

Synopsis: Convert physical to linear address

Declaration: `function get_linear_addr(phys_addr: LongInt; size: LongInt) : LongInt`

Visibility: default

Description: Converts a physical address into a linear address.

Parameters:

phys_addr physical address of device.

size Size of region to map in bytes.

Return value: Linear address that can be used to access the physical memory. Notes: It's the applications responsibility to allocate and set up a descriptor for access to the memory. This function shouldn't be used to map real mode addresses.

Errors: Check the `int31error` ([507](#)) variable.

See also: `allocate_ldt_descriptors` ([507](#)), `set_segment_limit` ([535](#)), `set_segment_base_address` ([534](#))

10.18.21 get_meminfo

Synopsis: Return information on the available memory

Declaration: `function get_meminfo(var meminfo: tmeminfo) : Boolean`

Visibility: default

Description: Returns information about the amount of available physical memory, linear address space, and disk space for page swapping.

Parameters:

meminfobuffer to fill memory information into.

Return values: Due to an implementation bug this function always returns `False`, but it always succeeds.

Remark: Notes: Only the first field of the returned structure is guaranteed to contain a valid value. Any fields that are not supported by the DPMI host will be set by the host to `-1` (`0FFFFFFFFH`) to indicate that the information is not available. The size of the pages used by the DPMI host can be obtained with the `get_page_size` (517) function.

Errors: Check the `int31error` (507) variable.

See also: `get_page_size` (517)

Listing: `./go32ex/meminfo.pp`

```

uses
    go32;

var
    meminfo : tmeminfo;

begin
    get_meminfo(meminfo);
    if (int31error <> 0) then begin
        Writeln('Error getting DPMI memory information... Halting');
        Writeln('DPMI error number : ', int31error);
    end else begin
        with meminfo do begin
            Writeln('Largest available free block : ',
                available_memory div 1024, ' kbytes');
            if (available_pages <> -1) then
                Writeln('Maximum available unlocked pages : ',
                    available_pages);
            if (available_lockable_pages <> -1) then
                Writeln('Maximum lockable available pages : ',
                    available_lockable_pages);
            if (linear_space <> -1) then
                Writeln('Linear address space size : ',
                    linear_space*get_page_size div 1024, ' kbytes');
            if (unlocked_pages <> -1) then
                Writeln('Total number of unlocked pages : ',
                    unlocked_pages);
            if (available_physical_pages <> -1) then
                Writeln('Total number of free pages : ',
                    available_physical_pages);
            if (total_physical_pages <> -1) then
                Writeln('Total number of physical pages : ',

```

```

                                total_physical_pages);
    if (free_linear_space <> -1) then
        WriteLn('Free linear address space : ',
                free_linear_space*get_page_size div 1024,
                ' kbytes');
    if (max_pages_in_paging_file <> -1) then
        WriteLn('Maximum size of paging file : ',
                max_pages_in_paging_file*get_page_size div 1024,
                ' kbytes');
    end;
end;
end.

```

10.18.22 get_next_selector_increment_value

Synopsis: Return selector increment value

Declaration: function get_next_selector_increment_value : Word

Visibility: default

Description: Returns the selector increment value when allocating multiple subsequent descriptors via allocate_ldt_descriptors (507).

Return value: Selector increment value.

Remark: Notes: Because allocate_ldt_descriptors (507) only returns the selector for the first descriptor and so the value returned by this function can be used to calculate the selectors for subsequent descriptors in the array.

Errors: Check the int31error (507) variable.

See also: allocate_ldt_descriptors (507), free_ldt_descriptor (513)

10.18.23 get_page_size

Synopsis: Return the page size

Declaration: function get_page_size : LongInt

Visibility: default

Description: Returns the size of a single memory page.

Return value: Size of a single page in bytes.

Remark: The returned size is typically 4096 bytes.

For an example, see get_meminfo (516).

Errors: Check the int31error (507) variable.

See also: get_meminfo (516)

10.18.24 `get_pm_exception_handler`

Synopsis: Get protected mode exception handler

Declaration: `function get_pm_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_pm_exception_handler` returns the protected mode exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` (515), `set_pm_exception_handler` (533)

10.18.25 `get_pm_interrupt`

Synopsis: Return protected mode interrupt handler

Declaration: `function get_pm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the address of a current protected mode interrupt handler.

Parameters:

vector interrupt handler number you want the address to.

intaddr buffer to store address.

Return values: `True` if successful, `False` if not.

Remark: The returned address is a protected mode selector:offset address.

For an example, see `set_pm_interrupt` (533).

Errors: Check the `int31error` (507) variable.

See also: `set_pm_interrupt` (533), `set_rm_interrupt` (534), `get_rm_interrupt` (521)

10.18.26 `get_rm_callback`

Synopsis: Return real mode callback

Declaration: `function get_rm_callback(pm_func: pointer; const reg: trealregs; var rmcb: tseginfo) : Boolean`

Visibility: default

Description: Returns a unique real mode `segment:offset` address, known as a "real mode callback," that will transfer control from real mode to a protected mode procedure.

Parameters:

pm_func pointer to the protected mode callback function.

reg supplied registers structure.

rmcb buffer to real mode address of callback function.

Return values: `True` if successful, otherwise `False`.

Remark: Callback addresses obtained with this function can be passed by a protected mode program for example to an interrupt handler, device driver, or TSR, so that the real mode program can call procedures within the protected mode program or notify the protected mode program of an event. The contents of the supplied `regs` structure is not valid after function call, but only at the time of the actual callback.

Errors: Check the `int31error` (507) variable.

See also: `free_rm_callback` (514)

Listing: `./go32ex/callback.pp`

```

{$ASMMODE ATT}
{$MODE FPC}

uses
    crt ,
    go32;

const
    mouseint = $33;

var
    mouse_regs      : trealregs; external name '___v2prt0_rmcb_regs';
    mouse_seginfo   : tseginfo;

var
    mouse_numbuttons : longint;

    mouse_action     : word;
    mouse_x, mouse_y : Word;
    mouse_b          : Word;

    userproc_installed : Longbool;
    userproc_length    : Longint;
    userproc_proc      : pointer;

procedure callback_handler; assembler;
asm
    pushw %ds
    pushl %eax
    movw %es, %ax
    movw %ax, %ds

    cmpl $1, USERPROC_INSTALLED
    jne .LNoCallback
    pushal
    movw DOSmemSELECTOR, %ax
    movw %ax, %fs
    call *USERPROC_PROC
    popal
.LNoCallback:

    popl %eax
    popw %ds

    pushl %eax

```

```

    movl (%esi), %eax
    movl %eax, %es: 42(%edi)
    addw $4, %es:46(%edi)
    popl %eax
    iret
end;
procedure mouse_dummy; begin end;

procedure textuserproc;
begin
    mouse_b := mouse_regs.bx;
    mouse_x := (mouse_regs.cx shr 3) + 1;
    mouse_y := (mouse_regs.dx shr 3) + 1;
end;

procedure install_mouse(userproc : pointer; userproclen : longint);
var r : trealregs;
begin
    r.eax := $0; realintr(mouseint, r);
    if (r.eax <> $FFFF) then begin
        WriteLn('No Microsoft compatible mouse found');
        WriteLn('A Microsoft compatible mouse driver is necessary ',
            'to run this example');
        halt;
    end;
    if (r.bx = $ffff) then mouse_numbuttons := 2
    else mouse_numbuttons := r.bx;
    WriteLn(mouse_numbuttons, ' button Microsoft compatible mouse ',
        ' found. ');
    if (userproc <> nil) then begin
        userproc_proc := userproc;
        userproc_installed := true;
        userproc_length := userproclen;
        lock_code(userproc_proc, userproc_length);
    end else begin
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    lock_data(mouse_x, sizeof(mouse_x));
    lock_data(mouse_y, sizeof(mouse_y));
    lock_data(mouse_b, sizeof(mouse_b));
    lock_data(mouse_action, sizeof(mouse_action));

    lock_data(userproc_installed, sizeof(userproc_installed));
    lock_data(userproc_proc, sizeof(userproc_proc));

    lock_data(mouse_regs, sizeof(mouse_regs));
    lock_data(mouse_seginf, sizeof(mouse_seginf));
    lock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    get_rm_callback(@callback_handler, mouse_regs, mouse_seginf);
    r.eax := $0c; r.ecx := $7f;
    r.edx := longint(mouse_seginf.offset);
    r.es := mouse_seginf.segment;
    realintr(mouseint, r);
    r.eax := $01;
    realintr(mouseint, r);

```

```

end;

procedure remove_mouse;
var
    r : trealregs;
begin
    r.eax := $02; realintr(mouseint, r);
    r.eax := $0c; r.ecx := 0; r.edx := 0; r.es := 0;
    realintr(mouseint, r);
    free_rm_callback(mouse_seginfo);
    if (userproc_installed) then begin
        unlock_code(userproc_proc, userproc_length);
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    unlock_data(mouse_x, sizeof(mouse_x));
    unlock_data(mouse_y, sizeof(mouse_y));
    unlock_data(mouse_b, sizeof(mouse_b));
    unlock_data(mouse_action, sizeof(mouse_action));

    unlock_data(userproc_proc, sizeof(userproc_proc));
    unlock_data(userproc_installed, sizeof(userproc_installed));

    unlock_data(mouse_regs, sizeof(mouse_regs));
    unlock_data(mouse_seginfo, sizeof(mouse_seginfo));
    unlock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    fillchar(mouse_seginfo, sizeof(mouse_seginfo), 0);
end;

begin
    install_mouse(@textuserproc, 400);
    Writeln('Press any key to exit...');
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('MouseX : ', mouse_x:2, ' MouseY : ', mouse_y:2,
            ' Buttons : ', mouse_b:2);
    end;
    remove_mouse;
end.

```

10.18.27 get_rm_interrupt

Synopsis: Get real mode interrupt vector

Declaration: `function get_rm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the contents of the current machine's real mode interrupt vector for the specified interrupt.

Parameters:

vector interrupt vector number.

intaddr buffer to store real mode segment:offset address.

Return values: `True` if successful, `False` otherwise.

Remark: The returned address is a real mode segment address, which isn't valid in protected mode.

Errors: Check the `int31error` (507) variable.

See also: `set_rm_interrupt` (534), `set_pm_interrupt` (533), `get_pm_interrupt` (518)

10.18.28 `get_run_mode`

Synopsis: Return current run mode

Declaration: `function get_run_mode : Word`

Visibility: `default`

Description: Returns the current mode your application runs with.

Return values: One of the constants used by this function.

Errors: None.

See also: `get_run_mode` (522)

Listing: `./go32ex/getrunmd.pp`

```

uses
    go32;

begin
    case (get_run_mode) of
        rm_unknown :
            WriteLn ('Unknown environment found');
        rm_raw :
            WriteLn ('You are currently running in raw mode ',
                '(without HIMEM)');
        rm_xms :
            WriteLn ('You are currently using HIMEM.SYS only');
        rm_vcpi :
            WriteLn ('VCPI server detected. You''re using HIMEM and ',
                'EMM386');
        rm_dpml :
            WriteLn ('DPML detected. You''re using a DPML host like ',
                'a windows DOS box or CWSDPML');
    end;
end.
```

10.18.29 `get_segment_base_address`

Synopsis: Return base address from descriptor table

Declaration: `function get_segment_base_address(d: Word) : LongInt`

Visibility: `default`

Description: Returns the 32-bit linear base address from the descriptor table for the specified segment.

Parameters:

`d` selector of the descriptor you want the base address of.

Return values: Linear base address of specified descriptor.

For an example, see `allocate_ldt_descriptors` (507).

Errors: Check the `int31error` (507) variable.

See also: `allocate_ldt_descriptors` (507), `set_segment_base_address` (534), `allocate_ldt_descriptors` (507), `set_segment_limit` (535), `get_segment_limit` (523)

10.18.30 `get_segment_limit`

Synopsis: Return segment limit from descriptor

Declaration: `function get_segment_limit(d: Word) : LongInt`

Visibility: default

Description: Returns a descriptors segment limit.

Parameters:

dselector.

Return value: Limit of the descriptor in bytes.

Errors: Returns zero if descriptor is invalid.

See also: `allocate_ldt_descriptors` (507), `set_segment_limit` (535), `set_segment_base_address` (534), `get_segment_base_address` (522)

10.18.31 `get_ss`

Synopsis: Return SS selector

Declaration: `function get_ss : Word`

Visibility: default

Description: Returns the ss selector.

Return values: The content of the ss segment register.

Errors: None.

See also: `get_ds` (515), `get_cs` (514)

10.18.32 `global_dos_alloc`

Synopsis: Allocate DOS real mode memory

Declaration: `function global_dos_alloc(bytes: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of dos real mode memory.

Parameters:

bytesize of requested real mode memory.

Return values: The low word of the returned value contains the selector to the allocated dos memory block, the high word the corresponding real mode segment value. The offset value is always zero. This function allocates memory from dos memory pool, i.e. memory below the 1 MB boundary that is controlled by dos. Such memory blocks are typically used to exchange data with real mode programs, TSRs, or device drivers. The function returns both the real mode segment base address of the block and one descriptor that can be used by protected mode applications to access the block. This function should only be used for temporary buffers to get real mode information (e.g. interrupts that need a data structure in ES:(E)DI), because every single block needs an unique selector. The returned selector should only be freed by a `global_dos_free` (525) call.

Errors: Check the `int31error` (507) variable.

See also: `global_dos_free` (525)

Listing: `./go32ex/buffer.pp`

```

uses
    go32;

procedure dosalloc(var selector : word;
    var segment : word; size : longint);
var
    res : longint;
begin
    res := global_dos_alloc(size);
    selector := word(res);
    segment := word(res shr 16);
end;

procedure dosfree(selector : word);
begin
    global_dos_free(selector);
end;

type
    VBEInfoBuf = packed record
        Signature : array[0..3] of char;
        Version : Word;
        reserved : array[0..505] of byte;
    end;

var
    selector ,
    segment : Word;

    r : trealregs;
    infobuf : VBEInfoBuf;

begin
    fillchar(r, sizeof(r), 0);
    fillchar(infobuf, sizeof(VBEInfoBuf), 0);
    dosalloc(selector, segment, sizeof(VBEInfoBuf));
    if (int31error <> 0) then begin
        WriteLn('Error while allocating real mode memory, halting');
        halt;
    end;
    infobuf.Signature := 'VBE2';
    dosmempnt(segment, 0, infobuf, sizeof(infobuf));

```

```

    r.ax := $4f00; r.es := segment;
    realintr($10, r);
    dosmemget(segment, 0, infobuf, sizeof(infobuf));
    dosfree(selector);
    if (r.ax <> $4f) then begin
        Writeln('VBE BIOS extension not available, function call ',
            'failed');
        halt;
    end;
    if (infobuf.signature[0] = 'V') and
        (infobuf.signature[1] = 'E') and
        (infobuf.signature[2] = 'S') and
        (infobuf.signature[3] = 'A') then begin
        Writeln('VBE version ', hi(infobuf.version), '.',
            lo(infobuf.version), ' detected');
    end;
end.

```

10.18.33 global_dos_free

Synopsis: Free DOS memory block

Declaration: `function global_dos_free(selector: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated dos memory block.

Parameters:

selector selector to the dos memory block.

Return value: `True` if successful, `False` otherwise.

Remark: The descriptor allocated for the memory block is automatically freed and hence invalid for further use. This function should only be used for memory allocated by `global_dos_alloc` (523).

For an example, see `global_dos_alloc` (523).

Errors: Check the `int31error` (507) variable.

See also: `global_dos_alloc` (523)

10.18.34 inportb

Synopsis: Read byte from I/O port

Declaration: `function inportb(port: Word) : Byte`

Visibility: default

Description: Reads 1 byte from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (528), `inportw` (526), `inportl` (526)

10.18.35 inportl

Synopsis: Read longint from I/O port

Declaration: `function inportl(port: Word) : LongInt`

Visibility: default

Description: Reads 1 longint from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` ([528](#)), `inportb` ([525](#)), `inportw` ([526](#))

10.18.36 inportw

Synopsis: Read word from I/O port

Declaration: `function inportw(port: Word) : Word`

Visibility: default

Description: Reads 1 word from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportw` ([529](#)), `inportb` ([525](#)), `inportl` ([526](#))

10.18.37 lock_code

Synopsis: Lock code memory range

Declaration: `function lock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which is in the code segment selector.

Parameters:

functionaddr address of the function to be locked.

size size in bytes to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` ([518](#)).

Errors: Check the `int31error` ([507](#)) variable.

See also: `lock_linear_region` ([527](#)), `lock_data` ([527](#)), `unlock_linear_region` ([537](#)), `unlock_data` ([537](#)), `unlock_code` ([536](#))

10.18.38 lock_data

Synopsis: Lock data memory range

Declaration: `function lock_data(var data;size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which resides in the data segment selector.

Parameters:

data address of data to be locked.

size length of data to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (518).

Errors: Check the `int31error` (507) variable.

See also: `lock_linear_region` (527), `lock_code` (526), `unlock_linear_region` (537), `unlock_data` (537), `unlock_code` (536)

10.18.39 lock_linear_region

Synopsis: Lock linear memory region

Declaration: `function lock_linear_region(linearaddr: LongInt;size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory region to prevent swapping of it.

Parameters:

linearaddr the linear address of the memory are to be locked.

size size in bytes to be locked.

Return value: `True` if successful, `False` otherwise.

Errors: Check the `int31error` (507) variable.

See also: `lock_data` (527), `lock_code` (526), `unlock_linear_region` (537), `unlock_data` (537), `unlock_code` (536)

10.18.40 map_device_in_memory_block

Synopsis: Map a device into program's memory space

Declaration: `function map_device_in_memory_block(handle: LongInt;offset: LongInt;
pagecount: LongInt;device: LongInt)
: Boolean`

Visibility: default

Description: `map_device_in_memory_block` allows to map a device in memory. This function is a direct call of the extender. For more information about it's arguments, see the extender documentation.

10.18.41 outportb

Synopsis: Write byte to I/O port

Declaration: `procedure outportb(port: Word; data: Byte)`

Visibility: default

Description: Sends 1 byte of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

Errors: None.

See also: `inportb` ([525](#)), `outportl` ([528](#)), `outportw` ([529](#))

Listing: `./go32ex/outport.pp`

uses

`crt ,
go32;`

begin

`outportb($61, $ff);
delay(50);
outportb($61, $0);`

end.

10.18.42 outportl

Synopsis: Write longint to I/O port

Declaration: `procedure outportl(port: Word; data: LongInt)`

Visibility: default

Description: Sends 1 longint of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see `outportb` ([528](#)).

Errors: None.

See also: `inportl` ([526](#)), `outportw` ([529](#)), `outportb` ([528](#))

10.18.43 outportw

Synopsis: Write word to I/O port

Declaration: `procedure outportw(port: Word; data: Word)`

Visibility: default

Description: Sends 1 word of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see `outportb` (528).

Errors: None.

See also: `inportw` (526), `outportl` (528), `outportb` (528)

10.18.44 realintr

Synopsis: Simulate interrupt

Declaration: `function realintr(intnr: Word; var regs: trealregs) : Boolean`

Visibility: default

Description: Simulates an interrupt in real mode.

Parameters:

intnr interrupt number to issue in real mode.

regs registers data structure.

Return values: The supplied registers data structure contains the values that were returned by the real mode interrupt. `True` if successful, `False` if not.

Remark: The function transfers control to the address specified by the real mode interrupt vector of `intnr`. The real mode handler must return by executing an `IRET`.

Errors: Check the `int31error` (507) variable.

Listing: `./go32ex/flags.pp`

```

uses
    go32;

var
    r : trealregs;

begin
    r.ax := $5300;
    r.bx := 0;
    realintr($15, r);
    if ((r.flags and carryflag)=0) then begin
        WriteLn('APM v', (r.ah and $f), '.',
                (r.al shr 4), (r.al and $f), ' detected');
    end else
        WriteLn('APM not present');
end.

```

10.18.45 request_linear_region

Synopsis: Request linear address region.

Declaration: `function request_linear_region(linearaddr: LongInt; size: LongInt;
var blockhandle: LongInt) : Boolean`

Visibility: default

Description: `request_linear_region` requests a linear range of addresses of size `Size`, starting at `linearaddr`. If successful, `True` is returned, and a handle to the address region is returned in `blockhandle`.

Errors: On error, `False` is returned.

10.18.46 segment_to_descriptor

Synopsis: Map segment address to descriptor

Declaration: `function segment_to_descriptor(seg: Word) : Word`

Visibility: default

Description: Maps a real mode segment (paragraph) address onto an descriptor that can be used by a protected mode program to access the same memory.

Parameters:

seg the real mode segment you want the descriptor to.

Return values: Descriptor to real mode segment address.

Remark: The returned descriptors limit will be set to 64 kB. Multiple calls to this function with the same segment address will return the same selector. Descriptors created by this function can never be modified or freed. Programs which need to examine various real mode addresses using the same selector should use the function `allocate_ldt_descriptors` (507) and change the base address as necessary.

For an example, see `seg_fillchar` (530).

Errors: Check the `int31error` (507) variable.

See also: `allocate_ldt_descriptors` (507), `free_ldt_descriptor` (513), `set_segment_base_address` (534)

10.18.47 seg_fillchar

Synopsis: Fill segment with byte value

Declaration: `procedure seg_fillchar(seg: Word; ofs: LongInt; count: LongInt; c: Char)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of bytes to set.

c byte data which is set.

Return values: None.

Notes: No range check is done in any way.

Errors: None.

See also: [seg_move \(532\)](#), [seg_fillword \(531\)](#), [dosmemfillchar \(504\)](#), [dosmemfillword \(504\)](#), [dosmemget \(505\)](#), [dosmempget \(505\)](#), [dosmemmove \(505\)](#)

Listing: ./go32ex/vgasel.pp

```

uses
    go32;

var
    vgasel : Word;
    r : trealregs;

begin
    r.eax := $13; realintr($10, r);
    vgasel := segment_to_descriptor($A000);
    seg_fillchar(vgasel, 0, 64000, #15);
    readln;
    r.eax := $3; realintr($10, r);
end.

```

10.18.48 seg_fillword

Synopsis: Fill segment with word value

Declaration: `procedure seg_fillword(seg: Word; ofs: LongInt; count: LongInt; w: Word)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of words to set.

w word data which is set.

Return values: None.

Notes: No range check is done in any way.

For an example, see [allocate_ldt_descriptors \(507\)](#).

Errors: None.

See also: [seg_move \(532\)](#), [seg_fillchar \(530\)](#), [dosmemfillchar \(504\)](#), [dosmemfillword \(504\)](#), [dosmemget \(505\)](#), [dosmempget \(505\)](#), [dosmemmove \(505\)](#)

10.18.49 seg_move

Synopsis: Move data between 2 locations

Declaration: `procedure seg_move(sseg: Word; source: LongInt; dseg: Word; dest: LongInt; count: LongInt)`

Visibility: default

Description: Copies data between two memory locations.

Parameters:

ssegsource selector.

sourcesource offset.

dsegdestination selector.

destdestination offset.

countsize in bytes to copy.

Return values: None.

Remark: Overlapping is only checked if the source selector is equal to the destination selector. No range check is done.

For an example, see `allocate_ldt_descriptors` (507).

Errors: None.

See also: `seg_fillchar` (530), `seg_fillword` (531), `dosmemfillchar` (504), `dosmemfillword` (504), `dosmemget` (505), `dosmemput` (505), `dosmemmove` (505)

10.18.50 set_descriptor_access_right

Synopsis: Set access rights to memory descriptor

Declaration: `function set_descriptor_access_right(d: Word; w: Word) : LongInt`

Visibility: default

Description: `set_descriptor_access_right` sets the access rights for descriptor `d` to `w`

10.18.51 set_exception_handler

Synopsis: Set exception handler

Declaration: `function set_exception_handler(e: Byte; const intaddr: tseginfo) : Boolean`

Visibility: default

Description: `set_exception_handler` sets the exception handler for exception `E` to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` (515), `set_pm_exception_handler` (533)

10.18.52 set_pm_exception_handler

Synopsis: Set protected mode exception handler

Declaration: `function set_pm_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_pm_exception_handler` sets the protected mode exception handler for exception E to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (532), `get_pm_exception_handler` (518)

10.18.53 set_pm_interrupt

Synopsis: Set protected mode interrupt handler

Declaration: `function set_pm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets the address of the protected mode handler for an interrupt.

Parameters:

vector number of protected mode interrupt to set.

intaddr selector:offset address to the interrupt vector.

Return values: `True` if successful, `False` otherwise.

Remark: The address supplied must be a valid `selector:offset` protected mode address.

Errors: Check the `int31error` (507) variable.

See also: `get_pm_interrupt` (518), `set_rm_interrupt` (534), `get_rm_interrupt` (521)

Listing: `./go32ex/intpm.pp`

uses

`crt ,
go32;`

const

`int1c = $1c;`

var

`oldint1c : tseginfo;
newint1c : tseginfo;`

`int1c_counter : Longint;`

`int1c_ds : Word; external name '___v2prt0_ds_alias';`

procedure `int1c_handler`; **assembler**;

asm

`cli
pushw %ds
pushw %ax`

```

    movw %cs:int1c_ds, %ax
    movw %ax, %ds
    incl int1c_counter
    popw %ax
    popw %ds
    sti
    iret
end;

var i : Longint;

begin
    newint1c.offset := @int1c_handler;
    newint1c.segment := get_cs;
    get_pm_interrupt(int1c, oldint1c);
    Writeln('-- Press any key to exit --');
    set_pm_interrupt(int1c, newint1c);
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('Number of interrupts occurred : ', int1c_counter);
    end;
    set_pm_interrupt(int1c, oldint1c);
end.

```

10.18.54 set_rm_interrupt

Synopsis: Set real mode interrupt handler

Declaration: `function set_rm_interrupt(vector: Byte; const intaddr: tseginfo) : Boolean`

Visibility: default

Description: Sets a real mode interrupt handler.

Parameters:

vector the interrupt vector number to set.

intaddr address of new interrupt vector.

Return values: True if successful, otherwise False.

Remark: The address supplied MUST be a real mode segment address, not a selector:offset address. So the interrupt handler must either reside in dos memory (below 1 Mb boundary) or the application must allocate a real mode callback address with `get_rm_callback` (518).

Errors: Check the `int31error` (507) variable.

See also: `get_rm_interrupt` (521), `set_pm_interrupt` (533), `get_pm_interrupt` (518), `get_rm_callback` (518)

10.18.55 set_segment_base_address

Synopsis: Set descriptor's base address

Declaration: `function set_segment_base_address(d: Word; s: LongInt) : Boolean`

Visibility: default

Description: Sets the 32-bit linear base address of a descriptor.

Parameters:

dselector.

snew base address of the descriptor.

Errors: Check the `int31error` (507) variable.

See also: `allocate_ldt_descriptors` (507), `get_segment_base_address` (522), `allocate_ldt_descriptors` (507), `set_segment_limit` (535), `get_segment_base_address` (522), `get_segment_limit` (523)

10.18.56 `set_segment_limit`

Synopsis: Set descriptor limit

Declaration: `function set_segment_limit(d: Word; s: LongInt) : Boolean`

Visibility: default

Description: Sets the limit of a descriptor.

Parameters:

dselector.

snew limit of the descriptor.

Return values: Returns `True` if successful, else `False`.

Remark: The new limit specified must be the byte length of the segment - 1. Segment limits bigger than or equal to 1MB must be page aligned, they must have the lower 12 bits set.

For an example, see `allocate_ldt_descriptors` (507).

Errors: Check the `int31error` (507) variable.

See also: `allocate_ldt_descriptors` (507), `set_segment_base_address` (534), `get_segment_limit` (523), `set_segment_limit` (535)

10.18.57 `tb_offset`

Synopsis: Return DOS transfer buffer offset

Declaration: `function tb_offset : LongInt`

Visibility: default

Description: `tb_offset` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (536), `tb_segment` (535), `tb_size` (536)

10.18.58 `tb_segment`

Synopsis: Return DOS transfer buffer segment

Declaration: `function tb_segment : LongInt`

Visibility: default

Description: `tb_segment` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (536), `tb_offset` (535), `tb_size` (536)

10.18.59 tb_size

Synopsis: Return DOS transfer memory buffer size

Declaration: `function tb_size : LongInt`

Visibility: default

Description: Returns the size of the pre-allocated dos memory buffer.

Return values: The size of the pre-allocated dos memory buffer. This block always seems to be 16k in size, but don't rely on this.

Errors: None.

See also: `transfer_buffer` (536), `copyfromdos` (510), `copytodos` (510)

10.18.60 transfer_buffer

Synopsis: Return offset of DOS transfer buffer

Declaration: `function transfer_buffer : LongInt`

Visibility: default

Description: `transfer_buffer` returns the offset of the transfer buffer.

Errors: None.

See also: `tb_size` (536)

10.18.61 unlock_code

Synopsis: Unlock code segment

Declaration: `function unlock_code(functionaddr: pointer;size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the code segment selector.

Parameters:

functionaddr address of function to be unlocked.

size size bytes to be unlocked.

Return value: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (518).

Errors: Check the `int31error` (507) variable.

See also: `unlock_linear_region` (537), `unlock_data` (537), `lock_linear_region` (527), `lock_data` (527), `lock_code` (526)

10.18.62 unlock_data

Synopsis: Unlock data segment

Declaration: `function unlock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the data segment selector.

Parameters:

data address of memory to be unlocked.

size size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (518).

Errors: Check the `int31error` (507) variable.

See also: `unlock_linear_region` (537), `unlock_code` (536), `lock_linear_region` (527), `lock_data` (527), `lock_code` (526)

10.18.63 unlock_linear_region

Synopsis: Unlock linear memory region

Declaration: `function unlock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Unlocks a previously locked linear region range to allow it to be swapped out again if needed.

Parameters:

linearaddr linear address of the memory to be unlocked.

size size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` (507) variable.

See also: `unlock_data` (537), `unlock_code` (536), `lock_linear_region` (527), `lock_data` (527), `lock_code` (526)

Chapter 11

Reference for unit 'gpm'

11.1 Used units

Table 11.1: Used units by unit 'gpm'

Name	Page
baseUnix	538

11.2 Overview

The GPM unit implements an interface to `libgpm`, the console program for mouse handling. This unit was created by Peter Vreman, and is only available on linux.

When this unit is used, your program is linked to the C libraries, so you must take care of the C library version. Also, it will only work with version 1.17 or higher of the `libgpm` library.

11.3 Constants, types and variables

11.3.1 Constants

`GPM_BOT` = 2

Bottom of area.

`GPM_B_LEFT` = 4

Left mouse button identifier.

`GPM_B_MIDDLE` = 2

Middle mouse button identifier.

`GPM_B_RIGHT` = 1

Right mouse button identifier.

GPM_DOUBLE = 32

Mouse double click event.

GPM_DOWN = 4

Mouse button down event.

GPM_DRAG = 2

Mouse drag event.

GPM_ENTER = 512

Enter area event.

GPM_HARD = 256

?

GPM_LEAVE = 1024

Leave area event.

GPM_LEFT = 4

Left side of area.

GPM_MAGIC = \$47706D4C

Constant identifying GPM in gpm_Open ([546](#)).

GPM_MFLAG = 128

Motion flag.

GPM_MOVE = 1

Mouse move event.

GPM_NODE_CTL = GPM_NODE_DEV

Control socket

GPM_NODE_DEV = '/dev/gpmctl'

Device socket filename

GPM_NODE_DIR = _PATH_VARRUN

Where to write socket.

`GPM_NODE_DIR_MODE = 0775`

Mode of socket.

`GPM_NODE_FIFO = '/dev/gpmdata'`

FIFO name

`GPM_NODE_PID = '/var/run/gpm.pid'`

Name of PID file.

`GPM_RGT = 8`

Right side of area.

`GPM_SINGLE = 16`

Mouse single click event.

`GPM_TOP = 1`

Top of area.

`GPM_TRIPLE = 64`

Mouse triple click event.

`GPM_UP = 8`

Mouse button up event.

`_PATH_DEV = '/dev/'`

Location of `/dev` directory.

`_PATH_VARRUN = '/var/run/'`

Location of run PID files directory.

11.3.2 Types

`Pgpmconnect = Pgpm_connect`

Pointer to `TGpmConnect` (542) record.

`Pgpmevent = Pgpm_event`

Pointer to TGpmEvent (542) record

```
Pgpmroi = Pgpm_roi
```

Pointer to TGpmRoi (542) record.

```
Pgpm_connect = ^TGpm_connect
```

Pointer to TGpm_Connect (542) record.

```
Pgpm_event = ^Tgpm_event
```

Pointer to TGpm_Event (542) record

```
Pgpm_roi = ^Tgpm_roi
```

Pointer to Tgpm_roi (542) record.

```
Tgpmconnect = Tgpm_connect
```

Alias for TGpm_Connect (542) record.

```
TGpmEtype = LongInt
```

Type for event type.

```
Tgpmevent = Tgpm_event
```

Alias for TGPM_EVent (542) record

```
TGpmHandler = function(var event: Tgpmevent; clientdata: pointer)
                  : LongInt
```

Mouse event handler callback.

```
TGpmMargin = LongInt
```

Type to hold area margin.

```
Tgpmroi = Tgpm_roi
```

Alias for TGpm_roi (542)Record

```
Tgpm_connect = packed record
  eventMask : Word;
  defaultMask : Word;
  minMod : Word;
  maxMod : Word;
  pid : LongInt;
  vc : LongInt;
end
```

GPM server connection information.

```
Tgpm_event = packed record
  buttons : Byte;
  modifiers : Byte;
  vc : Word;
  dx : Word;
  dy : Word;
  x : Word;
  y : Word;
  EventType : TGpmEtype;
  clicks : LongInt;
  margin : TGpmMargin;
  wdx : Word;
  wdy : Word;
end
```

Tgpm_event describes the events that are reported by GPM.

```
Tgpm_roi = packed record
  xmin : Integer;
  xmax : Integer;
  ymin : Integer;
  ymax : Integer;
  minmod : Word;
  maxmod : Word;
  eventmask : Word;
  owned : Word;
  handler : TGpmHandler;
  clientdata : pointer;
  prev : Pgpm_roi;
  next : Pgpm_roi;
end
```

Record used to define regions of interest.

11.3.3 Variables

```
gpm_current_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

```
gpm_handler : TGpmHandler
```

Internal gpm library variable. Do not use.

```
gpm_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

```
gpm_roi_data : pointer
```

Internal gpm library variable. Do not use.

`gpm_roi_handler : TGpmHandler`

Internal gpm library variable. Do not use.

11.4 Procedures and functions

11.4.1 Gpm_AnyDouble

Synopsis: Check whether event has double click event.

Declaration: `function Gpm_AnyDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnyDouble` returns True if `EventType` contains the `GPM_DOUBLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (548), `Gpm_AnySingle` (543), `Gpm_StrictDouble` (548), `Gpm_StrictTriple` (548), `Gpm_AnyTriple` (543)

11.4.2 Gpm_AnySingle

Synopsis: Check whether event has a single click event.

Declaration: `function Gpm_AnySingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_SINGLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (548), `Gpm_AnyDouble` (543), `Gpm_StrictDouble` (548), `Gpm_StrictTriple` (548), `Gpm_AnyTriple` (543)

11.4.3 Gpm_AnyTriple

Synopsis: Check whether event has a triple click event.

Declaration: `function Gpm_AnyTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_TRIPLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (548), `Gpm_AnyDouble` (543), `Gpm_StrictDouble` (548), `Gpm_StrictTriple` (548), `Gpm_AnySingle` (543)

11.4.4 gpm_close

Synopsis: Close connection to GPM server.

Declaration: `function gpm_close : LongInt`

Visibility: default

Description: `Gpm_Close` closes the current connection, and pops the connection stack; this means that the previous connection becomes active again.

The function returns -1 if the current connection is not the last one, and it returns 0 if the current connection is the last one.

for an example, see `Gpm_GetEvent` (544).

Errors: None.

See also: `Gpm_Open` (546)

11.4.5 gpm_fitvalues

Synopsis: Change coordinates to fit physical screen.

Declaration: `function gpm_fitvalues(var x: LongInt;var y: LongInt) : LongInt`

Visibility: default

Description: `Gpm_fitValues` changes `x` and `y` so they fit in the visible screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValuesM` (544)

11.4.6 gpm_fitvaluesM

Synopsis: Change coordinates to fit margin.

Declaration: `function gpm_fitvaluesM(var x: LongInt;var y: LongInt;margin: LongInt) : LongInt`

Visibility: default

Description: `Gpm_FitValuesM` changes `x` and `y` so they fit in the margin indicated by `margin`. If `margin` is -1, then the values are fitted to the screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValues` (544)

11.4.7 gpm_getevent

Synopsis: Get event from event queue.

Declaration: `function gpm_getevent(var event: Tgpm_event) : LongInt`

Visibility: default

Description: `Gpm_GetEvent` Reads an event from the file descriptor `gpm_fd`. This file is only for internal use and should never be called by a client application.

It returns 1 on succes, and -1 on failue.

Errors: On error, -1 is returned.

See also: `Gpm_GetSnapshot` (546)

Listing: `./gpmex/gpmex.pp`

```

program gpmex;

{
  Example program to demonstrate the use of the gpm unit.
}

uses gpm;

var
  connect : TGPMConnect;
  event : tgpmevent;

begin
  connect.EventMask:=GPM_MOVE or GPM_DRAG or GPM_DOWN or GPM_UP;
  connect.DefaultMask:=0;
  connect.MinMod:=0;
  connect.MaxMod:=0;
  if Gpm_Open(connect,0)=-1 then
    begin
      Writeln('No mouse handler present. ');
      Halt(1);
    end;
  Writeln('Click right button to end. ');
  Repeat
    gpm_getevent(Event);
    With Event do
      begin
        Write('Pos = ( ',X,', ',Y,', ') Buttons : ( ');
        if (buttons and Gpm_b_left)<>0 then
          write('left ');
        if (buttons and Gpm_b_right)<>0 then
          write('right ');
        if (buttons and Gpm_b_middle)<>0 then
          Write('middle ');
        Write(') Event : ');
        Case EventType and $F of
          GPM_MOVE: write('Move');
          GPM_DRAG: write('Drag');
          GPM_DOWN: write('Down');
          GPM_UP: write('Up');
        end;
        Writeln;
      end;
    Until (Event.Buttons and gpm_b_right)<>0;
    gpm_close;
  end.

```

11.4.8 gpm_getsnapshot

Synopsis: Return servers' current image of mouse state.

Declaration: `function gpm_getsnapshot (eptr: Pgpmevent) : LongInt`
`function gpm_getsnapshot (var eptr: Tgpmevent) : LongInt`

Visibility: default

Description: `Gpm_GetSnapshot` returns the picture that the server has of the current situation in `Event`. This call will not read the current situation from the mouse file descriptor, but returns a buffered version.

The function returns the number of mouse buttons, or -1 if this information is not available.

Errors: None.

See also: `Gpm_GetEvent` ([544](#))

11.4.9 gpm_lowerroi

Synopsis: Lower a region of interest in the stack.

Declaration: `function gpm_lowerroi (which: Pgpm_roi; after: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_LowerRoi` lowers the region of interest `which` after `after`. If `after` is `Nil`, the region of interest is moved to the bottom of the stack.

The return value is the new top of the region-of-interest stack.

Errors: None.

See also: `Gpm_RaiseRoi` ([547](#)), `Gpm_PopRoi` ([547](#)), `Gpm_PushRoi` ([547](#))

11.4.10 gpm_open

Synopsis: Open connection to GPM server.

Declaration: `function gpm_open (var conn: Tgpm_connect; flag: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Open` opens a new connection to the mouse server. The connection is described by the fields of the `conn` record of type `TGPMConnect` ([542](#)).

if `Flag` is 0, then the application only receives events that come from its own terminal device. If it is negative it will receive all events. If the value is positive then it is considered a console number to which to connect.

The return value is -1 on error, or the file descriptor used to communicate with the client. Under an X-Term the return value is -2.

for an example, see `Gpm_GetEvent` ([544](#)).

Errors: On Error, the return value is -1.

See also: `Gpm_Open` ([546](#))

11.4.11 gpm_poproi

Synopsis: Pop region of interest from the stack.

Declaration: `function gpm_poproi(which: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_PopRoi` pops the topmost region of interest from the stack. It returns the next element on the stack, or `Nil` if the current element was the last one.

Errors: None.

See also: `Gpm_RaiseRoi` (547), `Gpm_LowerRoi` (546), `Gpm_PushRoi` (547)

11.4.12 gpm_pushroi

Synopsis: Push region of interest on the stack.

Declaration: `function gpm_pushroi(x1: LongInt; y1: LongInt; x2: LongInt; y2: LongInt; mask: LongInt; fun: TGpmHandler; xtradata: pointer) : Pgpm_roi`

Visibility: default

Description: `Gpm_PushRoi` puts a new *region of interest* on the stack. The region of interest is defined by a rectangle described by the corners `(X1, Y1)` and `(X2, Y2)`.

The mask describes which events the handler {fun} will handle; `ExtraData` will be put in the `xtradata` field of the {TGPM_Roi} record passed to the fun handler.

Errors: None.

See also: `Gpm_RaiseRoi` (547), `Gpm_PopRoi` (547), `Gpm_LowerRoi` (546)

11.4.13 gpm_raiseroi

Synopsis: Raise region of interest in the stack.

Declaration: `function gpm_raiseroi(which: Pgpm_roi; before: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_RaiseRoi` raises the *region of interest* which till it is on top of region before. If before is nil then the region is put on top of the stack. The returned value is the top of the stack.

Errors: None.

See also: `Gpm_PushRoi` (547), `Gpm_PopRoi` (547), `Gpm_LowerRoi` (546)

11.4.14 gpm_repeat

Synopsis: Check for presence of mouse event.

Declaration: `function gpm_repeat(millisec: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Repeat` returns 1 if no mouse event arrives in the next `millisec` milliseconds, it returns 0 otherwise.

Errors: None.

See also: [Gpm_GetEvent \(544\)](#)

11.4.15 Gpm_StrictDouble

Synopsis: Check whether event contains only a double-click event.

Declaration: `function Gpm_StrictDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns `true` if `EventType` contains only a doubleclick event, `False` otherwise.

Errors: None.

See also: [Gpm_StrictSingle \(548\)](#), [Gpm_AnyTriple \(543\)](#), [Gpm_AnyDouble \(543\)](#), [Gpm_StrictTriple \(548\)](#), [Gpm_AnySingle \(543\)](#)

11.4.16 Gpm_StrictSingle

Synopsis: Check whether event contains only a single-click event.

Declaration: `function Gpm_StrictSingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictSingle` returns `True` if `EventType` contains only a singleclick event, `False` otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(543\)](#), [Gpm_StrictDouble \(548\)](#), [Gpm_AnyDouble \(543\)](#), [Gpm_StrictTriple \(548\)](#), [Gpm_AnySingle \(543\)](#)

11.4.17 Gpm_StrictTriple

Synopsis: Check whether event contains only a triple-click event.

Declaration: `function Gpm_StrictTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictTriple` returns `true` if `EventType` contains only a triple click event, `False` otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(543\)](#), [Gpm_StrictDouble \(548\)](#), [Gpm_AnyDouble \(543\)](#), [Gpm_StrictSingle \(548\)](#), [Gpm_AnySingle \(543\)](#)

Chapter 12

Reference for unit 'Graph'

12.1 Categorized functions: Text and font handling

Functions to set texts on the screen.

Table 12.1:

Name	Description
GetTextSettings (584)	Get current text settings
InstallUserFont (587)	Install a new font
OutText (588)	Write text at current cursor position
OutTextXY (575)	Write text at coordinates X,Y
RegisterBGIFont (590)	Register a new font
SetTextJustify (593)	Set text justification
SetTextStyle (594)	Set text style
SetUserCharSize (594)	Set text size
TextHeight (595)	Calculate height of text
TextWidth (595)	Calculate width of text

12.2 Categorized functions: Filled drawings

Functions for drawing filled regions.

12.3 Categorized functions: Drawing primitives

Functions for simple drawing.

12.4 Categorized functions: Color management

All functions related to color management.

Table 12.2:

Name	Description
Bar3D (577)	Draw a filled 3D-style bar
Bar (577)	Draw a filled rectangle
FloodFill (579)	Fill starting from coordinate
FillEllipse (578)	Draw a filled ellipse
FillPoly (579)	Draw a filled polygone
GetFillPattern (581)	Get current fill pattern
GetFillSettings (581)	Get current fill settings
SetFillPattern (591)	Set current fill pattern
SetFillStyle (592)	Set current fill settings

Table 12.3:

Name	Description
Arc (576)	Draw an arc
Circle (574)	Draw a complete circle
DrawPoly (578)	Draw a polygone with N points
Ellipse (578)	Draw an ellipse
GetArcCoords (579)	Get arc coordinates
GetLineSettings (582)	Get current line drawing settings
Line (575)	Draw line between 2 points
LineRel (587)	Draw line relative to current position
LineTo (588)	Draw line from current position to absolute position
MoveRel (588)	Move cursor relative to current position
MoveTo (588)	Move cursor to absolute position
PieSlice (589)	Draw a pie slice
PutPixel (576)	Draw 1 pixel
Rectangle (589)	Draw a non-filled rectangle
Sector (590)	Draw a sector
SetLineStyle (592)	Set current line drawing style

12.5 Categorized functions: Screen management

General drawing screen management functions.

12.6 Categorized functions: Initialization

Initialization of the graphics screen.

12.7 Target specific issues: Linux

There are several issues on Linux that need to be taken care of:

The Linux version of the Graph unit uses the libvga library. This library works on the console, not under X.

If you get an error similar to

Table 12.4:

Name	Description
GetBkColor (580)	Get current background color
GetColor (580)	Get current foreground color
GetDefaultPalette (580)	Get default palette entries
GetMaxColor (582)	Get maximum valid color
GetPaletteSize (584)	Get size of palette for current mode
GetPixel (575)	Get color of selected pixel
GetPalette (584)	Get palette entry
SetAllPalette (576)	Set all colors in palette
SetBkColor (591)	Set background color
SetColor (591)	Set foreground color
SetPalette (593)	Set palette entry
SetRGBPalette (576)	Set palette entry with RGB values

Table 12.5:

Name	Description
ClearViewPort (574)	Clear the current viewport
GetImage (574)	Copy image from screen to memory
GetMaxX (583)	Get maximum X coordinate
GetMaxY (583)	Get maximum Y coordinate
GetX (585)	Get current X position
GetY (585)	Get current Y position
ImageSize (575)	Get size of selected image
GetViewSettings (584)	Get current viewport settings
PutImage (575)	Copy image from memory to screen
SetActivePage (576)	Set active video page
SetAspectRatio (590)	Set aspect ratio for drawing routines
SetViewPort (595)	Set current viewport
SetVisualPage (576)	Set visual page
SetWriteMode (595)	Set write mode for screen operations

```
/usr/bin/ld: cannot find -lvga
```

This can mean one of two things: either libvga and its development package is not installed properly, or the directory where it is installed is not in the linker path.

To remedy the former, you should install both the libvga package and libvga-devel package (or compile and install from scratch).

To remedy the latter, you should add the path to the compiler command-line using the `-F` option.

Programs using **libvga** need root privileges to run. You can make them `setuid` root with the following command:

```
chown root.root myprogram
chmod u+s myprogram
```

The libvga library will give up the root privileges after it is initialized.

there is an experimental version of the Graphics library available that uses GGI to do all the drawing, but it is not well tested. It's called **ggigraph** and is distributed in source form only.

Table 12.6:

Name	Description
<code>ClearDevice</code> (577)	Empty the graphics screen
<code>CloseGraph</code> (577)	Finish drawing session, return to text mode
<code>DetectGraph</code> (578)	Detect graphical modes
<code>GetAspectRatio</code> (580)	Get aspect ratio of screen
<code>GetModeRange</code> (583)	Get range of valid modes for current driver
<code>GraphDefaults</code> (585)	Set defaults
<code>GetDriverName</code> (581)	Return name of graphical driver
<code>GetGraphMode</code> (582)	Return current or last used graphics mode
<code>GetMaxMode</code> (582)	Get maximum mode for current driver
<code>GetModeName</code> (583)	Get name of current mode
<code>GraphErrorMsg</code> (585)	String representation of graphical error
<code>GraphResult</code> (586)	Result of last drawing operation
<code>InitGraph</code> (586)	Initialize graphics drivers
<code>InstallUserDriver</code> (587)	Install a new driver
<code>RegisterBGIDriver</code> (589)	Register a new driver
<code>RestoreCRTMode</code> (590)	Go back to text mode
<code>SetGraphMode</code> (592)	Set graphical mode

Do not use the CRT unit together with the Graph unit: the console may end up in an unusable state. Instead, the `ncurses` unit may function fine.

12.8 Target specific issues: DOS

VESA modes (i.e., anything but 320x200x256 and 640x480x16) do not work under most installations of Windows NT, Windows 2000 and Windows XP. They also do not work for some people under Windows 98 and Windows ME, depending on their graphics drivers. However, the graph unit cannot detect this, because no errors are returned from the system. In such cases, the screen simply turns black, or will show garbage.

Nothing can be done about this, the reason is missing or buggy support in the graphics drivers of the operating system.

12.9 A word about mode selection

The graph unit was implemented for compatibility with the old Turbo Pascal graph unit. For this reason, the mode constants as they were defined in the Turbo Pascal graph unit are retained.

However, since

1. Video cards have evolved very much
2. Free Pascal runs on multiple platforms

it was decided to implement new mode and graphic driver constants, which are more independent of the specific platform the program runs on.

In this section we give a short explanation of the new mode system. the following drivers were defined:

```

D1bit = 11;
D2bit = 12;
D4bit = 13;
D6bit = 14; { 64 colors Half-brite mode - Amiga }
D8bit = 15;
D12bit = 16; { 4096 color modes HAM mode - Amiga }
D15bit = 17;
D16bit = 18;
D24bit = 19; { not yet supported }
D32bit = 20; { not yet supported }
D64bit = 21; { not yet supported }

lowNewDriver = 11;
highNewDriver = 21;

```

Each of these drivers specifies a desired color-depth.

The following modes have been defined:

```

detectMode = 30000;
m320x200 = 30001;
m320x256 = 30002; { amiga resolution (PAL) }
m320x400 = 30003; { amiga/atari resolution }
m512x384 = 30004; { mac resolution }
m640x200 = 30005; { vga resolution }
m640x256 = 30006; { amiga resolution (PAL) }
m640x350 = 30007; { vga resolution }
m640x400 = 30008;
m640x480 = 30009;
m800x600 = 30010;
m832x624 = 30011; { mac resolution }
m1024x768 = 30012;
m1280x1024 = 30013;
m1600x1200 = 30014;
m2048x1536 = 30015;

lowNewMode = 30001;
highNewMode = 30015;

```

These modes start at 30000 because Borland specified that the mode number should be ascending with increasing X resolution, and the new constants shouldn't interfere with the old ones.

The above constants can be used to set a certain color depth and resolution, as demonstrated in the below example.

If other modes than the ones above are supported by the graphics card, you will not be able to select them with this mechanism.

For this reason, there is also a 'dynamic' mode number, which is assigned at run-time. This number increases with increasing X resolution. It can be queried with the `getmoderange` call. This call will return the range of modes which are valid for a certain graphics driver. The numbers are guaranteed to be consecutive, and can be used to search for a certain resolution, as in the second example below.

Thus, the `getmoderange` function can be used to detect all available modes and drivers, as in the third example below:

12.10 Requirements

The unit Graph exports functions and procedures for graphical output. It requires at least a VGA-compatible Card or a VGA-Card with software-driver (min. **512Kb** video memory).

12.11 Overview

This document describes the GRAPH unit for Free Pascal, for all platforms. The unit was first written for dos by Florian kl\"ampfl, but was later completely rewritten by Carl-Eric Codere to be completely portable. The unit is provided for compatibility only: It is recommended to use more modern graphical systems. The graph unit will allow to recompile old programs, they will work to some extent, but if the application has heavy graphical needs, it's recommended to use another set of graphical routines, suited to the platform the program should work on.

12.12 Constants, types and variables

12.12.1 Constants

`AndPut = 3`

Draw operation: use AND

`AnsiToASCIITransTable : TCharsetTransTable = (#$00,$$01,$$02,$$03,$$04,$$05,$$06,$$07,$$08,$$09,$$0A,$$0B,$$0C,$$0D,$$0E,$$0F,$$10,$$11,$$12,$$13,$$14,$$15,$$16,$$17,$$18,$$19,$$1A,$$1B,$$1C,$$1D,$$1E,$$1F,$$20,$$21,$$22,$$23,$$24,$$25,$$26,$$27,$$28,$$29,$$2A,$$2B,$$2C,$$2D,$$2E,$$2F,$$30,$$31,$$32,$$33,$$34,$$35,$$36,$$37,$$38,$$39,$$3A,$$3B,$$3C,$$3D,$$3E,$$3F,$$40,$$41,$$42,$$43,$$44,$$45,$$46,$$47,$$48,$$49,$$4A,$$4B,$$4C,$$4D,$$4E,$$4F,$$50,$$51,$$52,$$53,$$54,$$55,$$56,$$57,$$58,$$59,$$5A,$$5B,$$5C,$$5D,$$5E,$$5F,$$60,$$61,$$62,$$63,$$64,$$65,$$66,$$67,$$68,$$69,$$6A,$$6B,$$6C,$$6D,$$6E,$$6F,$$70,$$71,$$72,$$73,$$74,$$75,$$76,$$77,$$78,$$79,$$7A,$$7B,$$7C,$$7D,$$7E,$$7F,$$80,$$81,$$82,$$83,$$84,$$85,$$86,$$87,$$88,$$89,$$8A,$$8B,$$8C,$$8D,$$8E,$$8F,$$90,$$91,$$92,$$93,$$94,$$95,$$96,$$97,$$98,$$99,$$9A,$$9B,$$9C,$$9D,$$9E,$$9F,$$A0,$$A1,$$A2,$$A3,$$A4,$$A5,$$A6,$$A7,$$A8,$$A9,$$AA,$$AB,$$AC,$$AD,$$AE,$$AF,$$B0,$$B1,$$B2,$$B3,$$B4,$$B5,$$B6,$$B7,$$B8,$$B9,$$BA,$$BB,$$BC,$$BD,$$BE,$$BF,$$C0,$$C1,$$C2,$$C3,$$C4,$$C5,$$C6,$$C7,$$C8,$$C9,$$CA,$$CB,$$CC,$$CD,$$CE,$$CF,$$D0,$$D1,$$D2,$$D3,$$D4,$$D5,$$D6,$$D7,$$D8,$$D9,$$DA,$$DB,$$DC,$$DD,$$DE,$$DF,$$E0,$$E1,$$E2,$$E3,$$E4,$$E5,$$E6,$$E7,$$E8,$$E9,$$EA,$$EB,$$EC,$$ED,$$EE,$$EF,$$F0,$$F1,$$F2,$$F3,$$F4,$$F5,$$F6,$$F7,$$F8,$$F9,$$FA,$$FB,$$FC,$$FD,$$FE,$$FF)`

Default ansi transliteration table.

`BkSlashFill = 5`

Fill style: Diagonal (backslash) lines

`black = 0`

Color code: black.

`blue = 1`

Color code: blue

`BoldFont = 10`

Font number: Bold font.

`BottomText = 0`

Vertical text alignment: Align text to bottom

`brown = 6`

Color code: brown

`CenterLn = 2`

Line style: centered line

`CenterText = 1`

Horizontal text alignment: Center text

`ClipOff = false`

Viewport clipping off

`ClipOn = true`

Viewport clipping on

`CloseDotFill = 11`

Fill style: Closely spaced dotted lines

`CopyPut = 0`

Draw operation: use Copy

`CurrentDriver = -128`

Currently used driver

`cyan = 3`

Color code: Cyan

`D12bit = 16`

Mode: Depth 12 bit

`D15bit = 17`

Mode: Depth 15 bit

`D16bit = 18`

Mode: Depth 16 bit

`D1bit = 11`

Mode: Depth 1 bit

`D24bit = 19`

Mode: Depth 24 bit

D2bit = 12

Mode: Depth 2 bit

D32bit = 20

Mode: Depth 32 bit

D4bit = 13

Mode: Depth 4 bit

D64bit = 21

Mode: Depth 64 bit

D6bit = 14

Mode: Depth 6 bit

D8bit = 15

Mode: Depth 8 bit

darkgray = 8

Color code: Dark gray

DashedLn = 3

Line style: dashed line

Default = 0

Default mode

DefaultFont = 0

Font number: Normal font

Detect = 0

Mode: Detect mode.

detectMode = 30000

Mode: Autodetect optimal mode

DottedLn = 1

Line style: Dotted line

`DrawTextBackground : Boolean = false`

Should the background of texts be drawn or should it be left untouched ?

`EGABlack = 0`

Color code: EGA Black

`EGABlue = 1`

Color code: EGA blue

`EGABrown = 20`

Color code: EGA brown

`EGACyan = 3`

Color code: EGA cyan

`EGADarkgray = 56`

Color code: EGA dark gray

`EGAGreen = 2`

Color code: EGA green

`EGALightblue = 57`

Color code: EGA Light blue

`EGALightcyan = 59`

Color code: EGA Light cyan

`EGALightgray = 7`

Color code: EGA Light gray

`EGALightgreen = 58`

Color code: EGA Light green

`EGALightmagenta = 61`

Color code: EGA light magenta

`EGALightred = 60`

Color code: EGA light red

EGAMagenta = 5

Color code: EGA magenta

$$\text{EGARed} = 4$$

Color code: EGA red

EGAWHITE = 63

Color code: EGA white

EGAYellow = 62

Color code: EGA yellow

EmptyFill = 0

Fill style: Do not fill

EuroFont = 9

Font number: ?

```
fillpatternTable : Array[0..12] of FillPatternType = ( ( $00,$00,$00,$00,$00,$00,$00
```

Table with standard fill patterns

$$G1024 \times 768 \times 16 = 30$$

Mode: Resolution 1024x768, 16 colors

$$G1024 \times 768 \times 16M = 25$$

Mode: Resolution 1024x768, 16M colors

$$G1024 \times 768 \times 16M32 = 36$$

Mode: Resolution 1024x758, 16M 32-bit colors

$$G1024 \times 768 \times 256 = 12$$

Mode: Resolution 1024x768, 256 colors

G1024x768x32K = 23

Mode: Resolution 1024x768, 32K colors

$$G1024 \times 768 \times 64K = 24$$

Mode: Resolution 1024x768, 64K colors

G1152x864x16 = 38

Mode: Resolution 1152x864, 16 colors

G1152x864x16M = 42

Mode: Resolution 1152x864, 16M colors

G1152x864x16M32 = 43

Mode: Resolution 1152x864, 16M 32-bit colors

G1152x864x256 = 39

Mode: Resolution 1152x864, 256 colors

G1152x864x32K = 40

Mode: Resolution 1152x864, 32K colors

G1152x864x64K = 41

Mode: Resolution 1152x864, 64K colors

G1280x1024x16 = 31

Mode: Resolution 1280x1024, 16 colors

G1280x1024x16M = 28

Mode: Resolution 1280x1024, 16M colors

G1280x1024x16M32 = 37

Mode: Resolution 1280x1024, 16M 32-bit colors

G1280x1024x256 = 13

Mode: Resolution 1280x1024, 256 colors

G1280x1024x32K = 26

Mode: Resolution 1280x1024, 32K colors

G1280x1024x64K = 27

Mode: Resolution 1280x1024, 64K colors

G1600x1200x16 = 44

Mode: Resolution 1600x1200, 16 colors

G1600x1200x16M = 48

Mode: Resolution 1600x1200, 16M colors

G1600x1200x16M32 = 49

Mode: Resolution 1600x1200, 16M 32-bit colors

G1600x1200x256 = 45

Mode: Resolution 1600x1200, 256 colors

G1600x1200x32K = 46

Mode: Resolution 1600x1200, 32K colors

G1600x1200x64K = 47

Mode: Resolution 1600x1200, 64K colors

G320x200x16 = 1

Mode: Resolution 320x200, 16 colors

G320x200x16M = 16

Mode: Resolution 320x200, 16M colors

G320x200x16M32 = 33

Mode: Resolution 320x200, 16M 32-bit colors

G320x200x256 = 5

Mode: Resolution 320x200, 256 colors

G320x200x32K = 14

Mode: Resolution 320x200, 32K colors

G320x200x64K = 15

Mode: Resolution 320x200, 64K colors

G320x240x256 = 6

Mode: Resolution 320x240, 256 colors

G320x400x256 = 7

Mode: Resolution 320x400, 256 colors

G360x480x256 = 8

Mode: Resolution 360x480, 256 colors

G640x200x16 = 2

Mode: Resolution x, colors

G640x350x16 = 3

Mode: Resolution x, colors

G640x480x16 = 4

Mode: Resolution x, colors

G640x480x16M = 19

Mode: Resolution 640x480, 16M colors

G640x480x16M32 = 34

Mode: Resolution 640x480, 16M 32-bit colors

G640x480x2 = 9

Mode: Resolution 640x480, 2 colors

G640x480x256 = 10

Mode: Resolution 640x480, 256 colors

G640x480x32K = 17

Mode: Resolution 640x480, 32K colors

G640x480x64K = 18

Mode: Resolution 640x480, 64K colors

G720x348x2 = 32

Mode: Resolution 720x348, 2 colors

G800x600x16 = 29

Mode: Resolution 800x600, 16 colors

G800x600x16M = 22

Mode: Resolution 800x600, 16M colors

G800x600x16M32 = 35

Mode: Resolution 800x600, 16M 32-bit colors

G800x600x256 = 11

Mode: Resolution 800x600, 256 colors

G800x600x32K = 20

Mode: Resolution 800x600, 32K colors

G800x600x64K = 21

Mode: Resolution 800x600, 64K colors

GothicFont = 4

Font number: Gothic font

GraphStringTransTable : PCharsetTransTable = nil

Table used when transliterating strings.

green = 2

Color code: green

grError = -11

Error: Unknown error.

grFileNotFound = -3

Error: File for driver not found.

grFontNotFound = -8

Error: font description file not found.

grInvalidDriver = -4

Error: Invalid driver specified

grInvalidFont = -13

Error: Invalid font description

grInvalidFontNum = -14

Error: Invalid font number

`grInvalidMode = -10`

Error: Invalid mode specified.

`grInvalidVersion = -18`

Error: Invalid version.

`grIOerror = -12`

Error: Unspecified Input/Output error.

`grNoFloodMem = -7`

Error: Could not allocate memory for flood operation.

`grNoFontMem = -9`

Error: Not enough memory to load font.

`grNoInitGraph = -1`

Error: Graphical system not initialized

`grNoLoadMem = -5`

Error: Memory error.

`grNoScanMem = -6`

Error: Could not allocate memory for scan

`grNotDetected = -2`

Error: Graphics device not detected.

`grOk = 0`

Graphical operation went OK.

`HatchFill = 7`

Fill style: Hatch lines

`HercMono = 7`

Mode: Hercules, mono color

`HercMonoHi = 0`

Mode: Hercules card, monochrome, high resolution

`highNewDriver = 21`

Mode: highest number for new driver

`highNewMode = 30015`

Mode: Highest possible value of the new modes.

`HorizDir = 0`

Text write direction: Horizontal

`InterleaveFill = 9`

Fill style: Interleaving lines

`LCOMFont = 8`

Font number: ?

`LeftText = 0`

Horizontal text alignment: Align text left

`lightblue = 9`

Color code: Light blue

`lightcyan = 11`

Color code: Light cyan

`lightgray = 7`

Color code: Light gray

`lightgreen = 10`

Color code: Light green

`lightmagenta = 13`

Color code: Light magenta

`lightred = 12`

Color code: Light red

`LineFill = 2`

Fill style: Fill using horizontal lines

`lowNewDriver = 11`

Mode: lowest number for new driver

`lowNewMode = 30001`

Mode: Lowest possible value of the new modes.

`LowRes = 1`

Mode: Low resolution.

`LtBkSlashFill = 6`

Fill style: Light diagonal (backslash) lines

`LtSlashFill = 3`

Fill style: Light diagonal (slash) lines

`m1024x768 = 30012`

Mode: Resolution 1024x768

`m1280x1024 = 30013`

Mode: Resolution 1280x1024

`m1600x1200 = 30014`

Mode: Resolution 1600x1200

`m2048x1536 = 30015`

Mode: Resolution 2048x1536

`m320x200 = 30001`

Mode: Resolution 320x200

`m320x256 = 30002`

Mode: Resolution 320x256

`m320x400 = 30003`

Mode: Resolution 320x400

`m512x384 = 30004`

Mode: Resolution 512x384

m640x200 = 30005

Mode: Resolution 640x200

m640x256 = 30006

Mode: Resolution 640x256

m640x350 = 30007

Mode: Resolution 640x350

m640x400 = 30008

Mode: Resolution 640x400

m640x480 = 30009

Mode: Resolution 640x480

m800x600 = 30010

Mode: Resolution 800x600

m832x624 = 30011

Mode: Resolution 832x624

magenta = 5

Color code: Magenta

MaxColors = 255

Max amount of colors in a palette

maxsmallint = high (smallint)

Maximum value for smallint type

NormalPut = 0

Draw operation: Use Normal (copy) operation

NormWidth = 1

Line width: Normal width

NotPut = 4

Draw operation: use NOT

OrPut = 2

Draw operation: use OR

red = 4

Color code: Red

resolutions : Array[lowNewMode..highNewMode] of TResolutionRec = ((x:320;y:200) ,

Array with actual resolutions of the new modes

RightText = 2

Horizontal text alignment: Align text right

SansSerifFont = 3

Font number: Sans Serif font

ScriptFont = 5

Font number: Script font

SimpleFont = 6

Font number: Simple font

SlashFill = 4

Fill style: Diagonal (slash) lines

SmallFont = 2

Font number: Small font

SolidFill = 1

Fill style: Solid fill.

SolidLn = 0

Line style: Solid line

ThickWidth = 3

Line width: double width

TopOff = false

Top off

TopOn = true

Top on

TopText = 2

Vertical text alignment: Align text to top

TriplexFont = 1

Font number: Triplex font

TSCRFont = 7

Font number: Terminal font

UserBitLn = 4

Line style: User defined

UserCharSize = 0

User character size

UserFill = 12

Fill style: User-defined fill.

VertDir = 1

Text write direction: Vertical

VESA = 10

Mode: VESA graphics adaptor.

VGA = 9

Mode: VGA graphics adaptor.

VGAHi = 2

Mode: VGA high resolution (640x480)

VGALo = 0

Mode: VGA low resolution (640x200)

VGAMed = 1

Mode: VGA medium resolution (640x350)

`white = 15`

Color code: White

`WideDotFill = 10`

Fill style: Widely spaced dotted lines

`XHatchFill = 8`

Fill style: Heavy hatch lines

`XORPut = 1`

Draw operation: use XOR

`yellow = 14`

Color code: Yellow

12.12.2 Types

```
ArcCoordsType = record
  x : SmallInt;
  y : SmallInt;
  xstart : SmallInt;
  ystart : SmallInt;
  xend : SmallInt;
  yend : SmallInt;
end
```

Describe the last arc which was drawn on screen

```
CircleProc = procedure(X: SmallInt;Y: SmallInt;Radius: Word)
```

Standard circle drawing routine prototype.

```
clrviewproc = procedure
```

Standard clearviewport routine prototype

```
defpixelproc = procedure(X: SmallInt;Y: SmallInt)
```

This is the standard putpixel routine used by all function drawing routines, it will use the viewport settings, as well as clip, and use the current foreground color to plot the desired pixel.

```
ellipseproc = procedure(X: SmallInt;Y: SmallInt;XRadius: Word;
  YRadius: Word;stAngle: Word;EndAngle: Word;
  fp: patternlineproc)
```

Standard ellipse drawing routine prototype.

```
FillPatternType = Array[1..8] of Byte
```

Bit pattern used when drawing lines. Set bits are drawn.

```
FillSettingsType = record
  pattern : Word;
  color : Word;
end
```

Record describing fill mode

```
getimageproc = procedure(X1: SmallInt;Y1: SmallInt;X2: SmallInt;
                          Y2: SmallInt;var Bitmap)
```

Standard GetImage (574) procedure prototype.

```
getpixelproc = function(X: SmallInt;Y: SmallInt) : Word
```

Standard pixel fetching routine prototype

```
getrgbpaletteproc = procedure(ColorNum: SmallInt;var RedValue: SmallInt;
                              var GreenValue: SmallInt;
                              var BlueValue: SmallInt)
```

This routine prototype is a hook for GetRGBPalette (575)

```
getscanlineproc = procedure(X1: SmallInt;X2: SmallInt;Y: SmallInt;
                             var data)
```

This routine is used for FloodFill (579) It returns an entire screen scan line with a word for each pixel in the scanline. Also handy for GetImage.

```
graphfreememprc = procedure(var P: Pointer;size: Word)
```

Procedure prototype, used when heap memory is freed by the graph routines.

```
graphgetmemprc = procedure(var P: pointer;size: Word)
```

Procedure prototype, used when heap memory is needed by the graph routines.

```
graph_float = single
```

The platform's preferred floating point size for fast graph operations

```
hlineproc = procedure(x: SmallInt;x2: SmallInt;y: SmallInt)
```

Standard procedure prototype to draw a single horizontal line

```
imagesizeproc = function(X1: SmallInt;Y1: SmallInt;X2: SmallInt;
                        Y2: SmallInt) : LongInt
```

Standard ImageSize (575) calculation procedure prototype.

```
initmodeproc = procedure
```

Standard routine prototype to initialize a mode.

```
lineproc = procedure(X1: SmallInt;Y1: SmallInt;X2: SmallInt;
                    Y2: SmallInt)
```

Standard line drawing routine prototype.

```
LineStyleType = record
    linestyle : Word;
    pattern   : Word;
    thickness  : Word;
end
```

Record describing current line drawing mode

```
OutTextXYProc = procedure(x: SmallInt;y: SmallInt;
                        const TextString: String)
```

This routine prototype is a hook for OutTextXY (575)

```
PaletteType = record
    Size : LongInt;
    Colors : Array[0..MaxColors] of RGBRec;
end
```

Record describing palette.

```
patternlineproc = procedure(x1: SmallInt;x2: SmallInt;y: SmallInt)
```

Standard procedure prototype to draw a patterned line

```
PCharsetTransTable = ^TCharsetTransTable
```

Pointer to TCharsetTransTable (573) array.

```
PModeInfo = ^TModeInfo
```

Pointer to TModeInfo (573) record

```
PointType = record
    x : SmallInt;
    y : SmallInt;
end
```


Record describing a point in a 2 dimensional plane

```
putimageproc = procedure(X: SmallInt;Y: SmallInt;var Bitmap;
                        BitBlt: Word)
```

Standard PutImage (575) procedure prototype.

```
putpixelproc = procedure(X: SmallInt;Y: SmallInt;Color: Word)
```

Standard pixel drawing routine prototype

```
restorestateproc = procedure
```

Standard routine prototype to restore the graphical state at a closegraph call.

```
RGBRec = packed record
    Red : SmallInt;
    Green : SmallInt;
    Blue : SmallInt;
end
```

Record describing palette RGB color

```
savestateproc = procedure
```

Standard routine prototype to save the graphical state before a mode is set.

```
setactivepageproc = procedure(page: Word)
```

Standard SetActivePage (576) procedure prototype.

```
SetAllPaletteProc = procedure(const Palette: PaletteType)
```

This routine prototype is a hook for SetAllPalette (576)

```
setrgbpaletteproc = procedure(ColorNum: SmallInt;RedValue: SmallInt;
                             GreenValue: SmallInt;BlueValue: SmallInt)
```

This routine prototype is a hook for SetRGBPalette (576)

```
setvisualpageproc = procedure(page: Word)
```

Standard SetVisualPage (576) procedure prototype.

```
smallint = -32768..32767
```

Type redefinition

```
TCharsetTransTable = Array[Char] of Char
```

Character transliteration table, with entries for 256 characters

```
TextSettingsType = record
  font : Word;
  direction : Word;
  charsize : Word;
  horiz : Word;
  vert : Word;
end
```

Record describing how texts are drawn.

```
TModeInfo = record
  DriverNumber : SmallInt;
  ModeNumber : SmallInt;
  internModeNumber : SmallInt;
  MaxColor : LongInt;
  PaletteSize : LongInt;
  XAspect : Word;
  YAspect : Word;
  MaxX : Word;
  MaxY : Word;
  DirectColor : Boolean;
  Hardwarepages : Byte;
  ModeName : String;
  DirectPutPixel : defpixelproc;
  GetPixel : getpixelproc;
  PutPixel : putpixelproc;
  SetRGBPalette : setrgbpaletteproc;
  GetRGBPalette : getrgbpaletteproc;
  SetAllPalette : SetAllPaletteProc;
  SetVisualPage : setvisualpageproc;
  SetActivePage : setactivepageproc;
  ClearViewPort : clrviewproc;
  PutImage : putimageproc;
  GetImage : getimageproc;
  ImageSize : imagesizeproc;
  GetScanLine : getscanlineproc;
  Line : lineproc;
  InternalEllipse : ellipseproc;
  PatternLine : patternlineproc;
  HLine : hlineproc;
  VLine : vlineproc;
  Circle : CircleProc;
  InitMode : initmodeproc;
  OutTextXY : OutTextXYProc;
  next : PModeInfo;
end
```

Record describing a graphical mode.

```
TNewModeInfo = record
```

```

modeInfo : Array[lowNewDriver..highNewDriver] of PModeInfo;
loHiModeNr : Array[lowNewDriver..highNewDriver] of ;
end

```

Mode information for new modes.a

```

TResolutionRec = record
  x : LongInt;
  y : LongInt;
end

```

Record describing resolution

```

ViewPortType = record
  x1 : SmallInt;
  y1 : SmallInt;
  x2 : SmallInt;
  y2 : SmallInt;
  Clip : Boolean;
end

```

Record describing a viewport

```

vlineproc = procedure(x: SmallInt;y: SmallInt;y2: SmallInt)

```

Standard procedure prototype to draw a single vertical line

12.12.3 Variables

```

Circle : CircleProc

```

Circle draws a complete circle with center at (X,Y), radius radius.

```

ClearViewPort : clrviewproc

```

Clears the current viewport. The current background color is used as filling color. The pointer is set at (0,0).

```

DirectPutPixel : defpixelproc

```

Hook to directly draw a pixel on the screen.

```

GetImage : getimageproc

```

GetImage Places a copy of the screen area (X1,Y1) to X2,Y2 in BitMap

```

GetPixel : getpixelproc

```

`GetPixel` returns the color of the point at (X, Y)

`GetRGBPalette` : `getrgbpaletteproc`

Hook to set a RGB palette entries.

`GetScanLine` : `getscanlineproc`

Hook to get a scan line from the screen.

`GraphFreeMemPtr` : `graphfreememprc`

Hook to free heap memory.

`GraphGetMemPtr` : `graphgetmemprc`

Hook to get heap memory

`HLine` : `hlineproc`

Hook to draw a solid horizontal line

`ImageSize` : `imagesizeproc`

`ImageSize` returns the number of bytes needed to store the image in the rectangle defined by (X1, Y1) and (X2, Y2).

`InternalEllipse` : `ellipseproc`

Hook to draw an ellipse

`Line` : `lineproc`

`Line` draws a line starting from (X1, Y1 to (X2, Y2), in the current line style and color. The current position is put to (X2, Y2)

`OutTextXY` : `OutTextXYProc`

`OutText` puts `TextString` on the screen, at position (X, Y), using the current font and text settings. The current position is moved to the end of the text.

`PatternLine` : `patternlineproc`

Hook to draw a patterned line

`PutImage` : `putimageproc`

`PutImage` Places the bitmap in `Bitmap` on the screen at (X1, Y1). `How` determines how the bitmap will be placed on the screen. Possible values are :

- `CopyPut`

- XORPut
- ORPut
- AndPut
- NotPut

PutPixel : putpixelproc

Puts a point at (X, Y) using color Color

RestoreVideoState : restorestateproc

Hook to restore a saved video mode

SaveVideoState : savestateproc

Hook to save the current video state

SetActivePage : setactivepageproc

Sets Page as the active page for all graphical output.

SetAllPalette : SetAllPaletteProc

Sets the current palette to Palette. Palette is an untyped variable, usually pointing to a record of type PaletteType

SetRGBPalette : setrgbpaletteproc

SetRGBPalette sets the ColorNr-th entry in the palette to the color with RGB-values Red, Green Blue.

SetVisualPage : setvisualpageproc

SetVisualPage sets the video page to page number Page.

VLine : vlineproc

Hook to draw a solid vertical line

12.13 Procedures and functions

12.13.1 Arc

Synopsis: Draw part of a circle

Declaration: `procedure Arc(X: SmallInt; Y: SmallInt; StAngle: Word; EndAngle: Word; Radius: Word)`

Visibility: default

Description: Arc draws part of a circle with center at (X, Y), radius radius, starting from angle start, stopping at angle stop. These angles are measured counterclockwise.

Errors: None.

See also: Circle ([574](#)), Ellipse ([578](#)), GetArcCoords ([579](#)), PieSlice ([589](#)), Sector ([590](#))

12.13.2 Bar

Synopsis: Draw filled rectangle

Declaration: `procedure Bar(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2) and fills it with the current color and fill-style.

Errors: None.

See also: Bar3D ([577](#)), Rectangle ([589](#))

12.13.3 Bar3D

Synopsis: Draw filled 3-dimensional rectangle

Declaration: `procedure Bar3D(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt;
depth: Word; top: Boolean)`

Visibility: default

Description: Bar3d draws a 3-dimensional Bar with corners at (X1, Y1) and (X2, Y2) and fills it with the current color and fill-style. Depth specifies the number of pixels used to show the depth of the bar.

If Top is true; then a 3-dimensional top is drawn.

Errors: None.

See also: Bar ([577](#)), Rectangle ([589](#))

12.13.4 ClearDevice

Synopsis: Clear the complete screen

Declaration: `procedure ClearDevice`

Visibility: default

Description: Clears the graphical screen (with the current background color), and sets the pointer at (0, 0).

Errors: None.

See also: ClearViewPort ([574](#)), SetBkColor ([591](#))

12.13.5 Closegraph

Synopsis: Close graphical system.

Declaration: `procedure Closegraph`

Visibility: default

Description: Closes the graphical system, and restores the screen modus which was active before the graphical modus was activated.

Errors: None.

See also: InitGraph ([586](#))

12.13.6 DetectGraph

Synopsis: Detect correct graphical driver to use

Declaration: `procedure DetectGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt)`

Visibility: default

Description: `DetectGraph` checks the hardware in the PC and determines the driver and screen-modus to be used. These are returned in `Driver` and `Modus`, and can be fed to `InitGraph`. See the `InitGraph` for a list of drivers and modi.

Errors: None.

See also: `InitGraph` ([586](#))

12.13.7 DrawPoly

Synopsis: Draw a polygone

Declaration: `procedure DrawPoly(NumPoints: Word; var polypoints)`

Visibility: default

Description: `DrawPoly` draws a polygone with `NumberOfPoints` corner points, using the current color and line-style. `PolyPoints` is an array of type `PointType` ([572](#)).

Errors: None.

See also: `Bar` ([577](#)), `Bar3D` ([577](#)), `Rectangle` ([589](#))

12.13.8 Ellipse

Synopsis: Draw an ellipse

Declaration: `procedure Ellipse(X: SmallInt; Y: SmallInt; stAngle: Word; EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Ellipse` draws part of an ellipse with center at `(X, Y)`. `XRadius` and `Yradius` are the horizontal and vertical radii of the ellipse. `Start` and `Stop` are the starting and stopping angles of the part of the ellipse. They are measured counterclockwise from the X-axis (3 o'clock is equal to 0 degrees). Only positive angles can be specified.

Errors: None.

See also: `Arc` ([576](#)), `Circle` ([574](#)), `FillEllipse` ([578](#))

12.13.9 FillEllipse

Synopsis: Draw and fill an ellipse

Declaration: `procedure FillEllipse(X: SmallInt; Y: SmallInt; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Ellipse` draws an ellipse with center at (X, Y) . `XRadiu`s and `Yradiu`s are the horizontal and vertical radii of the ellipse. The ellipse is filled with the current color and fill-style.

Errors: None.

See also: `Arc` ([576](#)), `Circle` ([574](#)), `GetArcCoords` ([579](#)), `PieSlice` ([589](#)), `Sector` ([590](#))

12.13.10 FillPoly

Synopsis: Draw, close and fill a polygone

Declaration: `procedure FillPoly (NumPoints: Word; var PolyPoints)`

Visibility: default

Description: `FillPoly` draws a polygone with `NumberOfPoints` corner points and fills it using the current color and line-style. `PolyPoints` is an array of type `PointType`.

Errors: None.

See also: `Bar` ([577](#)), `Bar3D` ([577](#)), `Rectangle` ([589](#))

12.13.11 FloodFill

Synopsis: Fill an area with a given color

Declaration: `procedure FloodFill (x: SmallInt; y: SmallInt; Border: Word)`

Visibility: default

Description: Fills the area containing the point (X, Y) , bounded by the color `BorderColor`.

Errors: None

See also: `SetColor` ([591](#)), `SetBkColor` ([591](#))

12.13.12 GetArcCoords

Synopsis: Return coordinates of last drawn arc or ellipse.

Declaration: `procedure GetArcCoords (var ArcCoords: ArcCoordsType)`

Visibility: default

Description: `GetArcCoords` returns the coordinates of the latest `Arc` or `Ellipse` call.

Errors: None.

See also: `Arc` ([576](#)), `Ellipse` ([578](#))

12.13.13 GetAspectRatio

Synopsis: Return screen resolution

Declaration: `procedure GetAspectRatio (var Xasp: Word; var Yasp: Word)`

Visibility: default

Description: `GetAspectRatio` determines the effective resolution of the screen. The aspect ration can then be calculated as $Xasp/Yasp$.

Errors: None.

See also: `InitGraph` ([586](#)), `SetAspectRatio` ([590](#))

12.13.14 GetBkColor

Synopsis: Return current background color

Declaration: `function GetBkColor : Word`

Visibility: default

Description: `GetBkColor` returns the current background color (the palette entry).

Errors: None.

See also: `GetColor` ([580](#)), `SetBkColor` ([591](#))

12.13.15 GetColor

Synopsis: Return current drawing color

Declaration: `function GetColor : Word`

Visibility: default

Description: `GetColor` returns the current drawing color (the palette entry).

Errors: None.

See also: `GetColor` ([580](#)), `SetBkColor` ([591](#))

12.13.16 GetDefaultPalette

Synopsis: Return default palette

Declaration: `procedure GetDefaultPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetDefaultPalette` returns the current palette in `Palette`.

Errors: None.

See also: `GetColor` ([580](#)), `GetBkColor` ([580](#))

12.13.17 GetDirectVideo

Synopsis: Determine whether direct video mode is active.

Declaration: `function GetDirectVideo : Boolean`

Visibility: default

Description: Determine whether direct video mode is active.

Errors:

12.13.18 GetDriverName

Synopsis: Return current driver name

Declaration: `function GetDriverName : String`

Visibility: default

Description: `GetDriverName` returns a string containing the name of the current driver.

Errors: None.

See also: `GetModeName` ([583](#)), `InitGraph` ([586](#))

12.13.19 GetFillPattern

Synopsis: Return current fill pattern

Declaration: `procedure GetFillPattern(var FillPattern: FillPatternType)`

Visibility: default

Description: `GetFillPattern` returns an array with the current fill-pattern in `FillPattern`

Errors: None

See also: `SetFillPattern` ([591](#))

12.13.20 GetFillSettings

Synopsis: Return current fill settings

Declaration: `procedure GetFillSettings(var Fillinfo: FillSettingsType)`

Visibility: default

Description: `GetFillSettings` returns the current fill-settings in `FillInfo`

Errors: None.

See also: `SetFillPattern` ([591](#))

12.13.21 GetGraphMode

Synopsis: Get current graphical modus

Declaration: `function GetGraphMode : SmallInt`

Visibility: default

Description: `GetGraphMode` returns the current graphical modus

Errors: None.

See also: `InitGraph` ([586](#))

12.13.22 GetLineSettings

Synopsis: Get current line drawing settings

Declaration: `procedure GetLineSettings (var ActiveLineInfo: LineSettingsType)`

Visibility: default

Description: `GetLineSettings` returns the current Line settings in `LineInfo`

Errors: None.

See also: `SetLineStyle` ([592](#))

12.13.23 GetMaxColor

Synopsis: return maximum number of colors

Declaration: `function GetMaxColor : Word`

Visibility: default

Description: `GetMaxColor` returns the maximum color-number which can be set with `SetColor`. Contrary to Turbo Pascal, this color isn't always guaranteed to be white (for instance in 256+ color modes).

Errors: None.

See also: `SetColor` ([591](#)), `GetPaletteSize` ([584](#))

12.13.24 GetMaxMode

Synopsis: Return biggest mode for the current driver

Declaration: `function GetMaxMode : SmallInt`

Visibility: default

Description: `GetMaxMode` returns the highest modus for the current driver.

Errors: None.

See also: `InitGraph` ([586](#))

12.13.25 GetMaxX

Synopsis: Return maximal X coordinate

Declaration: `function GetMaxX : SmallInt`

Visibility: default

Description: `GetMaxX` returns the maximum horizontal screen length

Errors: None.

See also: `GetMaxY` ([583](#))

12.13.26 GetMaxY

Synopsis: Return maximal Y coordinate

Declaration: `function GetMaxY : SmallInt`

Visibility: default

Description: `GetMaxY` returns the maximum number of screen lines

Errors: None.

See also: `GetMaxX` ([583](#))

12.13.27 GetModeName

Synopsis: Return description a modus

Declaration: `function GetModeName (ModeNumber: SmallInt) : String`

Visibility: default

Description: `GetModeName` Returns a string with the name of modus Modus

Errors: None.

See also: `GetDriverName` ([581](#)), `InitGraph` ([586](#))

12.13.28 GetModeRange

Synopsis: Return lowest and highest modus of current driver

Declaration: `procedure GetModeRange (GraphDriver: SmallInt; var LoMode: SmallInt;
var HiMode: SmallInt)`

Visibility: default

Description: `GetModeRange` returns the Lowest and Highest modus of the currently installed driver. If no modes are supported for this driver, `HiModus` will be -1.

Errors: None.

See also: `InitGraph` ([586](#))

12.13.29 GetPalette

Synopsis: Return current palette

Declaration: `procedure GetPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetPalette` returns in `Palette` the current palette.

Errors: None.

See also: `GetPaletteSize` ([584](#)), `SetPalette` ([593](#))

12.13.30 GetPaletteSize

Synopsis: Return maximal number of entries in current palette

Declaration: `function GetPaletteSize : SmallInt`

Visibility: default

Description: `GetPaletteSize` returns the maximum number of entries in the current palette.

Errors: None.

See also: `GetPalette` ([584](#)), `SetPalette` ([593](#))

12.13.31 GetTextSettings

Synopsis: Return current text style

Declaration: `procedure GetTextSettings (var TextInfo: TextSettingsType)`

Visibility: default

Description: `GetTextSettings` returns the current text style settings : The font, direction, size and placement as set with `SetTextStyle` and `SetTextJustify`

Errors: None.

See also: `SetTextStyle` ([594](#)), `SetTextJustify` ([593](#))

12.13.32 GetViewSettings

Synopsis: Return current viewport

Declaration: `procedure GetViewSettings (var viewport: ViewPortType)`

Visibility: default

Description: `GetViewSettings` returns the current viewport and clipping settings in `ViewPort`.

Errors: None.

See also: `SetViewPort` ([595](#))

12.13.33 GetX

Synopsis: Return current cursor X position

Declaration: `function GetX : SmallInt`

Visibility: default

Description: `GetX` returns the X-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetY` ([585](#))

12.13.34 GetY

Synopsis: Return current cursor Y position

Declaration: `function GetY : SmallInt`

Visibility: default

Description: `GetY` returns the Y-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetX` ([585](#))

12.13.35 GraphDefaults

Synopsis: Reset graphical mode to defaults

Declaration: `procedure GraphDefaults`

Visibility: default

Description: `GraphDefaults` resets all settings for viewport, palette, foreground and background pattern, line-style and pattern, filling style, filling color and pattern, font, text-placement and text size.

Errors: None.

See also: `SetViewPort` ([595](#)), `SetFillStyle` ([592](#)), `SetColor` ([591](#)), `SetBkColor` ([591](#)), `SetLineStyle` ([592](#))

12.13.36 GraphErrorMsg

Synopsis: Return a description of an error

Declaration: `function GraphErrorMsg(ErrorCode: SmallInt) : String`

Visibility: default

Description: `GraphErrorMsg` returns a string describing the error `Errorcode`. This string can be used to let the user know what went wrong.

Errors: None.

See also: `GraphResult` ([586](#))

12.13.37 GraphResult

Synopsis: Result of last graphical operation

Declaration: `function GraphResult : SmallInt`

Visibility: default

Description: `GraphResult` returns an error-code for the last graphical operation. If the returned value is zero, all went well. A value different from zero means an error has occurred. besides all operations which draw something on the screen, the following procedures also can produce a `GraphResult` different from zero:

- `InstallUserFont` ([587](#))
- `SetLineStyle` ([592](#))
- `SetWriteMode` ([595](#))
- `SetFillStyle` ([592](#))
- `SetTextJustify` ([593](#))
- `SetGraphMode` ([592](#))
- `SetTextStyle` ([594](#))

Errors: None.

See also: `GraphErrorMsg` ([585](#))

12.13.38 InitGraph

Synopsis: Initialize graphical system

Declaration: `procedure InitGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt; const PathToDriver: String)`

Visibility: default

Description: `InitGraph` initializes the graph package. `GraphDriver` has two valid values: `GraphDriver=0` which performs an auto detect and initializes the highest possible mode with the most colors. 1024x768x64K is the highest possible resolution supported by the driver, if you need a higher resolution, you must edit `MODES.PPI`. If you need another mode, then set `GraphDriver` to a value different from zero and `graphmode` to the mode you wish (VESA modes where 640x480x256 is 101h etc.). `PathToDriver` is only needed, if you use the BGI fonts from Borland. Free Pascal does not offer BGI fonts like Borland, these must be obtained separately.

Example code:

```

var
  gd,gm : integer;
  PathToDriver : string;
begin
  gd:=detect; { highest possible resolution }
  gm:=0; { not needed, auto detection }
  PathToDriver:='C:\PP\BGI'; { path to BGI fonts,
                             drivers aren't needed }
  InitGraph(gd,gm,PathToDriver);
  if GraphResult<>grok then
    halt; ..... { whatever you need }
  CloseGraph; { restores the old graphics mode }
end.

```

Errors: None.

See also: Modes ([552](#)), DetectGraph ([578](#)), CloseGraph ([577](#)), GraphResult ([586](#))

12.13.39 InstallUserDriver

Synopsis: Install a user driver

Declaration: `function InstallUserDriver (Name: String; AutoDetectPtr: Pointer)
: SmallInt`

Visibility: default

Description: `InstallUserDriver` adds the device-driver `DriverPath` to the list of .BGI drivers. `AutoDetectPtr` is a pointer to a possible auto-detect function.

Errors: None.

See also: `InitGraph` ([586](#)), `InstallUserFont` ([587](#))

12.13.40 InstallUserFont

Synopsis: Install a user-defined font

Declaration: `function InstallUserFont (const FontFileName: String) : SmallInt`

Visibility: default

Description: `InstallUserFont` adds the font in `FontPath` to the list of fonts of the .BGI system.

Errors: None.

See also: `InitGraph` ([586](#)), `InstallUserDriver` ([587](#))

12.13.41 LineRel

Synopsis: Draw a line starting from current position in given direction

Declaration: `procedure LineRel (Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `LineRel` draws a line starting from the current pointer position to the point (DX, DY) , `\textbf{relative}` to the current position, in the current line style and color. The Current Position is set to the endpoint of the line.

Errors: None.

See also: `Line` ([575](#)), `LineTo` ([588](#))

12.13.42 LineTo

Synopsis: Draw a line starting from current position to a given point

Declaration: `procedure LineTo(X: SmallInt;Y: SmallInt)`

Visibility: default

Description: `LineTo` draws a line starting from the current pointer position to the point $(DX, DY, \text{\textbf{relative}})$ to the current position, in the current line style and color. The Current position is set to the end of the line.

Errors: None.

See also: `LineRel` ([587](#)), `Line` ([575](#))

12.13.43 MoveRel

Synopsis: Move cursor relative to current position

Declaration: `procedure MoveRel(Dx: SmallInt;Dy: SmallInt)`

Visibility: default

Description: `MoveRel` moves the pointer to the point (DX, DY) , relative to the current pointer position

Errors: None.

See also: `MoveTo` ([588](#))

12.13.44 MoveTo

Synopsis: Move cursor to absolute position.

Declaration: `procedure MoveTo(X: SmallInt;Y: SmallInt)`

Visibility: default

Description: `MoveTo` moves the pointer to the point (X, Y) .

Errors: None.

See also: `MoveRel` ([588](#))

12.13.45 OutText

Synopsis: Write text on the screen at the current location.

Declaration: `procedure OutText(const TextString: String)`

Visibility: default

Description: `OutText` puts `TextString` on the screen, at the current pointer position, using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: `OutTextXY` ([575](#))

12.13.46 PieSlice

Synopsis: Draw a pie-slice

Declaration: `procedure PieSlice(X: SmallInt; Y: SmallInt; stangle: SmallInt;
 endAngle: SmallInt; Radius: Word)`

Visibility: default

Description: `PieSlice` draws and fills a sector of a circle with center (X, Y) and radius Radius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: Arc ([576](#)), Circle ([574](#)), Sector ([590](#))

12.13.47 queryadapterinfo

Synopsis: Function called to retrieve the current video adapter settings.

Declaration: `function queryadapterinfo : PModeInfo`

Visibility: default

12.13.48 Rectangle

Synopsis: Draw a rectangle on the screen.

Declaration: `procedure Rectangle(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2), using the current color and style.

Errors: None.

See also: Bar ([577](#)), Bar3D ([577](#))

12.13.49 RegisterBGIDriver

Synopsis: Register a new BGI driver.

Declaration: `function RegisterBGIDriver(driver: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: `InstallUserDriver` ([587](#)), `RegisterBGIFont` ([590](#))

12.13.50 RegisterBGIfont

Synopsis: Register a new BGI font

Declaration: `function RegisterBGIfont (font: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: `InstallUserFont` ([587](#)), `RegisterBGIDriver` ([589](#))

12.13.51 RestoreCrtMode

Synopsis: Restore text screen

Declaration: `procedure RestoreCrtMode`

Visibility: default

Description: Restores the screen modus which was active before the graphical modus was started.

To get back to the graph mode you were last in, you can use `SetGraphMode (GetGraphMode)`

Errors: None.

See also: `InitGraph` ([586](#))

12.13.52 Sector

Synopsis: Draw and fill a sector of an ellipse

Declaration: `procedure Sector (x: SmallInt; y: SmallInt; StAngle: Word; EndAngle: Word;
 XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Sector` draws and fills a sector of an ellipse with center (X, Y) and radii XRadius and YRadius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: `Arc` ([576](#)), `Circle` ([574](#)), `PieSlice` ([589](#))

12.13.53 SetAspectRatio

Synopsis: Set aspect ration of the screen

Declaration: `procedure SetAspectRatio (Xasp: Word; Yasp: Word)`

Visibility: default

Description: Sets the aspect ratio of the current screen to Xasp/Yasp.

Errors: None

See also: `InitGraph` ([586](#)), `GetAspectRatio` ([580](#))

12.13.54 SetBkColor

Synopsis: Set background drawing color

Declaration: `procedure SetBkColor (ColorNum: Word)`

Visibility: default

Description: Sets the background color to `Color`.

Errors: None.

See also: [GetBkColor \(580\)](#), [SetColor \(591\)](#), [SetWriteMode \(595\)](#)

12.13.55 SetColor

Synopsis: Set foreground drawing color

Declaration: `procedure SetColor (Color: Word)`

Visibility: default

Description: Sets the foreground color to `Color`.

Errors: None.

See also: [GetColor \(580\)](#), [SetBkColor \(591\)](#), [SetWriteMode \(595\)](#)

12.13.56 SetDirectVideo

Synopsis: Attempt to enter direct video mode.

Declaration: `procedure SetDirectVideo (DirectAccess: Boolean)`

Visibility: default

Description: `SetDirectVideo` attempts to enter direct video mode. In that mode, everything is drawn straight in the video buffer.

12.13.57 SetFillPattern

Synopsis: Set drawing fill pattern

Declaration: `procedure SetFillPattern (Pattern: FillPatternType; Color: Word)`

Visibility: default

Description: `SetFillPattern` sets the current fill-pattern to `FillPattern`, and the filling color to `Color`. The pattern is an 8x8 raster, corresponding to the 64 bits in `FillPattern`.

Errors: None

See also: [GetFillPattern \(581\)](#), [SetFillStyle \(592\)](#), [SetWriteMode \(595\)](#)

12.13.58 SetFillStyle

Synopsis: Set drawing fill style

Declaration: `procedure SetFillStyle (Pattern: Word; Color: Word)`

Visibility: default

Description: `SetFillStyle` sets the filling pattern and color to one of the predefined filling patterns. `Pattern` can be one of the following predefined constants :

EmptyFill Uses backgroundcolor.

SolidFill Uses filling color

LineFill Fills with horizontal lines.

ltSlashFill Fills with lines from left-under to top-right.

SlashFill Idem as previous, thick lines.

BkSlashFill Fills with thick lines from left-Top to bottom-right.

LtBkSlashFill Idem as previous, normal lines.

HatchFill Fills with a hatch-like pattern.

XHatchFill Fills with a hatch pattern, rotated 45 degrees.

InterLeaveFill

WideDotFill Fills with dots, wide spacing.

CloseDotFill Fills with dots, narrow spacing.

UserFill Fills with a user-defined pattern.

Errors: None.

See also: `SetFillPattern` ([591](#)), `SetWriteMode` ([595](#))

12.13.59 SetGraphMode

Synopsis: Set graphical mode

Declaration: `procedure SetGraphMode (Mode: SmallInt)`

Visibility: default

Description: `SetGraphMode` sets the graphical mode and clears the screen.

Errors: None.

See also: `InitGraph` ([586](#))

12.13.60 SetLineStyle

Synopsis: Set line drawing style

Declaration: `procedure SetLineStyle (LineStyle: Word; Pattern: Word; Thickness: Word)`

Visibility: default

Description: `SetLineStyle` sets the drawing style for lines. You can specify a `LineStyle` which is one of the following pre-defined constants:

SolidIn Draws a solid line.

DottedIn Draws a dotted line.

CenterIn Draws a non-broken centered line.

DashedIn Draws a dashed line.

UserBitIn Draws a User-defined bit pattern.

If **UserBitIn** is specified then **Pattern** contains the bit pattern. In all another cases, **Pattern** is ignored. The parameter **Width** indicates how thick the line should be. You can specify one of the following pre-defined constants:

NormWidth Normal line width

ThickWidth Double line width

Errors: None.

See also: [GetLineSettings \(582\)](#), [SetWriteMode \(595\)](#)

12.13.61 SetPalette

Synopsis: Set palette entry using color constant

Declaration: `procedure SetPalette (ColorNum: Word; Color: ShortInt)`

Visibility: default

Description: **SetPalette** changes the **ColorNr**-th entry in the palette to **NewColor**

Errors: None.

See also: [SetAllPalette \(576\)](#), [SetRGBPalette \(576\)](#)

12.13.62 SetTextJustify

Synopsis: Set text placement style

Declaration: `procedure SetTextJustify (horiz: Word; vert: Word)`

Visibility: default

Description: **SetTextJustify** controls the placement of new text, relative to the (graphical) cursor position. **Horizontal** controls horizontal placement, and can be one of the following pre-defined constants:

LeftText Text is set left of the pointer.

CenterText Text is set centered horizontally on the pointer.

RightText Text is set to the right of the pointer.

Vertical controls the vertical placement of the text, relative to the (graphical) cursor position. Its value can be one of the following pre-defined constants :

BottomText Text is placed under the pointer.

CenterText Text is placed centered vertically on the pointer.

TopText Text is placed above the pointer.

Errors: None.

See also: [OutText \(588\)](#), [OutTextXY \(575\)](#)

12.13.63 SetTextStyle

Synopsis: Set text style

Declaration: `procedure SetTextStyle(font: Word; direction: Word; charsize: Word)`

Visibility: default

Description: `SetTextStyle` controls the style of text to be put on the screen. pre-defined constants for `Font` are:

DefaultFontThe default font

TriplexFontA special font

SmallFontA smaller font

SansSerifFontA sans-serif font (like Arial)

GothicFontA gothic font

ScriptFontA script font

SimpleFontA simple font

TSCRFntTerminal screen font

LCOMFont?

EuroFont?

BoldFontA bold typeface font

Pre-defined constants for `Direction` are :

HorizDirWrite horizontal

VertDirWrite vertical

Errors: None.

See also: `GetTextSettings` ([584](#))

12.13.64 SetUserCharSize

Synopsis: Set user character size for vector font

Declaration: `procedure SetUserCharSize(Multx: Word; Divx: Word; Multy: Word; Divy: Word)`

Visibility: default

Description: Sets the width and height of vector-fonts. The horizontal size is given by `Xasp1/Xasp2`, and the vertical size by `Yasp1/Yasp2`.

Errors: None.

See also: `SetTextStyle` ([594](#))

12.13.65 SetViewPort

Synopsis: Set the graphical drawing window

Declaration: `procedure SetViewPort (X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt; Clip: Boolean)`

Visibility: default

Description: Sets the current graphical viewport (window) to the rectangle defined by the top-left corner (X1, Y1) and the bottom-right corner (X2, Y2). If Clip is true, anything drawn outside the viewport (window) will be clipped (i.e. not drawn). Coordinates specified after this call are relative to the top-left corner of the viewport.

Errors: None.

See also: `GetViewSettings` ([584](#))

12.13.66 SetWriteMode

Synopsis: Specify binary operation to perform when drawing on screen

Declaration: `procedure SetWriteMode (WriteMode: SmallInt)`

Visibility: default

Description: `SetWriteMode` controls the drawing of lines on the screen. It controls the binary operation used when drawing lines on the screen. Mode can be one of the following pre-defined constants:

CopyPutDraw as specified using current bitmask and color

XORPutDraw XOR-ing current bitmask and color

Errors: None.

See also: `SetColor` ([591](#)), `SetBkColor` ([591](#)), `SetLineStyle` ([592](#)), `SetFillStyle` ([592](#))

12.13.67 TextHeight

Synopsis: Return height (in pixels) of the given string

Declaration: `function TextHeight (const TextString: String) : Word`

Visibility: default

Description: `TextHeight` returns the height (in pixels) of the string S in the current font and text-size.

Errors: None.

See also: `TextWidth` ([595](#))

12.13.68 TextWidth

Synopsis: Return width (in pixels) of the given string

Declaration: `function TextWidth (const TextString: String) : Word`

Visibility: default

Description: `TextWidth` returns the width (in pixels) of the string S in the current font and text-size.

Errors: None.

See also: TextHeight ([595](#))

Chapter 13

Reference for unit 'heaptrc'

13.1 Controlling HeapTrc with environment variables

The `HeapTrc` unit can be controlled with the `HEAPTRC` environment variable. The contents of this variable controls the initial setting of some constants in the unit. `HEAPTRC` consists of one or more of the following strings, separated by spaces:

keepreleased If this string occurs, then the `KeepReleased` (599) variable is set to `True`

disabled If this string occurs, then the `UseHeapTrace` (599) variable is set to `False` and the heap trace is disabled. It does not make sense to combine this value with other values.

nohalt If this string occurs, then the `HaltOnError` (598) variable is set to `False`, so the program continues executing even in case of a heap error.

log=filename If this string occurs, then the output of `heaptrc` is sent to the specified `Filename`. (see also `SetHeapTraceOutput` (601))

The following are valid values for the `HEAPTRC` variable:

```
HEAPTRC=disabled
HEAPTRC="keepreleased log=heap.log"
HEAPTRC="log=myheap.log nohalt"
```

Note that these strings are case sensitive, and the name of the variable too.

13.2 HeapTrc Usage

All that you need to do is to include `heaptrc` in the `uses` clause of your program. Make sure that it is the first unit in the clause, otherwise memory allocated in initialization code of units that precede the `heaptrc` unit will not be accounted for, causing an incorrect memory usage report.

If you use the `-gh` switch, the compiler will insert the unit by itself, so you don't have to include it in your `uses` clause.

The below example shows how to use the `heaptrc` unit.

This is the memory dump shown when running this program in a standard way:

```

Marked memory at 0040FA50 invalid
Wrong size : 128 allocated 64 freed
  0x00408708
  0x0040CB49
  0x0040C481
Call trace for block 0x0040FA50 size 128
  0x0040CB3D
  0x0040C481

```

If you use the `lineinfo` unit (or use the `-gl` switch) as well, then `heaptrc` will also give you the filenames and line-numbers of the procedures in the backtrace:

```

Marked memory at 00410DA0 invalid
Wrong size : 128 allocated 64 freed
  0x004094B8
  0x0040D8F9  main,   line 25 of heapex.pp
  0x0040D231
Call trace for block 0x00410DA0 size 128
  0x0040D8ED  main,   line 23 of heapex.pp
  0x0040D231

```

If lines without filename/line-number occur, this means there is a unit which has no debug info included.

13.3 Overview

This document describes the HEAPTRC unit for Free Pascal. It was written by Pierre Muller. It is system independent, and works on all supported systems.

The HEAPTRC unit can be used to debug your memory allocation/deallocation. It keeps track of the calls to `getmem/freemem`, and, implicitly, of `New/Dispose` statements.

When the program exits, or when you request it explicitly. It displays the total memory used, and then dumps a list of blocks that were allocated but not freed. It also displays where the memory was allocated.

If there are any inconsistencies, such as memory blocks being allocated or freed twice, or a memory block that is released but with wrong size, this will be displayed also.

The information that is stored/displayed can be customized using some constants.

13.4 Constants, types and variables

13.4.1 Constants

```
add_tail : Boolean = true
```

If `add_tail` is `True` (the default) then a check is also performed on the memory location just behind the allocated memory.

```
HaltOnError : Boolean = true
```

If `HaltOnError` is set to `True` then an illegal call to `FreeMem` will cause the memory manager to execute a `halt (1)` instruction, causing a memory dump. By Default it is set to `True`.

```
keepreleased : Boolean = false
```

If `keepreleased` is set to `true`, then a list of freed memory blocks is kept. This is useful if you suspect that the same memory block is released twice. However, this option is very memory intensive, so use it sparingly, and only when it's really necessary.

```
quicktrace : Boolean = true
```

`Quicktrace` determines whether the memory manager checks whether a block that is about to be released is allocated correctly. This is a rather time consuming search, and slows program execution significantly, so by default it is set to `True`.

```
tracesize = 8
```

`Tracesize` specifies how many levels of calls are displayed of the call stack during the memory dump. If you specify `keepreleased:=True` then half the `TraceSize` is reserved for the `GetMem` call stack, and the other half is reserved for the `FreeMem` call stack. For example, the default value of 8 will cause eight levels of call frames to be dumped for the `getmem` call if `keepreleased` is `False`. If `KeepReleased` is `true`, then 4 levels of call frames will be dumped for the `GetMem` call and 4 frames will be dumped for the `FreeMem` call. If you want to change this value, you must recode the `heaptrc` unit.

```
usecrc : Boolean = true
```

If `usecrc` is `True` (the default) then a crc check is performed on locations before and after the allocated memory. This is useful to detect memory overwrites.

```
useheaptrace : Boolean = true
```

This variable must be set at program startup, through the help of an environment variable.

13.4.2 Types

```
tdisplayextrainfoProc = procedure(var ptext: text;p: pointer)
```

The `TDisplayExtraInfoType` is a procedural type used in the `SetHeapExtraInfo` (600) call to display a memory location which was previously filled with `TFillExtraInfoProc` (599)

```
tFillExtraInfoProc = procedure(p: pointer)
```

The `TFillExtraInfoProc` is a procedural type used in the `SetHeapExtraInfo` (600) call to fill a memory location with extra data for displaying.

13.5 Procedures and functions

13.5.1 DumpHeap

Synopsis: Dump memory usage report to stderr.

Declaration: `procedure DumpHeap`

Visibility: default

Description: DumpHeap dumps to standard output a summary of memory usage. It is called automatically by the heaptrc unit when your program exits (by installing an exit procedure), but it can be called at any time.

Errors: None.

See also: MarkHeap ([597](#))

13.5.2 SetHeapExtraInfo

Synopsis: Store extra information in blocks.

Declaration: `procedure SetHeapExtraInfo(size: puint; fillproc: tFillExtraInfoProc;
displayproc: tdisplayextrainfoProc)`

Visibility: default

Description: You can use SetHeapExtraInfo to store extra info in the blocks that the heaptrc unit reserves when tracing getmem calls. Size indicates the size (in bytes) that the trace mechanism should reserve for your extra information. For each call to getmem, FillProc will be called, and passed a pointer to the memory reserved.

When dumping the memory summary, the extra info is shown by calling displayproc and passing it the memory location which was filled by fillproc. It should write the information in readable form to the text file provided in the call to displayproc

Errors: You can only call SetHeapExtraInfo if no memory has been allocated yet. If memory was already allocated prior to the call to SetHeapExtraInfo, then an error will be displayed on standard error output, and a DumpHeap ([599](#)) is executed.

See also: DumpHeap ([599](#)), SetHeapTraceOutput ([601](#))

Listing: ./heapex/setinfo.pp

Program heapex;

{ Program used to demonstrate the usage of heaptrc unit }

Uses heaptrc;

Var P1 : ^Longint;
P2 : Pointer;
I : longint;
Marker : Longint;

Procedure SetMarker (P : pointer);

Type PLongint = ^Longint;

begin
PLongint(P)^:= Marker;
end;

Procedure Part1;

begin
// Blocks allocated here are marked with \$FFAFAFFA = -5570646

```

Marker := $FFAAFFAA;
New(P1);
New(P1);
Dispose(P1);
For I:=1 to 10 do
begin
  GetMem (P2,128);
  If (I mod 2) = 0 Then FreeMem(P2,128);
end;
GetMem(P2,128);
end;

Procedure Part2;

begin
  // Blocks allocated here are marked with $FAFAFAFA = -84215046
  Marker := $FAFAFAFA;
  New(P1);
  New(P1);
  Dispose(P1);
  For I:=1 to 10 do
  begin
    GetMem (P2,128);
    If (I mod 2) = 0 Then FreeMem(P2,128);
  end;
  GetMem(P2,128);
end;

begin
  SetExtraInfo ( SizeOf (Marker) , @SetMarker );
  WriteLn ( 'Part 1 ' );
  part1;
  WriteLn ( 'Part 2 ' );
  part2;
end.

```

13.5.3 SetHeapTraceOutput

Synopsis: Specify filename for heap trace output.

Declaration: `procedure SetHeapTraceOutput(const name: String)`

Visibility: default

Description: `SetHeapTraceOutput` sets the filename into which heap trace info will be written. By default information is written to standard output, this function allows you to redirect the information to a file with full filename name.

Errors: If the file cannot be written to, errors will occur when writing the trace.

See also: `SetHeapExtraInfo` ([600](#))

Chapter 14

Reference for unit 'ipc'

14.1 Used units

Table 14.1: Used units by unit 'ipc'

Name	Page
BaseUnix	602

14.2 Overview

This document describes the IPC unit for Free Pascal. It was written for linux by Michael Van Canneyt. It gives all the functionality of system V Inter-Process Communication: shared memory, semaphores and messages. It works only on the linux operating system.

Many constants here are provided for completeness only, and should under normal circumstances not be used by the programmer.

14.3 Constants, types and variables

14.3.1 Constants

`IPC_CREAT = 1 shl 9`

Create if key is nonexistent

`IPC_EXCL = 2 shl 9`

fail if key exists

`IPC_INFO = 3`

For ipcs call

`IPC_NOWAIT = 4 shl 9`

return error on wait

IPC_RMID = 0

Remove resource

IPC_SET = 1

set ipc_perm options

IPC_STAT = 2

get ipc_perm options

MSGMAX = 4056

Internal Message control code. Do not use

MSGMNB = 16384

Internal Message control code. Do not use

MSGMNI = 128

Internal Message control code. Do not use

MSG_EXCEPT = 2 shl 12

Internal Message control code. Do not use

MSG_NOERROR = 1 shl 12

Internal Message control code. Do not use

SEM_GETALL = 13

Semaphore operation: Get all semaphore values

SEM_GETNCNT = 14

Semaphore operation: Get number of processes waiting for resource.

SEM_GETPID = 11

Semaphore operation: Get process ID of last operation.

SEM_GETVAL = 12

Semaphore operation: Get current value of semaphore

SEM_GETZCNT = 15

Semaphore operation: Get number of processes waiting for semaphores to reach zero

`SEM_SEMMNI = 128`

Semaphore operation: ?

`SEM_SEMMNS = (SEM_SEMMNI * SEM_SEMMSL)`

Semaphore operation: ?

`SEM_SEMMSL = 32`

Semaphore operation: ?

`SEM_SEMOPM = 32`

Semaphore operation: ?

`SEM_SEVMX = 32767`

Semaphore operation: ?

`SEM_SETALL = 17`

Semaphore operation: Set all semaphore values

`SEM_SETVAL = 16`

Semaphore operation: Set semaphore value

`SEM_UNDO = $1000`

Constant for use in semop (618)

`SHM_LOCK = 11`

This constant is used in the shmctl (620) call.

`SHM_R = 4 shl 6`

This constant is used in the shmctl (620) call.

`SHM_RDONLY = 1 shl 12`

This constant is used in the shmctl (620) call.

`SHM_REMAP = 4 shl 12`

This constant is used in the shmctl (620) call.

`SHM_RND = 2 shl 12`

This constant is used in the shmctl (620) call.

```
SHM_UNLOCK = 12
```

This constant is used in the shmctl (620) call.

```
SHM_W = 2 shl 6
```

This constant is used in the shmctl (620) call.

14.3.2 Types

```
key_t = TKey
```

Alias for TKey (606) type

```
msglen_t = culong
```

Message length type

```
msgqnum_t = culong
```

Message queue number type

```
PIPC_Perm = ^TIPC_Perm
```

Pointer to TIPC_Perm (606) record.

```
PMSG = ^TMSG
```

Pointer to TMSG (606) record

```
PMSGbuf = ^TMSGbuf
```

Pointer to TMsgBuf (607) record

```
PMSGinfo = ^TMSGinfo
```

Pointer to TMSGinfo (607) record

```
PMSQid_ds = ^TMSQid_ds
```

Pointer to TMSQid_ds (607)

```
PSEMbuf = ^TSEMbuf
```

Pointer to TSembuf (607) record.

```
PSEMid_ds = ^TSEMid_ds
```

Pointer to TSEMid_ds (608) record.

```
PSEMinfo = ^TSEMinfo
```

Pointer to TSEMinfo (608) record.

```
PSEMun = ^TSEMun
```

Pointer to TSEMun (608) record

```
PShmid_DS = ^TShmid_ds
```

Pointer to TSHMid_ds (608) record.

```
PSHMinfo = ^TSHMinfo
```

```
TIPC_Perm = record
  key : TKey;
  uid : Word;
  gid : Word;
  cuid : Word;
  cgid : Word;
  mode : Word;
  seq : Word;
end
```

TIPC_Perm is used in all IPC systems to specify the permissions. It should never be used directly.

```
TKey = LongInt
```

Type returned by the ftok (609) key generating function.

```
TMSG = record
  msg_next : PMSG;
  msg_type : LongInt;
  msg_spot : PChar;
  msg_stime : LongInt;
  msg_ts : Integer;
end
```

Record used in the handling of message queues. Do not use directly.

```
TMSGbuf = record
  mtype : LongInt;
  mtext : Array[0..0] of Char;
end
```

The TMSGbuf record is a record containing the data of a record. you should never use this record directly, instead you should make your own record that follows the structure of the TMSGbuf record, but that has a size that is big enough to accomodate your messages. The `mtype` field should always be present, and should always be filled.

```
TMSGinfo = record
  msgpool : LongInt;
  msgmap : LongInt;
  msgmax : LongInt;
  msgmnb : LongInt;
  msgmni : LongInt;
  msgssz : LongInt;
  msgtql : LongInt;
  msgseg : Word;
end
```

Internal message system record. Do not use directly.

```
TMSGid_ds = record
  msg_perm : TIPC_Perm;
  msg_first : PMSG;
  msg_last : PMSG;
  msg_stime : LongInt;
  msg_rtime : LongInt;
  msg_ctime : LongInt;
  wwait : Pointer;
  rwait : pointer;
  msg_cbytes : Word;
  msg_qnum : Word;
  msg_qbytes : Word;
  msg_lspid : Word;
  msg_lrpid : Word;
end
```

This record should never be used directly, it is an internal kernel record. It's fields may change at any time.

```
TSEMbuf = record
  sem_num : cushort;
  sem_op : cshort;
  sem_flg : cshort;
end
```

The TSEMbuf record is used in the `semop` (618) call, and is used to specify which operations you want to do.

```
TSEMid_ds = record
  sem_perm : TIPC_Perm;
  sem_otime : LongInt;
  sem_ctime : LongInt;
```

```

sem_base : pointer;
sem_pending : pointer;
sem_pending_last : pointer;
undo : pointer;
sem_nsems : Word;
end

```

Structure returned by the `semctl` (613) call, contains all data of a semaphore

```

TSEMinfo = record
  semmap : cint;
  semmni : cint;
  semmns : cint;
  semmnu : cint;
  semmsl : cint;
  semopm : cint;
  semume : cint;
  semusz : cint;
  semvmx : cint;
  semaem : cint;
end

```

Internal semaphore system record. Do not use.

```

TSEMun = record
end

```

Record used in `semctl` (613) call.

```

TShmid_ds = record
  shm_perm : TIPC_Perm;
  shm_segsz : LongInt;
  shm_atime : LongInt;
  shm_dtime : LongInt;
  shm_ctime : LongInt;
  shm_cpid : Word;
  shm_lpid : Word;
  shm_nattch : Integer;
  shm_npages : Word;
  shm_pages : Pointer;
  attaches : pointer;
end

```

Record used in the `shmctl` (620) call to set or retrieve settings for shared memory.

```

TSHMinfo = record
  shmmax : cint;
  shmmni : cint;
  shmmni : cint;
end

```

```
shmseg : cint;
shmall : cint;
end
```

Record used by the shared memory system, Do not use directly.

14.4 Procedures and functions

14.4.1 ftok

Synopsis: Create token from filename

Declaration: `function ftok(Path: pchar; ID: cint) : TKey`

Visibility: default

Description: `ftok` returns a key that can be used in a `semget` (618), `shmget` (622) or `msgget` (612) call to access a new or existing IPC resource.

`Path` is the name of a file in the file system, `ID` is a character of your choice. The `ftok` call does the same as it's C counterpart, so a pascal program and a C program will access the same resource if they use the same `Path` and `ID`.

For an example, see `msgctl` (609), `semctl` (613) or `shmctl` (620).

Errors: `ftok` returns -1 if the file in `Path` doesn't exist.

See also: `semget` (618), `shmget` (622), `msgget` (612)

14.4.2 msgctl

Synopsis: Perform various operations on a message queue

Declaration: `function msgctl(msqid: cint; cmd: cint; buf: PMSQid_ds) : cint`

Visibility: default

Description: `msgctl` performs various operations on the message queue with id `ID`. Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

IPC_STAT In this case, the `msgctl` call fills the `TMSQid_ds` structure with information about the message queue.

IPC_SET In this case, the `msgctl` call sets the permissions of the queue as specified in the `ipc_perm` record inside `buf`.

IPC_RMID If this is specified, the message queue will be removed from the system.

`buf` contains the data that are needed by the call. It can be `Nil` in case the message queue should be removed.

The function returns `True` if successful, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set accordingly.

See also: `msgget` (612), `msgsnd` (613), `msgrcv` (612)

Listing: `./ipcex/msgtool.pp`

```

program msgtool;

Uses ipc,baseunix;

Type
  PMyMsgBuf = ^TMyMsgBuf;
  TMyMsgBuf = record
    mtype : Longint;
    mtext : string[255];
  end;

Procedure DoError (Const Msg : string);

begin
  Writeln (msg, ' returned an error : ',fpgeterrno);
  halt(1);
end;

Procedure SendMessage (Id : Longint;
                        Var Buf : TMyMsgBuf;
                        MType : Longint;
                        Const MText : String);

begin
  Writeln ( 'Sending message. ');
  Buf.mtype:=mtype;
  Buf.Mtext:=mtext;
  If msgsnd(Id,PMsgBuf(@Buf),256,0)=-1 then
    DoError('msgsnd');
end;

Procedure ReadMessage (ID : Longint;
                       Var Buf : TMyMsgBuf;
                       MType : longint);

begin
  Writeln ( 'Reading message. ');
  Buf.MType:=MType;
  If msgrcv(ID,PMSGBuf(@Buf),256,mtype,0)<>-1 then
    Writeln ( 'Type : ',buf.mtype, ' Text : ',buf.mtext)
  else
    DoError ( 'msgrcv ');
end;

Procedure RemoveQueue ( ID : Longint);

begin
  If msgctl (id,IPC_RMID,Nil)<>-1 then
    Writeln ( 'Removed Queue with id ',Id);
end;

Procedure ChangeQueueMode (ID,mode : longint);

Var QueueDS : TMSQid_ds;

begin
  If msgctl (Id,IPC_STAT,@QueueDS)=-1 then
    DoError ( 'msgctl : stat ');

```

```

Writeln ( 'Old permissions : ',QueueDS.msg_perm.mode);
QueueDS.msg_perm.mode:=Mode;
if msgctl ( ID,IPC_SET,@QueueDS)=0 then
    Writeln ( 'New permissions : ',QueueDS.msg_perm.mode)
else
    DoError ( 'msgctl : IPC_SET');
end;

procedure usage;

begin
    Writeln ( 'Usage : msgtool s(end) <type> <text> (max 255 characters)');
    Writeln ( '                      r(eceive) <type>');
    Writeln ( '                      d(elete)');
    Writeln ( '                      m(ode) <decimal mode>');
    halt(1);
end;

Function StrToInt (S : String): longint;

Var M : longint;
    C : Integer;

begin
    val (S,M,C);
    If C<>0 Then DoError ( 'StrToInt : '+S);
    StrToInt:=M;
end;

Var
    Key : TKey;
    ID : longint;
    Buf : TMyMsgBuf;

const ipckey = '.'#0;

begin
    If Paramcount<1 then Usage;
    key := Ftok (@ipckey[1],ord( 'M' ));
    ID:=msgget(key,IPC_CREAT or 438);
    If ID<0 then DoError ( 'MsgGet');
    Case upCase(Paramstr(1)[1]) of
        'S' : If ParamCount<>3 then
            Usage
        else
            SendMessage ( id ,Buf,StrToInt(Paramstr(2)),paramstr(3));
        'R' : If ParamCount<>2 then
            Usage
        else
            ReadMessage ( id ,buf,strtoint(Paramstr(2)));
        'D' : If ParamCount<>1 then
            Usage
        else
            RemoveQueue ( ID );
        'M' : If ParamCount<>2 then
            Usage
        else
            ChangeQueueMode ( id ,strtoint(paramstr(2)));
    end;

```



```

    else
        Usage
    end;
end.

```

14.4.3 msgget

Synopsis: Return message queue ID, possibly creating the queue

Declaration: `function msgget(key: TKey;msgflg: cint) : cint`

Visibility: default

Description: `msgget` returns the ID of the message queue described by `key`. Depending on the flags in `msgflg`, a new queue is created.

`msgflg` can have one or more of the following values (combined by ORs):

IPC_CREAT The queue is created if it doesn't already exist.

IPC_EXCL If used in combination with `IPC_CREAT`, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

For an example, see `msgctl` (609).

Errors: On error, -1 is returned, and `IPCError` is set.

See also: `ftok` (609), `msgsnd` (613), `msgrcv` (612), `msgctl` (609)

14.4.4 msgrcv

Synopsis: Retrieve a message from the queue

Declaration: `function msgrcv(msqid: cint;msgp: PMSGbuf;msgsz: size_t;msgtyp: cint;msgflg: cint) : cint`

Visibility: default

Description: `msgrcv` retrieves a message of type `msgtyp` from the message queue with ID `msqid`. `msgtyp` corresponds to the `mtype` field of the `TMSGbuf` record. The message is stored in the `MSGbuf` structure pointed to by `msgp`.

The `msgflg` parameter can be used to control the behaviour of the `msgrcv` call. It consists of an ORed combination of the following flags:

0 No special meaning.

IPC_NOWAIT If no messages are available, then the call returns immediately, with the `ENOMSG` error.

MSG_NOERROR If the message size is wrong (too large), no error is generated, instead the message is truncated. Normally, in such cases, the call returns an error (`E2BIG`)

The function returns `True` if the message was received correctly, `False` otherwise.

For an example, see `msgctl` (609).

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `msgget` (612), `msgsnd` (613), `msgctl` (609)

14.4.5 msgsnd

Synopsis: Send a message to the message queue

Declaration: `function msgsnd(msqid: cint;msgp: PMSGbuf;msgsz: size_t;msgflg: cint)
: cint`

Visibility: default

Description: `msgsend` sends a message to a message queue with ID `msqid`. `msgp` is a pointer to a message buffer, that should be based on the `TMsgBuf` type. `msgsz` is the size of the message (NOT of the message buffer record !)

The `msgflg` can have a combination of the following values (ORed together):

0No special meaning. The message will be written to the queue. If the queue is full, then the process is blocked.

IPC_NOWAITIf the queue is full, then no message is written, and the call returns immediately.

The function returns `True` if the message was sent successfully, `False` otherwise.

For an example, see `msgctl` (609).

Errors: In case of error, the call returns `False`, and `IPCError` is set.

See also: `msgget` (612), `msgrcv` (612), `msgctl` (609)

14.4.6 semctl

Synopsis: Perform various control operations on a semaphore set

Declaration: `function semctl(semid: cint;semnum: cint;cmd: cint;var arg: TSEMun)
: LongInt`

Visibility: default

Description: `semctl` performs various operations on the semaphore `semnum` with semaphore set id `ID`.

The `arg` parameter supplies the data needed for each call. This is a variant record that should be filled differently, according to the command:

```
Type
TSEMun = record
  case longint of
    0 : ( val : longint );
    1 : ( buf : PSEMid_ds );
    2 : ( arr : PWord );
    3 : ( padbuf : PSeminfo );
    4 : ( padpad : pointer );
  end;
```

Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

IPC_STATIn this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call fills this `TSEMid_ds` structure with information about the semaphore set.

IPC_SETIn this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call sets the permissions of the queue as specified in the `ipc_perm` record.

IPC_RMIDIf this is specified, the semaphore set is removed from the system.

GETALLIn this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be stored. The size of this memory area is `\var{SizeOf(Word)* Number of semaphores in the set}`. This call will then fill the memory array with all the values of the semaphores.

GETNCNTThis will fill the `val` field of the `arg` union with the number of processes waiting for resources.

GETPID`semctl` returns the process ID of the process that performed the last `semop` (618) call.

GETVAL`semctl` returns the value of the semaphore with number `semnum`.

GETZCNT`semctl` returns the number of processes waiting for semaphores that reach value zero.

SETALLIn this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be retrieved from. The size of this memory area is `\var{SizeOf(Word)* Number of semaphores in the set}`. This call will then set the values of the semaphores from the memory array.

SETVALThis will set the value of semaphore `semnum` to the value in the `val` field of the `arg` parameter.

The function returns -1 on error.

Errors: The function returns -1 on error, and `IPCError` is set accordingly.

See also: `semget` (618), `semop` (618)

Listing: `./ipccex/semtool.pp`

Program `semtool`;

{ Program to demonstrat the use of semaphores }

Uses `ipc,baseunix`;

Const `MaxSemValue = 5`;

Procedure `DoError (Const Msg : String)`;

```
begin
  Writeln ( 'Error : ',msg, ' Code : ',fpgeterrno);
  Halt(1);
end;
```

Function `getsemval (ID,Member : longint) : longint`;

Var `S : TSEMun`;

```
begin
  GetSemVal:= SemCtl(id ,member,SEM_GETVAL,S);
end;
```

Procedure `DispVal (ID,member : longint)`;

```
begin
  writeln ( 'Value for member ',member, ' is ',GetSemVal(ID,Member));
```

```

end;

Function GetMemberCount (ID : Longint) : longint;

Var opts : TSEMun;
    semds : TSEMid_ds;

begin
    opts.buf:=@semds;
    If semctl(Id,0,IPC_STAT,opts)<>-1 then
        GetMemberCount:=semds.sem_nsems
    else
        GetMemberCount:=-1;
end;

Function OpenSem (Key : TKey) : Longint;

begin
    OpenSem:=semget(Key,0,438);
    If OpenSem=-1 then
        DoError ('OpenSem');
end;

Function CreateSem (Key : TKey; Members : Longint) : Longint;

Var Count : Longint;
    Semopts : TSemun;

begin
    // the semmsl constant seems kernel specific
    { If members>semmsl then
        DoError ('Sorry, maximum number of semaphores in set exceeded');
    }
    WriteLn ('Trying to create a new semaphore set with ',members,' members. ');
    CreateSem:=semget(key,members,IPC_CREAT or IPC_Excl or 438);
    If CreateSem=-1 then
        DoError ('Semaphore set already exists. ');
    Semopts.val:=MaxSemValue; { Initial value of semaphores }
    For Count:=0 to Members-1 do
        semctl(CreateSem,count,SEM_SETVAL,semopts);
end;

Procedure lockSem (ID,Member: Longint);

Var lock : TSEMbuf;

begin
    With lock do
        begin
            sem_num:=0;
            sem_op:=-1;
            sem_flg:=IPC_NOWAIT;
        end;
        if (member<0) or (member>GetMemberCount(ID)-1) then
            DoError ('semaphore member out of range ');
        if getsemval(ID,member)=0 then
            DoError ('Semaphore resources exhausted (no lock) ');
        lock.sem_num:=member;

```

```

Writeln ( 'Attempting to lock member ',member, ' of semaphore ',ID );
if semop( Id ,@lock,1)=-1 then
    DoError ( 'Lock failed ' )
else
    Writeln ( 'Semaphore resources decremented by one ' );
    dispval( ID ,Member );
end;

Procedure UnlockSem ( ID ,Member: Longint );

Var Unlock : TSEMbuf;

begin
    With Unlock do
        begin
            sem_num:=0;
            sem_op:=1;
            sem_flg:=IPC_NOWAIT;
        end;
        if ( member<0 ) or ( member>GetMemberCount( ID )-1 ) then
            DoError ( 'semaphore member out of range ' );
        if getsemval( ID ,member)=MaxSemValue then
            DoError ( 'Semaphore not locked ' );
        Unlock.sem_num:=member;
        Writeln ( 'Attempting to unlock member ',member, ' of semaphore ',ID );
        if semop( Id ,@unlock,1)=-1 then
            DoError ( 'Unlock failed ' )
        else
            Writeln ( 'Semaphore resources incremented by one ' );
            dispval( ID ,Member );
        end;

Procedure RemoveSem ( ID : longint );

var S : TSemun;

begin
    If semctl( Id ,0 ,IPC_RMID ,s)<>-1 then
        Writeln ( 'Semaphore removed ' )
    else
        DoError ( 'Couldn't remove semaphore ' );
end;

Procedure ChangeMode ( ID ,Mode : longint );

Var rc : longint;
    opts : TSEMun;
    semds : TSEMid_ds;

begin
    opts.buf:=@semds;
    If not semctl ( Id ,0 ,IPC_STAT ,opts)<>-1 then
        DoError ( 'Couldn't stat semaphore ' );
    Writeln ( 'Old permissions were : ',semds.sem_perm.mode );
    semds.sem_perm.mode:=mode;
    If semctl( id ,0 ,IPC_SET ,opts)<>-1 then
        Writeln ( 'Set permissions to ',mode)

```

```

    else
        DoError ( 'Couldn't set permissions' );
end;

Procedure PrintSem ( ID : longint );

Var I, cnt : longint;

begin
    cnt:=getmembercount(ID);
    Writeln ( 'Semaphore ', ID, ' has ', cnt, ' Members' );
    For I:=0 to cnt-1 Do
        DispVal(id, i);
end;

Procedure USage;

begin
    Writeln ( 'Usage : semtool c(reate) <count>' );
    Writeln ( '          l(ock) <member>' );
    Writeln ( '          u(nlock) <member>' );
    Writeln ( '          d(etele)' );
    Writeln ( '          m(ode) <mode>' );
    halt(1);
end;

Function StrToInt ( S : String ): longint;

Var M : longint;
    C : Integer;

begin
    val ( S,M,C );
    If C<>0 Then DoError ( 'StrToInt : '+S );
    StrToInt:=M;
end;

Var Key : TKey;
    ID : Longint;

const ipckey='.'#0;

begin
    If ParamCount<1 then USage;
    key:=ftok ( @ipckey[1],ORD( 's' ));
    Case UpCase(Paramstr(1)[1]) of
        'C' : begin
            if paramcount<>2 then usage;
            CreateSem ( key, strtoint ( paramstr (2) ));
            end;
        'L' : begin
            if paramcount<>2 then usage;
            ID:=OpenSem ( key );
            LockSem ( ID, strtoint ( paramstr (2) ));
            end;
        'U' : begin
            if paramcount<>2 then usage;

```

```

        ID:=OpenSem ( key );
        UnLockSem ( ID , strtoint ( paramstr ( 2 ) ) );
        end;
'M' : begin
        if paramcount<>2 then usage;
        ID:=OpenSem ( key );
        ChangeMode ( ID , strtoint ( paramstr ( 2 ) ) );
        end;
'D' : Begin
        ID:=OpenSem ( Key );
        RemoveSem ( Id );
        end;
'P' : begin
        ID:=OpenSem ( Key );
        PrintSem ( Id );
        end;
    else
        Usage
    end;
end.

```

14.4.7 semget

Synopsis: Return the ID of a semaphore set, possibly creating the set

Declaration: `function semget (key: TKey;nsems: cint;semflg: cint) : cint`

Visibility: default

Description: `msgget` returns the ID of the semaphore set described by `key`. Depending on the flags in `semflg`, a new queue is created.

`semflg` can have one or more of the following values (combined by ORs):

IPC_CREATThe queue is created if it doesn't already exist.

IPC_EXCLIf used in combination with `IPC_CREAT`, causes the call to fail if the set already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new set of semaphores is created, then there will be `nsems` semaphores in it.

Errors: On error, -1 is returned, and `IPCError` is set.

See also: `ftok` ([609](#)), `semop` ([618](#)), `semctl` ([613](#))

14.4.8 semop

Synopsis: Perform semaphore operation.

Declaration: `function semop (semid: cint;sops: PSEMbuf;nsops: cuint) : cint`

Visibility: default

Description: `semop` performs a set of operations on a message queue. `sops` points to an array of type `TSEMbuf`. The array should contain `nsops` elements.

The fields of the `TSEMbuf` ([607](#)) structure

```
TSEMBuf = record
    sem_num : word;
    sem_op  : integer;
    sem_flg : integer;
```

should be filled as follows:

sem_numThe number of the semaphore in the set on which the operation must be performed.

sem_opThe operation to be performed. The operation depends on the sign of `sem_op`: A positive number is simply added to the current value of the semaphore. If 0 (zero) is specified, then the process is suspended until the specified semaphore reaches zero. If a negative number is specified, it is subtracted from the current value of the semaphore. If the value would become negative then the process is suspended until the value becomes big enough, unless `IPC_NOWAIT` is specified in the `sem_flg`.

sem_flgOptional flags: if `IPC_NOWAIT` is specified, then the calling process will never be suspended.

The function returns `True` if the operations were successful, `False` otherwise.

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `semget` (618), `semctl` (613)

14.4.9 shmat

Synopsis: Attach a shared memory block.

Declaration: `function shmat(shmid: cint; shmaddr: pointer; shmflg: cint) : pointer`

Visibility: default

Description: `shmat` attaches a shared memory block with identified `shmid` to the current process. The function returns a pointer to the shared memory block.

If `shmaddr` is `Nil`, then the system chooses a free unmapped memory region, as high up in memory space as possible.

If `shmaddr` is non-nil, and `SHM_RND` is in `shmflg`, then the returned address is `shmaddr`, rounded down to `SHMLBA`. If `SHM_RND` is not specified, then `shmaddr` must be a page-aligned address.

The parameter `shmflg` can be used to control the behaviour of the `shmat` call. It consists of a ORed combination of the following constants:

SHM_RNDThe suggested address in `shmaddr` is rounded down to `SHMLBA`.

SHM_RDONLYthe shared memory is attached for read access only. Otherwise the memory is attached for read-write. The process then needs read-write permissions to access the shared memory.

For an example, see `shmctl` (620).

Errors: If an error occurs, -1 is returned, and `IPCError` is set.

See also: `shmget` (622), `shmdt` (622), `shmctl` (620)

14.4.10 shmctl

Synopsis: Perform control operations on a shared memory block.

Declaration: `function shmctl(shmid: cint;cmd: cint;buf: PShmid_DS) : cint`

Visibility: default

Description: `shmctl` performs various operations on the shared memory block identified by identifier `shmid`.

The `buf` parameter points to a `TSHMid_ds` record. The `cmd` parameter is used to pass which operation is to be performed. It can have one of the following values :

IPC_STAT`shmctl` fills the `TSHMid_ds` record that `buf` points to with the available information about the shared memory block.

IPC_SETapplies the values in the `ipc_perm` record that `buf` points to, to the shared memory block.

IPC_RMIDthe shared memory block is destroyed (after all processes to which the block is attached, have detached from it).

If successful, the function returns `True`, `False` otherwise.

Errors: If an error occurs, the function returns `False`, and `IPCError` is set.

See also: `shmget` ([622](#)), `shmat` ([619](#)), `shmdt` ([622](#))

Listing: `./ipccex/shmtool.pp`

```

Program shmtool;

uses ipc , strings , Baseunix;

Const SegSize = 100;

var key : Tkey;
    shmid,cntr : longint;
    segptr : pchar;

Procedure USage;

begin
  Writeln ( 'Usage : shmtool w(rite) text' );
  writeln ( '                r(ead)' );
  writeln ( '                d(elete)' );
  writeln ( '                m(ode change) mode' );
  halt(1);
end;

Procedure Writeshm (ID : Longint; ptr : pchar; S : string);

begin
  strcpy ( ptr, S );
end;

Procedure Readshm(ID : longint; ptr : pchar);

begin
  Writeln ( 'Read : ',ptr );
end;

```

```

Procedure removeshm (ID : Longint);

begin
    shmctl (ID,IPC_RMID,Nil);
    writeln ( 'Shared memory marked for deletion ');
end;

Procedure CHangeMode (ID : longint; mode : String);

Var m : word;
    code : integer;
    data : TSHMid_ds;

begin
    val (mode,m,code);
    if code<>0 then
        usage;
    if shmctl (shmid,IPC_STAT,@data)=-1 then
        begin
            writeln ( 'Error : shmctl : ',fpgeterrno);
            halt(1);
        end;
    writeln ( 'Old permissions : ',data.shm_perm.mode);
    data.shm_perm.mode:=m;
    if shmctl (shmid,IPC_SET,@data)=-1 then
        begin
            writeln ( 'Error : shmctl : ',fpgeterrno);
            halt(1);
        end;
    writeln ( 'New permissions : ',data.shm_perm.mode);
end;

const ftokpath = '.'#0;

begin
    if paramcount<1 then usage;
    key := ftok (pchar(@ftokpath[1]),ord('S'));
    shmid := shmget(key,segsz,IPC_CREAT or IPC_EXCL or 438);
    if shmid=-1 then
        begin
            writeln ( 'Shared memory exists. Opening as client ');
            shmid := shmget(key,segsz,0);
            if shmid = -1 then
                begin
                    writeln ( 'shmget : Error ! ',fpgeterrno);
                    halt(1);
                end
            end
        else
            writeln ( 'Creating new shared memory segment. ');
            segptr:=shmat(shmid,Nil,0);
            if longint(segptr)=-1 then
                begin
                    writeln ( 'Shmat : error ! ',fpgeterrno);
                    halt(1);
                end;
            case upcase(paramstr(1)[1]) of

```

```

    'W' : writeshm ( shmId , segptr , paramstr (2));
    'R' : readshm ( shmId , segptr );
    'D' : removeshm (shmId);
    'M' : changemode ( shmId , paramstr (2));
  else
    begin
      writeln ( paramstr (1));
      usage;
    end;
  end;
end.

```

14.4.11 shmdt

Synopsis: Detach shared memory block.

Declaration: `function shmdt (shmaddr: pointer) : cint`

Visibility: default

Description: `shmdt` detaches the shared memory at address `shmaddr`. This shared memory block is unavailable to the current process, until it is attached again by a call to `shmat` (619).

The function returns `True` if the memory block was detached successfully, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set.

See also: `shmget` (622), `shmat` (619), `shmctl` (620)

14.4.12 shmget

Synopsis: Return the ID of a shared memory block, possibly creating it

Declaration: `function shmget (key: TKey; size: cint; flag: cint) : cint`

Visibility: default

Description: `shmget` returns the ID of a shared memory block, described by `key`. Depending on the flags in `flag`, a new memory block is created.

`flag` can have one or more of the following values (combined by ORs):

IPC_CREAT The queue is created if it doesn't already exist.

IPC_EXCL If used in combination with `IPC_CREAT`, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new memory block is created, then it will have size `Size` bytes in it.

Errors: On error, -1 is returned, and `IPCError` is set.

Chapter 15

Reference for unit 'keyboard'

15.1 Unix specific notes

On Unix, applications run on a "terminal", and the application writes to the screen and reads from the keyboard by communicating with the terminal. Unix keyboard handling is mostly backward compatible with the DEC vt100 and vt220 terminals from tens of years ago. The vt100 and vt220 had very different keyboards than today's PC's and this is where the problems start. To make it worse the protocol of both terminals has not been very well designed.

Because of this, the keyboard unit on Unix operating systems does a best effort to provide keyboard functionality. An implementation with full keyboard facilities like on other operating systems is not possible.

The exception is the Linux kernel. The terminal emulation of the Linux kernel is from a PC keyboard viewpoint hopeless as well, but unlike other terminal emulators it is configurable. On the Linux console, the Free Pascal keyboard unit tries to implement full functionality.

Users of applications using the keyboard unit should expect the following:

- Full functionality on the Linux console. It must be the bare console, SSH into another machine will kill the full functionality.
- Limited functionality otherwise.

Notes about Linux full functionality:

- The keyboard is reprogrammed. If the keyboard is for whatever reason not restored in its original state, please load your keymap to reinitialize it.
- Alt+function keys generate keycodes for those keys. To switch virtual consoles, use ctrl+alt+function key.
- Unlike what you're used to with other Unix software, escape works as you intuitively expect, it generates the keycode for an escape key **without a delay**.

The limited functionality does include these quirks:

- Escape must be pressed two times before it has effect.
- On the Linux console, when the user runs the program by logging into another machine:
 - Shift+F1 and Shift+F12 will generate keycodes for F11 and F12.

- Shift+arrow keys, shift+ins, shift+del, shift+home, shift+end do not work. The same is true about the control and alt combinations.
- Alt+function keys will switch virtual consoles instead of generating the right key sequences.
- Ctrl+function keys will generate the keycodes for the function keys without ctrl
- In Xterm:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
- In Konsole:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
 - Shift+arrow keys doesn't work, nor does ctrl+arrow keys

If you have a non-standard terminal, some keys may not work at all. When in limited functionality mode, the user can work around using an escape prefix:

- Esc+1 = F1, Esc+2 = F2.
- Esc before another key is equal to alt+key.

In such cases, if the terminal does output an escape sequence for those keys, please submit a bug report so we can add them.

15.2 Writing a keyboard driver

Writing a keyboard driver means that hooks must be created for most of the keyboard unit functions. The `TKeyboardDriver` record contains a field for each of the possible hooks:

```
TKeyboardDriver = Record
  InitDriver : Procedure;
  DoneDriver : Procedure;
  GetKeyEvent : Function : TKeyEvent;
  PollKeyEvent : Function : TKeyEvent;
  GetShiftState : Function : Byte;
  TranslateKeyEvent : Function (KeyEvent: TKeyEvent): TKeyEvent;
  TranslateKeyEventUnicode: Function (KeyEvent: TKeyEvent): TKeyEvent;
end;
```

The meaning of these hooks is explained below:

InitDriver Called to initialize and enable the driver. Guaranteed to be called only once. This should initialize all needed things for the driver.

DoneDriver Called to disable and clean up the driver. Guaranteed to be called after a call to `initDriver`. This should clean up all things initialized by `InitDriver`.

GetKeyEvent Called by `GetKeyEvent` (632). Must wait for and return the next key event. It should NOT store keys.

PollKeyEvent Called by `PollKeyEvent` (638). It must return the next key event if there is one. Should not store keys.

GetShiftState Called by `PollShiftStateEvent` (638). Must return the current shift state.

TranslateKeyEvent Should translate a raw key event to a correct key event, i.e. should fill in the shiftstate and convert function key scancodes to function key keycodes. If the `TranslateKeyEvent` is not filled in, a default translation function will be called which converts the known scancodes from the tables in the previous section to a correct keyevent.

TranslateKeyEventUnicode Should translate a key event to a unicode key representation.

Strictly speaking, only the `GetKeyEvent` and `PollKeyEvent` hooks must be implemented for the driver to function correctly.

The example unit demonstrates how a keyboard driver can be installed. It takes the installed driver, and hooks into the `GetKeyEvent` function to register and log the key events in a file. This driver can work on top of any other driver, as long as it is inserted in the `uses` clause *after* the real driver unit, and the real driver unit should set the driver record in its initialization section.

Note that with a simple extension of this unit could be used to make a driver that is capable of recording and storing a set of keyboard strokes, and replaying them at a later time, so a 'keyboard macro' capable driver. This driver could sit on top of any other driver.

15.3 Keyboard scan codes

Special physical keys are encoded with the DOS scan codes for these keys in the second byte of the `TKeyEvent` (630) type. A complete list of scan codes can be found in the below table. This is the list of keys that is used by the default key event translation mechanism. When writing a keyboard driver, either these constants should be returned by the various key event functions, or the `TranslateKeyEvent` hook should be implemented by the driver.

A list of scan codes for special keys and combinations with the SHIFT, ALT and CTRL keys can be found in the following table: They are for quick reference only.

15.4 Overview

The Keyboard unit implements a keyboard access layer which is system independent. It can be used to poll the keyboard state and wait for certain events. Waiting for a keyboard event can be done with the `GetKeyEvent` (632) function, which will return a driver-dependent key event. This key event can be translated to an interpretable event by the `TranslateKeyEvent` (641) function. The result of this function can be used in the other event examining functions.

A custom keyboard driver can be installed using the `SetKeyboardDriver` (640) function. The current keyboard driver can be retrieved using the `GetKeyboardDriver` (632) function. The last section of this chapter demonstrates how to make a keyboard driver.

15.5 Constants, types and variables

15.5.1 Constants

`AltPrefix : Byte = 0`

Alt key name index.

`CtrlPrefix : Byte = 0`

Alt key name index.

`errKbdBase = 1010`

Base of keyboard routine error reporting constants.

`errKbdInitError = errKbdBase + 0`

Failed to initialize keyboard driver

`errKbdNotImplemented = errKbdBase + 1`

Keyboard driver not implemented.

`kbAlt = 8`

Alt key modifier

`kbASCII = $00`

Ascii code key event

`kbCtrl = 4`

Control key modifier

`kbdApps = $FF17`

Application key (popup-menu) pressed.

`kbdDelete = $FF2A`

Delete key pressed

`kbdDown = $FF27`

Arrow down key pressed

`kbdEnd = $FF26`

End key pressed

`kbdF1 = $FF01`

F1 function key pressed.

`kbdF10 = $FF0A`

F10 function key pressed.

`kbdF11 = $FF0B`

F12 function key pressed.

kbdF12 = \$FF0C

F12 function key pressed.

kbdF13 = \$FF0D

F13 function key pressed.

kbdF14 = \$FF0E

F14 function key pressed.

kbdF15 = \$FF0F

F15 function key pressed.

kbdF16 = \$FF10

F16 function key pressed.

kbdF17 = \$FF11

F17 function key pressed.

kbdF18 = \$FF12

F18 function key pressed.

kbdF19 = \$FF13

F19 function key pressed.

kbdF2 = \$FF02

F2 function key pressed.

kbdF20 = \$FF14

F20 function key pressed.

kbdF3 = \$FF03

F3 function key pressed.

kbdF4 = \$FF04

F4 function key pressed.

kbdF5 = \$FF05

F5 function key pressed.

kbdF6 = \$FF06

F6 function key pressed.

kbdF7 = \$FF07

F7 function key pressed.

kbdF8 = \$FF08

F8 function key pressed.

kbdF9 = \$FF09

F9 function key pressed.

kbdHome = \$FF20

Home key pressed

kbdInsert = \$FF29

Insert key pressed

kbdLeft = \$FF23

Arrow left key pressed

kbdLWin = \$FF15

Left windows key pressed.

kbdMiddle = \$FF24

Middle key pad key pressed (numerical 5)

kbdPgDn = \$FF28

Page down key pressed

kbdPgUp = \$FF22

Page Up key pressed

kbdRight = \$FF25

Arrow right key pressed

kbdRWin = \$FF16

Right windows key pressed.

`kbdUp = $FF21`

Arrow up key pressed

`kbFnKey = $02`

function key pressed.

`kbLeftShift = 1`

Left shift key modifier

`kbPhys = $03`

Physical key code event

`kbReleased = $04`

Key release event

`kbRightShift = 2`

Right shift key modifier

`kbShift = kbLeftShift or kbRightShift`

Shift key modifier

`kbUnicode = $01`

Unicode code key event

`SAnd : String = 'AND'`

This constant is used as the 'And' word in key descriptions. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`ShiftPrefix : Byte = 0`

Shift key name index.

`SKeyPad : Array[0..($FF2F-kbdHome)] of String = ('Home', 'Up', 'PgUp', 'Left', 'Middle',`

This constant describes all keypad keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`SLeftRight : Array[1..2] of String = ('LEFT', 'RIGHT')`

This constant contains strings to describe left and right keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SScanCode : String = 'Key with scancode '
```

This constant contains a string to denote a scancode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SShift : Array[1..3] of String = ('SHIFT', 'CTRL', 'ALT' )
```

This constant describes the various modifier keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnicodeChar : String = 'Unicode character '
```

This constant contains a string to denote a unicode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnknownFunctionKey : String = 'Unknown function key : '
```

This constant contains a string to denote that an unknown function key was found. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

15.5.2 Types

```
TKeyboardDriver = record
  InitDriver : procedure;
  DoneDriver : procedure;
  GetKeyEvent : function : TKeyEvent;
  PollKeyEvent : function : TKeyEvent;
  GetShiftState : function : Byte;
  TranslateKeyEvent : function(KeyEvent: TKeyEvent) : TKeyEvent;
  TranslateKeyEventUniCode : function(KeyEvent: TKeyEvent) : TKeyEvent;
end
```

The `TKeyboardDriver` record can be used to install a custom keyboard driver with the `SetKeyboardDriver` (640) function.

The various fields correspond to the different functions of the keyboard unit interface. For more information about this record see `kbddriver` (624)

```
TKeyEvent = Cardinal
```

The `TKeyEvent` type is the base type for all keyboard events.

The key stroke is encoded in the 4 bytes of the `TKeyEvent` type. The various fields of the key stroke encoding can be obtained by typecasting the `TKeyEvent` type to the `TKeyRecord` (631) type.

```
TKeyRecord = packed record
  KeyCode : Word;
  ShiftState : Byte;
  Flags : Byte;
end
```

The structure of a `TKeyRecord` structure is explained in the following table:

The shift-state can be checked using the various shift-state constants, and the flags in the last byte can be checked using one of the `kbASCII`, `kbUnicode`, `kbFnKey`, `kbPhys`, `kbReleased` constants.

If there are two keys returning the same char-code, there's no way to find out which one was pressed (Gray+ and Simple+). If it needs to be known which was pressed, the untranslated keycodes must be used, but these are system dependent. System dependent constants may be defined to cover those, with possibly having the same name (but different value).

15.6 Procedures and functions

15.6.1 AddSequence

Declaration: `procedure AddSequence(const St: String; AChar: Byte; AScan: Byte)`

Visibility: default

15.6.2 DoneKeyboard

Synopsis: Deactivate keyboard driver.

Declaration: `procedure DoneKeyboard`

Visibility: default

Description: `DoneKeyboard` de-initializes the keyboard interface if the keyboard driver is active. If the keyboard driver is not active, the function does nothing.

This will cause the keyboard driver to clear up any allocated memory, or restores the console or terminal the program was running in to its initial state before the call to `InitKeyBoard` (636). This function should be called on program exit. Failing to do so may leave the terminal or console window in an unusable state. Its exact action depends on the platform on which the program is running.

On Unix the default keyboard driver restores the line ending of `system.output` to `#10`.

For an example, see most other functions.

Errors: None.

See also: `InitKeyBoard` (636)

15.6.3 FindSequence

Declaration: `function FindSequence(const St: String; var AChar: Byte; var AScan: Byte)
: Boolean`

Visibility: default

15.6.4 FunctionKeyName

Synopsis: Return string representation of a function key code.

Declaration: `function FunctionKeyName(KeyCode: Word) : String`

Visibility: default

Description: `FunctionKeyName` returns a string representation of the function key with code `KeyCode`. This can be an actual function key, or one of the cursor movement keys.

Errors: In case `KeyCode` does not contain a function code, the `SUnknownFunctionKey` string is returned, appended with the `KeyCode`.

See also: `ShiftStateToString` ([641](#)), `KeyEventToString` ([637](#))

Listing: `./kbdex/ex8.pp`

Program `Example8`;

{ Program to demonstrate the FunctionKeyName function. }

Uses `keyboard`;

Var

`K : TKeyEvent`;

begin

`InitKeyboard`;

WriteIn ('Press function keys , press "q" to end.');

Repeat

`K:=GetKeyEvent`;

`K:=TranslateKeyEvent(K)`;

If `IsFunctionKey(k)` **then**

begin

Write ('Got function key : ');

WriteIn (`FunctionKeyName(TkeyRecord(K).KeyCode)`);

end;

Until (`GetKeyEventChar(K)= 'q'`);

`DoneKeyboard`;

end.

15.6.5 GetKeyboardDriver

Synopsis: Return the current keyboard driver record.

Declaration: `procedure GetKeyboardDriver(var Driver: TKeyboardDriver)`

Visibility: `default`

Description: `GetKeyboardDriver` returns in `Driver` the currently active keyboard driver. This function can be used to enhance an existing keyboarddriver.

For more information on getting and setting the keyboard driver `kbddriver` ([624](#)).

Errors: None.

See also: `SetKeyboardDriver` ([640](#))

15.6.6 GetKeyEvent

Synopsis: Get the next raw key event, wait if needed.

Declaration: `function GetKeyEvent : TKeyEvent`

Visibility: `default`

Description: `GetKeyEvent` returns the last keyevent if one was stored in `PendingKeyEvent`, or waits for one if none is available. A non-blocking version is available in `PollKeyEvent` (638).

The returned key is encoded as a `TKeyEvent` type variable, and is normally the physical key scan code, (the scan code is driver dependent) which can be translated with one of the translation functions `TranslateKeyEvent` (641) or `TranslateKeyEventUnicode` (641). See the types section for a description of how the key is described.

Errors: If no key became available, 0 is returned.

See also: `PutKeyEvent` (639), `PollKeyEvent` (638), `TranslateKeyEvent` (641), `TranslateKeyEventUnicode` (641)

Listing: `./kbdex/ex1.pp`

```

program example1;

{ This program demonstrates the GetKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent;
    K:=TranslateKeyEvent(K);
    Write('Got key event with ');
    Case GetKeyEventFlags(K) of
      kbASCII      : Writeln('ASCII key');
      kbUnicode    : Writeln('Unicode key');
      kbFnKey      : Writeln('Function key');
      kbPhys       : Writeln('Physical key');
      kbReleased   : Writeln('Released key event');
    end;
    K:=TranslateKeyEvent(K);
    Writeln('Got key : ', KeyEventToString(K));
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard;
end.
```

15.6.7 GetKeyEventChar

Synopsis: Get the character key part of a key event.

Declaration: `function GetKeyEventChar(KeyEvent: TKeyEvent) : Char`

Visibility: default

Description: `GetKeyEventChar` returns the charcode part of the given `KeyEvent`, if it contains a translated character key keycode. The charcode is simply the ascii code of the character key that was pressed.

It returns the null character if the key was not a character key, but e.g. a function key.

For an example, see `GetKeyEvent` (632)

Errors: None.

See also: [GetKeyEventUnicode \(636\)](#), [GetKeyEventShiftState \(635\)](#), [GetKeyEventFlags \(634\)](#), [GetKeyEventCode \(634\)](#), [GetKeyEvent \(632\)](#)

15.6.8 GetKeyEventCode

Synopsis: Translate function key part of a key event code.

Declaration: `function GetKeyEventCode (KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventCode` returns the translated function keycode part of the given `KeyEvent`, if it contains a translated function key.

If the key pressed was not a function key, the null character is returned.

Errors: None.

See also: [GetKeyEventUnicode \(636\)](#), [GetKeyEventShiftState \(635\)](#), [GetKeyEventFlags \(634\)](#), [GetKeyEventChar \(633\)](#), [GetKeyEvent \(632\)](#)

Listing: `./kbdex/ex2.pp`

Program Example2;

{ Program to demonstrate the GetKeyEventCode function. }

Uses keyboard;

Var

K : TKeyEvent;

begin

InitKeyboard;

WriteIn ('Press function keys, or press "q" to end.');

Repeat

K:=GetKeyEvent;

K:=TranslateKeyEvent(K);

If (GetKeyEventFlags(K)<>KbfnKey) **then**

WriteIn ('Not a function key')

else

begin

Write ('Got key (',GetKeyEventCode(K));

WriteIn (') : ',KeyEventToString(K));

end;

Until (GetKeyEventChar(K)= 'q');

DoneKeyboard;

end.

15.6.9 GetKeyEventFlags

Synopsis: Extract the flags from a key event.

Declaration: `function GetKeyEventFlags (KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventFlags` returns the flags part of the given `KeyEvent`.

For an example, see `GetKeyEvent` (632)

Errors: None.

See also: `GetKeyEventUnicode` (636), `GetKeyEventShiftState` (635), `GetKeyEventCode` (634), `GetKeyEventChar` (633), `GetKeyEvent` (632)

15.6.10 `GetKeyEventShiftState`

Synopsis: Return the current state of the shift keys.

Declaration: `function GetKeyEventShiftState (KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventShiftState` returns the shift-state values of the given `KeyEvent`. This can be used to detect which of the modifier keys `Shift`, `Alt` or `Ctrl` were pressed. If none were pressed, zero is returned.

Note that this function does not always return expected results; In a unix X-Term, the modifier keys do not always work.

Errors: None.

See also: `GetKeyEventUnicode` (636), `GetKeyEventFlags` (634), `GetKeyEventCode` (634), `GetKeyEventChar` (633), `GetKeyEvent` (632)

Listing: `./kbdex/ex3.pp`

Program `Example3`;

{ Program to demonstrate the GetKeyEventShiftState function. }

Uses `keyboard`;

Var

`K : TKeyEvent;`
 `S : Byte;`

begin

`InitKeyBoard;`
 `Write('Press keys combined with CTRL/SHIFT/ALT');`
 `WriteLn(' , or press "q" to end.');`
 Repeat
 `K:=GetKeyEvent;`
 `K:=TranslateKeyEvent(K);`
 `S:=GetKeyEventShiftState(K);`
 If `(S=0)` **then**
 `WriteLn('No special keys pressed')`
 else
 begin
 `WriteLn('Detected special keys : ', ShiftStateToString(K, False));`
 `WriteLn('Got key : ', KeyEventToString(K));`
 end;
 Until `(GetKeyEventChar(K)= 'q');`
 `DoneKeyboard;`

end.

15.6.11 GetKeyEventUnicode

Synopsis: Return the unicode key event.

Declaration: `function GetKeyEventUnicode(KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventUnicode` returns the unicode part of the given `KeyEvent` if it contains a translated unicode character.

Errors: None.

See also: `GetKeyEventShiftState` (635), `GetKeyEventFlags` (634), `GetKeyEventCode` (634), `GetKeyEventChar` (633), `GetKeyEvent` (632)

15.6.12 InitKeyboard

Synopsis: Initialize the keyboard driver.

Declaration: `procedure InitKeyboard`

Visibility: default

Description: `InitKeyboard` initializes the keyboard driver. If the driver is already active, it does nothing. When the driver is initialized, it will do everything necessary to ensure the functioning of the keyboard, including allocating memory, initializing the terminal etc.

This function should be called once, before using any of the keyboard functions. When it is called, the `DoneKeyboard` (631) function should also be called before exiting the program or changing the keyboard driver with `SetKeyboardDriver` (640).

On Unix, the default keyboard driver sets terminal in raw mode. In raw mode the line feed behaves as an actual linefeed, i.e. the cursor is moved down one line. while the x coordinate does not change. To compensate, the default keyboard sets driver line ending of `system.output` to `#13#10`.

For an example, see most other functions.

Errors: None.

See also: `DoneKeyboard` (631), `SetKeyboardDriver` (640)

15.6.13 IsFunctionKey

Synopsis: Check whether a given event is a function key event.

Declaration: `function IsFunctionKey(KeyEvent: TKeyEvent) : Boolean`

Visibility: default

Description: `IsFunctionKey` returns `True` if the given key event in `KeyEvent` was a function key or not.

Errors: None.

See also: `GetKeyEvent` (632)

Listing: `./kbdex/ex7.pp`

```

program example1;

{ This program demonstrates the GetKeyEvent function }

uses keyboard;

Var
    K : TKeyEvent;

begin
    InitKeyBoard;
    WriteLn('Press keys , press "q" to end. ');
    Repeat
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
        If IsFunctionKey(K) then
            WriteLn('Got function key : ',KeyEventToString(K))
        else
            WriteLn('not a function key. ');
        Until ( GetKeyEventChar(K)= 'q' );
    DoneKeyBoard;
end.

```

15.6.14 KeyEventToString

Synopsis: Return a string describing the key event.

Declaration: `function KeyEventToString(KeyEvent: TKeyEvent) : String`

Visibility: default

Description: `KeyEventToString` translates the key event in `KeyEvent` to a human-readable description of the pressed key. It will use the constants described in the constants section to do so.

For an example, see most other functions.

Errors: If an unknown key is passed, the scancode is returned, prefixed with the `SScanCode` string.

See also: `FunctionKeyName` ([631](#)), `ShiftStateToString` ([641](#))

15.6.15 KeyPressed

Synopsis: Check event queue for key press

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` checks the keyboard event queue to see whether a key event is present, and returns `True` if a key event is available. This function simply calls `PollKeyEvent` ([638](#)) and checks for a valid result.

Errors: None.

See also: `PollKeyEvent` ([638](#)), `GetKeyEvent` ([632](#))

15.6.16 PollKeyEvent

Synopsis: Get next key event, but does not wait.

Declaration: `function PollKeyEvent : TKeyEvent`

Visibility: default

Description: `PollKeyEvent` checks whether a key event is available, and returns it if one is found. If no event is pending, it returns 0.

Note that this does not remove the key from the pending keys. The key should still be retrieved from the pending key events list with the `GetKeyEvent` (632) function.

Errors: None.

See also: `PutKeyEvent` (639), `GetKeyEvent` (632)

Listing: `./kbdex/ex4.pp`

```

program example4;

{ This program demonstrates the PollKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys , press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
        writeln;
        Writeln('Got key : ',KeyEventToString(K));
      end
    else
      write(' ');
    Until (GetKeyEventChar(K)= 'q ');
  DoneKeyBoard;
end.
```

15.6.17 PollShiftStateEvent

Synopsis: Check current shift state.

Declaration: `function PollShiftStateEvent : TKeyEvent`

Visibility: default

Description: `PollShiftStateEvent` returns the current shiftstate in a keyevent. This will return 0 if there is no key event pending.

Errors: None.

See also: [PollKeyEvent \(638\)](#), [GetKeyEvent \(632\)](#)

Listing: ./kbdex/ex6.pp

```

program example6;

{ This program demonstrates the PollShiftStateEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys , press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=PollShiftStateEvent;
        WriteLn('Got shift state : ', ShiftStateToString(K, False));
        // Consume the key.
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
      end
    else
      write(' ');
    Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
  end.
```

15.6.18 PutKeyEvent

Synopsis: Put a key event in the event queue.

Declaration: `procedure PutKeyEvent (KeyEvent : TKeyEvent)`

Visibility: default

Description: `PutKeyEvent` adds the given `KeyEvent` to the input queue. Please note that depending on the implementation this can hold only one value, i.e. when calling `PutKeyEvent` multiple times, only the last pushed key will be remembered.

Errors: None

See also: [PollKeyEvent \(638\)](#), [GetKeyEvent \(632\)](#)

Listing: ./kbdex/ex5.pp

```

program example5;

{ This program demonstrates the PutKeyEvent function }

uses keyboard;

Var
  K, k2 : TKeyEvent;
```

```

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end. ');
  K2:=0;
  Repeat
    K:=GetKeyEvent;
    If k<>0 then
      begin
        if (k2 mod 2)=0 then
          K2:=K+1
        else
          K2:=0;
        K:=TranslateKeyEvent(K);
        Writeln('Got key : ',KeyEventToString(K));
        if (K2<>0) then
          begin
            PutKeyEvent(k2);
            K2:=TranslateKeyEvent(K2);
            Writeln('Put key : ',KeyEventToString(K2))
          end
        end
      Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
  end.

```

15.6.19 RawReadKey

Declaration: function RawReadKey : Char

Visibility: default

15.6.20 RawReadString

Declaration: function RawReadString : String

Visibility: default

15.6.21 RestoreStartMode

Declaration: procedure RestoreStartMode

Visibility: default

15.6.22 SetKeyboardDriver

Synopsis: Set a new keyboard driver.

Declaration: function SetKeyboardDriver(const Driver: TKeyboardDriver) : Boolean

Visibility: default

Description: SetKeyBoardDriver sets the keyboard driver to Driver, if the current keyboard driver is not yet initialized. If the current keyboard driver is initialized, then SetKeyboardDriver does nothing. Before setting the driver, the currently active driver should be disabled with a call to DoneKeyboard ([631](#)).

The function returns `True` if the driver was set, `False` if not.

For more information on setting the keyboard driver, see `kbddriver` (624).

Errors: None.

See also: `GetKeyboardDriver` (632), `DoneKeyboard` (631)

15.6.23 ShiftStateToString

Synopsis: Return description of key event shift state

Declaration: `function ShiftStateToString(KeyEvent: TKeyEvent; UseLeftRight: Boolean) : String`

Visibility: default

Description: `ShiftStateToString` returns a string description of the shift state of the key event `KeyEvent`.

This can be an empty string.

The shift state is described using the strings in the `SShift` constant.

For an example, see `PollShiftStateEvent` (638).

Errors: None.

See also: `FunctionKeyName` (631), `KeyEventToString` (637)

15.6.24 TranslateKeyEvent

Synopsis: Translate raw event to ascii key event

Declaration: `function TranslateKeyEvent(KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEvent` performs ASCII translation of the `KeyEvent`. It translates a physical key to a function key if the key is a function key, and translates the physical key to the ordinal of the ascii character if there is an equivalent character key.

For an example, see `GetKeyEvent` (632)

Errors: None.

See also: `TranslateKeyEventUnicode` (641)

15.6.25 TranslateKeyEventUnicode

Synopsis: Translate raw event to UNICODE key event

Declaration: `function TranslateKeyEventUnicode(KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEventUnicode` performs Unicode translation of the `KeyEvent`. It is not yet implemented for all platforms.

Errors: If the function is not yet implemented, then the `ErrorCode` of the `system` unit will be set to `errKbdNotImplemented`

See also: `TranslateKeyEvent` (641)

Table 15.1: Key Scancodes

Code	Key	Code	Key	Code	Key
00	NoKey	3D	F3	70	ALT-F9
01	ALT-Esc	3E	F4	71	ALT-F10
02	ALT-Space	3F	F5	72	CTRL-PrtSc
04	CTRL-Ins	40	F6	73	CTRL-Left
05	SHIFT-Ins	41	F7	74	CTRL-Right
06	CTRL-Del	42	F8	75	CTRL-end
07	SHIFT-Del	43	F9	76	CTRL-PgDn
08	ALT-Back	44	F10	77	CTRL-Home
09	ALT-SHIFT-Back	47	Home	78	ALT-1
0F	SHIFT-Tab	48	Up	79	ALT-2
10	ALT-Q	49	PgUp	7A	ALT-3
11	ALT-W	4B	Left	7B	ALT-4
12	ALT-E	4C	Center	7C	ALT-5
13	ALT-R	4D	Right	7D	ALT-6
14	ALT-T	4E	ALT-GrayPlus	7E	ALT-7
15	ALT-Y	4F	end	7F	ALT-8
16	ALT-U	50	Down	80	ALT-9
17	ALT-I	51	PgDn	81	ALT-0
18	ALT-O	52	Ins	82	ALT-Minus
19	ALT-P	53	Del	83	ALT-Equal
1A	ALT-LftBrack	54	SHIFT-F1	84	CTRL-PgUp
1B	ALT-RgtBrack	55	SHIFT-F2	85	F11
1E	ALT-A	56	SHIFT-F3	86	F12
1F	ALT-S	57	SHIFT-F4	87	SHIFT-F11
20	ALT-D	58	SHIFT-F5	88	SHIFT-F12
21	ALT-F	59	SHIFT-F6	89	CTRL-F11
22	ALT-G	5A	SHIFT-F7	8A	CTRL-F12
23	ALT-H	5B	SHIFT-F8	8B	ALT-F11
24	ALT-J	5C	SHIFT-F9	8C	ALT-F12
25	ALT-K	5D	SHIFT-F10	8D	CTRL-Up
26	ALT-L	5E	CTRL-F1	8E	CTRL-Minus
27	ALT-SemiCol	5F	CTRL-F2	8F	CTRL-Center
28	ALT-Quote	60	CTRL-F3	90	CTRL-GreyPlus
29	ALT-OpQuote	61	CTRL-F4	91	CTRL-Down
2B	ALT-BkSlash	62	CTRL-F5	94	CTRL-Tab
2C	ALT-Z	63	CTRL-F6	97	ALT-Home
2D	ALT-X	64	CTRL-F7	98	ALT-Up
2E	ALT-C	65	CTRL-F8	99	ALT-PgUp
2F	ALT-V	66	CTRL-F9	9B	ALT-Left
30	ALT-B	67	CTRL-F10	9D	ALT-Right
31	ALT-N	68	ALT-F1	9F	ALT-end
32	ALT-M	69	ALT-F2	A0	ALT-Down
33	ALT-Comma	6A	ALT-F3	A1	ALT-PgDn
34	ALT-Period	6B	ALT-F4	A2	ALT-Ins
35	ALT-Slash	6C	ALT-F5	A3	ALT-Del
37	ALT-GreyAst	6D	ALT-F6	A5	ALT-Tab
3B	F1	6E	ALT-F7		
3C	F2	6F	ALT-F8		

Table 15.2: Special keys scan codes

Key	Code	SHIFT-Key	CTRL-Key	Alt-Key
NoKey	00			
F1	3B	54	5E	68
F2	3C	55	5F	69
F3	3D	56	60	6A
F4	3E	57	61	6B
F5	3F	58	62	6C
F6	40	59	63	6D
F7	41	5A	64	6E
F8	42	5A	65	6F
F9	43	5B	66	70
F10	44	5C	67	71
F11	85	87	89	8B
F12	86	88	8A	8C
Home	47		77	97
Up	48		8D	98
PgUp	49		84	99
Left	4B		73	9B
Center	4C		8F	
Right	4D		74	9D
end	4F		75	9F
Down	50		91	A0
PgDn	51		76	A1
Ins	52	05	04	A2
Del	53	07	06	A3
Tab	8	0F	94	A5
GreyPlus			90	4E

Table 15.3: Structure of TKeyRecord

Field	Meaning
KeyCode	Depending on <code>flags</code> either the physical representation of a key (under DOS scancode, ascii code pair), or the t
ShiftState	Shift-state when this key was pressed (or shortly after)
Flags	Determine how to interpret <code>KeyCode</code>

Chapter 16

Reference for unit 'Linux'

16.1 Used units

Table 16.1: Used units by unit 'Linux'

Name	Page
ctypes	644

16.2 Overview

The linux unit contains linux specific operating system calls.

The platform independent functionality of the FPC 1.0.X version of the linux unit has been split out over the unix ([1458](#)), baseunix ([91](#)) and unixutil ([1504](#)) units.

The X86-specific parts have been moved to the X86 ([1532](#)) unit.

People wanting to use the old version (FPC 1.0.X and before) of the linux can use the oldlinux ([857](#)) unit instead.

16.3 Constants, types and variables

16.3.1 Constants

`CLONE_FILES = $00000400`

Clone ([650](#)) option: open files shared between processes

`CLONE_FS = $00000200`

Clone ([650](#)) option: fs info shared between processes

`CLONE_PID = $00001000`

Clone ([650](#)) option: PID shared between processes

CLONE_SIGHAND = \$00000800

Clone (650) option: signal handlers shared between processes

CLONE_VM = \$00000100

Clone (650) option: VM shared between processes

CSIGNAL = \$000000ff

Clone (650) option: Signal mask to be sent at exit

EPOLLERR = \$08

Poll error condition

EPOLLET = \$80000000

Undocumented

EPOLLHUP = \$10

Poll hung up

EPOLLIN = \$01

Poll input file descriptor ready event

EPOLLOUT = \$02

Poll output file descriptor ready event

EPOLLPRI = \$04

Priority data available on input file descriptor

EPOLL_CTL_ADD = 1

Add filedescriptor to list of events

EPOLL_CTL_DEL = 3

Delete event for filedescriptor

EPOLL_CTL_MOD = 2

Modify event for filedescriptor

GIO_CMAP = \$4B70

IOCTL: Get colour palette on VGA+

GIO_FONT = \$4B60

IOCTL: Get font in expanded form.

GIO_FONTX = \$4B6B

IOCTL: Get font in consolefontdesc record.

GIO_SCRNMAP = \$4B40

IOCTL: get screen mapping from kernel

GIO_UNIMAP = \$4B66

IOCTL: get unicode-to-font mapping from kernel

GIO_UNISCRNMAP = \$4B69

IOCTL: get full Unicode screen mapping

KB_101 = 2

IOCTL: Keyboard types: 101 keys

KB_84 = 1

IOCTL: Keyboard types: 84 keys

KB_OTHER = 3

IOCTL: Keyboard types: other type

KDADDIO = \$4B34

IOCTL: add i/o port as valid

KDDELIO = \$4B35

IOCTL: delete i/o port as valid

KDDISABIO = \$4B37

IOCTL: disable i/o to video board

KDENABIO = \$4B36

IOCTL: enable i/o to video board

KDFONTOP = \$4B72

IOCTL: font operations

KDGETKEYCODE = \$4B4C

IOCTL: read kernel keycode table entry

KDGETLED = \$4B31

IOCTL: return current led state

KDGETMODE = \$4B3B

IOCTL: get current mode

KDGKBDIACR = \$4B4A

IOCTL: read kernel accent table

KDGKBTYPE = \$4B33

IOCTL: get keyboard type

KDMAPDISP = \$4B3C

IOCTL: map display into address space

KDMKTONE = \$4B30

IOCTL: generate tone

KDSETKEYCODE = \$4B4D

IOCTL: write kernel keycode table entry

KDSETLED = \$4B32

IOCTL: set led state

KDSETMODE = \$4B3A

IOCTL: set text/graphics mode

KDSIGACCEPT = \$4B4E

IOCTL: accept kbd generated signals

KDSKBDIACR = \$4B4B

IOCTL: write kernel accent table

KDUNMAPDISP = \$4B3D

IOCTL: unmap display from address space

KD_GRAPHICS = 1

IOCTL: Tty modes: graphics mode

KD_TEXT = 0

IOCTL: Tty modes: Text mode

KD_TEXT0 = 2

IOCTL: Tty modes: Text mode (obsolete)

KD_TEXT1 = 3

IOCTL: Tty modes: Text mode (obsolete)

KIOCSOUND = \$4B2F

IOCTL: start/stop sound generation (0 for off)

LED_CAP = 4

IOCTL: LED_CAP : caps lock led

LED_NUM = 2

IOCTL: LED_SCR : Num lock led

LED_SCR = 1

IOCTL: LED_SCR : scroll lock led

PIO_CMAP = \$4B71

IOCTL: Set colour palette on VGA+

PIO_FONT = \$4B61

IOCTL: Use font in expanded form.

PIO_FONTRESET = \$4B6D

IOCTL: Reset to default font

PIO_FONTX = \$4B6C

IOCTL: Set font in consolefontdesc record.

PIO_SCRNMAP = \$4B41

IOCTL: put screen mapping table in kernel

`PIO_UNIMAP = $4B67`

IOCTL: put unicode-to-font mapping in kernel

`PIO_UNIMAPCLR = $4B68`

IOCTL: clear table, possibly advise hash algorithm

`PIO_UNISCRNMAP = $4B6A`

IOCTL: set full Unicode screen mapping

16.3.2 Types

```
EPoll_Data = record
end
```

Data structure used in EPOLL IOCTL call.

```
EPoll_Event = record
  Events : cuint32;
  Data : TEPoll_Data;
end
```

Structure used in `epoll_ctl` (652) call.

`PEPoll_Data = ^EPoll_Data`

Pointer to `EPoll_Data` (649) record

`PEpoll_Event = ^EPoll_Event`

Pointer to `EPoll_Event` (649) type

`PSysInfo = ^TSysinfo`

Pointer to `TSysInfo` (650) record.

`TCloneFunc = function(args: pointer) : LongInt`

Clone function prototype.

`TEPoll_Data = EPoll_Data`

Alias for `EPoll_Data` (649) type

`TEPoll_Event = EPoll_Event`

Alias for `EPoll_Event` (649) type

```

TSysinfo = packed record
  uptime : LongInt;
  loads : Array[1..3] of LongInt;
  totalram : LongInt;
  freeram : LongInt;
  sharedram : LongInt;
  bufferram : LongInt;
  totalswap : LongInt;
  freeswap : LongInt;
  procs : Integer;
  s : String;
end

```

Record with system information, used by the SysInfo (653) call.

16.4 Procedures and functions

16.4.1 Clone

Synopsis: Clone current process (create new thread)

Declaration: `function Clone(func: TCloneFunc; sp: pointer; flags: LongInt; args: pointer) : LongInt`

Visibility: default

Description: `Clone` creates a child process which is a copy of the parent process, just like `FpFork` (137) does. In difference with `Fork`, however, the child process shares some parts of it's execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

CLONE_VMParent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

CLONE_FSParent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

CLONE_FILESthe file descriptor table of parent and child is shared.

CLONE_SIGHANDthe parent and child share the same table of signal handlers. The signal masks are different, though.

CLONE_PIDParent and child have the same process ID.

`Clone` returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagain Too many processes are running.

sys_enomem Not enough memory to create child process.

See also: `#rtl.baseunix.FpFork` ([137](#))

Listing: `./linuxex/ex71.pp`

```

program TestC{lone};

{$ifdef Linux}
// close is very Linux specific. 1.9.x threading is done via pthreads.

uses
  Linux , Errors , crt;

const
  Ready : Boolean = false;
  aChar : Char    = 'a';

function CloneProc( Arg: Pointer ): LongInt; Cdecl;
begin
  WriteLn( 'Hello from the clone ', PChar(Arg));
  repeat
    Write(aChar);
    Select(0,0,0,0,600);
  until Ready;
  WriteLn( 'Clone finished. ');
  CloneProc := 1;
end;

var
  PID : LongInt;

procedure MainProc;
begin
  WriteLn( 'cloned process PID: ', PID );
  WriteLn( 'Press <ESC> to kill ... ');
  repeat
    Write( '. ');
    Select(0,0,0,0,300);
    if KeyPressed then
      case ReadKey of
        #27: Ready := true;
        'a': aChar := 'A';
        'A': aChar := 'a';
        'b': aChar := 'b';
        'B': aChar := 'B';
      end;
    until Ready;
  WriteLn( 'Ready. ');
end;

const
  StackSize = 16384;
  theFlags = CLONE_VM+CLONE_FS+CLONE_FILES+CLONE_SIGHAND;
  aMsg      : PChar = 'Oops !';

var
```

```

theStack : Pointer;
ExitStat : LongInt;

begin
  GetMem(theStack, StackSize);
  PID := Clone(@CloneProc,
               Pointer( LongInt(theStack)+StackSize),
               theFlags,
               aMsg);
  if PID < 0 then
    WriteLn('Error : ', LinuxError, ' when cloning.')
  else
    begin
      MainProc;
      case WaitPID(0, @ExitStat, Wait_Untraced or wait_clone) of
        -1: WriteLn('error:', LinuxError, '; ', StrError(LinuxError));
        0: WriteLn('error:', LinuxError, '; ', StrError(LinuxError));
      else
        WriteLn('Clone exited with: ', ExitStat shr 8);
      end;
    end;
  FreeMem( theStack, StackSize );
{$else}
begin
{$endif}
end.

```

16.4.2 epoll_create

Synopsis: Create new epoll file descriptor

Declaration: `function epoll_create(size: cint) : cint`

Visibility: default

Description: `epoll_create` creates a new epoll file descriptor. The `size` argument indicates to the kernel approximately how many structures should be allocated, but is by no means an upper limit.

On success, a file descriptor is returned that can be used in subsequent `epoll_ctl` (652) or `epoll_wait` (653) calls, and should be closed using the `fpClose` (130) call.

Errors: On error, -1 is returned, and `errno` (91) is set.

See also: `epoll_ctl` (652), `epoll_wait` (653), `#rtl.baseunix.fpClose` (130)

16.4.3 epoll_ctl

Synopsis: Modify an epoll file descriptor

Declaration: `function epoll_ctl(epfd: cint; op: cint; fd: cint; event: PEPoll_Event) : cint`

Visibility: default

Description: `epoll_ctl` performs the `op` operation on epoll file descriptor `epfd`. The operation will be monitored on file descriptor `fd`, and is optionally controlled by `event`.

`op` can be one of the following values:

EPOLL_CTL_ADDAdd filedescriptor to list of events

EPOLL_CTL_MODModify event for filedescriptor

EPOLL_CTL_DELDelete event for filedescriptor

The `events` field in `event_data` is a bitmask of one or more of the following values:

EPOLLINThe file is ready for read operations

EPOLLOUTThe file is ready for write operations.

EPOLLPRIUrgent data is available for read operations.

EPOLLERRAn error condition is signaled on the file descriptor.

EPOLLHUPHang up happened on the file descriptor.

EPOLLETSet the Edge Triggered behaviour for the file descriptor.

EPOLLONESHOTSet One-Shot behaviour for the file descriptor. The event will be triggered only once.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` ([652](#)), `epoll_wait` ([653](#)), `#rtl.baseunix.fpClose` ([130](#))

16.4.4 `epoll_wait`

Synopsis: Wait for an event on an `epoll` file descriptor.

Declaration: `function epoll_wait(epfd: cint; events: PEPoll_Event; maxevents: cint; timeout: cint) : cint`

Visibility: default

Description: `epoll_wait` waits for `timeout` milliseconds for an event to occur on `epoll` file descriptor `epfd`. If `timeout` is -1, it waits indefinitely, if `timeout` is zero, it does not wait, but returns immediatly, even if no events were detected.

On return, data for at most `maxevents` will be returned in the memory pointed to by `events`. The function returns the number of file descriptors for which events were reported. This can be zero if the timeout was reached.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` ([652](#)), `epoll_ctl` ([652](#)), `#rtl.baseunix.fpClose` ([130](#))

16.4.5 `Sysinfo`

Synopsis: Return kernel system information

Declaration: `function Sysinfo(var Info: TSysinfo) : Boolean`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

uptimeNumber of seconds since boot.

loads1, 5 and 15 minute load averages.

totalramtotal amount of main memory.

freeramamount of free memory.

sharedram amount of shared memory.

bufferram amount of memory used by buffers.

totalswap total amount of swap space.

freeswap amount of free swap space.

procs number of current processes.

Errors: None.

See also: `#rtl.baseunix.fpUname` ([174](#))

Listing: `./linuxex/ex64.pp`

program Example64;

*{ Example to demonstrate the SysInfo function.
Sysinfo is Linux-only. }*

{ \$ifdef Linux }

Uses Linux;

Function Mb(L : Longint) : longint;

begin

 Mb:=L **div** (1024*1024);

end;

Var Info : TSysInfo;

 D,M,Secs,H : longint;

{ \$endif }

begin

{ \$ifdef Linux }

If Not SysInfo(Info) **then**

Halt(1);

With Info **do**

begin

 D:=Uptime **div** (3600*24);

 UpTime:=UpTime **mod** (3600*24);

 h:=uptime **div** 3600;

 uptime:=uptime **mod** 3600;

 m:=uptime **div** 60;

 secs:=uptime **mod** 60;

Writeln('Uptime : ',d,'days', 'h,' hours', 'm,' min', 'secs,' s.');

Writeln('Loads : ',Loads[1], '/' ,Loads[2], '/' ,Loads[3]);

Writeln('Total Ram : ',Mb(totalram), 'Mb.');

Writeln('Free Ram : ',Mb(freeram), 'Mb.');

Writeln('Shared Ram : ',Mb(sharedram), 'Mb.');

Writeln('Buffer Ram : ',Mb(bufferram), 'Mb.');

Writeln('Total Swap : ',Mb(totalswap), 'Mb.');

Writeln('Free Swap : ',Mb(freeswap), 'Mb.');

end;

{ \$endif }

end.

Chapter 17

Reference for unit 'math'

17.1 Geometrical functions

Table 17.1:

Name	Description
hypot (671)	Hypotenuse of triangle
norm (683)	Euclidian norm

17.2 Statistical functions

Table 17.2:

Name	Description
mean (679)	Mean of values
meanandstddev (679)	Mean and standard deviation of values
momentskewkurtosis (682)	Moments, skew and kurtosis
popnstddev (684)	Population standarddeviation
popnvariance (685)	Population variance
randg (687)	Gaussian distributed random value
stddev (691)	Standard deviation
sum (691)	Sum of values
sumofsquares (692)	Sum of squared values
sumsandsquares (693)	Sum of values and squared values
totalvariance (695)	Total variance of values
variance (696)	variance of values

Table 17.3:

Name	Description
ceil (665)	Round to infinity
floor (668)	Round to minus infinity
frexp (669)	Return mantissa and exponent

17.3 Number converting

17.4 Exponential and logarithmic functions

Table 17.4:

Name	Description
intpower (672)	Raise float to integer power
ldexp (674)	Calculate $2^p \times x$
lnxpl (674)	calculate $\log(x+1)$
log10 (675)	calculate 10-base log
log2 (675)	calculate 2-base log
logn (676)	calculate N-base log
power (685)	raise float to arbitrary power

17.5 Hyperbolic functions

Table 17.5:

Name	Description
arcosh (661)	calculate reverse hyperbolic cosine
arsinh (664)	calculate reverse hyperbolic sine
artanh (664)	calculate reverse hyperbolic tangent
cosh (665)	calculate hyperbolic cosine
sinh (690)	calculate hyperbolic sine
tanh (694)	calculate hyperbolic tangent

17.6 Trigonometric functions

17.7 Angle unit conversion

Routines to convert angles between different angle units.

Table 17.6:

Name	Description
<code>arccos</code> (660)	calculate reverse cosine
<code>arcsin</code> (662)	calculate reverse sine
<code>arctan2</code> (663)	calculate reverse tangent
<code>cotan</code> (666)	calculate cotangent
<code>sincos</code> (690)	calculate sine and cosine
<code>tan</code> (694)	calculate tangent

Table 17.7:

Name	Description
<code>cycleto rad</code> (666)	convert cycles to radians
<code>degtograd</code> (667)	convert degrees to grads
<code>degtorad</code> (667)	convert degrees to radians
<code>gradtodeg</code> (670)	convert grads to degrees
<code>gradtorad</code> (671)	convert grads to radians
<code>radto cycle</code> (686)	convert radians to cycles
<code>radtodeg</code> (686)	convert radians to degrees
<code>radto grad</code> (687)	convert radians to grads

17.8 Min/max determination

Functions to determine the minimum or maximum of numbers:

Table 17.8:

Name	Description
<code>max</code> (676)	Maximum of 2 values
<code>maxIntValue</code> (677)	Maximum of an array of integer values
<code>maxvalue</code> (678)	Maximum of an array of values
<code>min</code> (680)	Minimum of 2 values
<code>minIntValue</code> (681)	Minimum of an array of integer values
<code>minvalue</code> (681)	Minimum of an array of values

17.9 Used units

17.10 Overview

This document describes the `math` unit. The `math` unit was initially written by Florian Klaempfl. It provides mathematical functions which aren't covered by the system unit.

This chapter starts out with a definition of all types and constants that are defined, after which an overview is presented of the available functions, grouped by category, and the last part contains a complete explanation of each function.

The following things must be taken into account when using this unit:

Table 17.9: Used units by unit 'math'

Name	Page
sysutils	1278

1. This unit is compiled in Object Pascal mode so all `integers` are 32 bit.
2. Some overloaded functions exist for data arrays of integers and floats. When using the address operator (`@`) to pass an array of data to such a function, make sure the address is typecasted to the right type, or turn on the 'typed address operator' feature. failing to do so, will cause the compiler not be able to decide which function you want to call.

17.11 Constants, types and variables

17.11.1 Constants

`EqualsValue = 0`

Values are the same

`GreaterThanValue = High (TValueRelationship)`

First values is greater than second value

`Infinity = 1.0 / 0.0`

Value is infinity

`LessThanValue = Low (TValueRelationship)`

First value is less than second value

`MaxExtended = 1.1e + 4932`

Maximum value of extended type

`MaxFloat = MaxExtended`

Maximum value of float type

`MinExtended = 3.4e - 4932`

Minimum value (closest to zero) of extended type

`MinFloat = MinExtended`

Minimum value (closest to zero) of float type

`NaN = 0.0 / 0.0`

Value is Not a Number

```
NegativeValue = Low ( TValueSign )
```

Value is negative

```
PositiveValue = High ( TValueSign )
```

Value is positive

```
ZeroValue = 0
```

Value is zero

17.11.2 Types

```
float = extended
```

All calculations are done with the Float type. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type PFloat (659) is used in functions that accept an array of values of arbitrary length.

```
PFloat = ^float
```

Pointer to Float (659) type.

```
PInteger = ^Integer
```

Pointer to integer type

```
TFPUException = (exInvalidOp,exDenormalized,exZeroDivide,exOverflow,  
exUnderflow,exPrecision)
```

Table 17.10: Enumeration values for type TFPUException

Value	Explanation
exDenormalized	
exInvalidOp	Invalid operation error
exOverflow	Float overflow error
exPrecision	Precision error
exUnderflow	Float underflow error
exZeroDivide	Division by zero error.

Type describing Floating Point processor exceptions.

```
TFPUExceptionMask= Set of (exDenormalized,exInvalidOp,exOverflow,  
exPrecision,exUnderflow,exZeroDivide)
```

Type to set the Floating Point Unit exception mask.

Table 17.11: Enumeration values for type TFPUPrecisionMode

Value	Explanation
pmDouble	Double-type precision
pmExtended	Extended-type precision
pmReserved	?
pmSingle	Single-type precision

Table 17.12: Enumeration values for type TFPURoundingMode

Value	Explanation
rmDown	Round to biggest integer smaller than value.
rmNearest	Round to nearest integer value
rmTruncate	Cut off fractional part.
rmUp	Round to smallest integer larger than value.

`TFPUPrecisionMode = (pmSingle, pmReserved, pmDouble, pmExtended)`

Type describing the default precision for the Floating Point processor.

`TFPURoundingMode = (rmNearest, rmDown, rmUp, rmTruncate)`

Type describing the rounding mode for the Floating Point processor.

`tpaymenttime = (ptendofperiod, ptstartofperiod)`

Table 17.13: Enumeration values for type tpaymenttime

Value	Explanation
ptendofperiod	End of period.
ptstartofperiod	Start of period.

Type used in financial (interest) calculations.

`TValueRelationship = -1..1`

Type to describe relational order between values

`TValueSign = -1..1`

Type indicating sign of a valuea

17.12 Procedures and functions

17.12.1 arccos

Synopsis: Return inverse cosine

Declaration: `function arccos(x: float) : float`

Visibility: default

Description: `Arccos` returns the inverse cosine of its argument `x`. The argument `x` should lie between -1 and 1 (borders included).

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arcsin` (662), `arcosh` (661), `arsinh` (664), `artanh` (664)

Listing: `./mathex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the arccos function. }

Uses `math`;

Procedure `WriteRadDeg(X : float)`;

begin

`WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')`

end;

begin

`WriteRadDeg (arccos(1));`

`WriteRadDeg (arccos(sqrt(3)/2));`

`WriteRadDeg (arccos(sqrt(2)/2));`

`WriteRadDeg (arccos(1/2));`

`WriteRadDeg (arccos(0));`

`WriteRadDeg (arccos(-1));`

end.

17.12.2 arccosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function arccosh(x: float) : float`

Visibility: default

Description: `arccosh` returns the inverse hyperbolic cosine of its argument `x`.

This function is an alias for `arcosh` (661), provided for Delphi compatibility.

See also: `arcosh` (661)

17.12.3 arcosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function arcosh(x: float) : float`

Visibility: default

Description: `Arcosh` returns the inverse hyperbolic cosine of its argument `x`. The argument `x` should be larger than 1. The `arccosh` variant of this function is supplied for Delphi compatibility.

Errors: If the argument x is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `cosh` (665), `sinh` (690), `arcsin` (662), `arsinh` (664), `artanh` (664), `tanh` (694)

Listing: ./mathex/ex3.pp

Program Example3;

{ Program to demonstrate the arcosh function. }

Uses math;

begin

WriteIn(arcosh(1));

WriteIn(arcosh(2));

end.

17.12.4 arcsin

Synopsis: Return inverse sine

Declaration: `function arcsin(x: float) : float`

Visibility: default

Description: `Arcsin` returns the inverse sine of its argument x . The argument x should lie between -1 and 1.

Errors: If the argument x is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arccos` (660), `arcosh` (661), `arsinh` (664), `artanh` (664)

Listing: ./mathex/ex2.pp

Program Example1;

{ Program to demonstrate the arcsin function. }

Uses math;

Procedure WriteRadDeg(X : float);

begin

WriteIn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

end;

begin

 WriteRadDeg (arcsin(1));

 WriteRadDeg (arcsin(**sqrt**(3)/2));

 WriteRadDeg (arcsin(**sqrt**(2)/2));

 WriteRadDeg (arcsin(1/2));

 WriteRadDeg (arcsin(0));

 WriteRadDeg (arcsin(-1));

end.

17.12.5 arcsinh

Synopsis: Return inverse hyperbolic sine

Declaration: `function arcsinh(x: float) : float`

Visibility: default

Description: `arcsinh` returns the inverse hyperbolic sine of its argument `x`.

This function is an alias for `arsinh` (664), provided for Delphi compatibility.

See also: `arsinh` (664)

17.12.6 arctan2

Synopsis: Return arctangent of (y/x)

Declaration: `function arctan2(y: float; x: float) : float`

Visibility: default

Description: `arctan2` calculates `arctan(y/x)`, and returns an angle in the correct quadrant. The returned angle will be in the range $-\pi$ to π radians. The values of `x` and `y` must be between -2^{64} and 2^{64} , moreover `x` should be different from zero. On Intel systems this function is implemented with the native intel `fpatan` instruction.

Errors: If `x` is zero, an overflow error will occur.

See also: `arccos` (660), `arcosh` (661), `arsinh` (664), `artanh` (664)

Listing: `./mathex/ex6.pp`

Program Example6;

{ Program to demonstrate the arctan2 function. }

Uses math;

Procedure WriteRadDeg(X : float);

begin

WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

end;

begin

WriteRadDeg (arctan2(1,1));

end.

17.12.7 artanh

Synopsis: Return inverse hyperbolic tangent

Declaration: `function artanh(x: float) : float`

Visibility: default

Description: `arcsinh` returns the inverse hyperbolic tangent of its argument `x`.

This function is an alias for `artanh` (664), provided for Delphi compatibility.

See also: `artanh` (664)

17.12.8 arsinh

Synopsis: Return inverse hyperbolic sine

Declaration: `function arsinh(x: float) : float`

Visibility: default

Description: `arsinh` returns the inverse hyperbolic sine of its argument `x`. The `arscsinh` variant of this function is supplied for Delphi compatibility.

Errors: None.

See also: `arcosh` ([661](#)), `arccos` ([660](#)), `arcsin` ([662](#)), `artanh` ([664](#))

Listing: `./mathex/ex4.pp`

Program Example4;

{ Program to demonstrate the arsinh function. }

Uses math;

begin

WriteLn(`arsinh(0)`);

WriteLn(`arsinh(1)`);

end.

17.12.9 artanh

Synopsis: Return inverse hyperbolic tangent

Declaration: `function artanh(x: float) : float`

Visibility: default

Description: `artanh` returns the inverse hyperbolic tangent of its argument `x`, where `x` should lie in the interval `[-1,1]`, borders included. The `arctanh` variant of this function is supplied for Delphi compatibility.

Errors: In case `x` is not in the interval `[-1,1]`, an `EInvalidArgument` exception is raised.

See also: `arcosh` ([661](#)), `arccos` ([660](#)), `arcsin` ([662](#)), `artanh` ([664](#))

Listing: `./mathex/ex5.pp`

Program Example5;

{ Program to demonstrate the artanh function. }

Uses math;

begin

WriteLn(`artanh(0)`);

WriteLn(`artanh(0.5)`);

end.

17.12.10 ceil

Synopsis: Return the lowest integer number greater than or equal to argument

Declaration: `function ceil(x: float) : Integer`

Visibility: default

Description: `Ceil` returns the lowest integer number greater than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If the absolute value of `x` is larger than `maxint`, an overflow error will occur.

See also: `floor` ([668](#))

Listing: `./mathex/ex7.pp`

Program Example7;

{ Program to demonstrate the Ceil function. }

Uses math;

begin

`WriteLn(Ceil(-3.7)); // should be -3`

`WriteLn(Ceil(3.7)); // should be 4`

`WriteLn(Ceil(-4.0)); // should be -4`

end.

17.12.11 ClearExceptions

Synopsis: Clear Floating Point Unit exceptions

Declaration: `procedure ClearExceptions(RaisePending: Boolean)`

Visibility: default

Description: Clear Floating Point Unit exceptions

17.12.12 cosh

Synopsis: Return hyperbolic cosine

Declaration: `function cosh(x: float) : float`

Visibility: default

Description: `Cosh` returns the hyperbolic cosine of its argument `{x}`.

Errors: None.

See also: `arcosh` ([661](#)), `sinh` ([690](#)), `arsinh` ([664](#))

Listing: `./mathex/ex8.pp`

```

Program Example8;

{ Program to demonstrate the cosh function. }

Uses math;

begin
  WriteLn (Cosh (0));
  WriteLn (Cosh (1));
end .

```

17.12.13 cotan

Synopsis: Return cotangent

Declaration: `function cotan(x: float) : float`

Visibility: default

Description: `Cotan` returns the cotangent of it's argument `x`. `x` should be different from zero.

Errors: If `x` is zero then a overflow error will occur.

See also: `tanh` ([694](#))

Listing: `./mathex/ex9.pp`

```

Program Example9;

{ Program to demonstrate the cotan function. }

Uses math;

begin
  writeln (cotan (pi / 2));
  WriteLn (cotan (pi / 3));
  WriteLn (cotan (pi / 4));
end .

```

17.12.14 cycletorad

Synopsis: Convert cycle angle to radians angle

Declaration: `function cycletorad(cycle: float) : float`

Visibility: default

Description: `Cycletorad` transforms it's argument `cycle` (an angle expressed in cycles) to radians. (1 cycle is 2π radians).

Errors: None.

See also: `degtograd` ([667](#)), `degtorad` ([667](#)), `radto deg` ([686](#)), `radto grad` ([687](#)), `radto cycle` ([686](#))

Listing: `./mathex/ex10.pp`

Program Example10;

{ Program to demonstrate the cycletorad function. }

Uses math;

begin

writeln(cos(cycletorad(1/6))); *// Should print 1/2*

writeln(cos(cycletorad(1/8))); *// should be sqrt(2)/2*

end.

17.12.15 degtograd

Synopsis: Convert degree angle to grads angle

Declaration: function degtograd(deg: float) : float

Visibility: default

Description: Degtograd transforms it's argument deg (an angle in degrees) to grads. (90 degrees is 100 grad.)

Errors: None.

See also: cycletorad ([666](#)), degtorad ([667](#)), radto deg ([686](#)), radto grad ([687](#)), radto cycle ([686](#))

Listing: ./mathex/ex11.pp

Program Example11;

{ Program to demonstrate the degtograd function. }

Uses math;

begin

writeln(degtograd(90));

writeln(degtograd(180));

writeln(degtograd(270))

end.

17.12.16 degtorad

Synopsis: Convert degree angle to radians angle.

Declaration: function degtorad(deg: float) : float

Visibility: default

Description: Degtograd converts it's argument deg (an angle in degrees) to radians. (pi radians is 180 degrees)

Errors: None.

See also: cycletorad ([666](#)), degtograd ([667](#)), radto deg ([686](#)), radto grad ([687](#)), radto cycle ([686](#))

Listing: ./mathex/ex12.pp

Program Example12;

{ Program to demonstrate the degtorad function. }

Uses math;

begin

```
writeln(degtorad(45));
writeln(degtorad(90));
writeln(degtorad(180));
writeln(degtorad(270));
writeln(degtorad(360));
```

end.

17.12.17 DivMod

Synopsis: Return DIV and MOD of arguments

Declaration: `procedure DivMod(Dividend: Integer; Divisor: Word; var Result: Word; var Remainder: Word)`

Visibility: default

Description: DivMod returns Dividend DIV Divisor in Result, and Dividend MOD Divisor in Remainder

17.12.18 EnsureRange

Synopsis: Change value to it falls in specified range.

Declaration: `function EnsureRange(const AValue: Integer; const AMin: Integer; const AMax: Integer) : Integer`
`function EnsureRange(const AValue: Int64; const AMin: Int64; const AMax: Int64) : Int64`

Visibility: default

Description: EnsureRange returns Value if AValue is in the range AMin..AMax. It returns AMin if the value is less than AMin, or AMax if the value is larger than AMax.

See also: InRange ([672](#))

17.12.19 floor

Synopsis: Return the largest integer smaller than or equal to argument

Declaration: `function floor(x: float) : Integer`

Visibility: default

Description: Floor returns the largest integer smaller than or equal to x. The absolute value of x should be less than maxint.

Errors: If x is larger than maxint, an overflow will occur.

See also: ceil ([665](#))

Listing: ./mathex/ex13.pp

Program Example13;

{ Program to demonstrate the floor function. }

Uses math;

begin

WriteLn(Ceil(-3.7)); *// should be -4*

WriteLn(Ceil(3.7)); *// should be 3*

WriteLn(Ceil(-4.0)); *// should be -4*

end.

17.12.20 Frexp

Synopsis: Return mantissa and exponent.

Declaration: `procedure Frexp(X: float; var Mantissa: float; var Exponent: Integer)`

Visibility: default

Description: `Frexp` returns the mantissa and exponent of its argument `x` in mantissa and exponent.

Errors: None

Listing: ./mathex/ex14.pp

Program Example14;

{ Program to demonstrate the frexp function. }

Uses math;

Procedure dofexp(**Const** X : extended);

var man : extended;

exp: longint;

begin

 man:=0;

exp:=0;

 frexp(x,man,**exp**);

write(x, ' has ');

WriteLn('mantissa ',man,' and exponent ',**exp**);

end;

begin

// dofexp(1.00);

 dofexp(1.02e-1);

 dofexp(1.03e-2);

 dofexp(1.02e1);

 dofexp(1.03e2);

end.

17.12.21 GetExceptionMask

Synopsis: Get the Floating Point Unit exception mask.

Declaration: `function GetExceptionMask : TFPUEExceptionMask`

Visibility: default

Description: Get the Floating Point Unit exception mask.

17.12.22 GetPrecisionMode

Synopsis: Return the Floating Point Unit precision mode.

Declaration: `function GetPrecisionMode : TFPUPrecisionMode`

Visibility: default

Description: Return the Floating Point Unit precision mode.

17.12.23 GetRoundMode

Synopsis: Return the Floating Point Unit rounding mode.

Declaration: `function GetRoundMode : TFPURoundingMode`

Visibility: default

Description: Return the Floating Point Unit rounding mode.

17.12.24 GetSSECSR

Synopsis: Get MXCSR control word (Intel only)

Declaration: `function GetSSECSR : dword`

Visibility: default

Description: `GetSSECSR` can be used to get the SSE/SSE2 control DWord. It is equivalent to the `LDMXCSR` assembler instruction, and returns the control dword.

17.12.25 gradtodeg

Synopsis: Convert grads angle to degrees angle

Declaration: `function gradtodeg(grad: float) : float`

Visibility: default

Description: `Gradtodeg` converts its argument `grad` (an angle in grads) to degrees. (100 grad is 90 degrees)

Errors: None.

See also: `cycletorad` ([666](#)), `degtograd` ([667](#)), `radtodeg` ([686](#)), `radtograd` ([687](#)), `radtcycle` ([686](#)), `gradtorad` ([671](#))

Listing: `./mathex/ex15.pp`

Program Example15;

{ Program to demonstrate the gradtodeg function. }

Uses math;

begin
 writeln (gradtodeg(100));
 writeln (gradtodeg(200));
 writeln (gradtodeg(300));
end.

17.12.26 gradtorad

Synopsis: Convert grads angle to radians angle

Declaration: `function gradtorad(grad: float) : float`

Visibility: default

Description: `Gradtorad` converts its argument `grad` (an angle in grads) to radians. (200 grad is pi degrees).

Errors: None.

See also: `cycletorad` ([666](#)), `degtograd` ([667](#)), `radtodeg` ([686](#)), `radtograd` ([687](#)), `radtcycle` ([686](#)), `gradtodeg` ([670](#))

Listing: ./mathex/ex16.pp

Program Example16;

{ Program to demonstrate the gradtorad function. }

Uses math;

begin
 writeln (gradtorad(100));
 writeln (gradtorad(200));
 writeln (gradtorad(300));
end.

17.12.27 hypot

Synopsis: Return hypotenuse of triangle

Declaration: `function hypot(x: float;y: float) : float`

Visibility: default

Description: `Hypot` returns the hypotenuse of the triangle where the sides adjacent to the square angle have lengths `x` and `y`. The function uses Pythagoras' rule for this.

Errors: None.

Listing: ./mathex/ex17.pp

```

Program Example17;

{ Program to demonstrate the hypot function. }

Uses math;

begin
    WriteLn(hypot(3,4)); // should be 5
end.

```

17.12.28 ifthen

Synopsis: Return one of two values, depending on a boolean condition

Declaration:

```

function ifthen(val: Boolean;const iftrue: Integer;
               const iffalse: Integer) : Integer
function ifthen(val: Boolean;const iftrue: Int64;const iffalse: Int64)
               : Int64
function ifthen(val: Boolean;const iftrue: double;const iffalse: double)
               : double

```

Visibility: default

Description: ifthen returns iftrue if val is True, and False if val is False.

This function can be used in expressions.

17.12.29 InRange

Synopsis: Check whether value is in range.

Declaration:

```

function InRange(const AValue: Integer;const AMin: Integer;
                const AMax: Integer) : Boolean
function InRange(const AValue: Int64;const AMin: Int64;
                const AMax: Int64) : Boolean

```

Visibility: default

Description: InRange returns True if AValue is in the range AMin..AMax. It returns False if Value lies outside the specified range.

See also: EnsureRange ([668](#))

17.12.30 intpower

Synopsis: Return integer power.

Declaration:

```

function intpower(base: float;const exponent: Integer) : float

```

Visibility: default

Description: Intpower returns base to the power exponent, where exponent is an integer value.

Errors: If base is zero and the exponent is negative, then an overflow error will occur.

See also: power ([685](#))

Listing: ./mathex/ex18.pp

Program Example18;

```
{ Program to demonstrate the intpower function. }
```

Uses math;

Procedure DoIntpower (X : extended; Pow : Integer);

begin

```
  writeln(X:8:4, '^', Pow:2, ' = ', intpower(X, pow):8:4);
end;
```

begin

```
  dointpower(0.0,0);
  dointpower(1.0,0);
  dointpower(2.0,5);
  dointpower(4.0,3);
  dointpower(2.0,-1);
  dointpower(2.0,-2);
  dointpower(-2.0,4);
  dointpower(-4.0,3);
```

end.

17.12.31 IsInfinite

Synopsis: Check whether value is infinite

Declaration: function IsInfinite(const d: Double) : Boolean

Visibility: default

Description: IsInfinite returns True if the double d contains the infinite value.

See also: IsZero ([673](#)), IsInfinite ([673](#))

17.12.32 IsNan

Synopsis: Check whether value is Not a Number

Declaration: function IsNan(const d: Double) : Boolean

Visibility: default

Description: IsNan returns True if the double d contains Not A Number (a value which cannot be represented correctly in double format).

See also: IsZero ([673](#)), IsInfinite ([673](#))

17.12.33 IsZero

Synopsis: Check whether value is zero

Declaration: function IsZero(const A: Single; Epsilon: Single) : Boolean

```
function IsZero(const A: Single) : Boolean
```

```
function IsZero(const A: Extended; Epsilon: Extended) : Boolean
```

```
function IsZero(const A: Extended) : Boolean
```

Visibility: default

Description: `IsZero` checks whether the float value `A` is zero, up to a precision of `Epsilon`. It returns `True` if `Abs(A)` is less than `Epsilon`.

The default value for `Epsilon` is dependent on the type of the arguments, but is `MinFloat` (658) for the float type.

See also: `IsNan` (673), `IsInfinite` (673), `SameValue` (688)

17.12.34 `ldexp`

Synopsis: Return (2 to the power `p`) times `x`

Declaration: `function ldexp(x: float; const p: Integer) : float`

Visibility: default

Description: `Ldexp` returns (2 to the power `p`) times `x`.

Errors: None.

See also: `lnxp1` (674), `log10` (675), `log2` (675), `logn` (676)

Listing: `./mathex/ex19.pp`

Program `Example19`;

{ Program to demonstrate the ldexp function. }

Uses `math`;

begin

writeln (`ldexp(2,4):8:4`);

writeln (`ldexp(0.5,3):8:4`);

end.

17.12.35 `lnxp1`

Synopsis: Return natural logarithm of `1+X`

Declaration: `function lnxp1(x: float) : float`

Visibility: default

Description: `Lnxp1` returns the natural logarithm of `1+X`. The result is more precise for small values of `x`. `x` should be larger than `-1`.

Errors: If `$x \leq -1` then an `EInvalidArgument` exception will be raised.

See also: `ldexp` (674), `log10` (675), `log2` (675), `logn` (676)

Listing: `./mathex/ex20.pp`

Program `Example20`;

{ Program to demonstrate the lnxp1 function. }

Uses `math`;

```

begin
  writeln(lnxp1(0));
  writeln(lnxp1(0.5));
  writeln(lnxp1(1));
end.

```

17.12.36 log10

Synopsis: Return 10-Based logarithm.

Declaration: `function log10(x: float) : float`

Visibility: default

Description: `Log10` returns the 10-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (674), `lnxp1` (674), `log2` (675), `logn` (676)

Listing: `./mathex/ex21.pp`

Program Example21;

{ Program to demonstrate the log10 function. }

Uses math;

```

begin
  Writeln(Log10(10):8:4);
  Writeln(Log10(100):8:4);
  Writeln(Log10(1000):8:4);
  Writeln(Log10(1):8:4);
  Writeln(Log10(0.1):8:4);
  Writeln(Log10(0.01):8:4);
  Writeln(Log10(0.001):8:4);
end.

```

17.12.37 log2

Synopsis: Return 2-based logarithm

Declaration: `function log2(x: float) : float`

Visibility: default

Description: `Log2` returns the 2-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (674), `lnxp1` (674), `log10` (675), `logn` (676)

Listing: `./mathex/ex22.pp`

```

Program Example22;

{ Program to demonstrate the log2 function. }

Uses math;

begin
  Writeln(Log2(2):8:4);
  Writeln(Log2(4):8:4);
  Writeln(Log2(8):8:4);
  Writeln(Log2(1):8:4);
  Writeln(Log2(0.5):8:4);
  Writeln(Log2(0.25):8:4);
  Writeln(Log2(0.125):8:4);
end.

```

17.12.38 logn

Synopsis: Return N-based logarithm.

Declaration: `function logn(n: float;x: float) : float`

Visibility: default

Description: Logn returns the n-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` ([674](#)), `lnxp1` ([674](#)), `log10` ([675](#)), `log2` ([675](#))

Listing: ./mathex/ex23.pp

```

Program Example23;

{ Program to demonstrate the logn function. }

Uses math;

begin
  Writeln(Logn(3,4):8:4);
  Writeln(Logn(2,4):8:4);
  Writeln(Logn(6,9):8:4);
  Writeln(Logn(exp(1),exp(1)):8:4);
  Writeln(Logn(0.5,1):8:4);
  Writeln(Logn(0.25,3):8:4);
  Writeln(Logn(0.125,5):8:4);
end.

```

17.12.39 Max

Synopsis: Return largest of 2 values

Declaration: `function Max(a: Integer;b: Integer) : Integer`
`function Max(a: Int64;b: Int64) : Int64`
`function Max(a: Extended;b: Extended) : Extended`

Visibility: default

Description: `Max` returns the maximum of `Int1` and `Int2`.

Errors: None.

See also: `min` (680), `maxIntValue` (677), `maxvalue` (678)

Listing: ./mathex/ex24.pp

```
Program Example24;

{ Program to demonstrate the max function. }

Uses math;

Var
  A,B : Cardinal;

begin
  A:=1;b:=2;
  writeln(max(a,b));
end.
```

17.12.40 MaxIntValue

Synopsis: Return largest element in integer array

Declaration: `function MaxIntValue(const Data: Array[] of Integer) : Integer`

Visibility: default

Description: `MaxIntValue` returns the largest integer out of the `Data` array.

This function is provided for Delphi compatibility, use the `maxvalue` (678) function instead.

Errors: None.

See also: `maxvalue` (678), `minvalue` (681), `minIntValue` (681)

Listing: ./mathex/ex25.pp

```
Program Example25;

{ Program to demonstrate the MaxIntValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

Uses math;

Type
  TExArray = Array[1..100] of Integer;

Var
  I : Integer;
  ExArray : TExArray;

begin
```

```

Randomize;
for i:=low(exarray) to high(exarray) do
  ExArray[i]:=Random(i)-Random(100);
WriteLn(MaxIntValue(ExArray));
end.

```

17.12.41 maxvalue

Synopsis: Return largest value in array

Declaration: `function maxvalue(const data: Array[] of float) : float`
`function maxvalue(const data: Array[] of Integer) : Integer`
`function maxvalue(const data: PFloat;const N: Integer) : float`
`function maxvalue(const data: PInteger;const N: Integer) : Integer`

Visibility: default

Description: `Maxvalue` returns the largest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: `maxIntValue` (677), `minvalue` (681), `minIntValue` (681)

Listing: `./mathex/ex26.pp`

program Example26;

{ Program to demonstrate the MaxValue function. }

{ Make sure integer is 32 bit }
{ \$mode objfpc }

uses math;

var i:1..100;
 f_array:array[1..100] of Float;
 i_array:array[1..100] of Integer;
 Pf_array:PFloat;
 Pi_array:PInteger;

begin

randomize;

 Pf_array:=@f_array[1];

 Pi_array:=@i_array[1];

for i:=low(f_array) **to** high(f_array) **do**

 f_array[i]:=(random-random)*100;

for i:=low(i_array) **to** high(i_array) **do**

 i_array[i]:=random(i)-random(100);

WriteLn('Max Float : ',MaxValue(f_array):8:4);

WriteLn('Max Float (b) : ',MaxValue(Pf_array,100):8:4);

WriteLn('Max Integer : ',MaxValue(i_array):8);

WriteLn('Max Integer (b) : ',MaxValue(Pi_array,100):8);

end.

17.12.42 mean

Synopsis: Return mean value of array

Declaration: `function mean(const data: Array[] of float) : float`
`function mean(const data: PFloat; const N: LongInt) : float`

Visibility: default

Description: `Mean` returns the average value of `data`. The second form accepts a pointer to an array of `N` values.

Errors: None.

See also: `meanandstddev` (679), `momentskewkurtosis` (682), `sum` (691)

Listing: `./mathex/ex27.pp`

Program `Example27`;

{ Program to demonstrate the Mean function. }

Uses `math`;

Type

`TExArray = Array[1..100] of Float;`

Var

`I : Integer;`
`ExArray : TExArray;`

begin

`Randomize;`

`for I:=low(ExArray) to high(ExArray) do`

`ExArray[I]:= (Random-Random)*100;`

`WriteLn('Max : ',MaxValue(ExArray):8:4);`

`WriteLn('Min : ',MinValue(ExArray):8:4);`

`WriteLn('Mean : ',Mean(ExArray):8:4);`

`WriteLn('Mean (b) : ',Mean(@ExArray[1],100):8:4);`

end.

17.12.43 meanandstddev

Synopsis: Return mean and standard deviation of array

Declaration: `procedure meanandstddev(const data: Array[] of float; var mean: float;`
`var stddev: float)`
`procedure meanandstddev(const data: PFloat; const N: LongInt;`
`var mean: float; var stddev: float)`

Visibility: default

Description: `meanandstddev` calculates the mean and standard deviation of `data` and returns the result in `mean` and `stddev`, respectively. `Stddev` is zero if there is only one value. The second form accepts a pointer to an array of `N` values.

Errors: None.

See also: `mean` (679), `sum` (691), `sumofsquares` (692), `momentskewkurtosis` (682)

Listing: ./mathex/ex28.pp

Program Example28;

{ Program to demonstrate the Meanandstddev function. }

Uses math;

Type

TExArray = **Array**[1..100] **of** Extended;

Var

I : Integer;
ExArray : TExArray;
Mean, stddev : Extended;

begin

Randomize;
for I:=**low**(ExArray) **to high**(ExArray) **do**
 ExArray[I] := (**Random**-**Random**)*100;
MeanAndStdDev(ExArray, Mean, StdDev);
WriteIn('Mean : ', Mean:8:4);
WriteIn('StdDev : ', StdDev:8:4);
MeanAndStdDev(@ExArray[1], 100, Mean, StdDev);
WriteIn('Mean (b) : ', Mean:8:4);
WriteIn('StdDev (b) : ', StdDev:8:4);

end.

17.12.44 Min

Synopsis: Return smallest of two values.

Declaration: function Min(a: Integer; b: Integer) : Integer
 function Min(a: Int64; b: Int64) : Int64
 function Min(a: Extended; b: Extended) : Extended

Visibility: default

Description: min returns the smallest value of Int1 and Int2;

Errors: None.

See also: max ([676](#))

Listing: ./mathex/ex29.pp

Program Example29;

{ Program to demonstrate the min function. }

Uses math;

Var

A, B : Cardinal;

begin

A:=1; b:=2;
writeln(min(a, b));

end.

17.12.45 MinIntValue

Synopsis: Return smallest value in integer array

Declaration: `function MinIntValue(const Data: Array[] of Integer) : Integer`

Visibility: default

Description: `MinIntValue` returns the smallest value in the `Data` array.

This function is provided for Delphi compatibility, use `minvalue` instead.

Errors: None

See also: `minvalue` (681), `maxIntValue` (677), `maxvalue` (678)

Listing: `./mathex/ex30.pp`

Program `Example30`;

{ Program to demonstrate the MinIntValue function. }

{ Make sure integer is 32 bit }
{ \$mode objfpc }

Uses `math`;

Type

`TExArray = Array[1..100] of Integer;`

Var

`I : Integer;`
`ExArray : TExArray;`

begin

`Randomize;`

`for I:=low(ExArray) to high(ExArray) do`

`ExArray[I]:=Random(I)-Random(100);`

`WriteLn(MinIntValue(ExArray));`

end.

17.12.46 minvalue

Synopsis: Return smallest value in array

Declaration: `function minvalue(const data: Array[] of float) : float`
`function minvalue(const data: Array[] of Integer) : Integer`
`function minvalue(const data: PFloat;const N: Integer) : float`
`function MinValue(const Data: PInteger;const N: Integer) : Integer`

Visibility: default

Description: `Minvalue` returns the smallest value in the `data` array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of `N` integer or float values.

Errors: None.

See also: `maxIntValue` (677), `maxvalue` (678), `minIntValue` (681)

Listing: ./mathex/ex31.pp

```

program Example31;

{ Program to demonstrate the MinValue function. }

{ Make sure integer is 32 bit}
{$mode objfpc}

uses math;

var i:1..100;
    f_array:array[1..100] of Float;
    i_array:array[1..100] of Integer;
    Pf_array:Pfloat;
    Pi_array:Pinteger;

begin
    randomize;

    Pf_array:=@f_array[1];
    Pi_array:=@i_array[1];

    for i:=low(f_array) to high(f_array) do
        f_array[i]:=(random-random)*100;
    for i:=low(i_array) to high(i_array) do
        i_array[i]:=random(1)-random(100);

    WriteLn('Min Float      : ',MinValue(f_array):8:4);
    WriteLn('Min Float   (b) : ',MinValue(Pf_array,100):8:4);
    WriteLn('Min Integer   : ',MinValue(i_array):8);
    WriteLn('Min Integer (b) : ',MinValue(Pi_array,100):8);
end.

```

17.12.47 momentskewkurtosis

Synopsis: Return 4 first moments of distribution

Declaration:

```

procedure momentskewkurtosis(const data: Array[] of float;var m1: float;
                               var m2: float;var m3: float;var m4: float;
                               var skew: float;var kurtosis: float)
procedure momentskewkurtosis(const data: PFloat;const N: Integer;
                               var m1: float;var m2: float;var m3: float;
                               var m4: float;var skew: float;
                               var kurtosis: float)

```

Visibility: default

Description: momentskewkurtosis calculates the 4 first moments of the distribution of values in data and returns them in m1,m2,m3 and m4, as well as the skew and kurtosis.

Errors: None.

See also: mean ([679](#)), meanandstddev ([679](#))

Listing: ./mathex/ex32.pp

```

program Example32;

{ Program to demonstrate the momentskewkurtosis function. }

uses math;

var distarray: array[1..1000] of float;
    l: longint;
    m1,m2,m3,m4,skew,kurtosis: float;

begin
    randomize;
    for l:=low(distarray) to high(distarray) do
        distarray[l]:=random;
    momentskewkurtosis(DistArray,m1,m2,m3,m4,skew,kurtosis);

    Writeln ('1st moment : ',m1:8:6);
    Writeln ('2nd moment : ',m2:8:6);
    Writeln ('3rd moment : ',m3:8:6);
    Writeln ('4th moment : ',m4:8:6);
    Writeln ('Skew      : ',skew:8:6);
    Writeln ('kurtosis   : ',kurtosis:8:6);
end.

```

17.12.48 norm

Synopsis: Return Euclidian norm

Declaration: `function norm(const data: Array[] of float) : float`
`function norm(const data: PFloat;const N: Integer) : float`

Visibility: default

Description: `Norm` calculates the Euclidian norm of the array of data. This equals `sqrt (sumofsquares (data))`.
 The second form accepts a pointer to an array of N values.

Errors: None.

See also: `sumofsquares` ([692](#))

Listing: ./mathex/ex33.pp

```

program Example33;

{ Program to demonstrate the norm function. }

uses math;

var v: array[1..10] of Float;
    l: 1..10;

begin
    for l:=low(v) to high(v) do
        v[l]:=random;
    writeln(norm(v));
end.

```

17.12.49 operator $^{}(\text{float}, \text{float}): \text{float}$**

Declaration: `function operator $^{**}(\text{float}, \text{float}): \text{float}(\text{bas}: \text{float}; \text{expo}: \text{float})$
: float`

Visibility: default

17.12.50 operator $^{}(\text{Int64}, \text{Int64}): \text{Int64}$**

Declaration: `function operator $^{**}(\text{Int64}, \text{Int64}): \text{Int64}(\text{bas}: \text{Int64}; \text{expo}: \text{Int64})$
: Int64`

Visibility: default

17.12.51 popnstddev

Synopsis: Return population variance

Declaration: `function popnstddev(const data: Array[] of float) : float
function popnstddev(const data: PFloat; const N: Integer) : float`

Visibility: default

Description: `Popnstddev` returns the square root of the population variance of the values in the `Data` array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of `N` values.

Errors: None.

See also: `popnvariance` ([685](#)), `mean` ([679](#)), `meanandstddev` ([679](#)), `stddev` ([691](#)), `momentskewkurtosis` ([682](#))

Listing: `./mathex/ex35.pp`

Program `Example35;`

{ Program to demonstrate the PopnStdDev function. }

Uses `Math;`

Type

`TExArray = Array[1..100] of Float;`

Var

`I : Integer;
ExArray : TExArray;`

begin

`Randomize;`

`for I:=low(ExArray) to high(ExArray) do`

`ExArray[I]:= (Random-Random)*100;`

`WriteLn('Max : ', MaxValue(ExArray):8:4);`

`WriteLn('Min : ', MinValue(ExArray):8:4);`

`WriteLn('Pop. stddev. : ', PopnStdDev(ExArray):8:4);`

`WriteLn('Pop. stddev. (b) : ', PopnStdDev(@ExArray[1], 100):8:4);`

`end.`

17.12.52 popnvariance

Synopsis: Return population variance

Declaration: `function popnvariance(const data: PFloat; const N: Integer) : float`
`function popnvariance(const data: Array[] of float) : float`

Visibility: default

Description: `Popnvariance` returns the square root of the population variance of the values in the `Data` array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of `N` values.

Errors: None.

See also: `popnstddev` (684), `mean` (679), `meanandstddev` (679), `stddev` (691), `momentskewkurtosis` (682)

Listing: `./mathex/ex36.pp`

Program `Example36`;

{ Program to demonstrate the PopnVariance function. }

Uses `math`;

Var

`I : Integer;`
`ExArray : Array[1..100] of Float;`

begin

`Randomize`;

`for I:=low(ExArray) to high(ExArray) do`

`ExArray[I]:= (Random-Random)*100;`

`Writeln('Max : ',MaxValue(ExArray):8:4);`

`Writeln('Min : ',MinValue(ExArray):8:4);`

`Writeln('Pop. var. : ',PopnVariance(ExArray):8:4);`

`Writeln('Pop. var. (b) : ',PopnVariance(@ExArray[1],100):8:4);`

`end.`

17.12.53 power

Synopsis: Return real power.

Declaration: `function power(base: float; exponent: float) : float`

Visibility: default

Description: `power` raises `base` to the power `power`. This is equivalent to `exp(power*ln(base))`. Therefore `base` should be non-negative.

Errors: None.

See also: `intpower` (672)

Listing: `./mathex/ex34.pp`

Program Example34;

{ Program to demonstrate the power function. }

Uses Math;

procedure dopower(x,y : float);

begin

writeln(x:8:6, '^', y:8:6, ' = ', power(x,y):8:6)

end;

begin

 dopower(2,2);

 dopower(2,-2);

 dopower(2,0.0);

end.

17.12.54 radtocycle

Synopsis: Convert radians angle to cycle angle

Declaration: `function radtocycle(rad: float) : float`

Visibility: default

Description: `Radtocycle` converts its argument `rad` (an angle expressed in radians) to an angle in cycles.
(1 cycle equals 2 π radians)

Errors: None.

See also: `degtograd` ([667](#)), `degtorad` ([667](#)), `radtodeg` ([686](#)), `radtograd` ([687](#)), `cycletorad` ([666](#))

Listing: ./mathex/ex37.pp

Program Example37;

{ Program to demonstrate the radtocycle function. }

Uses math;

begin

writeln(radtocycle(2*pi):8:6);

writeln(radtocycle(pi):8:6);

writeln(radtocycle(pi/2):8:6);

end.

17.12.55 radtodeg

Synopsis: Convert radians angle to degrees angle

Declaration: `function radtodeg(rad: float) : float`

Visibility: default

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in degrees. (180 degrees equals pi radians)

Errors: None.

See also: `degtograd` ([667](#)), `degtorad` ([667](#)), `radtocycle` ([686](#)), `radtograd` ([687](#)), `cycletorad` ([666](#))

Listing: `./mathex/ex38.pp`

Program `Example38`;

{ Program to demonstrate the radtodeg function. }

Uses `math`;

begin

`writeln (radtodeg (2*pi):8:6);`

`writeln (radtodeg (pi):8:6);`

`writeln (radtodeg (pi/2):8:6);`

end.

17.12.56 radtograd

Synopsis: Convert radians angle to grads angle

Declaration: `function radtograd(rad: float) : float`

Visibility: `default`

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in grads. (200 grads equals pi radians)

Errors: None.

See also: `degtograd` ([667](#)), `degtorad` ([667](#)), `radtocycle` ([686](#)), `radtodeg` ([686](#)), `cycletorad` ([666](#))

Listing: `./mathex/ex39.pp`

Program `Example39`;

{ Program to demonstrate the radtograd function. }

Uses `math`;

begin

`writeln (radtograd (2*pi):8:6);`

`writeln (radtograd (pi):8:6);`

`writeln (radtograd (pi/2):8:6);`

end.

17.12.57 randg

Synopsis: Return gaussian distributed random number.

Declaration: `function randg(mean: float;stddev: float) : float`

Visibility: `default`

Description: `randg` returns a random number which - when produced in large quantities - has a Gaussian distribution with mean `mean` and standarddeviation `stddev`.

Errors: None.

See also: `mean` (679), `stddev` (691), `meanandstddev` (679)

Listing: `./mathex/ex40.pp`

Program `Example40`;

{ Program to demonstrate the randg function. }

Uses `Math`;

Var

`I` : Integer;
`ExArray` : **Array**[1..10000] of Float;;
`Mean`, `stddev` : Float;

begin

Randomize;

for `I` := **low**(`ExArray`) **to** **high**(`ExArray`) **do**

`ExArray`[`i`] := `Randg`(1, 0.2);

`MeanAndStdDev`(`ExArray`, `Mean`, `StdDev`);

WriteIn('Mean : ', `Mean`:8:4);

WriteIn('StdDev : ', `StdDev`:8:4);

end.

17.12.58 SameValue

Synopsis: Check whether 2 float values are the same

Declaration: `function SameValue(const A: Extended;const B: Extended) : Boolean`
`function SameValue(const A: Single;const B: Single) : Boolean`
`function SameValue(const A: Extended;const B: Extended;`
`Epsilon: Extended) : Boolean`
`function SameValue(const A: Single;const B: Single;Epsilon: Single)`
`: Boolean`

Visibility: default

Description: `SameValue` returns `True` if the floating-point values `A` and `B` are the same, i.e. whether the absolute value of their difference is smaller than `Epsilon`. If their difference is larger, then `False` is returned.

The default value for `Epsilon` is dependent on the type of the arguments, but is `MinFloat` (658) for the float type.

See also: `MinFloat` (658), `IsZero` (673)

17.12.59 SetExceptionMask

Synopsis: Set the Floating Point Unit exception mask.

Declaration: `function SetExceptionMask(const Mask: TFPUEExceptionMask)`
`: TFPUEExceptionMask`

Visibility: default

Description: Set the Floating Point Unit exception mask.

17.12.60 SetPrecisionMode

Synopsis: Set the Floating Point Unit precision mode.

Declaration: `function SetPrecisionMode(const Precision: TFPUPrecisionMode)
: TFPUPrecisionMode`

Visibility: default

Description: Set the Floating Point Unit precision mode.

17.12.61 SetRoundMode

Synopsis: Set the Floating Point Unit rounding mode.

Declaration: `function SetRoundMode(const RoundMode: TFPURoundingMode)
: TFPURoundingMode`

Visibility: default

Description: Set the Floating Point Unit rounding mode.

17.12.62 SetSSECSR

Synopsis: Set MXCSR control word (Intel only)

Declaration: `procedure SetSSECSR(w: dword)`

Visibility: default

Description: `SetSSECSR` can be used to set the SSE/SSE2 control DWord. It is equivalent to the `STMXCSR` assembler instruction, and stores `w` in the control dword.

17.12.63 Sign

Synopsis: Return sign of argument

Declaration: `function Sign(const AValue: Integer) : TValueSign
function Sign(const AValue: Int64) : TValueSign
function Sign(const AValue: Double) : TValueSign`

Visibility: default

Description: `Sign` returns the sign of it's argument, which can be an Integer, 64 bit integer, or a double. The returned value is an integer which is -1, 0 or 1, and can be used to do further calculations with.

17.12.64 sincos

Synopsis: Return sine and cosine of argument

Declaration: `procedure sincos(theta: float; var sinus: float; var cosinus: float)`

Visibility: default

Description: `Sincos` calculates the sine and cosine of the angle `theta`, and returns the result in `sinus` and `cosinus`.

On Intel hardware, This calculation will be faster than making 2 calls to calculate the sine and cosine separately.

Errors: None.

See also: `arcsin` ([662](#)), `arccos` ([660](#))

Listing: `./mathex/ex41.pp`

Program `Example41`;

{ Program to demonstrate the sincos function. }

Uses `math`;

Procedure `dosincos`(`Angle` : `Float`);

Var

`Sine`, `Cosine` : `Float`;

begin

`sincos`(`angle`, `sine`, `cosine`);

Write('Angle : ', `Angle`:8:6);

Write(' Sine : ', `sine`:8:6);

Write(' Cosine : ', `cosine`:8:6);

end;

begin

`dosincos`(**pi**);

`dosincos`(**pi**/2);

`dosincos`(**pi**/3);

`dosincos`(**pi**/4);

`dosincos`(**pi**/6);

end.

17.12.65 sinh

Synopsis: Return hyperbolic sine

Declaration: `function sinh(x: float) : float`

Visibility: default

Description: `Sinh` returns the hyperbolic sine of its argument `x`.

Errors:

See also: `cosh` ([665](#)), `arsinh` ([664](#)), `tanh` ([694](#)), `artanh` ([664](#))

Listing: ./mathex/ex42.pp

Program Example42;

{ Program to demonstrate the sinh function. }

Uses math;

begin
 writeln(sinh(0));
 writeln(sinh(1));
 writeln(sinh(-1));
end.

17.12.66 stddev

Synopsis: Return standard deviation of data

Declaration: function stddev(const data: Array[] of float) : float
 function stddev(const data: PFloat;const N: Integer) : float

Visibility: default

Description: Stddev returns the standard deviation of the values in Data. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: mean ([679](#)), meanandstddev ([679](#)), variance ([696](#)), totalvariance ([695](#))

Listing: ./mathex/ex43.pp

Program Example40;

{ Program to demonstrate the stddev function. }

Uses Math;

Var
 I : Integer;
 ExArray : **Array**[1..10000] of Float;

begin
 Randomize;
 for I:=**low**(ExArray) **to high**(ExArray) **do**
 ExArray[I]:=Randg(1,0.2);
 Writeln('StdDev : ',StdDev(ExArray):8:4);
 Writeln('StdDev (b) : ',StdDev(@ExArray[0],10000):8:4);
end.

17.12.67 sum

Synopsis: Return sum of values

Declaration: function sum(const data: Array[] of float) : float
 function sum(const data: PFloat;const N: LongInt) : float

Visibility: default

Description: `Sum` returns the sum of the values in the `data` array.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `sumofsquares` (692), `sumsandsquares` (693), `totalvariance` (695), `variance` (696)

Listing: `./mathex/ex44.pp`

Program `Example44`;

{ Program to demonstrate the Sum function. }

Uses `math`;

Var

`I : 1..100;`

`ExArray : Array[1..100] of Float;`

begin

`Randomize;`

`for I:=low(ExArray) to high(ExArray) do`

`ExArray[I]:=(Random-Random)*100;`

`WriteLn('Max : ',MaxValue(ExArray):8:4);`

`WriteLn('Min : ',MinValue(ExArray):8:4);`

`WriteLn('Sum : ',Sum(ExArray):8:4);`

`WriteLn('Sum (b) : ',Sum(@ExArray[1],100):8:4);`

end.

17.12.68 `sumInt`

Synopsis: Return the sum of an array of integers

Declaration: `function sumInt(const data: PInt64;const N: LongInt) : Int64`
`function sumInt(const data: Array[] of Int64) : Int64`

Visibility: default

Description: `SumInt` returns the sum of the `N` integers in the `Data` array, where this can be an open array or a pointer to an array.

Errors: An overflow may occur.

17.12.69 `sumofsquares`

Synopsis: Return sum of squares of values

Declaration: `function sumofsquares(const data: Array[] of float) : float`
`function sumofsquares(const data: PFloat;const N: Integer) : float`

Visibility: default

Description: `Sumofsquares` returns the sum of the squares of the values in the `data` array.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: [sum \(691\)](#), [sumofsquares \(692\)](#), [totalvariance \(695\)](#), [variance \(696\)](#)

Listing: ./mathex/ex45.pp

Program Example45;

{ Program to demonstrate the SumOfSquares function. }

Uses math;

Var

 I : 1..100;
 ExArray : **Array**[1..100] of Float;

begin

Randomize;

for I:=**low**(ExArray) **to high**(ExArray) **do**

 ExArray[I]:= (**Random-~~Random~~**)*100;

WriteIn ('Max : ',MaxValue(ExArray):8:4);

WriteIn ('Min : ',MinValue(ExArray):8:4);

WriteIn ('Sum squares : ',SumOfSquares(ExArray):8:4);

WriteIn ('Sum squares (b) : ',SumOfSquares(@ExArray[1],100):8:4);

end.

17.12.70 sumsandsquares

Synopsis: Return sum and sum of squares of values.

Declaration: `procedure sumsandsquares(const data: Array[] of float;var sum: float;
 var sumofsquares: float)
 procedure sumsandsquares(const data: PFloat;const N: Integer;
 var sum: float;var sumofsquares: float)`

Visibility: default

Description: `sumsandsquares` calculates the sum of the values and the sum of the squares of the values in the `data` array and returns the results in `sum` and `sumofsquares`.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [sum \(691\)](#), [sumofsquares \(692\)](#), [totalvariance \(695\)](#), [variance \(696\)](#)

Listing: ./mathex/ex46.pp

Program Example45;

{ Program to demonstrate the SumOfSquares function. }

Uses math;

Var

 I : 1..100;
 ExArray : **Array**[1..100] of Float
 s,ss : float;

```

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  WriteLn('Max           : ',MaxValue(ExArray):8:4);
  WriteLn('Min           : ',MinValue(ExArray):8:4);
  SumsAndSquares(ExArray,S,SS);
  WriteLn('Sum           : ',S:8:4);
  WriteLn('Sum squares    : ',SS:8:4);
  SumsAndSquares(@ExArray[1],100,S,SS);
  WriteLn('Sum (b)        : ',S:8:4);
  WriteLn('Sum squares (b) : ',SS:8:4);
end.

```

17.12.71 tan

Synopsis: Return tangent

Declaration: `function tan(x: float) : float`

Visibility: default

Description: Tan returns the tangent of x.

Errors: If x (normalized) is pi/2 or 3pi/2 then an overflow will occur.

See also: tanh ([694](#)), arcsin ([662](#)), sincos ([690](#)), arccos ([660](#))

Listing: ./mathex/ex47.pp

```

Program Example47;

{ Program to demonstrate the Tan function. }

Uses math;

Procedure DoTan(Angle : Float);

begin
  Write('Angle : ',RadToDeg(Angle):8:6);
  WriteLn('Tangent : ',Tan(Angle):8:6);
end;

begin
  DoTan(0);
  DoTan(Pi);
  DoTan(Pi/3);
  DoTan(Pi/4);
  DoTan(Pi/6);
end.

```

17.12.72 tanh

Synopsis: Return hyperbolic tangent

Declaration: `function tanh(x: float) : float`

Visibility: default

Description: `Tanh` returns the hyperbolic tangent of `x`.

Errors: None.

See also: `arcsin` (662), `sincos` (690), `arccos` (660)

Listing: `./mathex/ex48.pp`

Program `Example48`;

{ Program to demonstrate the Tanh function. }

Uses `math`;

begin
 writeln(`tanh(0)`);
 writeln(`tanh(1)`);
 writeln(`tanh(-1)`);
end.

17.12.73 totalvariance

Synopsis: Return total variance of values

Declaration: `function totalvariance(const data: Array[] of float) : float`
 `function totalvariance(const data: PFloat; const N: Integer) : float`

Visibility: default

Description: `TotalVariance` returns the total variance of the values in the `data` array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `variance` (696), `stddev` (691), `mean` (679)

Listing: `./mathex/ex49.pp`

Program `Example49`;

{ Program to demonstrate the TotalVariance function. }

Uses `math`;

Type
 `TExArray = Array[1..100] of Float`;

Var
 `I : Integer`;
 `ExArray : TExArray`;
 `TV : float`;

begin
 Randomize;
 for `I:=1 to 100 do`

```

    ExArray[i] := (Random-Random)*100;
    TV := TotalVariance (ExArray);
    WriteLn('Total variance      : ',TV:8:4);
    TV := TotalVariance (@ExArray[1],100);
    WriteLn('Total Variance (b) : ',TV:8:4);
end.

```

17.12.74 variance

Synopsis: Return variance of values

Declaration: `function variance(const data: Array[] of float) : float`
`function variance(const data: PFloat;const N: Integer) : float`

Visibility: default

Description: `Variance` returns the variance of the values in the `data` array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `totalvariance` (695), `stddev` (691), `mean` (679)

Listing: `./mathex/ex50.pp`

Program Example50;

{ Program to demonstrate the Variance function. }

Uses math;

Var

```

    I : 1..100;
    ExArray : Array[1..100] of Float;
    V : float;

```

begin

```

    Randomize;
    for I:=low(ExArray) to high(ExArray) do
        ExArray[I] := (Random-Random)*100;
    V:=Variance (ExArray);
    WriteLn('Variance      : ',V:8:4);
    V:=Variance (@ExArray[1],100);
    WriteLn('Variance (b) : ',V:8:4);

```

end.

17.13 einvalidargument

17.13.1 Description

Exception raised when invalid arguments are passed to a function.

Chapter 18

Reference for unit 'matrix'

18.1 Overview

The unit `matrix` is a unit that provides objects for the common two, three and four dimensional vectors matrixes. These vectors and matrixes are very common in computer graphics and are often implemented from scratch by programmers while every implementation provides exactly the same functionality.

It makes therefore sense to provide this functionality in the runtime library. This eliminates the need for programmers to reinvent the wheel and also allows libraries that use matrix operations to become more compatible.

The matrix unit does not provide n-dimensional matrixes. The functionality needs of a general matrix unit varies from application to application; one can think of reduced memory usage tricks for matrixes that only have data around the diagonal etc., desire for parallelization etc. etc. It is believed that programmers that do use n-dimensional matrices would not necessarily benefit from such a unit in the runtime library.

Design goals:

- Provide common dimensions, two three and four.
- Provide multiple floating point precisions, single, double, extended.
- Simple trivial binary representation; it is possible to typecast vectors into other implementations that use the same trivial representation.
- No dynamic memory management in the background. It must be possible to write expressions like `matrix A * B * C` without worrying about memory management.

Design decisions:

- Class object model is ruled out. The objects object model, without virtual methods, is suitable.
- Operator overloading is a good way to allow programmers to write matrix expressions.
- 3 dimensions * 3 precision means 9 vector and 9 matrix objects. Macro's have been used in the source to take care of this.

18.2 Constants, types and variables

18.2.1 Types

`Tmatrix2_double_data = Array[0..1,0..1] of double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix2_extended_data = Array[0..1,0..1] of extended`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix2_single_data = Array[0..1,0..1] of single`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_double_data = Array[0..2,0..2] of double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_extended_data = Array[0..2,0..2] of extended`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_single_data = Array[0..2,0..2] of single`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix4_double_data = Array[0..3,0..3] of double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_extended_data = Array[0..3,0..3] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_single_data = Array[0..3,0..3] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_double_data = Array[0..1] of double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_extended_data = Array[0..1] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_single_data = Array[0..1] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_double_data = Array[0..2] of double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_extended_data = Array[0..2] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_single_data = Array[0..2] of single
```


This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_double_data = Array[0..3] of double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_extended_data = Array[0..3] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_single_data = Array[0..3] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

18.3 Procedures and functions

18.3.1 operator *(Tvector2_double, Tvector2_double): Tvector2_double

Synopsis: Multiply two vectors element wise

Declaration: `function operator *(Tvector2_double, Tvector2_double): Tvector2_double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.2 operator *(Tvector2_extended, Tvector2_extended): Tvector2_extended

Synopsis: Multiply two vectors element wise

Declaration:

```
function
(const x: Tvector2_extended,
const y: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.3 operator *(Tvector2_single, Tvector2_single): Tvector2_single

Synopsis: Multiply two vectors element wise

Declaration: `function operator *(Tvector2_single, Tvector2_single): Tvector2_single`

```
(const x: Tvector2_single,
const y: Tvector2_single)
: Tvector2_single
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.4 operator *(Tvector3_double, Tvector3_double): Tvector3_double

Synopsis: Multiply two vectors element wise

Declaration: `function operator *(Tvector3_double, Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.5 operator *(Tvector3_extended, Tvector3_extended): Tvector3_extended

Synopsis: Multiply two vectors element wise

Declaration:

```
function
(const x: Tvector3_extended,
const y: Tvector3_extended)
: Tvector3_extended
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.6 operator *(Tvector3_single, Tvector3_single): Tvector3_single

Synopsis: Multiply two vectors element wise

Declaration: `function operator *(Tvector3_single, Tvector3_single): Tvector3_single`

```
(const x: Tvector3_single,
const y: Tvector3_single)
: Tvector3_single
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.7 operator *(Tvector4_double, Tvector4_double): Tvector4_double

Synopsis: Multiply two vectors element wise

Declaration: `function operator *(Tvector4_double, Tvector4_double): Tvector4_double`

```
(const x: Tvector4_double,
const y: Tvector4_double)
: Tvector4_double
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.8 operator *(Tvector4_extended, Tvector4_extended): Tvector4_extended

Synopsis: Multiply two vectors element wise

Declaration:

```
function operator *(
const x: Tvector4_extended,
const y: Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.9 operator *(Tvector4_single, Tvector4_single): Tvector4_single

Synopsis: Multiply two vectors element wise

Declaration: `function operator *(Tvector4_single, Tvector4_single): Tvector4_single`

```
(const x: Tvector4_single,
const y: Tvector4_single)
: Tvector4_single
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

18.3.10 operator **(Tvector2_double, Tvector2_double): double

Synopsis: Calculate the internal product of two vectors.

Declaration: `function operator **(Tvector2_double, Tvector2_double): double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: double
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.11 operator(Tvector2_extended, Tvector2_extended): extended**

Synopsis: Calculate the internal product of two vectors.

Declaration: `function operator ** (Tvector2_extended, Tvector2_extended): extended`
`(const x: Tvector2_extended, const y: Tvector2_extended): extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.12 operator(Tvector2_single, Tvector2_single): single**

Synopsis: Calculate the internal product of two vectors.

Declaration: `function operator ** (Tvector2_single, Tvector2_single): single`
`(const x: Tvector2_single, const y: Tvector2_single): single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.13 operator(Tvector3_double, Tvector3_double): double**

Synopsis: Calculate the internal product of two vectors.

Declaration: `function operator ** (Tvector3_double, Tvector3_double): double`
`(const x: Tvector3_double, const y: Tvector3_double): double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.14 operator(Tvector3_extended, Tvector3_extended): extended**

Synopsis: Calculate the internal product of two vectors.

Declaration: `function operator ** (Tvector3_extended, Tvector3_extended): extended`
`(const x: Tvector3_extended, const y: Tvector3_extended): extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.15 operator **(Tvector3_single, Tvector3_single): single

Synopsis: Calculate the internal product of two vectors.

Declaration:

```
function operator **(Tvector3_single, Tvector3_single): single
                                (const x: Tvector3_single,
                                const y: Tvector3_single)
                                : single
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.16 operator **(Tvector4_double, Tvector4_double): double

Synopsis: Calculate the internal product of two vectors.

Declaration:

```
function operator **(Tvector4_double, Tvector4_double): double
                                (const x: Tvector4_double,
                                const y: Tvector4_double)
                                : double
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.17 operator **(Tvector4_extended, Tvector4_extended): extended

Synopsis: Calculate the internal product of two vectors.

Declaration:

```
function operator **(Tvector4_extended, Tvector4_extended): extended
                                (const x: Tvector4_extended,
                                const y: Tvector4_extended)
                                : extended
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.18 operator **(Tvector4_single, Tvector4_single): single

Synopsis: Calculate the internal product of two vectors.

Declaration:

```
function operator **(Tvector4_single, Tvector4_single): single
                                (const x: Tvector4_single,
                                const y: Tvector4_single)
                                : single
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

18.3.19 operator +(Tvector2_double, Tvector2_double): Tvector2_double

Synopsis: Add two-dimensional double precision vectors together

Declaration: `function operator +(Tvector2_double, Tvector2_double): Tvector2_double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.20 operator +(Tvector2_extended, Tvector2_extended): Tvector2_extended

Synopsis: Add two-dimensional extended precision vectors together

Declaration:

```
function operator +(
const x: Tvector2_extended,
const y: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.21 operator +(Tvector2_single, Tvector2_single): Tvector2_single

Synopsis: Add two-dimensional single precision vectors together

Declaration: `function operator +(Tvector2_single, Tvector2_single): Tvector2_single`

```
(const x: Tvector2_single,
const y: Tvector2_single)
: Tvector2_single
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.22 operator +(Tvector3_double, Tvector3_double): Tvector3_double

Synopsis: Add three-dimensional double precision vectors together

Declaration: `function operator +(Tvector3_double, Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.23 operator +(Tvector3_extended, Tvector3_extended): Tvector3_extended

Synopsis: Add three-dimensional extended precision vectors together

Declaration:

```
function
(const x: Tvec
const y: Tvec
: Tvec
```

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.24 operator +(Tvector3_single, Tvector3_single): Tvector3_single

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `function operator +(Tvector3_single, Tvector3_single): Tvector3_single`

```
(const x: Tvec
const y: Tvec
: Tvector3_si
```

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.25 operator +(Tvector4_double, Tvector4_double): Tvector4_double

Synopsis: Add four-dimensional double precision vectors together

Declaration: `function operator +(Tvector4_double, Tvector4_double): Tvector4_double`

```
(const x: Tvec
const y: Tvec
: Tvector4_do
```

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.26 operator +(Tvector4_extended, Tvector4_extended): Tvector4_extended

Synopsis: Add four-dimensional extended precision vectors together

Declaration:

```
function
(const x: Tvec
const y: Tvec
: Tvec
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.27 operator +(Tvector4_single, Tvector4_single): Tvector4_single

Synopsis: Add four-dimensional single precision vectors together

Declaration: `function operator +(Tvector4_single, Tvector4_single): Tvector4_single`

```
(const x: Tvector4_single,
const y: Tvector4_single)
: Tvector4_single
```

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

18.3.28 operator -(Tvector2_double): Tvector2_double

Synopsis: Negate two-dimensional vector.

Declaration: `function operator -(Tvector2_double): Tvector2_double`

```
(const x: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.29 operator -(Tvector2_double, Tvector2_double): Tvector2_double

Synopsis: Subtract two-dimensional double precision vectors from each other

Declaration: `function operator -(Tvector2_double, Tvector2_double): Tvector2_double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.30 operator -(Tvector2_extended): Tvector2_extended

Synopsis: Negate two-dimensional vector.

Declaration: `function operator -(Tvector2_extended): Tvector2_extended`

```
(const x: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.31 operator -(Tvector2_extended, Tvector2_extended): Tvector2_extended

Synopsis: Subtract two-dimensional extended precision vectors from each other

Declaration:

```
function
(const x: Tvector2_extended,
const y: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.32 operator -(Tvector2_single): Tvector2_single

Synopsis: Negate two-dimensional vector.

Declaration: `function operator -(Tvector2_single): Tvector2_single`
`(const x: Tvector2_single)`
`: Tvector2_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.33 operator -(Tvector2_single, Tvector2_single): Tvector2_single

Synopsis: Subtract two-dimensional single precision vectors from each other

Declaration: `function operator -(Tvector2_single, Tvector2_single): Tvector2_single`
`(const x: Tvector2_single, const y: Tvector2_single)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.34 operator -(Tvector3_double): Tvector3_double

Synopsis: Negate three-dimensional vector.

Declaration: `function operator -(Tvector3_double): Tvector3_double`
`(const x: Tvector3_double)`
`: Tvector3_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.35 operator -(Tvector3_double, Tvector3_double): Tvector3_double

Synopsis: Subtract three-dimensional double precision vectors from each other

Declaration: `function operator -(Tvector3_double, Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.36 operator -(Tvector3_extended): Tvector3_extended

Synopsis: Negate three-dimensional vector.

Declaration: `function operator -(Tvector3_extended): Tvector3_extended`

```
(const x: Tvector3_extended)
: Tvector3_extended
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.37 operator -(Tvector3_extended, Tvector3_extended): Tvector3_extended

Synopsis: Subtract three-dimensional extended precision vectors from each other

Declaration:

```
function operator -(
const x: Tvector3_extended,
const y: Tvector3_extended)
: Tvector3_extended
```

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.38 operator -(Tvector3_single): Tvector3_single

Synopsis: Negate three-dimensional vector.

Declaration: `function operator -(Tvector3_single): Tvector3_single`

```
(const x: Tvector3_single)
: Tvector3_single
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.39 operator -(Tvector3_single, Tvector3_single): Tvector3_single

Synopsis: Subtract three-dimensional single precision vectors from each other

Declaration: `function operator -(Tvector3_single, Tvector3_single): Tvector3_single`

```
(const x: Tvector3_single,
const y: Tvector3_single)
: Tvector3_single
```

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.40 operator -(Tvector4_double): Tvector4_double

Synopsis: Negate four-dimensional vector.

Declaration: `function operator -(Tvector4_double): Tvector4_double`

```
(const x: Tvector4_double)
: Tvector4_double
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.41 operator -(Tvector4_double, Tvector4_double): Tvector4_double

Synopsis: Subtract four-dimensional double precision vectors from each other

Declaration: `function operator -(Tvector4_double, Tvector4_double): Tvector4_double`

```
(const x: Tvector4_double,
const y: Tvector4_double)
: Tvector4_double
```

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.42 operator -(Tvector4_extended): Tvector4_extended

Synopsis: Negate four-dimensional vector.

Declaration: `function operator -(Tvector4_extended): Tvector4_extended`

```
(const x: Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.43 operator -(Tvector4_extended, Tvector4_extended): Tvector4_extended

Synopsis: Subtract four-dimensional extended precision vectors from each other

Declaration:

```
function
(const x: Tvector4_extended,
const y: Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.44 operator -(Tvector4_single): Tvector4_single

Synopsis: Negate four-dimensional vector.

Declaration: `function operator -(Tvector4_single): Tvector4_single`
`(const x: Tvector4_single)`
`: Tvector4_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

18.3.45 operator -(Tvector4_single, Tvector4_single): Tvector4_single

Synopsis: Subtract four-dimensional single precision vectors from each other

Declaration: `function operator -(Tvector4_single, Tvector4_single): Tvector4_single`
`(const x: Tvector4_single, const y: Tvector4_single)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

18.3.46 operator :=(Tvector2_double): Tvector2_extended

Synopsis: Allow assignment of double precision vector to extended precision vector

Declaration: `function operator :=(Tvector2_double): Tvector2_extended`
`(const v: Tvector2_double)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever an extended precision vector is expected.

18.3.47 operator :=(Tvector2_double): Tvector2_single

Synopsis: Allow assignment of double precision vector to single precision vector

Declaration: `function operator :=(Tvector2_double): Tvector2_single`
`(const v: Tvector2_double)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever a single precision vector is expected, at the cost of loosing some precision.

18.3.48 operator :=(Tvector2_double): Tvector3_double

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector2_double): Tvector3_double`
`(const v: Tvector2_double)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

18.3.49 operator :=(Tvector2_double): Tvector3_extended

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector2_double): Tvector3_extended`
`(const v: Tvector2_double)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

18.3.50 operator :=(Tvector2_double): Tvector3_single

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector2_double): Tvector3_single`
`(const v: Tvector2_double)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

18.3.51 operator :=(Tvector2_double): Tvector4_double

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector2_double): Tvector4_double`
`(const v: Tvector2_double)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

18.3.52 operator :=(Tvector2_double): Tvector4_extended

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector2_double): Tvector4_extended`
`(const v: Tvector2_double)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

18.3.53 operator :=(Tvector2_double): Tvector4_single

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector2_double): Tvector4_single`
`(const v: Tvector2_double)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

18.3.54 operator :=(Tvector2_extended): Tvector2_double

Synopsis: Allow assignment of extended precision vector to double precision vector

Declaration: `function operator :=(Tvector2_extended): Tvector2_double`
`(const v: Tvector2_extended)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a double precision vector is expected, at the cost of losing some precision.

18.3.55 operator :=(Tvector2_extended): Tvector2_single

Synopsis: Allow assignment of extended precision vector to single precision vector

Declaration: `function operator :=(Tvector2_extended) : Tvector2_single`
`(const v: Tvector2_extended)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a single precision vector is expected, at the cost of loosing some precision.

18.3.56 operator :=(Tvector2_extended): Tvector3_double

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector2_extended) : Tvector3_double`
`(const v: Tvector2_extended)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

18.3.57 operator :=(Tvector2_extended): Tvector3_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector2_extended) : Tvector3_extended`
`(const v: Tvector2_extended)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

18.3.58 operator :=(Tvector2_extended): Tvector3_single

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector2_extended) : Tvector3_single`
`(const v: Tvector2_extended)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

18.3.59 operator :=(Tvector2_extended): Tvector4_double

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector2_extended): Tvector4_double`
`(const v: Tvector2_extended)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

18.3.60 operator :=(Tvector2_extended): Tvector4_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector2_extended): Tvector4_extended`
`(const v: Tvector2_extended)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

18.3.61 operator :=(Tvector2_extended): Tvector4_single

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector2_extended): Tvector4_single`
`(const v: Tvector2_extended)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

18.3.62 operator :=(Tvector2_single): Tvector2_double

Synopsis: Allow assignment of single precision vector to double precision vector

Declaration: `function operator :=(Tvector2_single): Tvector2_double`
`(const v: Tvector2_single)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever a double precision vector is expected.

18.3.63 operator :=(Tvector2_single): Tvector2_extended

Synopsis: Allow assignment of single precision vector to extended precision vector

Declaration: `function operator :=(Tvector2_single): Tvector2_extended`
`(const v: Tvector2_single)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever an extended precision vector is expected.

18.3.64 operator :=(Tvector2_single): Tvector3_double

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector2_single): Tvector3_double`
`(const v: Tvector2_single)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

18.3.65 operator :=(Tvector2_single): Tvector3_extended

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector2_single): Tvector3_extended`
`(const v: Tvector2_single)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

18.3.66 operator :=(Tvector2_single): Tvector3_single

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector2_single): Tvector3_single`
`(const v: Tvector2_single)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The third dimension is set to 0.0.

18.3.67 operator :=(Tvector2_single): Tvector4_double

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector2_single): Tvector4_double`
`(const v: Tvector2_single)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

18.3.68 operator :=(Tvector2_single): Tvector4_extended

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector2_single): Tvector4_extended`
`(const v: Tvector2_single)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

18.3.69 operator :=(Tvector2_single): Tvector4_single

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector2_single): Tvector4_single`
`(const v: Tvector2_single)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The third and fourth dimensions are set to 0.0.

18.3.70 operator :=(Tvector3_double): Tvector2_double

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional double precision vector

Declaration: `function operator :=(Tvector3_double): Tvector2_double`
`(const v: Tvector3_double)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

18.3.71 operator :=(Tvector3_double): Tvector2_extended

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_double): Tvector2_extended`
`(const v: Tvector3_double)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

18.3.72 operator :=(Tvector3_double): Tvector2_single

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional single precision vector

Declaration: `function operator :=(Tvector3_double): Tvector2_single`
`(const v: Tvector3_double)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

18.3.73 operator :=(Tvector3_double): Tvector3_extended

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_double): Tvector3_extended`
`(const v: Tvector3_double)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected.

18.3.74 operator :=(Tvector3_double): Tvector3_single

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector3_double): Tvector3_single`
`(const v: Tvector3_double)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some precision is lost because of the conversion.

18.3.75 operator :=(Tvector3_double): Tvector4_double

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector3_double): Tvector4_double`
`(const v: Tvector3_double)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

18.3.76 operator :=(Tvector3_double): Tvector4_extended

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_double): Tvector4_extended`
`(const v: Tvector3_double)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

18.3.77 operator :=(Tvector3_double): Tvector4_single

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector3_double): Tvector4_single`
`(const v: Tvector3_double)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some precision is lost because of the conversion.

18.3.78 operator :=(Tvector3_extended): Tvector2_double

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `function operator :=(Tvector3_extended): Tvector2_double`
`(const v: Tvector3_extended)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

18.3.79 operator :=(Tvector3_extended): Tvector2_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_extended) : Tvector2_extended`
`(const v: Tvector3_extended)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

18.3.80 operator :=(Tvector3_extended): Tvector2_single

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `function operator :=(Tvector3_extended) : Tvector2_single`
`(const v: Tvector3_extended)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

18.3.81 operator :=(Tvector3_extended): Tvector3_double

Synopsis: Allow assignment of three-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector3_extended) : Tvector3_double`
`(const v: Tvector3_extended)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

18.3.82 operator :=(Tvector3_extended): Tvector3_single

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector3_extended) : Tvector3_single`
`(const v: Tvector3_extended)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

18.3.83 operator :=(Tvector3_extended): Tvector4_double

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector3_extended): Tvector4_double`
`(const v: Tvector3_extended)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

18.3.84 operator :=(Tvector3_extended): Tvector4_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_extended): Tvector4_extended`
`(const v: Tvector3_extended)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

18.3.85 operator :=(Tvector3_extended): Tvector4_single

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector3_extended): Tvector4_single`
`(const v: Tvector3_extended)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

18.3.86 operator :=(Tvector3_single): Tvector2_double

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional double precision vector

Declaration: `function operator :=(Tvector3_single): Tvector2_double`
`(const v: Tvector3_single)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

18.3.87 operator :=(Tvector3_single): Tvector2_extended

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_single): Tvector2_extended`
`(const v: Tvector3_single)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

18.3.88 operator :=(Tvector3_single): Tvector2_single

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional single precision vector

Declaration: `function operator :=(Tvector3_single): Tvector2_single`
`(const v: Tvector3_single)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away.

18.3.89 operator :=(Tvector3_single): Tvector3_double

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector3_single): Tvector3_double`
`(const v: Tvector3_single)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected.

18.3.90 operator :=(Tvector3_single): Tvector3_extended

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_single): Tvector3_extended`
`(const v: Tvector3_single)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected.

18.3.91 operator :=(Tvector3_single): Tvector4_double

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector3_single): Tvector4_double`
`(const v: Tvector3_single)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

18.3.92 operator :=(Tvector3_single): Tvector4_extended

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector3_single): Tvector4_extended`
`(const v: Tvector3_single)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

18.3.93 operator :=(Tvector3_single): Tvector4_single

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector3_single): Tvector4_single`
`(const v: Tvector3_single)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0.

18.3.94 operator :=(Tvector4_double): Tvector2_double

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional double precision vector

Declaration: `function operator :=(Tvector4_double): Tvector2_double`
`(const v: Tvector4_double)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

18.3.95 operator :=(Tvector4_double): Tvector2_extended

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_double): Tvector2_extended`
`(const v: Tvector4_double)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

18.3.96 operator :=(Tvector4_double): Tvector2_single

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional single precision vector

Declaration: `function operator :=(Tvector4_double): Tvector2_single`
`(const v: Tvector4_double)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

18.3.97 operator :=(Tvector4_double): Tvector3_double

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector4_double): Tvector3_double`
`(const v: Tvector4_double)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

18.3.98 operator :=(Tvector4_double): Tvector3_extended

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_double): Tvector3_extended`
`(const v: Tvector4_double)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

18.3.99 operator :=(Tvector4_double): Tvector3_single

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector4_double): Tvector3_single`
`(const v: Tvector4_double)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

18.3.100 operator :=(Tvector4_double): Tvector4_extended

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_double): Tvector4_extended`
`(const v: Tvector4_double)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected.

18.3.101 operator :=(Tvector4_double): Tvector4_single

Synopsis: Allow assignment of four-dimensional double precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector4_double): Tvector4_single`
`(const v: Tvector4_double)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

18.3.102 operator :=(Tvector4_extended): Tvector2_double

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `function operator :=(Tvector4_extended): Tvector2_double`
`(const v: Tvector4_extended)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

18.3.103 operator :=(Tvector4_extended): Tvector2_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_extended) : Tvector2_extended`
`(const v: Tvector4_extended)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

18.3.104 operator :=(Tvector4_extended): Tvector2_single

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `function operator :=(Tvector4_extended) : Tvector2_single`
`(const v: Tvector4_extended)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

18.3.105 operator :=(Tvector4_extended): Tvector3_double

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector4_extended) : Tvector3_double`
`(const v: Tvector4_extended)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

18.3.106 operator :=(Tvector4_extended): Tvector3_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_extended) : Tvector3_extended`
`(const v: Tvector4_extended)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimensions are thrown away.

18.3.107 operator :=(Tvector4_extended): Tvector3_single

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector4_extended): Tvector3_single`
`(const v: Tvector4_extended)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

18.3.108 operator :=(Tvector4_extended): Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector4_extended): Tvector4_double`
`(const v: Tvector4_extended)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion.

18.3.109 operator :=(Tvector4_extended): Tvector4_single

Synopsis: Allow assignment of four-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `function operator :=(Tvector4_extended): Tvector4_single`
`(const v: Tvector4_extended)`
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

18.3.110 operator :=(Tvector4_single): Tvector2_double

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional double precision vector

Declaration: `function operator :=(Tvector4_single): Tvector2_double`
`(const v: Tvector4_single)`
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

18.3.111 operator :=(Tvector4_single): Tvector2_extended

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_single): Tvector2_extended`
`(const v: Tvector4_single)`
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

18.3.112 operator :=(Tvector4_single): Tvector2_single

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional single precision vector

Declaration: `function operator :=(Tvector4_single): Tvector2_single`
`(const v: Tvector4_single)`
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away.

18.3.113 operator :=(Tvector4_single): Tvector3_double

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional double precision vector

Declaration: `function operator :=(Tvector4_single): Tvector3_double`
`(const v: Tvector4_single)`
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

18.3.114 operator :=(Tvector4_single): Tvector3_extended

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_single): Tvector3_extended`
`(const v: Tvector4_single)`
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

18.3.115 operator :=(Tvector4_single): Tvector3_single

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional single precision vector

Declaration: `function operator :=(Tvector4_single): Tvector3_single`
`(const v: Tvector4_single)`
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away.

18.3.116 operator :=(Tvector4_single): Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `function operator :=(Tvector4_single): Tvector4_double`
`(const v: Tvector4_single)`
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected.

18.3.117 operator :=(Tvector4_single): Tvector4_extended

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `function operator :=(Tvector4_single): Tvector4_extended`
`(const v: Tvector4_single)`
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected.

18.4 Tmatrix2_double

18.4.1 Description

The `Tmatrix2_double` object provides a matrix of 2*2 double precision scalars.

18.4.2 Method overview

Page	Property	Description
731	<code>determinant</code>	Calculates the determinant of the matrix.
731	<code>get_column</code>	Returns the c-th column of the matrix as vector.
731	<code>get_row</code>	Returns the r-th row of the matrix as vector.
730	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
730	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
730	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
731	<code>inverse</code>	Calculates the inverse of the matrix.
731	<code>set_column</code>	Sets c-th column of the matrix with a vector.
731	<code>set_row</code>	Sets r-th row of the matrix with a vector.
732	<code>transpose</code>	Returns the transposition of the matrix.

18.4.3 Tmatrix2_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.4.4 Tmatrix2_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.4.5 Tmatrix2_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: double;ab: double;ba: double;bb: double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.4.6 Tmatrix2_double.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

18.4.7 Tmatrix2_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

18.4.8 Tmatrix2_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

18.4.9 Tmatrix2_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

18.4.10 Tmatrix2_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : double`

Visibility: default

Description: Returns the determinant of the matrix.

18.4.11 Tmatrix2_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: double) : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

18.4.12 Tmatrix2_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.5 Tmatrix2_extended

18.5.1 Description

The `Tmatrix2_extended` object provides a matrix of 2*2 extended precision scalars.

18.5.2 Method overview

Page	Property	Description
733	<code>determinant</code>	Calculates the determinant of the matrix.
733	<code>get_column</code>	Returns the c-th column of the matrix as vector.
733	<code>get_row</code>	Returns the r-th row of the matrix as vector.
733	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
732	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
732	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
734	<code>inverse</code>	Calculates the inverse of the matrix.
733	<code>set_column</code>	Sets c-th column of the matrix with a vector.
733	<code>set_row</code>	Sets r-th row of the matrix with a vector.
734	<code>transpose</code>	Returns the transposition of the matrix.

18.5.3 Tmatrix2_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.5.4 Tmatrix2_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.5.5 Tmatrix2_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ba: extended; bb: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.5.6 Tmatrix2_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

18.5.7 Tmatrix2_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

18.5.8 Tmatrix2_extended.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

18.5.9 Tmatrix2_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

18.5.10 Tmatrix2_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

18.5.11 Tmatrix2_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: extended) : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

18.5.12 Tmatrix2_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.6 Tmatrix2_single

18.6.1 Description

The `Tmatrix2_single` object provides a matrix of 2*2 single precision scalars.

18.6.2 Method overview

Page	Property	Description
736	<code>determinant</code>	Calculates the determinant of the matrix.
735	<code>get_column</code>	Returns the c-th column of the matrix as vector.
735	<code>get_row</code>	Returns the r-th row of the matrix as vector.
735	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
735	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
734	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
736	<code>inverse</code>	Calculates the inverse of the matrix.
735	<code>set_column</code>	Sets c-th column of the matrix with a vector.
736	<code>set_row</code>	Sets r-th row of the matrix with a vector.
736	<code>transpose</code>	Returns the transposition of the matrix.

18.6.3 Tmatrix2_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.6.4 Tmatrix2_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.6.5 Tmatrix2_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single;ab: single;ba: single;bb: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.6.6 Tmatrix2_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

18.6.7 Tmatrix2_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

18.6.8 Tmatrix2_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte;const v: Tvector2_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

18.6.9 Tmatrix2_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

18.6.10 Tmatrix2_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

18.6.11 Tmatrix2_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

18.6.12 Tmatrix2_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.7 Tmatrix3_double

18.7.1 Description

The `Tmatrix3_double` object provides a matrix of 3*3 double precision scalars.

18.7.2 Method overview

Page	Property	Description
738	determinant	Calculates the determinant of the matrix.
737	get_column	Returns the c-th column of the matrix as vector.
738	get_row	Returns the r-th row of the matrix as vector.
737	init	Initializes the matrix, setting its elements to the values passed to the constructor.
737	init_identity	Initializes the matrix and sets its elements to the identity matrix.
737	init_zero	Initializes the matrix and sets its elements to zero
738	inverse	Calculates the inverse of the matrix.
738	set_column	Sets c-th column of the matrix with a vector.
738	set_row	Sets r-th row of the matrix with a vector.
738	transpose	Returns the transposition of the matrix.

18.7.3 Tmatrix3_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.7.4 Tmatrix3_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.7.5 Tmatrix3_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: double;ab: double;ac: double;ba: double;bb: double;
bc: double;ca: double;cb: double;cc: double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.7.6 Tmatrix3_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

18.7.7 Tmatrix3_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

18.7.8 Tmatrix3_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

18.7.9 Tmatrix3_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

18.7.10 Tmatrix3_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : double`

Visibility: default

Description: Returns the determinant of the matrix.

18.7.11 Tmatrix3_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: double) : Tmatrix3_double`

Visibility: default

Description: `Tmatrix3_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

18.7.12 Tmatrix3_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the *x* and *y* coordinates of the values swapped.

18.8 Tmatrix3_extended

18.8.1 Description

The Tmatrix3_extended object provides a matrix of 3*3 extended precision scalars.

18.8.2 Method overview

Page	Property	Description
740	determinant	Calculates the determinant of the matrix.
740	get_column	Returns the c-th column of the matrix as vector.
740	get_row	Returns the r-th row of the matrix as vector.
739	init	Initializes the matrix, setting its elements to the values passed to the constructor.
739	init_identity	Initializes the matrix and sets its elements to the identity matrix.
739	init_zero	Initializes the matrix and sets its elements to zero
740	inverse	Calculates the inverse of the matrix.
740	set_column	Sets r-th column of the matrix with a vector.
740	set_row	Sets r-th row of the matrix with a vector.
741	transpose	Returns the transposition of the matrix.

18.8.3 Tmatrix3_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.8.4 Tmatrix3_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.8.5 Tmatrix3_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended;ab: extended;ac: extended;ba: extended;
bb: extended;bc: extended;ca: extended;cb: extended;
cc: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.8.6 Tmatrix3_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

18.8.7 Tmatrix3_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

18.8.8 Tmatrix3_extended.set_column

Synopsis: Sets *r*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

18.8.9 Tmatrix3_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

18.8.10 Tmatrix3_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

18.8.11 Tmatrix3_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: extended) : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix3_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

18.8.12 Tmatrix3_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.9 Tmatrix3_single

18.9.1 Description

The `Tmatrix3_single` object provides a matrix of 3*3 single precision scalars.

18.9.2 Method overview

Page	Property	Description
743	<code>determinant</code>	Calculates the determinant of the matrix.
742	<code>get_column</code>	Returns the c-th column of the matrix as vector.
742	<code>get_row</code>	Returns the r-th row of the matrix as vector.
742	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
741	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
741	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
743	<code>inverse</code>	Calculates the inverse of the matrix.
742	<code>set_column</code>	Sets c-th column of the matrix with a vector.
742	<code>set_row</code>	Sets r-th row of the matrix with a vector.
743	<code>transpose</code>	Returns the transposition of the matrix.

18.9.3 Tmatrix3_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.9.4 Tmatrix3_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.9.5 Tmatrix3_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single;ab: single;ac: single;ba: single;bb: single;
bc: single;ca: single;cb: single;cc: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.9.6 Tmatrix3_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

18.9.7 Tmatrix3_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

18.9.8 Tmatrix3_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte;const v: Tvector3_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

18.9.9 Tmatrix3_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte;const v: Tvector3_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

18.9.10 Tmatrix3_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

18.9.11 Tmatrix3_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: single) : Tmatrix3_single`

Visibility: default

Description: `Tmatrix3_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

18.9.12 Tmatrix3_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.10 Tmatrix4_double

18.10.1 Description

The `Tmatrix4_double` object provides a matrix of 4*4 double precision scalars.

18.10.2 Method overview

Page	Property	Description
745	<code>determinant</code>	Calculates the determinant of the matrix.
744	<code>get_column</code>	Returns the c-th column of the matrix as vector.
744	<code>get_row</code>	Returns the r-th row of the matrix as vector.
744	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
744	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
744	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
745	<code>inverse</code>	Calculates the inverse of the matrix.
745	<code>set_column</code>	Sets c-th column of the matrix with a vector.
745	<code>set_row</code>	Sets r-th row of the matrix with a vector.
745	<code>transpose</code>	Returns the transposition of the matrix.

18.10.3 Tmatrix4_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.10.4 Tmatrix4_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.10.5 Tmatrix4_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: double;ab: double;ac: double;ad: double;ba: double;
bb: double;bc: double;bd: double;ca: double;cb: double;
cc: double;cd: double;da: double;db: double;dc: double;
dd: double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.10.6 Tmatrix4_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

18.10.7 Tmatrix4_double.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_double`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

18.10.8 Tmatrix4_double.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

18.10.9 Tmatrix4_double.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

18.10.10 Tmatrix4_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : double`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

18.10.11 Tmatrix4_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: double) : Tmatrix4_double`

Visibility: default

Description: `Tmatrix4_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

18.10.12 Tmatrix4_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.11 Tmatrix4_extended

18.11.1 Description

The `Tmatrix4_extended` object provides a matrix of 4*4 extended precision scalars.

18.11.2 Method overview

Page	Property	Description
747	<code>determinant</code>	Calculates the determinant of the matrix.
747	<code>get_column</code>	Returns the c-th column of the matrix as vector.
747	<code>get_row</code>	Returns the r-th row of the matrix as vector.
746	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
746	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
746	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
748	<code>inverse</code>	Calculates the inverse of the matrix.
747	<code>set_column</code>	Sets c-th column of the matrix with a vector.
747	<code>set_row</code>	Sets r-th row of the matrix with a vector.
748	<code>transpose</code>	Returns the transposition of the matrix.

18.11.3 Tmatrix4_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.11.4 Tmatrix4_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.11.5 Tmatrix4_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended; ad: extended;
ba: extended; bb: extended; bc: extended; bd: extended;
ca: extended; cb: extended; cc: extended; cd: extended;
da: extended; db: extended; dc: extended; dd: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.11.6 Tmatrix4_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

18.11.7 Tmatrix4_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

18.11.8 Tmatrix4_extended.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

18.11.9 Tmatrix4_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

18.11.10 Tmatrix4_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

18.11.11 Tmatrix4_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix4_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

18.11.12 Tmatrix4_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.12 Tmatrix4_single

18.12.1 Description

The `Tmatrix4_single` object provides a matrix of 4*4 single precision scalars.

18.12.2 Method overview

Page	Property	Description
750	<code>determinant</code>	Calculates the determinant of the matrix.
749	<code>get_column</code>	Returns the c-th column of the matrix as vector.
749	<code>get_row</code>	Returns the r-th row of the matrix as vector.
749	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
749	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
748	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
750	<code>inverse</code>	Calculates the inverse of the matrix.
749	<code>set_column</code>	Sets c-th column of the matrix with a vector.
750	<code>set_row</code>	Sets r-th row of the matrix with a vector.
750	<code>transpose</code>	Returns the transposition of the matrix.

18.12.3 Tmatrix4_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.12.4 Tmatrix4_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

18.12.5 Tmatrix4_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single;ab: single;ac: single;ad: single;ba: single;
bb: single;bc: single;bd: single;ca: single;cb: single;
cc: single;cd: single;da: single;db: single;dc: single;
dd: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

18.12.6 Tmatrix4_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

18.12.7 Tmatrix4_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

18.12.8 Tmatrix4_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte;const v: Tvector4_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

18.12.9 Tmatrix4_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

18.12.10 Tmatrix4_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

18.12.11 Tmatrix4_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: single) : Tmatrix4_single`

Visibility: default

Description: `Tmatrix4_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

18.12.12 Tmatrix4_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

18.13 Tvector2_double**18.13.1 Description**

The `Tvector2_double` object provides a vector of two double precision scalars.

18.13.2 Method overview

Page	Property	Description
751	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
751	<code>init_one</code>	Initializes the vector and sets its elements to one
751	<code>init_zero</code>	Initializes the vector and sets its elements to zero
751	<code>length</code>	Calculates the length of the vector.
751	<code>squared_length</code>	Calculates the squared length of the vector.

18.13.3 Tvector2_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.13.4 Tvector2_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.13.5 Tvector2_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: double;b: double)`

Visibility: default

18.13.6 Tvector2_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([751](#)) if you are able to, as it is faster.

18.13.7 Tvector2_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

18.14 Tvector2_extended

18.14.1 Description

The `Tvector2_extended` object provides a vector of two extended precision scalars.

18.14.2 Method overview

Page	Property	Description
752	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
752	<code>init_one</code>	Initializes the vector and sets its elements to one
752	<code>init_zero</code>	Initializes the vector and sets its elements to zero
752	<code>length</code>	Calculates the length of the vector.
753	<code>squared_length</code>	Calculates the squared length of the vector.

18.14.3 Tvector2_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.14.4 Tvector2_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.14.5 Tvector2_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended;b: extended)`

Visibility: default

18.14.6 Tvector2_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([753](#)) if you are able to, as it is faster.

18.14.7 Tvector2_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

18.15 Tvector2_single

18.15.1 Description

The `Tvector2_single` object provides a vector of two single precision scalars.

18.15.2 Method overview

Page	Property	Description
753	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
753	<code>init_one</code>	Initializes the vector and sets its elements to one
753	<code>init_zero</code>	Initializes the vector and sets its elements to zero
754	<code>length</code>	Calculates the length of the vector.
754	<code>squared_length</code>	Calculates the squared length of the vector.

18.15.3 Tvector2_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.15.4 Tvector2_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.15.5 Tvector2_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single;b: single)`

Visibility: default

18.15.6 Tvector2_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` (754) if you are able to, as it is faster.

18.15.7 Tvector2_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

18.16 Tvector3_double

18.16.1 Description

The `Tvector3_double` object provides a vector of three double precision scalars.

18.16.2 Method overview

Page	Property	Description
755	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
754	<code>init_one</code>	Initializes the vector and sets its elements to one
754	<code>init_zero</code>	Initializes the vector and sets its elements to zero
755	<code>length</code>	Calculates the length of the vector.
755	<code>squared_length</code>	Calculates the squared length of the vector.

18.16.3 Tvector3_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.16.4 Tvector3_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.16.5 Tvector3_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: double;b: double;c: double)`

Visibility: default

18.16.6 Tvector3_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (755) if you are able to, as it is faster.

18.16.7 Tvector3_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

18.17 Tvector3_extended

18.17.1 Description

The `Tvector3_extended` object provides a vector of three extended precision scalars.

18.17.2 Method overview

Page	Property	Description
756	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
756	<code>init_one</code>	Initializes the vector and sets its elements to one
755	<code>init_zero</code>	Initializes the vector and sets its elements to zero
756	<code>length</code>	Calculates the length of the vector.
756	<code>squared_length</code>	Calculates the squared length of the vector.

18.17.3 Tvector3_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.17.4 Tvector3_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.17.5 Tvector3_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended;b: extended;c: extended)`

Visibility: default

18.17.6 Tvector3_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (756) if you are able to, as it is faster.

18.17.7 Tvector3_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

18.18 Tvector3_single

18.18.1 Description

The `Tvector3_single` object provides a vector of three single precision scalars.

18.18.2 Method overview

Page	Property	Description
757	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
757	<code>init_one</code>	Initializes the vector and sets its elements to one
757	<code>init_zero</code>	Initializes the vector and sets its elements to zero
757	<code>length</code>	Calculates the length of the vector.
757	<code>squared_length</code>	Calculates the squared length of the vector.

18.18.3 Tvector3_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.18.4 Tvector3_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.18.5 Tvector3_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single;b: single;c: single)`

Visibility: default

18.18.6 Tvector3_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: $\text{length} = \sqrt{\text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2}$. Try to use `squared_length` (757) if you are able to, as it is faster.

18.18.7 Tvector3_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: $\text{squared_length} = \text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2$.

18.19 Tvector4_double

18.19.1 Description

The `Tvector4_double` object provides a vector of four double precision scalars.

18.19.2 Method overview

Page	Property	Description
758	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
758	<code>init_one</code>	Initializes the vector and sets its elements to one
758	<code>init_zero</code>	Initializes the vector and sets its elements to zero
758	<code>length</code>	Calculates the length of the vector.
758	<code>squared_length</code>	Calculates the squared length of the vector.

18.19.3 Tvector4_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.19.4 Tvector4_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.19.5 Tvector4_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: double;b: double;c: double;d: double)`

Visibility: default

18.19.6 Tvector4_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([758](#)) if you are able to, as it is faster.

18.19.7 Tvector4_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

18.20 Tvector4_extended

18.20.1 Description

The `Tvector4_extended` object provides a vector of four extended precision scalars.

18.20.2 Method overview

Page	Property	Description
759	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
759	<code>init_one</code>	Initializes the vector and sets its elements to one
759	<code>init_zero</code>	Initializes the vector and sets its elements to zero
759	<code>length</code>	Calculates the length of the vector.
760	<code>squared_length</code>	Calculates the squared length of the vector.

18.20.3 Tvector4_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.20.4 Tvector4_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.20.5 Tvector4_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended;b: extended;c: extended;d: extended)`

Visibility: default

18.20.6 Tvector4_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([760](#)) if you are able to, as it is faster.

18.20.7 Tvector4_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

18.21 Tvector4_single

18.21.1 Description

The `Tvector4_single` object provides a vector of four single precision scalars.

18.21.2 Method overview

Page	Property	Description
760	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
760	<code>init_one</code>	Initializes the vector and sets its elements to one
760	<code>init_zero</code>	Initializes the vector and sets its elements to zero
761	<code>length</code>	Calculates the length of the vector.
761	<code>squared_length</code>	Calculates the squared length of the vector.

18.21.3 Tvector4_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

18.21.4 Tvector4_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

18.21.5 Tvector4_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single;b: single;c: single;d: single)`

Visibility: default

18.21.6 Tvector4_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([761](#)) if you are able to, as it is faster.

18.21.7 Tvector4_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

Chapter 19

Reference for unit 'mmx'

19.1 Overview

This document describes the MMX unit. This unit allows you to use the MMX capabilities of the Free Pascal compiler. It was written by Florian Klaempfl for the I386 processor. It should work on all platforms that use the Intel processor.

19.2 Constants, types and variables

19.2.1 Constants

```
is_amd_3d_cpu : Boolean = false
```

The `is_amd_3d_cpu` initialized constant allows you to determine if the computer has the AMD 3D extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_dsp_cpu : Boolean = false
```

The `is_amd_3d_dsp_cpu` initialized constant allows you to determine if the computer has the AMD 3D DSP extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_mmx_cpu : Boolean = false
```

The `is_amd_3d_mmx_cpu` initialized constant allows you to determine if the computer has the AMD 3D MMX extensions. It is set correctly in the unit's initialization code.

```
is_mmx_cpu : Boolean = false
```

The `is_mmx_cpu` initialized constant allows you to determine if the computer has MMX extensions. It is set correctly in the unit's initialization code.

```
is_sse2_cpu : Boolean = false
```

The `is_sse2_cpu` initialized constant allows you to determine if the computer has the SSE2 extensions. It is set correctly in the unit's initialization code.

```
is_sse_cpu : Boolean = false
```

The `is_sse_cpu` initialized constant allows you to determine if the computer has the SSE extensions. It is set correctly in the unit's initialization code.

19.2.2 Types

`pmmxbyte = ^tmmxbyte`

Pointer to `tmmxbyte` (763) array type

`pmmxcardinal = ^tmmxcardinal`

Pointer to `tmmxcardinal` (763) array type

`pmmxinteger = ^tmmxinteger`

Pointer to `tmmxinteger` (763) array type

`pmmxlongint = ^tmmxlongint`

Pointer to `tmmxlongint` (763) array type

`pmmxshortint = ^tmmxshortint`

Pointer to `tmmxshortint` (763) array type

`pmmxsingle = ^tmmxsingle`

Pointer to `tmmxsingle` (763) array type

`pmmxword = ^tmmxword`

Pointer to `tmmxword` (763) array type

`tmmxbyte = Array[0..7] of Byte`

Array of bytes, 64 bits in size

`tmmxcardinal = Array[0..1] of cardinal`

Array of cardinals, 64 bits in size

`tmmxinteger = Array[0..3] of Integer`

Array of integers, 64 bits in size

`tmmxlongint = Array[0..1] of LongInt`

Array of longint, 64 bits in size

`tmmxshortint = Array[0..7] of ShortInt`

Array of shortints, 64 bits in size

`tmmxsingle = Array[0..1] of single`

Array of singles, 64 bits in size

`tmmxword = Array[0..3] of Word`

Array of words, 64 bits in size

19.3 Procedures and functions

19.3.1 emms

Synopsis: Reset floating point registers

Declaration: `procedure emms`

Visibility: `default`

Description: `Emms` sets all floating point registers to empty. This procedure must be called after you have used any MMX instructions, if you want to use floating point arithmetic. If you just want to move floating point data around, it isn't necessary to call this function, the compiler doesn't use the FPU registers when moving data. Only when doing calculations, you should use this function. The following code demonstrates this:

```
Program MMXDemo;
uses mmx;
var
  dl : double;
  a : array[0..10000] of double;
  i : longint;
begin
  dl:=1.0;
  {$mmx+}
  { floating point data is used, but we do _no_ arithmetic }
  for i:=0 to 10000 do
    a[i]:=d2; { this is done with 64 bit moves }
  {$mmx-}
  emms; { clear fpu }
  { now we can do floating point arithmetic again }
end.
```

See also: `femms` ([764](#))

19.3.2 femms

Synopsis: Reset floating point registers - AMD version

Declaration: `procedure femms`

Visibility: `default`

Description: `femms` executes the `femms` assembler instruction for AMD processors. it is not supported by all assemblers, hence it is coded as byte codes.

See also: `emms` ([764](#))

Chapter 20

Reference for unit 'Mouse'

20.1 Writing a custom mouse driver

The `mouse` unit has support for adding a custom mouse driver. This can be used to add support for mice not supported by the standard Free Pascal driver, but also to enhance an existing driver for instance to log mouse events or to implement a record and playback function.

The following unit shows how a mouse driver can be enhanced by adding some logging capabilities to the driver.

20.2 Overview

The `Mouse` unit implements a platform independent mouse handling interface. It is implemented identically on all platforms supported by Free Pascal and can be enhanced with custom drivers, should this be needed. It is intended to be used only in text-based screens, for instance in conjunction with the keyboard and video unit. No support for graphical screens is implemented, and there are (currently) no plans to implement this.

20.3 Constants, types and variables

20.3.1 Constants

```
errMouseBase = 1030
```

Base for mouse error codes.

```
errMouseInitError = errMouseBase + 0
```

Mouse initialization error

```
errMouseNotImplemented = errMouseBase + 1
```

Mouse driver not implemented.

```
MouseActionDown = $0001
```

Mouse button down event signal.

```
MouseActionMove = $0004
```

Mouse cursor move event signal.

```
MouseActionUp = $0002
```

Mouse button up event signal.

```
MouseEventBufSize = 16
```

The mouse unit has a mechanism to buffer mouse events. This constant defines the size of the event buffer.

```
MouseLeftButton = $01
```

Left mouse button event.

```
MouseMiddleButton = $04
```

Middle mouse button event.

```
MouseRightButton = $02
```

Right mouse button event.

20.3.2 Types

```
PMouseEvent = ^TMouseEvent
```

Pointer to TMouseEvent ([767](#)) record.

```
TMouseDriver = record
  UseDefaultQueue : Boolean;
  InitDriver : procedure;
  DoneDriver : procedure;
  DetectMouse : function : Byte;
  ShowMouse : procedure;
  HideMouse : procedure;
  GetMouseX : function : Word;
  GetMouseY : function : Word;
  GetMouseButtons : function : Word;
  SetMouseXY : procedure(x: Word;y: Word);
  GetMouseEvent : procedure(var MouseEvent: TMouseEvent);
  PollMouseEvent : function(var MouseEvent: TMouseEvent) : Boolean;
  PutMouseEvent : procedure(const MouseEvent: TMouseEvent);
end
```

The TMouseDriver record is used to implement a mouse driver in the SetMouseDriver ([772](#)) function. Its fields must be filled in before calling the SetMouseDriver ([772](#)) function.

```

TMouseEvent = packed record
  buttons : Word;
  x : Word;
  y : Word;
  Action : Word;
end

```

The `TMouseEvent` is the central type of the mouse unit, it is used to describe all mouse events.

The `Buttons` field describes which buttons were down when the event occurred. The `x`, `y` fields describe where the event occurred on the screen. The `Action` describes what action was going on when the event occurred. The `Buttons` and `Action` field can be examined using the constants defined in the unit interface.

20.3.3 Variables

```
MouseButtons : Byte
```

This variable keeps track of the last known mouse button state. Do not use.

```
MouseIntFlag : Byte
```

This variable keeps track of the last known internal mouse state. Do not use.

```
MouseWhereX : Word
```

This variable keeps track of the last known cursor position. Do not use.

```
MouseWhereY : Word
```

This variable keeps track of the last known cursor position. Do not use.

20.4 Procedures and functions

20.4.1 DetectMouse

Synopsis: Detect the presence of a mouse.

Declaration: `function DetectMouse : Byte`

Visibility: default

Description: `DetectMouse` detects whether a mouse is attached to the system or not. If there is no mouse, then zero is returned. If a mouse is attached, then the number of mouse buttons is returned.

This function should be called after the mouse driver was initialized.

Errors: None.

See also: `InitMouse` ([771](#)), `DoneMouse` ([768](#))

Listing: `./mouseex/ex1.pp`

```

Program Example1;

{ Program to demonstrate the DetectMouse function. }

Uses mouse;

Var
    Buttons : Byte;

begin
    InitMouse;
    Buttons:=DetectMouse;
    If Buttons=0 then
        WriteLn( 'No mouse present.' )
    else
        WriteLn( 'Found mouse with ',Buttons, ' buttons.' );
    DoneMouse;
end.

```

20.4.2 DoneMouse

Synopsis: Deinitialize mouse driver.

Declaration: `procedure DoneMouse`

Visibility: default

Description: `DoneMouse` De-initializes the mouse driver. It cleans up any memory allocated when the mouse was initialized, or removes possible mouse hooks from memory. The mouse functions will not work after `DoneMouse` was called. If `DoneMouse` is called a second time, it will exit at once. `InitMouse` should be called before `DoneMouse` can be called again.

For an example, see most other mouse functions.

Errors: None.

See also: `DetectMouse` ([767](#)), `InitMouse` ([771](#))

20.4.3 GetMouseButtons

Synopsis: Get the state of the mouse buttons

Declaration: `function GetMouseButtons : Word`

Visibility: default

Description: `GetMouseButtons` returns the current button state of the mouse, i.e. it returns a or-ed combination of the following constants:

MouseLeftButton When the left mouse button is held down.

MouseRightButton When the right mouse button is held down.

MouseMiddleButton When the middle mouse button is held down.

Errors: None.

See also: `GetMouseEvent` ([769](#)), `GetMouseX` ([769](#)), `GetMouseY` ([770](#))

Listing: ./mouseex/ex2.pp

Program Example2;

{ Program to demonstrate the GetMouseButtons function. }

Uses mouse;

begin

 InitMouse;

WriteLn('Press right mouse button to exit program');

While (GetMouseButtons<>MouseRightButton) **do** ;

 DoneMouse;

end.

20.4.4 GetMouseDriver

Synopsis: Get a copy of the currently active mouse driver.

Declaration: procedure GetMouseDriver (var Driver: TMouseDriver)

Visibility: default

Description: GetMouseDriver returns the currently set mouse driver. It can be used to retrieve the current mouse driver, and override certain callbacks.

A more detailed explanation about getting and setting mouse drivers can be found in mousedrv (765).

For an example, see the section on writing a custom mouse driver, mousedrv (765)

Errors: None.

See also: SetMouseDriver (772)

20.4.5 GetMouseEvent

Synopsis: Get next mouse event from the queue.

Declaration: procedure GetMouseEvent (var MouseEvent: TMouseEvent)

Visibility: default

Description: GetMouseEvent returns the next mouse event (a movement, button press or button release), and waits for one if none is available in the queue.

Some mouse drivers can implement a mouse event queue which can hold multiple events till they are fetched. Others don't, and in that case, a one-event queue is implemented for use with Poll-MouseEvent (772).

Errors: None.

See also: GetMouseButtons (768), GetMouseX (769), GetMouseY (770)

20.4.6 GetMouseX

Synopsis: Query the current horizontal position of the mouse cursor.

Declaration: function GetMouseX : Word

Visibility: default

Description: `GetMouseX` returns the current X position of the mouse. X is measured in characters, starting at 0 for the left side of the screen.

Errors: None.

See also: `GetMouseButtons` (768), `GetMouseEvent` (769), `GetMouseY` (770)

Listing: `./mouseex/ex4.pp`

Program `Example4`;

{ Program to demonstrate the GetMouseX,GetMouseY functions. }

Uses `mouse`;

Var

`X,Y : Word`;

begin

`InitMouse`;

WriteLn ('Move mouse cursor to square 10,10 to end');

Repeat

`X:=GetMouseX`;

`Y:=GetMouseY`;

WriteLn ('X,Y= (',X,' ',',Y,' '');

Until (`X=9`) **and** (`Y=9`);

`DoneMouse`;

end.

20.4.7 GetMouseY

Synopsis: Query the current vertical position of the mouse cursor.

Declaration: `function GetMouseY : Word`

Visibility: default

Description: `GetMouseY` returns the current Y position of the mouse. Y is measured in characters, starting at 0 for the top of the screen.

For an example, see `GetMouseX` (769)

Errors: None.

See also: `GetMouseButtons` (768), `GetMouseEvent` (769), `GetMouseX` (769)

20.4.8 HideMouse

Synopsis: Hide the mouse cursor.

Declaration: `procedure HideMouse`

Visibility: default

Description: `HideMouse` hides the mouse cursor. This may or may not be implemented on all systems, and depends on the driver.

Errors: None.

See also: ShowMouse ([773](#))

Listing: ./mouseex/ex5.pp

Program Example5;

{ Program to demonstrate the HideMouse function. }

Uses mouse;

Var

Event : TMouseEvent;

Visible : Boolean;

begin

InitMouse;

ShowMouse;

Visible:=True;

WriteIn('Press left mouse button to hide/show, right button quits');

Repeat

GetMouseEvent(Event);

With Event **do**

If (Buttons=MouseLeftbutton) **and**

(Action=MouseActionDown) **then**

begin

If Visible **then**

HideMouse

else

ShowMouse;

Visible:=**Not** Visible;

end;

Until (Event.Buttons=MouseRightButton) **and**

(Event.Action=MouseActionDown);

DoneMouse;

end.

20.4.9 InitMouse

Synopsis: Initialize the FPC mouse driver.

Declaration: procedure InitMouse

Visibility: default

Description: InitMouse Initializes the mouse driver. This will allocate any data structures needed for the mouse to function. All mouse functions can be used after a call to InitMouse.

A call to InitMouse must always be followed by a call to DoneMouse ([768](#)) at program exit. Failing to do so may leave the mouse in an unusable state, or may result in memory leaks.

For an example, see most other functions.

Errors: None.

See also: DoneMouse ([768](#)), DetectMouse ([767](#))

20.4.10 PollMouseEvent

Synopsis: Query next mouse event. Do not wait if none available.

Declaration: `function PollMouseEvent (var MouseEvent: TMouseEvent) : Boolean`

Visibility: default

Description: `PollMouseEvent` checks whether a mouse event is available, and returns it in `MouseEvent` if one is found. The function result is `True` in that case. If no mouse event is pending, the function result is `False`, and the contents of `MouseEvent` is undefined.

Note that after a call to `PollMouseEvent`, the event should still be removed from the mouse event queue with a call to `GetMouseEvent`.

Errors: None.

See also: `GetMouseEvent` (769), `PutMouseEvent` (772)

20.4.11 PutMouseEvent

Synopsis: Put a mouse event in the event queue.

Declaration: `procedure PutMouseEvent (const MouseEvent: TMouseEvent)`

Visibility: default

Description: `PutMouseEvent` adds `MouseEvent` to the input queue. The next call to `GetMouseEvent` (769) or `PollMouseEvent` will then return `MouseEvent`.

Please note that depending on the implementation the mouse event queue can hold only one value.

Errors: None.

See also: `GetMouseEvent` (769), `PollMouseEvent` (772)

20.4.12 SetMouseDriver

Synopsis: Set a new mouse driver.

Declaration: `procedure SetMouseDriver (const Driver: TMouseDriver)`

Visibility: default

Description: `SetMouseDriver` sets the mouse driver to `Driver`. This function should be called before `InitMouse` (771) is called, or after `DoneMouse` is called. If it is called after the mouse has been initialized, it does nothing.

For more information on setting the mouse driver, `mousedrv` (765).

For an example, see `mousedrv` (765)

Errors:

See also: `InitMouse` (771), `DoneMouse` (768), `GetMouseDriver` (769)

20.4.13 SetMouseXY

Synopsis: Set the mouse cursor position.

Declaration: `procedure SetMouseXY(x: Word; y: Word)`

Visibility: default

Description: `SetMouseXY` places the mouse cursor on X, Y. X and Y are zero based character coordinates: 0, 0 is the top-left corner of the screen, and the position is in character cells (i.e. not in pixels).

Errors: None.

See also: `GetMouseX` ([769](#)), `GetMouseY` ([770](#))

Listing: `./mouseex/ex7.pp`

Program `Example7;`

{ Program to demonstrate the SetMouseXY function. }

Uses `mouse;`

begin

`InitMouse;`

`WriteLn('Click right mouse button to quit.');`

`SetMouseXY(40,12);`

Repeat

`WriteLn(GetMouseX, ' ', GetMouseY);`

If `(GetMouseX>70) then`

`SetMouseXY(10,GetMouseY);`

If `(GetMouseY>20) then`

`SetMouseXY(GetMouseX, 5);`

Until `(GetMouseButtons=MouseRightButton);`

`DoneMouse;`

end.

20.4.14 ShowMouse

Synopsis: Show the mouse cursor.

Declaration: `procedure ShowMouse`

Visibility: default

Description: `ShowMouse` shows the mouse cursor if it was previously hidden. The capability to hide or show the mouse cursor depends on the driver.

For an example, see `HideMouse` ([770](#))

Errors: None.

See also: `HideMouse` ([770](#))

Chapter 21

Reference for unit 'Objects'

21.1 Overview

This document documents the `objects` unit. The unit was implemented by many people, and was mainly taken from the FreeVision sources. It has been ported to all supported platforms.

The methods and fields that are in a `Private` part of an object declaration have been left out of this documentation.

21.2 Constants, types and variables

21.2.1 Constants

`coIndexError = -1`

Collection list error: Index out of range

`coOverflow = -2`

Collection list error: Overflow

`DefaultTPCompatible : Boolean = false`

`DefaultTPCompatible` is used to initialize `tstream.tpcompatible` (??).

`MaxBytes = 128 * 1024 * 128`

Maximum data size (in bytes)

`MaxCollectionSize = MaxBytes div SizeOf (Pointer)`

Maximum collection size (in items)

`MaxPtrs = MaxBytes div SizeOf (Pointer)`

Maximum data size (in pointers)

MaxReadBytes = \$7fffffff

Maximum data that can be read from a stream (not used)

MaxTPCompatibleCollectionSize = 65520 div 4

Maximum collection size (in items, same value as in TP)

MaxWords = MaxBytes div SizeOf (Word)

Maximum data size (in words)

RCollection : TStreamRec = (ObjType:50;VmtLink:Ofs (TypeOf (TCollection) ^) ;Load

Default stream record for the TCollection (791) object.

RStrCollection : TStreamRec = (ObjType:69;VmtLink:Ofs (TypeOf (TStrCollection) ^

Default stream record for the TStrCollection (830) object.

RStringCollection : TStreamRec = (ObjType:51;VmtLink:Ofs (TypeOf (TStringCollection

Default stream record for the TStringCollection (840) object.

RStringList : TStreamRec = (ObjType:52;VmtLink:Ofs (TypeOf (TStringList) ^) ;Load

Default stream record for the TStringList (842) object.

RStrListMaker : TStreamRec = (ObjType:52;VmtLink:Ofs (TypeOf (TStrListMaker) ^)

Default stream record for the TStrListMaker (844) object.

stCreate = \$3C00

Stream initialization mode: Create new file

stError = -1

Stream error codes: Access error

stGetError = -5

Stream error codes: Get object error

stInitError = -2

Stream error codes: Initialize error

stOk = 0

Stream error codes: No error

`stOpen = $3D02`

Stream initialization mode: Read/write access

`stOpenError = -8`

Stream error codes: Error opening stream

`stOpenRead = $3D00`

Stream initialization mode: Read access only

`stOpenWrite = $3D01`

Stream initialization mode: Write access only

`stPutError = -6`

Stream error codes: Put object error

`stReadError = -3`

Stream error codes: Stream read error

`StreamError : Pointer = nil`

Pointer to default stream error handler.

`stSeekError = -7`

Stream error codes: Seek error in stream

`stWriteError = -4`

Stream error codes: Stream write error

`vmtHeaderSize = 8`

Size of the VMT header in an object (not used).

21.2.2 Types

`AsciiZ = Array[0..255] of Char`

Filename - null terminated array of characters.

`FNameStr = String`

Filename - shortstring version.

```
LongRec = packed record
  Hi : Word;
  Lo : Word;
end
```

Record describing a longint (in Words)

```
PBufStream = ^TBufStream
```

Pointer to TBufStream (787) object.

```
PByteArray = ^TByteArray
```

Pointer to TByteArray (779)

```
PCharSet = ^TCharSet
```

Pointer to TCharSet (779).

```
PCollection = ^TCollection
```

Pointer to TCollection (791) object.

```
PDosStream = ^TDosStream
```

Pointer to TDosStream (805) object.

```
PItemList = ^TItemList
```

Pointer to TItemList (779) object.

```
PMemoryStream = ^TMemoryStream
```

Pointer to TMemoryStream (810) object.

```
PObject = ^TObject
```

Pointer to TObject (812) object.

```
PPoint = ^TPoint
```

Pointer to TPoint (814) record.

```
PPointerArray = ^TPointerArray
```

Pointer to TPointerArray (779)

```
PRect = ^TRect
```

Pointer to TRect (814) object.

`PResourceCollection = ^TResourceCollection`

Pointer to `TResourceCollection` (820) object.

`PResourceFile = ^TResourceFile`

Pointer to `TResourceFile` (821) object.

`PSortedCollection = ^TSortedCollection`

Pointer to `TSortedCollection` (824) object.

`PStrCollection = ^TStrCollection`

Pointer to `TStrCollection` (830) object.

`PStream = ^TStream`

Pointer type to `TStream` (832)

`PStreamRec = ^TStreamRec`

Pointer to `TStreamRec` (779)

`PStrIndex = ^TStrIndex`

Pointer to `TStrIndex` (779) array.

`PString = PShortString`

Pointer to a shortstring.

`PStringCollection = ^TStringCollection`

Pointer to `TStringCollection` (840) object.

`PStringList = ^TStringList`

Pointer to `TStringList` (842) object.

`PStrListMaker = ^TStrListMaker`

Pointer to `TStrListMaker` (844) object.

```
PTrRec = packed record
  Ofs : Word;
  Seg : Word;
end
```

Record describing a pointer to a memory location.

PUnSortedStrCollection = ^TUnSortedStrCollection

Pointer to TUnsortedStrCollection (845) object.

PWordArray = ^TWordArray

Pointer to TWordArray (780)

Sw_Integer = LongInt

Alias for longint

Sw_Word = Cardinal

Alias for Cardinal

TByteArray = Array[0..MaxBytes-1] of Byte

Array with maximum allowed number of bytes.

TCharSet = Set of Char

Generic set of characters type.

TItemList = Array[0..MaxCollectionSize-1] of Pointer

Pointer array type used in a TCollection (791)

TPointerArray = Array[0..MaxPtrs-1] of Pointer

Array with maximum allowed number of pointers

```
TStreamRec = packed record
  ObjType : Sw_Word;
  VmtLink : pointer;
  Load : Pointer;
  Store : Pointer;
  Next : PStreamRec;
end
```

TStreamRec is used by the **Objects** unit streaming mechanism: when an object is registered, a TStreamRec record is added to a list of records. This list is used when objects need to be streamed from/streamed to a stream. It contains all the information needed to stream the object.

TStrIndex = Array[0..9999] of TStrIndexRec

Pointer array type used in a TStringList (842)


```
TStrIndexRec = packed record
  Key : Sw_Word;
  Count : Word;
  Offset : Word;
end
```

Record type used in a TStringList (842) to store the strings

```
TWordArray = Array[0..MaxWords-1] of Word
```

Array with maximum allowed number of words.

```
WordRec = packed record
  Hi : Byte;
  Lo : Byte;
end
```

Record describing a Word (in bytes)

21.2.3 Variables

```
invalidhandle : THandle
```

Value for invalid handle. Initial value for file stream handles or when the stream is closed.

21.3 Procedures and functions

21.3.1 Abstract

Synopsis: Abstract error handler.

Declaration: `procedure Abstract`

Visibility: default

Description: When implementing abstract methods, do not declare them as `abstract`. Instead, define them simply as `virtual`. In the implementation of such abstract methods, call the `Abstract` procedure. This allows explicit control of what happens when an abstract method is called.

The current implementation of `Abstract` terminates the program with a run-time error 211.

Errors: None.

21.3.2 CallPointerConstructor

Synopsis: Call a constructor with a pointer argument.

Declaration: `function CallPointerConstructor(Ctor: pointer; Obj: pointer; VMT: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. `Param1` is passed to the constructor. The return value is a pointer to the instance.

Note that this can only be used on constructors that require a pointer as the sole argument. It can also be used to call a constructor with a single argument by reference.

Errors: If the constructor expects other arguments than a pointer, the stack may be corrupted.

See also: `CallVoidConstructor` (782), `CallPointerMethod` (781), `CallVoidLocal` (782), `CallPointerLocal` (781), `CallVoidMethodLocal` (783), `CallPointerMethodLocal` (781)

21.3.3 CallPointerLocal

Synopsis: Call a local nested function with a pointer argument

Declaration: `function CallPointerLocal(Func: pointer;Frame: Pointer;Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (781), `CallVoidMethod` (782), `CallVoidLocal` (782), `CallVoidMethodLocal` (783), `CallPointerMethodLocal` (781), `CallVoidConstructor` (782), `CallPointerConstructor` (780)

21.3.4 CallPointerMethod

Synopsis: Call a method with a single pointer argument

Declaration: `function CallPointerMethod(Method: pointer;Obj: pointer;Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethod` calls the method with address `Method` for instance `Obj`. It passes `Param1` to the method as the single argument. It returns a pointer to the instance.

Errors: If the method expects other parameters than a single pointer, the stack may become corrupted.

See also: `CallVoidMethod` (782), `CallVoidLocal` (782), `CallPointerLocal` (781), `CallVoidMethodLocal` (783), `CallPointerMethodLocal` (781), `CallVoidConstructor` (782), `CallPointerConstructor` (780)

21.3.5 CallPointerMethodLocal

Synopsis: Call a local procedure of a method with a pointer argument

Declaration: `function CallPointerMethodLocal(Func: pointer;Frame: Pointer;Obj: pointer;Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: [CallPointerMethod \(781\)](#), [CallVoidMethod \(782\)](#), [CallPointerLocal \(781\)](#), [CallVoidLocal \(782\)](#), [CallVoidMethodLocal \(783\)](#), [CallVoidConstructor \(782\)](#), [CallPointerConstructor \(780\)](#)

21.3.6 CallVoidConstructor

Synopsis: Call a constructor with no arguments

Declaration: `function CallVoidConstructor (Ctor: pointer; Obj: pointer; VMT: pointer)
: pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. The return value is a pointer to the instance.

Note that this can only be used on constructors that require no arguments.

Errors: If the constructor expects arguments, the stack may be corrupted.

See also: [CallPointerConstructor \(780\)](#), [CallPointerMethod \(781\)](#), [CallVoidLocal \(782\)](#), [CallPointerLocal \(781\)](#), [CallVoidMethodLocal \(783\)](#), [CallPointerMethodLocal \(781\)](#)

21.3.7 CallVoidLocal

Synopsis: Call a local nested procedure.

Declaration: `function CallVoidLocal (Func: pointer; Frame: Pointer) : pointer`

Visibility: default

Description: `CallVoidLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: [CallPointerMethod \(781\)](#), [CallVoidMethod \(782\)](#), [CallPointerLocal \(781\)](#), [CallVoidMethodLocal \(783\)](#), [CallPointerMethodLocal \(781\)](#), [CallVoidConstructor \(782\)](#), [CallPointerConstructor \(780\)](#)

21.3.8 CallVoidMethod

Synopsis: Call an object method

Declaration: `function CallVoidMethod (Method: pointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethod` calls the method with address `Method` for instance `Obj`. It returns a pointer to the instance.

Errors: If the method expects parameters, the stack may become corrupted.

See also: [CallPointerMethod \(781\)](#), [CallVoidLocal \(782\)](#), [CallPointerLocal \(781\)](#), [CallVoidMethodLocal \(783\)](#), [CallPointerMethodLocal \(781\)](#), [CallVoidConstructor \(782\)](#), [CallPointerConstructor \(780\)](#)

21.3.9 CallVoidMethodLocal

Synopsis: Call a local procedure of a method

Declaration: `function CallVoidMethodLocal(Func: pointer;Frame: Pointer;Obj: pointer)
: pointer`

Visibility: default

Description: `CallVoidMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` (781), `CallVoidMethod` (782), `CallPointerLocal` (781), `CallVoidLocal` (782), `CallPointerMethodLocal` (781), `CallVoidConstructor` (782), `CallPointerConstructor` (780)

21.3.10 DisposeStr

Synopsis: Dispose of a shortstring which was allocated on the heap.

Declaration: `procedure DisposeStr(P: PString)`

Visibility: default

Description: `DisposeStr` removes a dynamically allocated string from the heap.

For an example, see `NewStr` (784).

Errors: None.

See also: `NewStr` (784), `SetStr` (786)

21.3.11 LongDiv

Synopsis: Overflow safe divide

Declaration: `function LongDiv(X: LongInt;Y: Integer) : Integer`

Visibility: default

Description: `LongDiv` divides `X` by `Y`. The result is of type `Integer` instead of type `Longint`, as you would get normally.

Errors: If `Y` is zero, a run-time error will be generated.

See also: `LongMul` (783)

21.3.12 LongMul

Synopsis: Overflow safe multiply.

Declaration: `function LongMul(X: Integer;Y: Integer) : LongInt`

Visibility: default

Description: `LongMul` multiplies `X` with `Y`. The result is of type `Longint`. This avoids possible overflow errors you would normally get when multiplying `X` and `Y` that are too big.

Errors: None.

See also: `LongDiv` (783)

21.3.13 NewStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `function NewStr(const S: String) : PString`

Visibility: default

Description: `NewStr` makes a copy of the string `S` on the heap, and returns a pointer to this copy. If the string is empty then `Nil` is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: `DisposeStr` ([783](#)), `SetStr` ([786](#))

Listing: `./objectex/ex40.pp`

```

Program ex40;

{ Program to demonstrate the NewStr function }

Uses Objects;

Var S : String;
    P : PString;

begin
  S := 'Some really cute string';
  P := NewStr(S);
  If P^ <> S then
    WriteLn ('Oh-oh... Something is wrong !!');
  DisposeStr(P);
end.

```

21.3.14 RegisterObjects

Synopsis: Register standard objects.

Declaration: `procedure RegisterObjects`

Visibility: default

Description: `RegisterObjects` registers the following objects for streaming:

1. `TCollection`, see `TCollection` ([791](#)).
2. `TStringCollection`, see `TStringCollection` ([840](#)).
3. `TStrCollection`, see `TStrCollection` ([830](#)).

Errors: None.

See also: `RegisterType` ([785](#))

21.3.15 RegisterType

Synopsis: Register new object for streaming.

Declaration: `procedure RegisterType (var S: TStreamRec)`

Visibility: default

Description: `RegisterType` registers a new type for streaming. An object cannot be streamed unless it has been registered first. The stream record `S` needs to have the following fields set:

ObjType: Sw_Word This should be a unique identifier. Each possible type should have it's own identifier.

VmtLink: pointer This should contain a pointer to the VMT (Virtual Method Table) of the object you try to register.

Load : Pointer is a pointer to a method that initializes an instance of that object, and reads the initial values from a stream. This method should accept as it's sole argument a `PStream` type variable.

Store: Pointer is a pointer to a method that stores an instance of the object to a stream. This method should accept as it's sole argument a `PStream` type variable.

The VMT of the object can be retrieved with the following expression:

```
VmtLink: Ofs (TypeOf (MyType) ^);
```

Errors: In case of error (if a object with the same `ObjType`) is already registered), run-time error 212 occurs.

Listing: `./objectex/myobject.pp`

```
Unit MyObject;
```

Interface

```
Uses Objects;
```

Type

```
PMyObject = ^TMyObject;
TMyObject = Object (TObject)
  Field : Longint;
  Constructor Init;
  Constructor Load (Var Stream : TStream);
  Destructor Done;
  Procedure Store (Var Stream : TStream);
  Function GetField : Longint;
  Procedure SetField (Value : Longint);
end;
```

Implementation

```
Constructor TMyobject.Init;

begin
  Inherited Init;
  Field := -1;
end;
```

```

Constructor TMyobject.Load ( Var Stream : TStream);

begin
    Stream.Read( Field , Sizeof( Field ));
end;

Destructor TMyObject.Done;

begin
end;

Function TMyObject.GetField : Longint;

begin
    GetField:= Field;
end;

Procedure TMyObject.SetField ( Value : Longint);

begin
    Field:= Value;
end;

Procedure TMyObject.Store ( Var Stream : TStream);

begin
    Stream.Write( Field , SizeOf( Field ));
end;

Const MyObjectRec : TStreamRec = (
    Objtype : 666;
    vmtlink : Ofs( TypeOf( TMyObject ) ^ );
    Load : @TMyObject.Load;
    Store : @TMyObject.Store;
    );

begin
    RegisterObjects;
    RegisterType ( MyObjectRec );
end.

```

21.3.16 SetStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `procedure SetStr(var p: PString; const s: String)`

Visibility: default

Description: `SetStr` makes a copy of the string `S` on the heap and returns the pointer to this copy in `P`. If `P` pointed to another string (i.e. was not `Nil`, the memory is released first. Contrary to `NewStr` (784), if the string is empty then a pointer to an empty string is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: `DisposeStr` ([783](#)), `NewStr` ([784](#))

21.4 TBufStream

21.4.1 Description

`TBufStream` implements a buffered file stream. That is, all data written to the stream is written to memory first. Only when the buffer is full, or on explicit request, the data is written to disk.

Also, when reading from the stream, first the buffer is checked if there is any unread data in it. If so, this is read first. If not the buffer is filled again, and then the data is read from the buffer.

The size of the buffer is fixed and is set when constructing the file.

This is useful if you need heavy throughput for your stream, because it speeds up operations.

21.4.2 Method overview

Page	Property	Description
788	<code>Close</code>	Flush data and Close the file.
788	<code>Done</code>	Close the file and cleans up the instance.
788	<code>Flush</code>	FLush data from buffer, and write it to stream.
787	<code>Init</code>	Initialize an instance of <code>TBufStream</code> and open the file.
790	<code>Open</code>	Open the file if it is closed.
790	<code>Read</code>	Read data from the file to a buffer in memory.
789	<code>Seek</code>	Set current position in file.
789	<code>Truncate</code>	Flush buffer, and truncate the file at current position.
790	<code>Write</code>	Write data to the file from a buffer in memory.

21.4.3 TBufStream.Init

Synopsis: Initialize an instance of `TBufStream` and open the file.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word; Size: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TBufStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

`stCreate` Creates a new file.

`stOpenRead` Read access only.

`stOpenWrite` Write access only.

`stOpenRead` and write access.

The `Size` parameter determines the size of the buffer that will be created. It should be different from zero.

For an example see `TBufStream.Flush` ([788](#)).

Errors: On error, `Status` is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Init` ([806](#)), `TBufStream.Done` ([788](#))

21.4.4 TBufStream.Done

Synopsis: Close the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` flushes and closes the file if it was open and cleans up the instance of `TBufStream`.

For an example see `TBufStream.Flush` (788).

Errors: None.

See also: `TDosStream.Done` (806), `TBufStream.Init` (787), `TBufStream.Close` (788)

21.4.5 TBufStream.Close

Synopsis: Flush data and Close the file.

Declaration: `procedure Close; Virtual`

Visibility: `default`

Description: `Close` flushes and closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (788) it does not clean up the instance of `TBufStream`

For an example see `TBufStream.Flush` (788).

Errors: None.

See also: `TStream.Close` (836), `TBufStream.Init` (787), `TBufStream.Done` (788)

21.4.6 TBufStream.Flush

Synopsis: FLush data from buffer, and write it to stream.

Declaration: `procedure Flush; Virtual`

Visibility: `default`

Description: When the stream is in write mode, the contents of the buffer are written to disk, and the buffer position is set to zero. When the stream is in read mode, the buffer position is set to zero.

Errors: Write errors may occur if the file was in write mode. see `Write` (790) for more info on the errors.

See also: `TStream.Close` (836), `TBufStream.Init` (787), `TBufStream.Done` (788)

Listing: `./objectex/ex15.pp`

Program `ex15;`

{ Program to demonstrate the TStream.Flush method }

Uses `Objects;`

Var `L : String;`

`P : PString;`

`S : PBufStream; { Only one with Flush implemented. }`

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PBufStream, Init('test.dat', stcreate, 100));
WriteIn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
{ At this moment, there is no data on disk yet. }
S^.Flush;
{ Now there is. }
S^.WriteStr(@L);
{ Close calls flush first }
S^.Close;
WriteIn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteIn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);
end.

```

21.4.7 TBufStream.Truncate

Synopsis: Flush buffer, and truncate the file at current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: If the status of the stream is `stOK`, then `Truncate` tries to flush the buffer, and then truncates the stream size to the current file position.

For an example, see `TDosStream.Truncate` (807).

Errors: Errors can be those of `Flush` (788) or `TDosStream.Truncate` (807).

See also: `TStream.Truncate` (837), `TDosStream.Truncate` (807), `TStream.GetSize` (834)

21.4.8 TBufStream.Seek

Synopsis: Set current position in file.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

For an example, see `TStream.Seek` (838);

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` (838), `TStream.GetPos` (834)

21.4.9 TBufStream.Open

Synopsis: Open the file if it is closed.

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (788) call.

For an example, see `TDosStream.Open` (809).

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (836), `TBufStream.Close` (788)

21.4.10 TBufStream.Read

Synopsis: Read data from the file to a buffer in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

`Read` will first try to read the data from the stream's internal buffer. If insufficient data is available, the buffer will be filled before continuing to read. This process is repeated until all needed data has been read.

For an example, see `TStream.Read` (839).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (839), `TBufStream.Write` (790)

21.4.11 TBufStream.Write

Synopsis: Write data to the file from a buffer in memory.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

`Write` will first try to write the data to the stream's internal buffer. When the internal buffer is full, then the contents will be written to disk. This process is repeated until all data has been written.

For an example, see `TStream.Read` (839).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` (839), `TBufStream.Read` (790)

21.5 TCollection

21.5.1 Description

The `TCollection` object manages a collection of pointers or objects. It also provides a series of methods to manipulate these pointers or objects.

Whether or not objects are used depends on the kind of calls you use. All kinds come in 2 flavors, one for objects, one for pointers.

21.5.2 Method overview

Page	Property	Description
793	<code>At</code>	Return the item at a certain index.
801	<code>AtDelete</code>	Delete item at certain position.
800	<code>AtFree</code>	Free an item at the indicates position, calling it's destructor.
804	<code>AtInsert</code>	Insert an element at a certain position in the collection.
804	<code>AtPut</code>	Set collection item, overwriting an existing value.
800	<code>Delete</code>	Delete an item from the collection, but does not destroy it.
798	<code>DeleteAll</code>	Delete all elements from the collection. Objects are not destroyed.
792	<code>Done</code>	Clean up collection, release all memory.
803	<code>Error</code>	Set error code.
795	<code>FirstThat</code>	Return first item which matches a test.
802	<code>ForEach</code>	Execute procedure for each item in the list.
799	<code>Free</code>	Free item from collection, calling it's destructor.
797	<code>FreeAll</code>	Release all objects from the collection.
801	<code>FreeItem</code>	Destroy a non-nil item.
794	<code>GetItem</code>	Read one item off the stream.
793	<code>IndexOf</code>	Find the position of a certain item.
791	<code>Init</code>	Instantiate a new collection.
799	<code>Insert</code>	Insert a new item in the collection at the end.
795	<code>LastThat</code>	Return last item which matches a test.
792	<code>Load</code>	Initialize a new collection and load collection from a stream.
796	<code>Pack</code>	Remove all <code>>Nil</code> pointers from the collection.
805	<code>PutItem</code>	Put one item on the stream
803	<code>SetLimit</code>	Set maximum number of elements in the collection.
805	<code>Store</code>	Write collection to a stream.

21.5.3 TCollection.Init

Synopsis: Instantiate a new collection.

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` initializes a new instance of a collection. It sets the (initial) maximum number of items in the collection to `ALimit`. `ADelta` is the increase size : The number of memory places that will be allocated in case `ALimit` is reached, and another element is added to the collection.

For an example, see `TCollection.ForEach` ([802](#)).

Errors: None.

See also: `TCollection.Load` ([792](#)), `TCollection.Done` ([792](#))

21.5.4 TCollection.Load

Synopsis: Initialize a new collection and load collection from a stream.

Declaration: constructor Load(var S: TStream)

Visibility: default

Description: Load initializes a new instance of a collection. It reads from stream S the item count, the item limit count, and the increase size. After that, it reads the specified number of items from the stream.

Errors: Errors returned can be those of GetItem (794).

See also: TCollection.Init (791), TCollection.GetItem (794), TCollection.Done (792)

Listing: ./objectex/ex22.pp

Program ex22;

{ Program to demonstrate the TCollection.Load method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M : PMyObject;
 I : Longint;
 S : PMemoryStream;

begin

 C:=**New**(PCollection, Init(100,10));

For I:=1 **to** 100 **do**

begin

 M:=**New**(PMyObject, Init);

 M^.SetField(100-I);

 C^.Insert(M);

end;

WriteLn ('Inserted ', C^.Count, ' objects');

 S:=**New**(PMemoryStream, Init(1000,10));

 C^.Store(S^);

 C^.FreeAll;

Dispose(C, Done);

 S^.Seek(0);

 C^.Load(S^);

WriteLn ('Read ', C^.Count, ' objects from stream.');

Dispose(S, Done);

Dispose(C, Done);

end.

21.5.5 TCollection.Done

Synopsis: Clean up collection, release all memory.

Declaration: destructor Done; Virtual

Visibility: default

Description: Done frees all objects in the collection, and then releases all memory occupied by the instance.

For an example, see TCollection.ForEach (802).

Errors: None.

See also: `TCollection.Init` ([791](#)), `TCollection.FreeAll` ([797](#))

21.5.6 TCollection.At

Synopsis: Return the item at a certain index.

Declaration: `function At(Index: Sw_Integer) : Pointer`

Visibility: default

Description: `At` returns the item at position `Index`.

Errors: If `Index` is less than zero or larger than the number of items in the collection, `seep1{Error}{TCollection.Error}` is called with `coIndexError` and `Index` as arguments, resulting in a run-time error.

See also: `TCollection.Insert` ([799](#))

Listing: `./objectex/ex23.pp`

Program `ex23`;

{ Program to demonstrate the TCollection.At method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin
 `C:=New(PCollection, Init(100,10));`
 For `I:=1 to 100 do`
 begin
 `M:=New(PMyObject, Init);`
 `M^.SetField(100-I);`
 `C^.Insert(M);`
 end;
 For `I:=0 to C^.Count-1 do`
 begin
 `M:=C^.At(I);`
 `Writeln('Object ',i,' has field : ',M^.GetField);`
 end;
 `C^.FreeAll;`
 `Dispose(C, Done);`
end.

21.5.7 TCollection.IndexOf

Synopsis: Find the position of a certain item.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. If `Item` isn't present in the collection, -1 is returned.

Errors: If the item is not present, -1 is returned.

See also: `TCollection.At` (793), `TCollection.GetItem` (794), `TCollection.Insert` (799)

Listing: ./objectex/ex24.pp

Program ex24;

{ Program to demonstrate the TCollection.IndexOf method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M, Keep : PMyObject;
 I : Longint;

begin

Randomize;

 C:=**New**(PCollection, Init(100,10));

 Keep:=**Nil**;

For I:=1 **to** 100 **do**

begin

 M:=**New**(PMyObject, Init);

 M^.SetField(I-1);

If Random<0.1 **then**

 Keep:=M;

 C^.Insert(M);

end;

If Keep=**Nil** **then**

begin

Writeln ('Please run again. No object selected');

Halt (1);

end;

Writeln ('Selected object has field : ', Keep^.GetField);

Write ('Selected object has index : ', C^.IndexOf(Keep));

Writeln (' should match it's field.');

 C^.FreeAll;

Dispose(C, Done);

end.

21.5.8 TCollection.GetItem

Synopsis: Read one item off the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a single item off the stream S, and returns a pointer to this item. This method is used internally by the `Load` method, and should not be used directly.

Errors: Possible errors are the ones from `TStream.Get` (832).

See also: `TStream.Get` (832), `TCollection.Store` (805)

21.5.9 TCollection.LastThat

Synopsis: Return last item which matches a test.

Declaration: `function LastThat (Test: Pointer) : Pointer`

Visibility: default

Description: This function returns the last item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.FirstThat` ([795](#))

Listing: ./objectex/ex25.pp

Program ex21;

{ Program to demonstrate the TCollection.Foreach method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M : PMyObject;
 I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin
 If P^.GetField < 56 **then**
 CheckField := 1
 else
 CheckField := 0;
end;

begin
 C := **New**(PCollection, Init(100, 10));
 For I := 1 **to** 100 **do**
 begin
 M := **New**(PMyObject, Init);
 M^.SetField(I);
 C^.Insert(M);
 end;
 WriteLn ('Inserted ', C^.Count, ' objects');
 WriteLn ('Last one for which Field < 56 has index (should be 54) : ',
 C^.IndexOf(C^.LastThat(@CheckField)));
 C^.FreeAll;
 Dispose(C, Done);
end.

21.5.10 TCollection.FirstThat

Synopsis: Return first item which matches a test.

Declaration: `function FirstThat (Test: Pointer) : Pointer`

Visibility: default

Description: This function returns the first item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.LastThat` ([795](#))

Listing: `./objectex/ex26.pp`

Program `ex21`;

{ Program to demonstrate the TCollection.FirstThat method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

Function `CheckField` (`Dummy`: `Pointer`; `P` : `PMMyObject`) : `Longint`;

begin
 If `P^.GetField > 56` **then**
 `Checkfield := 1`
 else
 `CheckField := 0`;
end;

begin
 `C := New(PCollection, Init(100, 10));`
 For `I := 1` **to** `100` **do**
 begin
 `M := New(PMyObject, Init);`
 `M^.SetField(I);`
 `C^.Insert(M);`
 end;
 Writeln ('Inserted ', `C^.Count`, ' objects');
 Writeln ('first one for which Field > 56 has index (should be 56) : ',
 `C^.IndexOf(C^.FirstThat(@CheckField))`);
 `C^.FreeAll`;
 Dispose(`C`, `Done`);
end.

21.5.11 TCollection.Pack

Synopsis: Remove all `>Nil` pointers from the collection.

Declaration: `procedure Pack`

Visibility: `default`

Description: `Pack` removes all `Nil` pointers from the collection, and adjusts `Count` to reflect this change. No memory is freed as a result of this call. In order to free any memory, you can call `SetLimit` with an argument of `Count` after a call to `Pack`.

Errors: None.

See also: `TCollection.SetLimit` ([803](#))

Listing: ./objectex/ex26.pp

Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M : PMyObject;
 I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin

If P^.GetField > 56 **then**
 Checkfield := 1

else
 CheckField := 0;

end;

begin

 C := **New**(PCollection, Init(100, 10));

For I := 1 **to** 100 **do**

begin

 M := **New**(PMyObject, Init);

 M^.SetField(I);

 C^.Insert(M);

end;

WriteLn ('Inserted ', C^.Count, ' objects');

WriteLn ('first one for which Field > 56 has index (should be 56) : ',
 C^.IndexOf(C^.FirstThat(@CheckField)));

 C^.FreeAll;

Dispose(C, Done);

end.

21.5.12 TCollection.FreeAll

Synopsis: Release all objects from the collection.

Declaration: `procedure FreeAll`

Visibility: default

Description: `FreeAll` calls the destructor of each object in the collection. It doesn't release any memory occupied by the collection itself, but it does set `Count` to zero.

Errors:

See also: `TCollection.DeleteAll` ([798](#)), `TCollection.FreeItem` ([801](#))

Listing: ./objectex/ex28.pp

Program ex28;

{ Program to demonstrate the TCollection.FreeAll method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteIn ('Added 100 Items. ');
  C^.FreeAll;
  WriteIn ('Freed all objects. ');
  Dispose(C, Done);
end.

```

21.5.13 TCollection.DeleteAll

Synopsis: Delete all elements from the collection. Objects are not destroyed.

Declaration: `procedure DeleteAll`

Visibility: default

Description: `DeleteAll` deletes all elements from the collection. It just sets the `Count` variable to zero. Contrary to `FreeAll` (797), `DeleteAll` doesn't call the destructor of the objects.

Errors: None.

See also: `TCollection.FreeAll` (797), `TCollection.Delete` (800)

Listing: `./objectex/ex29.pp`

Program `ex29`;

```

{
  Program to demonstrate the TCollection.DeleteAll method
  Compare with example 28, where FreeAll is used.
}

```

Uses `Objects, MyObject; { For TMyObject definition and registration }`

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteIn ('Added 100 Items. ');
  C^.FreeAll;
  WriteIn ('Freed all objects. ');
  Dispose(C, Done);
end.

```

```

    end;
    Writeln ( 'Added 100 Items. ');
    C^.DeleteAll;
    Writeln ( 'Deleted all objects. ');
    Dispose(C,Done);
end.

```

21.5.14 TCollection.Free

Synopsis: Free item from collection, calling it's destructor.

Declaration: `procedure Free(Item: Pointer)`

Visibility: default

Description: `Free` Deletes `Item` from the collection, and calls the destructor `Done` of the object.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.FreeItem` ([801](#))

Listing: `./objectex/ex30.pp`

```

Program ex30;

{ Program to demonstrate the TCollection.Free method }

Uses Objects,MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;

begin
    Randomize;
    C:=New(PCollection, Init(120,10));
    For I:=1 to 100 do
        begin
            M:=New(PMyObject, Init);
            M^.SetField(I-1);
            C^.Insert(M);
        end;
    Writeln ( 'Added 100 Items. ');
    With C^ do
        While Count>0 do Free(At(Count-1));
    Writeln ( 'Freed all objects. ');
    Dispose(C,Done);
end.

```

21.5.15 TCollection.Insert

Synopsis: Insert a new item in the collection at the end.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts `Item` in the collection. `TCollection` inserts this item at the end, but descendent objects may insert it at another place.

Errors: None.

See also: `TCollection.AtInsert` (804), `TCollection.AtPut` (804)

21.5.16 TCollection.Delete

Synopsis: Delete an item from the collection, but does not destroy it.

Declaration: `procedure Delete(Item: Pointer)`

Visibility: default

Description: `Delete` deletes `Item` from the collection. It doesn't call the item's destructor, though. For this the `Free` (799) call is provided.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.AtDelete` (801), `TCollection.Free` (799)

Listing: `./objectex/ex31.pp`

```

Program ex31;

{ Program to demonstrate the TCollection.Delete method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ( 'Added 100 Items. ');
  With C^ do
    While Count>0 do Delete(At(Count-1));
  WriteLn ( 'Freed all objects ');
  Dispose(C, Done);
end.
```

21.5.17 TCollection.AtFree

Synopsis: Free an item at the indicates position, calling it's destructor.

Declaration: `procedure AtFree(Index: Sw_Integer)`

Visibility: default

Description: `AtFree` deletes the item at position `Index` in the collection, and calls the item's destructor if it is not `Nil`.

Errors: If `Index` isn't valid then `Error` (803) is called with `CoIndexError`.

See also: `TCollection.Free` (799), `TCollection.AtDelete` (801)

Listing: `./objectex/ex32.pp`

Program `ex32`;

{ Program to demonstrate the TCollection.AtFree method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New`(`PCollection`, `Init`(120,10));
 For `I:=1` **to** 100 **do**
 begin
 `M:=New`(`PMyObject`, `Init`);
 `M^.SetField`(`I-1`);
 `C^.Insert`(`M`);
 end;
 WriteLn ('Added 100 Items');
 With `C^` **do**
 While `Count>0` **do** `AtFree`(`Count-1`);
 WriteLn ('Freed all objects.');
 Dispose(`C`, `Done`);
end.

21.5.18 TCollection.FreeItem

Synopsis: Destroy a non-nil item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: `default`

Description: `FreeItem` calls the destructor of `Item` if it is not nil.

Remark: This function is used internally by the `TCollection` object, and should not be called directly.

Errors: None.

See also: `TCollection.Free` (799), `TCollection.AtFree` (800)

21.5.19 TCollection.AtDelete

Synopsis: Delete item at certain position.

Declaration: `procedure AtDelete(Index: Sw_Integer)`

Visibility: `default`

Description: `AtDelete` deletes the pointer at position `Index` in the collection. It doesn't call the object's destructor.

Errors: If `Index` isn't valid then `Error` (803) is called with `CoIndexError`.

See also: `TCollection.Delete` (800)

Listing: `./objectex/ex33.pp`

Program `ex33`;

{ Program to demonstrate the TCollection.AtDelete method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New`(`PCollection` , `Init`(120,10));
 For `I:=1` **to** 100 **do**
 begin
 `M:=New`(`PMMyObject` , `Init`);
 `M^.SetField`(`I-1`);
 `C^.Insert`(`M`);
 end;
 WriteLn ('Added 100 Items.');
 With `C^` **do**
 While `Count>0` **do** `AtDelete`(`Count-1`);
 WriteLn ('Freed all objects.');
 Dispose(`C`, `Done`);
end.

21.5.20 TCollection.ForEach

Synopsis: Execute procedure for each item in the list.

Declaration: `procedure ForEach(Action: Pointer)`

Visibility: default

Description: `ForEach` calls `Action` for each element in the collection, and passes the element as an argument to `Action`.

`Action` is a procedural type variable that accepts a pointer as an argument.

Errors: None.

See also: `TCollection.FirstThat` (795), `TCollection.LastThat` (795)

Listing: `./objectex/ex21.pp`

Program `ex21`;

{ Program to demonstrate the TCollection.ForEach method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer;P : PMyObject);

begin
  WriteLn ( 'Field : ',P^.GetField);
end;

begin
  C:=New( PCollection , Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(100-I);
      C^.Insert(M);
    end;
  WriteLn ( 'Inserted ',C^.Count,' objects ');
  C^.ForEach( @PrintField );
  C^.FreeAll;
  Dispose(C,Done);
end.

```

21.5.21 TCollection.SetLimit

Synopsis: Set maximum number of elements in the collection.

Declaration: `procedure SetLimit(ALimit: Sw_Integer); Virtual`

Visibility: default

Description: `SetLimit` sets the maximum number of elements in the collection. `ALimit` must not be less than `Count`, and should not be larger than `MaxCollectionSize`

For an example, see [Pack \(796\)](#).

Errors: None.

See also: `TCollection.Init` ([791](#))

21.5.22 TCollection.Error

Synopsis: Set error code.

Declaration: `procedure Error(Code: Integer;Info: Integer); Virtual`

Visibility: default

Description: `Error` is called by the various `TCollection` methods in case of an error condition. The default behaviour is to make a call to `RunError` with an error of `212-Code`.

This method can be overridden by descendent objects to implement a different error-handling.

Errors:

See also: `Abstract` ([780](#))

21.5.23 TCollection.AtPut

Synopsis: Set collection item, overwriting an existing value.

Declaration: `procedure AtPut (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtPut` sets the element at position `Index` in the collection to `Item`. Any previous value is overwritten.

For an example, see `Pack` (796).

Errors: If `Index` isn't valid then `Error` (803) is called with `CoIndexError`.

21.5.24 TCollection.AtInsert

Synopsis: Insert an element at a certain position in the collection.

Declaration: `procedure AtInsert (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtInsert` inserts `Item` in the collection at position `Index`, shifting all elements by one position. In case the current limit is reached, the collection will try to expand with a call to `SetLimit`

Errors: If `Index` isn't valid then `Error` (803) is called with `CoIndexError`. If the collection fails to expand, then `coOverflow` is passed to `Error`.

See also: `TCollection.Insert` (799)

Listing: `./objectex/ex34.pp`

Program `ex34`;

{ Program to demonstrate the TCollection.AtInsert method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

Procedure `PrintField` (`Dummy`: `Pointer`; `P` : `PMMyObject`);

begin
 `WriteLn` ('Field : ', `P`^.`GetField`);
end;

begin
 `Randomize`;
 `C` := `New`(`PCollection`, `Init`(120, 10));
 `WriteLn` ('Inserting 100 records at random places.');
 For `I` := 1 **to** 100 **do**
 begin
 `M` := `New`(`PMMyObject`, `Init`);
 `M`^.`SetField`(`I` - 1);
 If `I` = 1 **then**
 `C`^.`Insert`(`M`)
 end

```

    else
      With C^ do
        AtInsert(Random(Count),M);
      end;
      WriteLn ('Values : ');
      C^.Foreach (@PrintField);
      Dispose(C,Done);
    end.

```

21.5.25 TCollection.Store

Synopsis: Write collection to a stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by writeing the current `Count`, `Limit` and `Delta` to the stream, and then writing each item to the stream.

The contents of the stream are then suitable for instantiating another collection with `Load` ([792](#)).

For an example, see `TCollection.Load` ([792](#)).

Errors: Errors returned are those by `TStream.Put` ([837](#)).

See also: `TCollection.Load` ([792](#)), `TCollection.PutItem` ([805](#))

21.5.26 TCollection.PutItem

Synopsis: Put one item on the stream

Declaration: `procedure PutItem(var S: TStream;Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to stream `S`. This method is used internaly by the `TCollection` object, and should not be called directly.

Errors: Errors are those returned by `TStream.Put` ([837](#)).

See also: `TCollection.Store` ([805](#)), `TCollection.GetItem` ([794](#))

21.6 TDosStream

21.6.1 Description

`TDosStream` is a stream that stores it's contents in a file. it overrides a couple of methods of `TStream` ([832](#)) for this.

In addition to the fields inherited from `TStream` (see `TStream` ([832](#))), there are some extra fields, that describe the file. (mainly the name and the OS file handle)

No buffering in memory is done when using `TDosStream`. All data are written directly to the file. For a stream that buffers in memory, see `TBufStream` ([787](#)).

21.6.2 Method overview

Page	Property	Description
807	Close	Close the file.
806	Done	Closes the file and cleans up the instance.
806	Init	Instantiate a new instance of TDosStream.
809	Open	Open the file stream
809	Read	Read data from the stream to a buffer.
808	Seek	Set file position.
807	Truncate	Truncate the file on the current position.
810	Write	Write data from a buffer to the stream.

21.6.3 TDosStream.Init

Synopsis: Instantiate a new instance of TDosStream.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TDosStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreate Creates a new file.

stOpenRead Read access only.

stOpenWrite Write access only.

stOpenRead and write access.

For an example, see `TDosStream.Truncate` ([807](#)).

Errors: On error, `Status` (??) is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Done` ([806](#))

21.6.4 TDosStream.Done

Synopsis: Closes the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` closes the file if it was open and cleans up the instance of `TDosStream`.
for an example, see e.g. `TDosStream.Truncate` ([807](#)).

Errors: None.

See also: `TDosStream.Init` ([806](#)), `TDosStream.Close` ([807](#))

21.6.5 TDosStream.Close

Synopsis: Close the file.

Declaration: `procedure Close; Virtual`

Visibility: `default`

Description: `Close` closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (806) it does not clean up the instance of `TDosStream`

For an example, see `TDosStream.Open` (809).

Errors: None.

See also: `TStream.Close` (836), `TDosStream.Init` (806), `TDosStream.Done` (806)

21.6.6 TDosStream.Truncate

Synopsis: Truncate the file on the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: If the status of the stream is `stOK`, then `Truncate` tries to truncate the stream size to the current file position.

Errors: If an error occurs, the stream's status is set to `stError` and `ErrorInfo` is set to the OS error code.

See also: `TStream.Truncate` (837), `TStream.GetSize` (834)

Listing: `./objectex/ex16.pp`

Program `ex16;`

{ Program to demonstrate the TStream.Truncate method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PDosStream; { Only one with Truncate implemented. }`

begin

```

  L:= 'Some constant string';
  { Buffer size of 100 }
  S:=New(PDosStream, Init('test.dat', stcreate));
  Writeln ('Writing "', L, '" to stream with handle ', S.Handle);
  S^.WriteStr(@L);
  S^.WriteStr(@L);
  { Close calls flush first }
  S^.Close;
  S^.Open (stOpen);
  Writeln ('Size of stream is : ', S.GetSize);
  P:=S^.ReadStr;
  L:=P^;
  DisposeStr(P);
  Writeln ('Read "', L, '" from stream with handle ', S.Handle);

```

```

S^.Truncate;
Writeln ( 'Truncated stream. Size is : ',S^.GetSize);
S^.Close;
Dispose (S,Done);
end.

```

21.6.7 TDosStream.Seek

Synopsis: Set file position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([838](#)), `TStream.GetPos` ([834](#))

Listing: `./objectex/ex17.pp`

```

Program ex17;

{ Program to demonstrate the TStream.Seek method }

Uses Objects;

Var L : String;
    Marker : Word;
    P : PString;
    S : PDosStream;

begin
  L:= 'Some constant string';
  { Buffer size of 100 }
  S:=New(PDosStream, Init( 'test.dat', stcreate));
  Writeln ( 'Writing "',L, '" to stream.' );
  S^.WriteStr(@L);
  Marker:=S^.GetPos;
  Writeln ( 'Set marker at ',Marker);
  L:= 'Some other constant String';
  Writeln ( 'Writing "',L, '" to stream.' );
  S^.WriteStr(@L);
  S^.Close;
  S^.Open (stOpenRead);
  Writeln ( 'Size of stream is : ',S^.GetSize);
  Writeln ( 'Seeking to marker');
  S^.Seek(Marker);
  P:=S^.ReadStr;
  L:=P^;
  DisposeStr(P);
  Writeln ( 'Read "',L, '" from stream.' );
  S^.Close;
  Dispose (S,Done);
end.

```

21.6.8 TDosStream.Open

Synopsis: Open the file stream

Declaration: `procedure Open (OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (807) call.

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (836), `TDosStream.Close` (807)

Listing: `./objectex/ex14.pp`

Program `ex14;`

{ Program to demonstrate the TStream.Close method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PDosStream; { Only one with Close implemented. }`

begin

```

L:= 'Some constant string';
S:=New(PDosStream, Init('test.dat', stcreate));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);

```

end.

21.6.9 TDosStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `procedure Read (var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

For an example, see `TStream.Read` (839).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (839), `TDosStream.Write` (810)

21.6.10 TDosStream.Write

Synopsis: Write data from a buffer to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

For an example, see `TStream.Read` (839).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` (839), `TDosStream.Read` (809)

21.7 TMemoryStream

21.7.1 Description

The `TMemoryStream` object implements a stream that stores it's data in memory. The data is stored on the heap, with the possibility to specify the maximum amount of data, and the the size of the memory blocks being used.

21.7.2 Method overview

Page	Property	Description
811	<code>Done</code>	Clean up memory and destroy the object instance.
810	<code>Init</code>	Initialize memory stream, reserves memory for stream data.
812	<code>Read</code>	Read data from the stream to a location in memory.
811	<code>Truncate</code>	Set the stream size to the current position.
812	<code>Write</code>	Write data to the stream.

21.7.3 TMemoryStream.Init

Synopsis: Initialize memory stream, reserves memory for stream data.

Declaration: `constructor Init(ALimit: LongInt; ABlockSize: Word)`

Visibility: default

Description: `Init` instantiates a new `TMemoryStream` object. The `memorystreamobject` will initially allocate at least `ALimit` bytes memory, divided into memory blocks of size `ABlockSize`. The number of blocks needed to get to `ALimit` bytes is rounded up.

By default, the number of blocks is 1, and the size of a block is 8192. This is selected if you specify 0 as the blocksize.

For an example, see e.g `TStream.CopyFrom` (840).

Errors: If the stream cannot allocate the initial memory needed for the memory blocks, then the stream's status is set to `stInitError`.

See also: `TMemoryStream.Done` (811)

21.7.4 TMemoryStream.Done

Synopsis: Clean up memory and destroy the object instance.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` releases the memory blocks used by the stream, and then cleans up the memory used by the stream object itself.

For an example, see e.g `TStream.CopyFrom` (840).

Errors: `None`.

See also: `TMemoryStream.Init` (810)

21.7.5 TMemoryStream.Truncate

Synopsis: Set the stream size to the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: `Truncate` sets the size of the memory stream equal to the current position. It de-allocates any memory-blocks that are no longer needed, so that the new size of the stream is the current position in the stream, rounded up to the first multiple of the stream blocksize.

Errors: If an error occurs during memory de-allocation, the stream's status is set to `stError`

See also: `TStream.Truncate` (837)

Listing: `./objectex/ex20.pp`

Program `ex20;`

{ Program to demonstrate the TMemoryStream.Truncate method }

Uses `Objects;`

Var `L : String;`
`P : PString;`
`S : PMemoryStream;`
`I : Longint;`

begin

```

  L:= 'Some constant string';
  { Buffer size of 100 }
  S:=New(PMemoryStream, Init(1000,100));
  Writeln ( 'Writing 100 times "',L,'" to stream.' );
  For I:=1 to 100 do
    S^.WriteStr(@L);
  Writeln ( 'Finished.' );
  S^.Seek(100);
  S^.Truncate;
  Writeln ( 'Truncated at byte 100.' );
  Dispose (S,Done);
  Writeln ( 'Finished.' );
end.
```

21.7.6 TMemoryStream.Read

Synopsis: Read data from the stream to a location in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read reads Count bytes from the stream to Buf. It updates the position of the stream.

For an example, see TStream.Read (839).

Errors: If there is not enough data available, no data is read, and the stream's status is set to stReadError.

See also: TStream.Read (839), TMemoryStream.Write (812)

21.7.7 TMemoryStream.Write

Synopsis: Write data to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write copies Count bytes from Buf to the stream. It updates the position of the stream.

If not enough memory is available to hold the extra Count bytes, then the stream will try to expand, by allocating as much blocks with size BlkSize (as specified in the constructor call Init (810)) as needed.

For an example, see TStream.Read (839).

Errors: If the stream cannot allocate more memory, then the status is set to stWriteError

See also: TStream.Write (839), TMemoryStream.Read (812)

21.8 TObject

21.8.1 Description

This type serves as the basic object for all other objects in the Objects unit.

21.8.2 Method overview

Page	Property	Description
814	Done	Destroy an object.
813	Free	Destroy an object and release all memory.
812	Init	Construct (initialize) a new object
813	Is_Object	Check whether a pointer points to an object.

21.8.3 TObject.Init

Synopsis: Construct (initialize) a new object

Declaration: `constructor Init`

Visibility: default

Description: Instantiates a new object of type `TObject`. It fills the instance up with Zero bytes.

For an example, see [Free \(813\)](#)

Errors: None.

See also: [TObject.Free \(813\)](#), [TObject.Done \(814\)](#)

21.8.4 TObject.Free

Synopsis: Destroy an object and release all memory.

Declaration: `procedure Free`

Visibility: default

Description: `Free` calls the destructor of the object, and releases the memory occupied by the instance of the object.

Errors: No checking is performed to see whether `self` is `nil` and whether the object is indeed allocated on the heap.

See also: [TObject.Init \(812\)](#), [TObject.Done \(814\)](#)

Listing: `./objectex/ex7.pp`

```

program ex7;

  { Program to demonstrate the TObject.Free call }

Uses Objects;

Var O : TObject;

begin
  // Allocate memory for object.
  O:=New(TObject, Init);
  // Free memory of object.
  O^.free;
end.

```

21.8.5 TObject.Is_Object

Synopsis: Check whether a pointer points to an object.

Declaration: `function Is_Object(P: Pointer) : Boolean`

Visibility: default

Description: `Is_Object` returns `True` if the pointer `P` points to an instance of a `TObject` descendent, it returns `false` otherwise.

21.8.6 TObject.Done

Synopsis: Destroy an object.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done`, the destructor of `TObject` does nothing. It is mainly intended to be used in the `TObject.Free` (813) method.

The destructore `Done` does not free the memory occupied by the object.

Errors: None.

See also: `TObject.Free` (813), `TObject.Init` (812)

Listing: `./objectex/ex8.pp`

```

program ex8;

  { Program to demonstrate the TObject.Done call }

Uses Objects;

Var O : PObject;

begin
  // Allocate memory for object.
  O:=New(PObject, Init);
  O^.Done;
end.

```

21.9 TPoint

21.9.1 Description

Record describing a point in a 2 dimensional plane.

21.10 TRect

21.10.1 Description

Describes a rectangular region in a plane.

21.10.2 Method overview

Page	Property	Description
819	Assign	Set rectangle corners.
816	Contains	Determine if a point is inside the rectangle
816	Copy	Copy cornerpoints from another rectangle.
815	Empty	Is the surface of the rectangle zero
816	Equals	Do the corners of the rectangles match
819	Grow	Expand rectangle with certain size.
817	Intersect	Reduce rectangle to intersection with another rectangle
818	Move	Move rectangle along a vector.
817	Union	Enlarges rectangle to encompass another rectangle.

21.10.3 TRect.Empty

Synopsis: Is the surface of the rectangle zero

Declaration: `function Empty : Boolean`

Visibility: default

Description: `Empty` returns `True` if the rectangle defined by the corner points A, B has zero or negative surface.

Errors: None.

See also: `TRect.Equals` ([816](#)), `TRect.Contains` ([816](#))

Listing: `./objectex/ex1.pp`

Program `ex1;`

{ Program to demonstrate TRect.Empty }

Uses `objects;`

Var `ARect,BRect : TRect;`
 `P : TPoint;`

begin

With `ARect.A do`

begin

`X:=10;`

`Y:=10;`

end;

With `ARect.B do`

begin

`X:=20;`

`Y:=20;`

end;

{ Offset B by (5,5) }

With `BRect.A do`

begin

`X:=15;`

`Y:=15;`

end;

With `BRect.B do`

begin

`X:=25;`

`Y:=25;`

end;

{ Point }

With `P do`

begin

`X:=15;`

`Y:=15;`

end;

Writeln (`'A empty : ',ARect.Empty`);

Writeln (`'B empty : ',BRect.Empty`);

Writeln (`'A Equals B : ',ARect.Equals(BRect)`);

Writeln (`'A Contains (15,15) : ',ARect.Contains(P)`);

end.

21.10.4 TRect.Equals

Synopsis: Do the corners of the rectangles match

Declaration: `function Equals(R: TRect) : Boolean`

Visibility: default

Description: `Equals` returns `True` if the rectangle has the same corner points A, B as the rectangle R, and `False` otherwise.

For an example, see `TRect.Empty` (815)

Errors: None.

See also: `TRect.Empty` (815), `TRect.Contains` (816)

21.10.5 TRect.Contains

Synopsis: Determine if a point is inside the rectangle

Declaration: `function Contains(P: TPoint) : Boolean`

Visibility: default

Description: `Contains` returns `True` if the point P is contained in the rectangle (including borders), `False` otherwise.

Errors: None.

See also: `TRect.Intersect` (817), `TRect.Equals` (816)

21.10.6 TRect.Copy

Synopsis: Copy cornerpoints from another rectangle.

Declaration: `procedure Copy(R: TRect)`

Visibility: default

Description: Assigns the rectangle R to the object. After the call to `Copy`, the rectangle R has been copied to the object that invoked `Copy`.

Errors: None.

See also: `TRect.Assign` (819)

Listing: `./objectex/ex2.pp`

Program `ex2;`

`{ Program to demonstrate TRect.Copy }`

Uses `objects;`

Var `ARect, BRect, CRect : TRect;`

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

```

CRect.Copy(ARect);
If ARect.Equals(CRect) Then
  Writeln ( 'ARect equals CRect')
Else
  Writeln ( 'ARect does not equal CRect !');
end.

```

21.10.7 TRect.Union

Synopsis: Enlarges rectangle to encompass another rectangle.

Declaration: `procedure Union(R: TRect)`

Visibility: default

Description: `Union` enlarges the current rectangle so that it becomes the union of the current rectangle with the rectangle `R`.

Errors: None.

See also: `TRect.Intersect` ([817](#))

Listing: `./objectex/ex3.pp`

Program `ex3`;

{ Program to demonstrate TRect.Union }

Uses `objects`;

Var `ARect, BRect, CRect : TRect`;

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

{ CRect is union of ARect and BRect }

`CRect.Assign(10,10,25,25);`

{ Calculate it explicitly }

`ARect.Union(BRect);`

If `ARect.Equals(CRect)` **Then**

`Writeln ('ARect equals CRect')`

Else

`Writeln ('ARect does not equal CRect !');`

end.

21.10.8 TRect.Intersect

Synopsis: Reduce rectangle to intersection with another rectangle

Declaration: `procedure Intersect(R: TRect)`

Visibility: default

Description: `Intersect` makes the intersection of the current rectangle with `R`. If the intersection is empty, then the rectangle is set to the empty rectangle at coordinate (0,0).

Errors: None.

See also: TRect.Union ([817](#))

Listing: ./objectex/ex4.pp

```

Program ex4;

{ Program to demonstrate TRect.Intersect }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is intersection of ARect and BRect }
  CRect.Assign(15,15,20,20);
  { Calculate it explicitly }
  ARect.Intersect(BRect);
  If ARect.Equals(CRect) Then
    Writeln ( 'ARect equals CRect' )
  Else
    Writeln ( 'ARect does not equal CRect !' );
  BRect.Assign(25,25,30,30);
  ARect.Intersect(BRect);
  If ARect.Empty Then
    Writeln ( 'ARect is empty' );
end.

```

21.10.9 TRect.Move

Synopsis: Move rectangle along a vector.

Declaration: `procedure Move(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Move` moves the current rectangle along a vector with components (ADX, ADY). It adds ADX to the X-coordinate of both corner points, and ADY to both end points.

Errors: None.

See also: TRect.Grow ([819](#))

Listing: ./objectex/ex5.pp

```

Program ex5;

{ Program to demonstrate TRect.Move }

Uses objects;

Var ARect, BRect : TRect;

```

```

begin
  ARect.Assign(10,10,20,20);
  ARect.Move(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(15,15,25,25);
  If ARect.Equals(BRect) Then
    Writeln ( 'ARect equals BRect' )
  Else
    Writeln ( 'ARect does not equal BRect !' );
end.

```

21.10.10 TRect.Grow

Synopsis: Expand rectangle with certain size.

Declaration: `procedure Grow(ADX: Sw_Integer;ADY: Sw_Integer)`

Visibility: default

Description: `Grow` expands the rectangle with an amount `ADX` in the `X` direction (both on the left and right side of the rectangle, thus adding a length `2*ADX` to the width of the rectangle), and an amount `ADY` in the `Y` direction (both on the top and the bottom side of the rectangle, adding a length `2*ADY` to the height of the rectangle).

`ADX` and `ADY` can be negative. If the resulting rectangle is empty, it is set to the empty rectangle at `(0,0)`.

Errors: None.

See also: `TRect.Move` ([818](#))

Listing: `./objectex/ex6.pp`

```

Program ex6;

{ Program to demonstrate TRect.Grow }

Uses objects;

Var ARect,BRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  ARect.Grow(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(5,5,25,25);
  If ARect.Equals(BRect) Then
    Writeln ( 'ARect equals BRect' )
  Else
    Writeln ( 'ARect does not equal BRect !' );
end.

```

21.10.11 TRect.Assign

Synopsis: Set rectangle corners.

Declaration: `procedure Assign(XA: Sw_Integer; YA: Sw_Integer; XB: Sw_Integer;
YB: Sw_Integer)`

Visibility: default

Description: `Assign` sets the corner points of the rectangle to `(XA, YA)` and `(XB, YB)`.

For an example, see `TRect.Copy` (816).

Errors: None.

See also: `TRect.Copy` (816)

21.11 TResourceCollection

21.11.1 Description

A `TResourceCollection` manages a collection of resource names. It stores the position and the size of a resource, as well as the name of the resource. It stores these items in records that look like this:

```
TYPE
  TResourceItem = packed RECORD
    Posn: LongInt;
    Size: LongInt;
    Key : String;
  End;
  PResourceItem = ^TResourceItem;
```

It overrides some methods of `TStringCollection` in order to accomplish this.

Remark: Remark that the `TResourceCollection` manages the names of the resources and their associated positions and sizes, it doesn't manage the resources themselves.

21.11.2 Method overview

Page	Property	Description
821	<code>FreeItem</code>	Release memory occupied by item.
821	<code>GetItem</code>	Read an item from the stream.
820	<code>KeyOf</code>	Return the key of an item in the collection.
821	<code>PutItem</code>	Write an item to the stream.

21.11.3 TResourceCollection.KeyOf

Synopsis: Return the key of an item in the collection.

Declaration: `function KeyOf(Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key of an item in the collection. For resources, the key is a pointer to the string with the resource name.

Errors: None.

See also: `TStringCollection.Compare` (841)

21.11.4 TResourceCollection.GetItem

Synopsis: Read an item from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a resource item from the stream `S`. It reads the position, size and name from the stream, in that order. It DOES NOT read the resource itself from the stream.

The resulting item is not inserted in the collection. This call is mainly for internal use by the `TCollection.Load (792)` method.

Errors: Errors returned are those by `TStream.Read (839)`

See also: `TCollection.Load (792)`, `TStream.Read (839)`

21.11.5 TResourceCollection.FreeItem

Synopsis: Release memory occupied by item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` releases the memory occupied by `Item`. It de-allocates the name, and then the resource item record.

It does NOT remove the item from the collection.

Errors: None.

See also: `TCollection.FreeItem (801)`

21.11.6 TResourceCollection.PutItem

Synopsis: Write an item to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to the stream `S`. It does this by writing the position and size and name of the resource item to the stream.

This method is used primarily by the `Store (805)` method.

Errors: Errors returned are those by `TStream.Write (839)`.

See also: `TCollection.Store (805)`

21.12 TResourceFile

21.12.1 Description

`TResourceFile (821)` represents the resources in a binary file image.

21.12.2 Method overview

Page	Property	Description
822	Count	Number of resources in the file
824	Delete	Delete a resource from the file
822	Done	Destroy the instance and remove it from memory.
823	Flush	Writes the resources to the stream.
823	Get	Return a resource by key name.
822	Init	Instantiate a new instance.
823	KeyAt	Return the key of the item at a certain position.
824	Put	Set a resource by key name.
823	SwitchTo	Write resources to a new stream.

21.12.3 TResourceFile.Init

Synopsis: Instantiate a new instance.

Declaration: `constructor Init (AStream: PStream)`

Visibility: default

Description: `Init` instantiates a new instance of a `TResourceFile` object. If `AStream` is not nil then it is considered as a stream describing an executable image on disk.

`Init` will try to position the stream on the start of the resources section, and read all resources from the stream.

Errors: None.

See also: `TResourceFile.Done` ([822](#))

21.12.4 TResourceFile.Done

Synopsis: Destroy the instance and remove it from memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` cleans up the instance of the `TResourceFile` Object. If `Stream` was specified at initialization, then `Stream` is disposed of too.

Errors: None.

See also: `TResourceFile.Init` ([822](#))

21.12.5 TResourceFile.Count

Synopsis: Number of resources in the file

Declaration: `function Count : Sw_Integer`

Visibility: default

Description: `Count` returns the number of resources. If no resources were read, zero is returned.

Errors: None.

See also: `TResourceFile.Init` ([822](#))

21.12.6 TResourceFile.KeyAt

Synopsis: Return the key of the item at a certain position.

Declaration: `function KeyAt (I: Sw_Integer) : String`

Visibility: default

Description: `KeyAt` returns the key (the name) of the `I`-th resource.

Errors: In case `I` is invalid, `TCollection.Error` will be executed.

See also: `TResourceFile.Get` (823)

21.12.7 TResourceFile.Get

Synopsis: Return a resource by key name.

Declaration: `function Get (Key: String) : PObject`

Visibility: default

Description: `Get` returns a pointer to a instance of a resource identified by `Key`. If `Key` cannot be found in the list of resources, then `Nil` is returned.

Errors: Errors returned may be those by `TStream.Get`

21.12.8 TResourceFile.SwitchTo

Synopsis: Write resources to a new stream.

Declaration: `function SwitchTo (AStream: PStream; Pack: Boolean) : PStream`

Visibility: default

Description: `SwitchTo` switches to a new stream to hold the resources in. `AStream` will be the new stream after the call to `SwitchTo`.

If `Pack` is true, then all the known resources will be copied from the current stream to the new stream (`AStream`). If `Pack` is False, then only the current resource is copied.

The return value is the value of the original stream: `Stream`.

The `Modified` flag is set as a consequence of this call.

Errors: Errors returned can be those of `TStream.Read` (839) and `TStream.Write` (839).

See also: `TResourceFile.Flush` (823)

21.12.9 TResourceFile.Flush

Synopsis: Writes the resources to the stream.

Declaration: `procedure Flush`

Visibility: default

Description: If the `Modified` flag is set to `True`, then `Flush` writes the resources to the stream `Stream`. It sets the `Modified` flag to true after that.

Errors: Errors can be those by `TStream.Seek` (838) and `TStream.Write` (839).

See also: `TResourceFile.SwitchTo` (823)

21.12.10 TResourceFile.Delete

Synopsis: Delete a resource from the file

Declaration: `procedure Delete(Key: String)`

Visibility: `default`

Description: `Delete` deletes the resource identified by `Key` from the collection. It sets the `Modified` flag to `true`.

Errors: `None`.

See also: `TResourceFile.Flush` ([823](#))

21.12.11 TResourceFile.Put

Synopsis: Set a resource by key name.

Declaration: `procedure Put(Item: PObject; Key: String)`

Visibility: `default`

Description: `Put` sets the resource identified by `Key` to `Item`. If no such resource exists, a new one is created. The item is written to the stream.

Errors: Errors returned may be those by `TStream.Put` ([837](#)) and `TStream.Seek`

See also: `TResourceFile.Get` ([823](#))

21.13 TSortedCollection

21.13.1 Description

`TSortedCollection` is an abstract class, implementing a sorted collection. You should never use an instance of `TSortedCollection` directly, instead you should declare a descendent type, and override the `Compare` ([826](#)) method.

Because the collection is ordered, `TSortedCollection` overrides some `TCollection` methods, to provide faster routines for lookup.

The `Compare` ([826](#)) method decides how elements in the collection should be ordered. Since `TCollection` has no way of knowing how to order pointers, you must override the compare method.

Additionally, `TCollection` provides a means to filter out duplicates. if you set `Duplicates` to `False` (the default) then duplicates will not be allowed.

The example below defines a descendent of `TSortedCollection` which is used in the examples.

21.13.2 Method overview

Page	Property	Description
826	Compare	Compare two items in the collection.
826	IndexOf	Return index of an item in the collection.
825	Init	Instantiates a new instance of a <code>TSortedCollection</code>
828	Insert	Insert new item in collection.
825	KeyOf	Return the key of an item
825	Load	Instantiates a new instance of a <code>TSortedCollection</code> and loads it from stream.
827	Search	Search for item with given key.
829	Store	Write the collection to the stream.

21.13.3 `TSortedCollection.Init`

Synopsis: Instantiates a new instance of a `TSortedCollection`

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` calls the inherited constructor (see `TCollection.Init` ([791](#))) and sets the `Duplicates` flag to `false`.

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

Errors: None.

See also: `TSortedCollection.Load` ([825](#)), `TCollection.Done` ([792](#))

21.13.4 `TSortedCollection.Load`

Synopsis: Instantiates a new instance of a `TSortedCollection` and loads it from stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` calls the inherited constructor (see `TCollection.Load` ([792](#))) and reads the `Duplicates` flag from the stream..

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

For an example, see `TCollection.Load` ([792](#)).

Errors: None.

See also: `TSortedCollection.Init` ([825](#)), `TCollection.Done` ([792](#))

21.13.5 `TSortedCollection.KeyOf`

Synopsis: Return the key of an item

Declaration: `function KeyOf (Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key associated with `Item`. `TSortedCollection` returns the item itself as the key, descendent objects can override this method to calculate a (unique) key based on the item passed (such as hash values).

`Keys` are used to sort the objects, they are used to search and sort the items in the collection. If descendent types override this method then it allows possibly for faster search/sort methods based on keys rather than on the objects themselves.

Errors: None.

See also: `TSortedCollection.IndexOf` (826), `TSortedCollection.Compare` (826)

21.13.6 `TSortedCollection.IndexOf`

Synopsis: Return index of an item in the collection.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. It searches for the object based on it's key. If duplicates are allowed, then it returns the index of last object that matches `Item`.

In case `Item` is not found in the collection, -1 is returned.

For an example, see `TCollection.IndexOf` (793)

Errors: None.

See also: `TSortedCollection.Search` (827), `TSortedCollection.Compare` (826)

21.13.7 `TSortedCollection.Compare`

Synopsis: Compare two items in the collection.

Declaration: `function Compare(Key1: Pointer;Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `Compare` is an abstract method that should be overridden by descendent objects in order to compare two items in the collection. This method is used in the `Search` (827) method and in the `Insert` (828) method to determine the ordering of the objects.

The function should compare the two keys of items and return the following function results:

Result < 0 If `Key1` is logically before `Key2` (`Key1<Key2`)

Result = 0 If `Key1` and `Key2` are equal. (`Key1=Key2`)

Result > 0 If `Key1` is logically after `Key2` (`Key1>Key2`)

Errors: An 'abstract run-time error' will be generated if you call `TSortedCollection.Compare` directly.

See also: `TSortedCollection.IndexOf` (826), `TSortedCollection.Search` (827)

Listing: `./objectex/mysortc.pp`

Unit MySortC;

Interface

Uses Objects;

Type

```

PMySortedCollection = ^TMySortedCollection;
TMySortedCollection = Object(TSortedCollection)
    Function Compare (Key1,Key2 : Pointer) : Sw_integer; virtual;
    end;

```

Implementation

Uses MyObject;

Function TMySortedCollection.Compare (Key1,Key2 : Pointer) : sw_integer;

begin

```

    Compare:=PMyobject(Key1)^.GetField - PMyObject(Key2)^.GetField;

```

end;

end.

21.13.8 TSortedCollection.Search

Synopsis: Search for item with given key.

Declaration: `function Search(Key: Pointer;var Index: Sw_Integer) : Boolean; Virtual`

Visibility: default

Description: Search looks for the item with key Key and returns the position of the item (if present) in the collection in Index.

Instead of a linear search as TCollection does, TSortedCollection uses a binary search based on the keys of the objects. It uses the Compare (826) function to implement this search.

If the item is found, Search returns True, otherwise False is returned.

Errors: None.

See also: TCollection.IndexOf (793)

Listing: ./objectex/ex36.pp

Program ex36;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;

{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;

 M : PMyObject;

 I : Longint;

Procedure PrintField (Dummy: Pointer;P : PMyObject);


```

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  C^.Duplicates:=True;
  Writeln ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(Random(100));
      C^.Insert(M)
    end;
  M:=New(PMyObject, Init);
  Repeat;
    Write ( 'Value to search for (-1 stops) : ' );
    read ( I );
    If I<>-1 then
      begin
        M^.SetField(i);
        If Not C^.Search (M,I) then
          Writeln ( 'No such value found' )
        else
          begin
            Write ( 'Value ', PMyObject(C^.At(I))^ .GetField );
            Writeln ( ' present at position ', I );
          end;
        end;
    Until I=-1;
    Dispose (M, Done );
    Dispose (C, Done );
  end.

```

21.13.9 TSortedCollection.Insert

Synopsis: Insert new item in collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts an item in the collection at the correct position, such that the collection is ordered at all times. You should never use `Atinsert` (804), since then the collection ordering is not guaranteed.

If `Item` is already present in the collection, and `Duplicates` is `False`, the item will not be inserted.

Errors: None.

See also: `TCollection.AtInsert` (804)

Listing: `./objectex/ex35.pp`

```

Program ex35;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;
      { For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
  WriteLn ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  WriteLn ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^.SetField( Random(100));
      C^.Insert( M )
    end;
  WriteLn ( 'Values : ' );
  C^.Foreach( @PrintField );
  Dispose(C, Done);
end.

```

21.13.10 TSortedCollection.Store

Synopsis: Write the collection to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by calling the inherited `TCollection.Store` (805), and then writing the `Duplicates` flag to the stream.

After a `Store`, the collection can be loaded from the stream with the constructor `Load` (825)

For an example, see `TCollection.Load` (792).

Errors: Errors can be those of `TStream.Put` (837).

See also: `TSortedCollection.Load` (825)

21.14 TStrCollection

21.14.1 Description

The `TStrCollection` object manages a sorted collection of null-terminated strings (pchar strings). To this end, it overrides the `Compare` (826) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

21.14.2 Method overview

Page	Property	Description
830	<code>Compare</code>	Compare two strings in the collection.
831	<code>FreeItem</code>	Free null-terminated string from the collection.
831	<code>GetItem</code>	Read a null-terminated string from the stream.
831	<code>PutItem</code>	Write a null-terminated string to the stream.

21.14.3 TStrCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer;Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStrCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns

-1if the first string is alphabetically earlier than the second string.

0if the two strings are equal.

1if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` (826)

Listing: `./objectex/ex38.pp`

Program `ex38;`

{ Program to demonstrate the TStrCollection.Compare method }

Uses `Objects , Strings ;`

Var `C : PStrCollection ;`

`S : String ;`

`I : longint ;`

`P : Pchar ;`

begin

`Randomize ;`

`C:=New(PStrCollection , Init(120,10));`

`C^.Duplicates:=True; { Duplicates allowed }`

`WriteLn ('Inserting 100 records at random places.');`

For `I:=1 to 100 do`

`begin`

`Str(Random(100),S);`

```

S:= 'String with value '+S;
P:= StrAlloc (Length(S)+1);
C^.Insert(StrPCopy(P,S));
end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(I),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',I);
    Dispose(C,Done);
  end.

```

21.14.4 TStrCollection.GetItem

Synopsis: Read a null-terminated string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a null-terminated string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.StrRead` ([833](#)).

See also: `TStrCollection.PutItem` ([831](#))

21.14.5 TStrCollection.FreeItem

Synopsis: Free null-terminated string from the collection.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStrCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([801](#))

21.14.6 TStrCollection.PutItem

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.StrWrite` ([838](#)).

See also: `TStrCollection.GetItem` ([831](#))

21.15 TStream

21.15.1 Description

The `TStream` object is the ancestor for all streaming objects, i.e. objects that have the capability to store and retrieve data.

It defines a number of methods that are common to all objects that implement streaming, many of them are virtual, and are only implemented in the descendent types.

Programs should not instantiate objects of type `TStream` directly, but instead instantiate a descendant type, such as `TDosStream`, `TMemoryStream`.

21.15.2 Method overview

Page	Property	Description
836	<code>Close</code>	Close the stream
840	<code>CopyFrom</code>	Copy data from another stream.
838	<code>Error</code>	Set stream status
837	<code>Flush</code>	Flush the stream data from the buffer, if any.
832	<code>Get</code>	Read an object definition from the stream.
834	<code>GetPos</code>	Return current position in the stream
834	<code>GetSize</code>	Return the size of the stream.
832	<code>Init</code>	Constructor for <code>TStream</code> instance
836	<code>Open</code>	Open the stream
837	<code>Put</code>	Write an object to the stream.
839	<code>Read</code>	Read data from stream to buffer.
835	<code>ReadStr</code>	Read a shortstring from the stream.
836	<code>Reset</code>	Reset the stream
838	<code>Seek</code>	Set stream position.
833	<code>StrRead</code>	Read a null-terminated string from the stream.
838	<code>StrWrite</code>	Write a null-terminated string to the stream.
837	<code>Truncate</code>	Truncate the stream size on current position.
839	<code>Write</code>	Write a number of bytes to the stream.
838	<code>WriteStr</code>	Write a pascal string to the stream.

21.15.3 TStream.Init

Synopsis: Constructor for `TStream` instance

Declaration: `constructor Init`

Visibility: `default`

Description: `Init` initializes a `TStream` instance. Descendent streams should always call the inherited `Init`.

21.15.4 TStream.Get

Synopsis: Read an object definition from the stream.

Declaration: `function Get : PObject`

Visibility: `default`

Description: `Get` reads an object definition from a stream, and returns a pointer to an instance of this object.

Errors: On error, TStream.Status (??) is set, and NIL is returned.

See also: TStream.Put ([837](#))

Listing: ./objectex/ex9.pp

Program ex9;

{ Program to demonstrate TStream.Get and TStream.Put }

Uses Objects, MyObject; *{ Definition and registration of TMyObject }*

Var Obj : PMyObject;
S : PStream;

begin

```
Obj:=New(PMyObject, Init);
Obj^.SetField($1111);
Writeln('Field value : ', Obj^.GetField);
{ Since Stream is an abstract type, we instantiate a TMemoryStream }
S:=New(PMemoryStream, Init(100,10));
S^.Put(Obj);
Writeln('Disposing object');
S^.Seek(0);
Dispose(Obj, Done);
Writeln('Reading object');
Obj:=PMyObject(S^.Get);
Writeln('Field Value : ', Obj^.GetField);
Dispose(Obj, Done);
```

end.

21.15.5 TStream.StrRead

Synopsis: Read a null-terminated string from the stream.

Declaration: `function StrRead : PChar`

Visibility: default

Description: StrRead reads a string from the stream, allocates memory for it, and returns a pointer to a null-terminated copy of the string on the heap.

Errors: On error, Nil is returned.

See also: TStream.StrWrite ([838](#)), TStream.ReadStr ([835](#))

Listing: ./objectex/ex10.pp

Program ex10;

*{
Program to demonstrate the TStream.StrRead TStream.StrWrite functions
}*

Uses objects;

Var P : PChar;
S : PStream;

```

begin
  P:= 'Constant Pchar string';
  Writeln ('Writing to stream : ',P,'');
  S:=New(PMemoryStream, Init(100,10));
  S^.StrWrite(P);
  S^.Seek(0);
  P:= Nil;
  P:=S^.StrRead;
  Dispose (S,Done);
  Writeln ('Read from stream : ',P,'');
  Freemem(P, Strlen(P)+1);
end.

```

21.15.6 TStream.GetPos

Synopsis: Return current position in the stream

Declaration: `function GetPos : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk`, `GetPos` returns the current position in the stream. Otherwise it returns `-1`

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([838](#)), `TStream.GetSize` ([834](#))

Listing: `./objectex/ex11.pp`

```

Program ex11;

{ Program to demonstrate the TStream.GetPos function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ('Stream position before write : ',S^.GetPos);
  S^.WriteStr(@L);
  Writeln ('Stream position after write : ',S^.GetPos);
  Dispose(S,Done);
end.

```

21.15.7 TStream.GetSize

Synopsis: Return the size of the stream.

Declaration: `function GetSize : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk` then `GetSize` returns the size of the stream, otherwise it returns `-1`.

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([838](#)), `TStream.GetPos` ([834](#))

Listing: `./objectex/ex12.pp`

```

Program ex12;

{ Program to demonstrate the TStream.GetSize function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ( 'Stream size before write : ',S^.GetSize);
  S^.WriteStr(@L);
  Writeln ( 'Stream size after write : ',S^.GetSize);
  Dispose(S,Done);
end.

```

21.15.8 TStream.ReadStr

Synopsis: Read a shortstring from the stream.

Declaration: `function ReadStr : PString`

Visibility: default

Description: `ReadStr` reads a string from the stream, copies it to the heap and returns a pointer to this copy. The string is saved as a pascal string, and hence is NOT null terminated.

Errors: On error (e.g. not enough memory), `Nil` is returned.

See also: `TStream.StrRead` ([833](#))

Listing: `./objectex/ex13.pp`

```

Program ex13;

{
  Program to demonstrate the TStream.ReadStr TStream.WriteStr functions
}

Uses objects;

Var P : PString;
    L : String;
    S : PStream;

begin
  L:= 'Constant string line';
  Writeln ( 'Writing to stream : " ',L,'" ');

```

```

S:=New(PMemoryStream, Init(100,10));
S^.WriteStr(@L);
S^.Seek(0);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
Dispose(S, Done);
WriteLn('Read from stream : "', L, '"');
end.

```

21.15.9 TStream.Open

Synopsis: Open the stream

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: `Open` is an abstract method, that should be overridden by descendent objects. Since opening a stream depends on the stream's type this is not surprising.

For an example, see `TDosStream.Open` (809).

Errors: None.

See also: `TStream.Close` (836), `TStream.Reset` (836)

21.15.10 TStream.Close

Synopsis: Close the stream

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` is an abstract method, that should be overridden by descendent objects. Since Closing a stream depends on the stream's type this is not surprising.

for an example, see `TDosStream.Open` (809).

Errors: None.

See also: `TStream.Open` (836), `TStream.Reset` (836)

21.15.11 TStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` sets the stream's status to 0, as well as the `ErrorInfo`

Errors: None.

See also: `TStream.Open` (836), `TStream.Close` (836)

21.15.12 TStream.Flush

Synopsis: Flush the stream data from the buffer, if any.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: `Flush` is an abstract method that should be overridden by descendent objects. It serves to enable the programmer to tell streams that implement a buffer to clear the buffer.

for an example, see `TBufStream.Flush` ([788](#)).

Errors: None.

See also: `TStream.Truncate` ([837](#))

21.15.13 TStream.Truncate

Synopsis: Truncate the stream size on current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: `Truncate` is an abstract procedure that should be overridden by descendent objects. It serves to enable the programmer to truncate the size of the stream to the current file position.

For an example, see `TDosStream.Truncate` ([807](#)).

Errors: None.

See also: `TStream.Seek` ([838](#))

21.15.14 TStream.Put

Synopsis: Write an object to the stream.

Declaration: `procedure Put (P: PObject)`

Visibility: default

Description: `Put` writes the object pointed to by `P`. `P` should be non-nil. The object type must have been registered with `RegisterType` ([785](#)).

After the object has been written, it can be read again with `Get` ([832](#)).

For an example, see `TStream.Get` ([832](#));

Errors: No check is done whether `P` is `Nil` or not. Passing `Nil` will cause a run-time error 216 to be generated. If the object has not been registered, the status of the stream will be set to `stPutError`.

See also: `TStream.Get` ([832](#))

21.15.15 TStream.StrWrite

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure StrWrite(P: PChar)`

Visibility: default

Description: `StrWrite` writes the null-terminated string `P` to the stream. `P` can only be 65355 bytes long.

For an example, see `TStream.StrRead` (833).

Errors: None.

See also: `TStream.WriteString` (838), `TStream.StrRead` (833), `TStream.ReadStr` (835)

21.15.16 TStream.WriteString

Synopsis: Write a pascal string to the stream.

Declaration: `procedure WriteStr(P: PString)`

Visibility: default

Description: `StrWrite` writes the pascal string pointed to by `P` to the stream.

For an example, see `TStream.ReadStr` (835).

Errors: None.

See also: `TStream.StrWrite` (838), `TStream.StrRead` (833), `TStream.ReadStr` (835)

21.15.17 TStream.Seek

Synopsis: Set stream position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: `Seek` sets the position to `Pos`. This position is counted from the beginning, and is zero based. (i.e. `seek(0)` sets the position pointer on the first byte of the stream)

For an example, see `TDosStream.Seek` (808).

Errors: If `Pos` is larger than the stream size, `Status` is set to `StSeekError`.

See also: `TStream.GetPos` (834), `TStream.GetSize` (834)

21.15.18 TStream.Error

Synopsis: Set stream status

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` sets the stream's status to `Code` and `ErrorInfo` to `Info`. If the `StreamError` procedural variable is set, `Error` executes it, passing `Self` as an argument.

This method should not be called directly from a program. It is intended to be used in descendent objects.

Errors: None.

21.15.19 TStream.Read

Synopsis: Read data from stream to buffer.

Declaration: `procedure Read(var Buf;Count: LongInt); Virtual`

Visibility: default

Description: Read is an abstract method that should be overridden by descendent objects.

Read reads Count bytes from the stream into Buf. It updates the position pointer, increasing it's value with Count. Buf must be large enough to contain Count bytes.

Errors: No checking is done to see if Buf is large enough to contain Count bytes.

See also: TStream.Write (839), TStream.ReadStr (835), TStream.StrRead (833)

Listing: ./objectex/ex18.pp

```

program ex18;

{ Program to demonstrate the TStream.Read method }

Uses Objects;

Var Buf1, Buf2 : Array[1..1000] of Byte;
    I : longint;
    S : PMemoryStream;

begin
    For I:=1 to 1000 do
        Buf1[I]:=Random(1000);
    Buf2:=Buf1;
    S:=New(PMemoryStream, Init(100,10));
    S^.Write(Buf1, SizeOf(Buf1));
    S^.Seek(0);
    For I:=1 to 1000 do
        Buf1[I]:=0;
    S^.Read(Buf1, SizeOf(Buf1));
    For I:=1 to 1000 do
        If Buf1[I]<>Buf2[I] then
            WriteLn('Buffer differs at position ',I);
    Dispose(S, Done);
end.

```

21.15.20 TStream.Write

Synopsis: Write a number of bytes to the stream.

Declaration: `procedure Write(var Buf;Count: LongInt); Virtual`

Visibility: default

Description: Write is an abstract method that should be overridden by descendent objects.

Write writes Count bytes to the stream from Buf. It updates the position pointer, increasing it's value with Count.

For an example, see TStream.Read (839).

Errors: No checking is done to see if Buf actually contains Count bytes.

See also: TStream.Read (839), TStream.WriteString (838), TStream.StrWrite (838)

21.15.21 TStream.CopyFrom

Synopsis: Copy data from another stream.

Declaration: `procedure CopyFrom(var S: TStream; Count: LongInt)`

Visibility: default

Description: `CopyFrom` reads `Count` bytes from stream `S` and stores them in the current stream. It uses the `Read` (839) method to read the data, and the `Write` (839) method to write in the current stream.

Errors: None.

See also: `TStream.Read` (839), `TStream.Write` (839)

Listing: `./objectex/ex19.pp`

Program `ex19`;

{ Program to demonstrate the TStream.CopyFrom function }

Uses `objects`;

Var `P` : `PString`;
 `L` : **String**;
 `S1,S2` : `PStream`;

begin
 `L:= 'Constant string line';`
 Writeln ('Writing to stream 1 : " ',`L`, ' " ');
 `S1:=New(PMemoryStream, Init(100,10));`
 `S2:=New(PMemoryStream, Init(100,10));`
 `S1^.WriteStr(@L);`
 `S1^.Seek(0);`
 Writeln ('Copying contents of stream 1 to stream 2 ');
 `S2^.Copyfrom(S1^,S1^.GetSize);`
 `S2^.Seek(0);`
 `P:=S2^.ReadStr;`
 `L:=P^;`
 DisposeStr(`P`);
 Dispose (`S1`, `Done`);
 Dispose (`S2`, `Done`);
 Writeln ('Read from stream 2 : " ',`L`, ' " ');
end.

21.16 TStringCollection

21.16.1 Description

The `TStringCollection` object manages a sorted collection of pascal strings. To this end, it overrides the `Compare` (826) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

21.16.2 Method overview

Page	Property	Description
841	Compare	Compare two strings in the collection.
842	FreeItem	Dispose a string in the collection from memory.
841	GetItem	Get string from the stream.
842	PutItem	Write a string to the stream.

21.16.3 TStringCollection.GetItem

Synopsis: Get string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.ReadStr` ([835](#)).

See also: `TStringCollection.PutItem` ([842](#))

21.16.4 TStringCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStringCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns the following results:

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` ([826](#))

Listing: `./objectex/ex37.pp`

Program `ex37`;

{ Program to demonstrate the TStringCollection.Compare method }

Uses `Objects`;

Var `C : PStringCollection`;
 `S : String`;
 `I : longint`;

begin
 `Randomize`;

```

C:=New(PStringCollection, Init(120,10));
C^.Duplicates:=True; { Duplicates allowed }
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    Str(Random(100),S);
    S:='String with value '+S;
    C^.Insert(NewStr(S));
  end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(i),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',i);
Dispose(C,Done);
end.

```

21.16.5 TStringCollection.FreeItem

Synopsis: Dispose a string in the collection from memory.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStringCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` (801)

21.16.6 TStringCollection.PutItem

Synopsis: Write a string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.WriteString` (838).

See also: `TStringCollection.GetItem` (841)

21.17 TStringList

21.17.1 Description

A `TStringList` object can be used to read a collection of strings stored in a stream. If you register this object with the `RegisterType` (785) function, you cannot register the `TStrListMaker` object.

21.17.2 Method overview

Page	Property	Description
843	Done	Clean up the instance
843	Get	Return a string by key name
843	Load	Load stringlist from stream.

21.17.3 TStringList.Load

Synopsis: Load stringlist from stream.

Declaration: `constructor Load(var S: TStream)`

Visibility: default

Description: The `Load` constructor reads the `TStringList` object from the stream `S`. It also reads the descriptions of the strings from the stream. The string descriptions are stored as an array of `TStrIndexrec` records, where each record describes a string on the stream. These records are kept in memory.

Errors: If an error occurs, a stream error is triggered.

See also: `TStringList.Done` ([843](#))

21.17.4 TStringList.Done

Synopsis: Clean up the instance

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor frees the memory occupied by the string descriptions, and destroys the object.

Errors: None.

See also: `TStringList.Load` ([843](#)), `TObject.Done` ([814](#))

21.17.5 TStringList.Get

Synopsis: Return a string by key name

Declaration: `function Get(Key: Sw_Word) : String`

Visibility: default

Description: `Get` reads the string with key `Key` from the list of strings on the stream, and returns this string. If there is no string with such a key, an empty string is returned.

Errors: If no string with key `Key` is found, an empty string is returned. A stream error may result if the stream doesn't contain the needed strings.

See also: `TStrListMaker.Put` ([844](#))

21.18 TStrListMaker

21.18.1 Description

The `TStrListMaker` object can be used to generate a stream with strings, which can be read with the `TStringList` object. If you register this object with the `RegisterType` (785) function, you cannot register the `TStringList` object.

21.18.2 Method overview

Page	Property	Description
844	<code>Done</code>	Clean up the instance and free all related memory.
844	<code>Init</code>	Instantiate a new instance of <code>TStrListMaker</code>
844	<code>Put</code>	Add a new string to the list with associated key.
845	<code>Store</code>	Write the strings to the stream.

21.18.3 TStrListMaker.Init

Synopsis: Instantiate a new instance of `TStrListMaker`

Declaration: constructor `Init (AStrSize: Sw_Word; AIndexSize: Sw_Word)`

Visibility: default

Description: The `Init` constructor creates a new instance of the `TstrListMaker` object. It allocates `AStrSize` bytes on the heap to hold all the strings you wish to store. It also allocates enough room for `AIndexSize` key description entries (of the type `TStrIndexrec`).

`AStrSize` must be large enough to contain all the strings you wish to store. If not enough memory is allocated, other memory will be overwritten. The same is true for `AIndexSize` : maximally `AIndexSize` strings can be written to the stream.

Errors: None.

See also: `TObject.Init` (812), `TStrListMaker.Done` (844)

21.18.4 TStrListMaker.Done

Synopsis: Clean up the instance and free all related memory.

Declaration: destructor `Done; Virtual`

Visibility: default

Description: The `Done` destructor de-allocates the memory for the index description records and the string data, and then destroys the object.

Errors: None.

See also: `TObject.Done` (814), `TStrListMaker.Init` (844)

21.18.5 TStrListMaker.Put

Synopsis: Add a new string to the list with associated key.

Declaration: procedure `Put (Key: Sw_Word; S: String)`

Visibility: default

Description: `Put` adds the string `S` with key `Key` to the collection of strings. This action doesn't write the string to a stream. To write the strings to the stream, see the `Store` (845) method.

Errors: None.

See also: `TStrListMaker.Store` (845)

21.18.6 TStrListMaker.Store

Synopsis: Write the strings to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection of strings to the stream `S`. The collection can then be read with the `TStringList` object.

Errors: A stream error may occur when writing the strings to the stream.

See also: `TStringList.Load` (843), `TStrListMaker.Put` (844)

21.19 TUnSortedStrCollection

21.19.1 Description

The `TUnSortedStrCollection` object manages an unsorted list of strings. To this end, it overrides the `TStringCollection.Insert` (840) method to add strings at the end of the collection, rather than in the alphabetically correct position.

Take care, the `Search` (827) and `IndexOf` (793) methods will not work on an unsorted string collection.

21.19.2 Method overview

Page	Property	Description
845	<code>Insert</code>	Insert a new string in the collection.

21.19.3 TUnSortedStrCollection.Insert

Synopsis: Insert a new string in the collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts a string at the end of the collection, instead of on its alphabetical place, resulting in an unsorted collection of strings.

Errors: None.

See also: `TCollection.Insert` (799)

Listing: `./objectex/ex39.pp`

```
Program ex39;  
  
{ Program to demonstrate the TUnsortedStrCollection.Insert method }  
  
Uses Objects , Strings ;  
  
Var C : PUnsortedStrCollection ;  
      S : String ;  
      I : longint ;  
      P : Pchar ;  
  
begin  
  Randomize ;  
  C:=New(PUnsortedStrCollection , Init(120,10));  
  Writeln ( 'Inserting 100 records at random places.' );  
  For I:=1 to 100 do  
    begin  
      Str(Random(100),S);  
      S:= 'String with value ' + S;  
      C^. Insert(NewStr(S));  
    end ;  
  For I:=0 to 99 do  
    Writeln ( I:2, ' : ', PString(C^. At(i))^ );  
  Dispose(C,Done);  
end.
```

Chapter 22

Reference for unit 'objpas'

22.1 Overview

The `objpas` unit is meant for compatibility with Object Pascal as implemented by Delphi. The unit is loaded automatically by the Free Pascal compiler whenever the `Delphi` or `objfpc` more is entered, either through the command line switches `-Sd` or `-Sh` or with the `{ $MODE DELPHI }` or `{ $MODE OBJFPC }` directives.

It redefines some basic pascal types, introduces some functions for compatibility with Delphi's system unit, and introduces some methods for the management of the resource string tables.

22.2 Constants, types and variables

22.2.1 Constants

`MaxInt = MaxLongint`

Maximum value for Integer (847) type.

22.2.2 Types

`Integer = LongInt`

In OBJPAS mode and in DELPHI mode, an `Integer` has a size of 32 bit. In TP or regular FPC mode, an integer is 16 bit.

`IntegerArray = Array[0..$efffffff] of Integer`

Generic array of integer (847)

`PInteger = ^Integer`

Pointer to Integer (847) type.

`PIntegerArray = ^IntegerArray`

Pointer to TIntegerArray (848) type.

`PointerArray = Array[0..512*1024*1024-2] of Pointer`

Generic Array of pointers.

`PPointerArray = ^PointerArray`

Pointer to PointerArray (848)

`PResStringRec = ^AnsiString`

Pointer to ansistring (Delphi compatibility).

`PString = PAnsiString`

Pointer to ansistring type.

`TBoundArray = Array[] of Integer`

Array of integer, used in interfaces.

`TIntegerArray = IntegerArray`

Alias for IntegerArray (847)

`TPointerArray = PointerArray`

Alias for PointerArray (848)

`TResourceIterator = function(Name: AnsiString;Value: AnsiString;
Hash: LongInt;arg: pointer) : AnsiString`

The resource string tables can be managed with a callback function which the user must provide:

`TResourceIterator.`

`TResStringRec = AnsiString`

Ansistring record in resource table (Delphi compatibility).

22.3 Procedures and functions

22.3.1 AssignFile

Synopsis: Assign text or untyped file

Declaration: `procedure AssignFile(var f: File;const Name: String)`
`procedure AssignFile(var f: File;p: pchar)`
`procedure AssignFile(var f: File;c: Char)`
`procedure AssignFile(var t: Text;const s: String)`
`procedure AssignFile(var t: Text;p: pchar)`
`procedure AssignFile(var t: Text;c: Char)`
`procedure AssignFile(var f: TypedFile;const Name: String)`
`procedure AssignFile(var f: TypedFile;p: pchar)`
`procedure AssignFile(var f: TypedFile;c: Char)`

Visibility: default

Description: AssignFile is completely equivalent to the system unit's Assign (1116) function: It assigns Name to a function of any type (FileType can be Text or a typed or untyped File variable). Name can be a string, a single character or a PChar.

It is most likely introduced to avoid confusion between the regular Assign (1116) function and the Assign method of TPersistent in the Delphi VCL.

Errors: None.

See also: CloseFile (849), #rtl.system.Assign (1116), #rtl.system.Reset (1234), #rtl.system.Rewrite (1236), #rtl.system.Append (1114)

Listing: ./refex/ex88.pp

Program Example88;

{ Program to demonstrate the AssignFile and CloseFile functions. }

{ \$MODE Delphi }

Var F : text;

begin

 AssignFile(F, 'textfile.tmp');

 Rewrite(F);

 WriteLn (F, 'This is a silly example of AssignFile and CloseFile.');

 CloseFile(F);

end.

22.3.2 CloseFile

Synopsis: Close text or untyped file

Declaration: procedure CloseFile(var f: File)
 procedure CloseFile(var t: Text)

Visibility: default

Description: CloseFile flushes and closes a file F of any file type. F can be Text or a typed or untyped File variable. After a call to CloseFile, any attempt to write to the file F will result in an error.

It is most likely introduced to avoid confusion between the regular Close (1123) function and the Close method of TForm in the Delphi VCL.

for an example, see AssignFile (848).

Errors: None.

See also: #rtl.system.Close (1123), AssignFile (848), #rtl.system.Reset (1234), #rtl.system.Rewrite (1236), #rtl.system.Append (1114)

22.3.3 GetStringCurrentValue

Synopsis: Return current value of resourcestring

Declaration: function GetStringCurrentValue(TableIndex: LongInt;
 StringIndex: LongInt) : AnsiString

Visibility: default

Description: `GetResourceStringCurrentValue` returns the current value of the resourcestring in table `TableIndex` with index `StringIndex`.

The current value depends on the system of internationalization that was used, and which language is selected when the program is executed.

Errors: If either `TableIndex` or `StringIndex` are out of range, then a empty string is returned.

See also: `SetResourceStrings` (854), `GetResourceStringDefaultValue` (850), `GetResourceStringHash` (851), `GetResourceStringName` (851), `ResourceStringTableCount` (854), `ResourceStringCount` (854)

Listing: `./refex/ex90.pp`

Program `Example90`;

```
{ Program to demonstrate the GetResourceStringCurrentValue function. }
{ $Mode Delphi }
```

`ResourceString`

```
First = 'First string';
Second = 'Second String';
```

`Var I,J : Longint;`

begin

```
{ Print current values of all resourcestrings }
For I:=0 to ResourceStringTableCount-1 do
  For J:=0 to ResourceStringCount(i)-1 do
    Writeln ( I, ', ', J, ' : ', GetResourceStringCurrentValue ( I, J ));
```

end.

22.3.4 GetResourceStringDefaultValue

Synopsis: Return default (original) value of resourcestring

Declaration: `function GetResourceStringDefaultValue (TableIndex: LongInt;
StringIndex: LongInt) : AnsiString`

Visibility: default

Description: `GetResourceStringDefaultValue` returns the default value of the resourcestring in table `TableIndex` with index `StringIndex`.

The default value is the value of the string that appears in the source code of the programmer, and is compiled into the program.

Errors: If either `TableIndex` or `StringIndex` are out of range, then a empty string is returned.

See also: `SetResourceStrings` (854), `GetResourceStringCurrentValue` (849), `GetResourceStringHash` (851), `GetResourceStringName` (851), `ResourceStringTableCount` (854), `ResourceStringCount` (854)

Listing: `./refex/ex91.pp`

Program Example91;

```
{ Program to demonstrate the GetStringDefaultValue function. }
{$Mode Delphi}
```

```
ResourceString
```

```
    First  = 'First string';
    Second = 'Second String';
```

```
Var I,J : Longint;
```

```
begin
```

```
    { Print default values of all resourcestrings }
```

```
    For I:=0 to ResourceStringTableCount-1 do
```

```
        For J:=0 to ResourceStringCount(i)-1 do
```

```
            WriteLn (I,',',J,' : ',GetStringDefaultValue(I,J));
```

```
end.
```

22.3.5 GetStringHash

Synopsis: Return hash value of resource string

Declaration: function GetStringHash(TableIndex: LongInt; StringIndex: LongInt)
: LongInt

Visibility: default

Description: GetStringHash returns the hash value associated with the resource string in table TableIndex, with index StringIndex.

The hash value is calculated from the default value of the resource string in a manner that gives the same result as the GNU gettext mechanism. It is stored in the resourcestring tables, so retrieval is faster than actually calculating the hash for each string.

For an example, see Hash (852).

Errors: If either TableIndex or StringIndex is zero, 0 is returned.

See also: Hash (852), SetResourceStrings (854), GetStringDefaultValue (850), GetStringHash (851), GetStringName (851), ResourceStringTableCount (854), ResourceStringCount (854)

22.3.6 GetStringName

Synopsis: Return name of resource string.

Declaration: function GetStringName(TableIndex: LongInt; StringIndex: LongInt)
: Ansistring

Visibility: default

Description: GetStringName returns the name of the resourcestring in table TableIndex with index StringIndex. The name of the string is always the unit name in which the string was declared, followed by a period and the name of the constant, all in lowercase.

If a unit MyUnit declares a resourcestring MyTitle then the name returned will be myunit.mytitle. A resourcestring in the program file will have the name of the program prepended.

The name returned by this function is also the name that is stored in the resourcestring file generated by the compiler.

Strictly speaking, this information isn't necessary for the functioning of the program, it is provided only as a means to easier translation of strings.

Errors: If either `TableIndex` or `StringIndex` is zero, an empty string is returned.

See also: `SetResourceStrings` (854), `GetResourceStringDefaultValue` (850), `GetResourceStringHash` (851), `GetResourceStringName` (851), `ResourceStringTableCount` (854), `ResourceStringCount` (854)

Listing: ./refex/ex92.pp

Program Example92;

```
{ Program to demonstrate the GetResourceStringName function. }
{$Mode Delphi}
```

ResourceString

```
First = 'First string';
Second = 'Second String';
```

Var I,J : Longint;

begin

```
{ Print names of all resourcestrings }
For I:=0 to ResourceStringTableCount-1 do
  For J:=0 to ResourceStringCount(I)-1 do
    Writeln (I, ', ', J, ' : ', GetResourceStringName(I, J));
```

end.

22.3.7 Hash

Synopsis: Create GNU Gettext hash value for a string

Declaration: `function Hash(S: AnsiString) : LongInt`

Visibility: default

Description: `Hash` calculates the hash value of the string `S` in a manner that is compatible with the GNU gettext hash value for the string. It is the same value that is stored in the Resource string tables, and which can be retrieved with the `GetResourceStringHash` (851) function call.

Errors: None. In case the calculated hash value should be 0, the returned result will be -1.

See also: `GetResourceStringHash` (851)

Listing: ./refex/ex93.pp

Program Example93;

```
{ Program to demonstrate the Hash function. }
{$Mode Delphi}
```

ResourceString

```
First = 'First string';
```

```

    Second = 'Second String';

    Var I,J : Longint;

    begin
        For I:=0 to ResourceStringTableCount-1 do
            For J:=0 to ResourceStringCount(i)-1 do
                If Hash( GetResourceStringDefaultValue(I,J))
                    <>GetResourceStringHash(I,J) then
                    WriteLn ( 'Hash mismatch at ',I,', ',J)
                else
                    WriteLn ( 'Hash ( ',I,', ',J, ' ) matches. ');
            end.
    end.

```

22.3.8 LoadResString

Synopsis: Load resource string

Declaration: `function LoadResString(p: PResStringRec) : AnsiString`

Visibility: default

22.3.9 ParamStr

Synopsis: Return command-line parameter

Declaration: `function ParamStr(Param: Integer) : Ansistring`

Visibility: default

Description: `ParamStr` returns the `Param`-th command-line parameter as an `AnsiString`. The system unit `Paramstr` ([853](#)) function limits the result to 255 characters, and is overridden with this function.

The zeroeth command-line parameter contains the path of the executable. On some operating systems (BSD) it may be simply the command as typed on the command-line, because the OS does not offer a method to retrieve the full binary name.

For an example, see `#rtl.system.Paramstr` ([1227](#)).

Errors: In case `Param` is an invalid value, an empty string is returned.

See also: `Paramstr` ([853](#))

22.3.10 ResetResourceTables

Synopsis: Restore all resource strings to their declared values

Declaration: `procedure ResetResourceTables`

Visibility: default

Description: `ResetResourceTables` resets all resource strings to their default (i.e. as in the source code) values.

Normally, this should never be called from a user's program. It is called in the initialization code of the `objpas` unit. However, if the `resourcetables` get messed up for some reason, this procedure will fix them again.

Errors: None.

See also: [SetResourceStrings \(854\)](#), [GetResourceStringDefaultValue \(850\)](#), [GetResourceStringHash \(851\)](#), [GetResourceStringName \(851\)](#), [ResourceStringTableCount \(854\)](#), [ResourceStringCount \(854\)](#)

22.3.11 ResourceStringCount

Synopsis: Return number of resource strings in table

Declaration: `function ResourceStringCount (TableIndex: LongInt) : LongInt`

Visibility: default

Description: `ResourceStringCount` returns the number of resource strings in the table with index `TableIndex`. The strings in a particular table are numbered from 0 to `ResourceStringCount-1`, i.e. they're zero based.

For an example, see [GetResourceStringDefaultValue \(850\)](#)

Errors: If an invalid `TableIndex` is given, -1 is returned.

See also: [SetResourceStrings \(854\)](#), [GetResourceStringCurrentValue \(849\)](#), [GetResourceStringDefaultValue \(850\)](#), [GetResourceStringHash \(851\)](#), [GetResourceStringName \(851\)](#), [ResourceStringTableCount \(854\)](#)

22.3.12 ResourceStringTableCount

Synopsis: Return number of resource string tables

Declaration: `function ResourceStringTableCount : LongInt`

Visibility: default

Description: `ResourceStringTableCount` returns the number of resource string tables; this may be zero if no resource strings are used in a program.

The tables are numbered from 0 to `ResourceStringTableCount-1`, i.e. they're zero based.

For an example, see [GetResourceStringDefaultValue \(850\)](#)

Errors:

See also: [SetResourceStrings \(854\)](#), [GetResourceStringDefaultValue \(850\)](#), [GetResourceStringHash \(851\)](#), [GetResourceStringName \(851\)](#), [ResourceStringCount \(854\)](#)

22.3.13 SetResourceStrings

Synopsis: Set values of all resource strings.

Declaration: `procedure SetResourceStrings (SetFunction: TResourceIterator;
arg: pointer)`

Visibility: default

Description: `SetResourceStrings` calls `SetFunction` for all resource strings in the resource string tables and sets the resource string's current value to the value returned by `SetFunction`.

The `Name`, `Value` and `Hash` parameters passed to the iterator function are the values stored in the tables.

Errors: None.

See also: [GetResourceStringCurrentValue \(849\)](#), [GetResourceStringDefaultValue \(850\)](#), [GetResourceStringHash \(851\)](#), [GetResourceStringName \(851\)](#), [ResourceStringTableCount \(854\)](#), [ResourceStringCount \(854\)](#)

Listing: ./refex/ex95.pp

Program Example95;

```
{ Program to demonstrate the SetResourceStrings function. }
{$Mode objfpc}
```

ResourceString

```
First = 'First string';
Second = 'Second String';
```

```
Var I,J : Longint;
    S : AnsiString;
```

Function Translate (**Name**, Value : AnsiString; Hash : longint): AnsiString;

begin

```
WriteLn ( 'Translate ( ',Name, ' ) => ',Value);
Write ( '→');
ReadLn (Result);
```

end;

begin

```
SetResourceStrings(@Translate);
WriteLn ( 'Translated strings : ');
For I:=0 to ResourceStringTableCount-1 do
  For J:=0 to ResourceStringCount(i)-1 do
    begin
      WriteLn ( GetResourceStringDefaultValue(I,J));
      WriteLn ( 'Translates to : ');
      WriteLn ( GetResourceStringCurrentValue(I,J));
    end;
```

end.

22.3.14 SetResourceStringValue

Synopsis: Set value of a resource string

Declaration: function SetResourceStringValue(TableIndex: LongInt;
StringIndex: LongInt;Value: Ansistring)
: Boolean

Visibility: default

Description: SetResourceStringValue assigns Value to the resource string in table TableIndex with index StringIndex.

Errors:

See also: [SetResourceStrings \(854\)](#), [GetResourceStringCurrentValue \(849\)](#), [GetResourceStringDefaultValue \(850\)](#), [GetResourceStringHash \(851\)](#), [GetResourceStringName \(851\)](#), [ResourceStringTableCount \(854\)](#), [ResourceStringCount \(854\)](#)

Listing: ./refex/ex94.pp

Program Example94;

```
{ Program to demonstrate the SetResourceStringValue function. }  
{ $Mode Delphi }
```

ResourceString

```
First  = 'First string';  
Second = 'Second String';
```

```
Var I,J : Longint;  
      S : AnsiString;
```

begin

```
{ Print current values of all resourcestrings }  
For I:=0 to ResourceStringTableCount-1 do  
  For J:=0 to ResourceStringCount(i)-1 do  
    begin  
      Writeln ( 'Translate => ',GetResourceStringDefaultValue(I,J));  
      Write    ( '→');  
      Readln(S);  
      SetResourceStringValue(I,J,S);  
    end;  
  Writeln ( 'Translated strings : ');  
  For I:=0 to ResourceStringTableCount-1 do  
    For J:=0 to ResourceStringCount(i)-1 do  
      begin  
        Writeln ( GetResourceStringDefaultValue(I,J));  
        Writeln ( 'Translates to : ');  
        Writeln ( GetResourceStringCurrentValue(I,J));  
      end;
```

end.

Chapter 23

Reference for unit 'oldlinux'

23.1 Utility routines

Auxiliary functions that are useful in connection with the other functions.

Table 23.1:

Name	Description
CreateShellArgV (918)	Create an array of pchars from string
EpochToLocal (921)	Convert epoch time to local time
FD_Clr (932)	Clear item of select filedescriptors
FD_IsSet (932)	Check item of select filedescriptors
FD_Set (932)	Set item of select filedescriptors
FD_ZERO (933)	Clear all items in select filedescriptors
LocalToEpoch (951)	Convert local time to epoch time
MMap (954)	Map a file into memory
MUnMap (955)	Unmap previously mapped memory file
Octal (957)	Convert octal to digital
S_ISBLK (973)	Check file mode for block device
S_ISCHR (974)	Check file mode for character device
S_ISDIR (974)	Check file mode for directory
S_ISFIFO (974)	Check file mode for FIFO
S_ISLNK (974)	Check file mode for symboloc link
S_ISREG (975)	Check file mode for regular file
S_ISSOCK (975)	Check file mode for socket
StringToPPchar (970)	Create an array of pchars from string

23.2 Terminal functions

Functions for controlling the terminal to which the process is connected.

23.3 System information

Functions for retrieving system information such as date and time.

Table 23.2:

Name	Description
CFMakeRaw (913)	Set terminal to raw mode
CFSetISpeed (913)	Set terminal reading speed
CFSetOSpeed (913)	Set terminal writing speed
IOCtl (948)	General IO control call
IsATTY (950)	See if filedescriptor is a terminal
TCDrain (976)	Wait till all output was written
TCFlow (976)	Suspend transmission or receipt of data
TCFlush (976)	Discard data written to terminal
TCGetAttr (977)	Get terminal attributes
TCGetPGrp (977)	Return PID of foreground process
TCSendBreak (978)	Send data for specific time
TCSetAttr (978)	Set terminal attributes
TCSetPGrp (979)	Set foreground process
TTYName (979)	Name of tty file

Table 23.3:

Name	Description
GetDate (939)	Return system date
GetDateTime (939)	Return system date and time
GetDomainName (940)	Return system domain name
GetEpochTime (941)	Return epoch time
GetHostName (943)	Return system host name
GetLocalTimezone (944)	Return system timezone
GetTime (946)	Return system time
GetTimeOfDay (946)	Return system time
GetTimezoneFile (947)	Return name of timezone file
ReadTimezoneFile (962)	Read timezone file contents
SysInfo (972)	Return general system information
Uname (980)	Return system information

23.4 Signals

Functions for managing and responding to signals.

23.5 Process handling

Functions for managing processes and programs.

23.6 Directory handling routines

Functions for reading and searching directories.

Table 23.4:

Name	Description
Alarm (909)	Send alarm signal to self
Kill (950)	Send arbitrary signal to process
pause (959)	Wait for signal to arrive
SigAction (966)	Set signal action
Signal (967)	Set signal action
SigPending (968)	See if signals are waiting
SigProcMask (968)	Set signal processing mask
SigRaise (969)	Send signal to self
SigSuspend (970)	Sets signal mask and waits for signal
NanoSleep (956)	Waits for a specific amount of time

23.7 Pipes, FIFOs and streams

Functions for creating and managing pipes.

23.8 General File handling routines

Functions for handling files on disk.

23.9 File Input/Output routines

Functions for handling file input/output.

23.10 Overview

This document describes the LINUX unit for Free Pascal. The unit was written by Michael van Canneyt. It works only on the Linux/BSD operating systems.

23.11 Constants, types and variables

23.11.1 Constants

B0 = \$00000000

B110 = \$00000003

B115200 = \$0001002

B1200 = \$00000009

Table 23.5:

Name	Description
Clone (916)	Create a thread
Execl (922)	Execute process with command-line list
Execle (923)	Execute process with command-line list and environment
Execlp (923)	Search in path and execute process with command list
Execv (924)	Execute process
Execve (925)	Execute process with environment
Execvp (926)	Search in path and execute process
Fork (935)	Spawn child process
GetEGid (940)	Get effective group id
GetEnv (941)	Get environment variable
GetEUid (942)	Get effective user id
GetGid (943)	Get group id
GetPid (944)	Get process id
GetPPid (945)	Get parent process id
GetPriority (945)	Get process priority
GetUid (947)	Get user id
Nice (957)	Change priority of process
SetPriority (965)	Change priority of process
Shell (965)	Execute shell command
WaitPid (982)	Wait for child process to terminate

Table 23.6:

Name	Description
CloseDir (918)	Close directory handle
Glob (947)	Return files matching a search expression
GlobFree (948)	Free result of Glob
OpenDir (958)	Open directory for reading
ReadDir (960)	Read directory entry
SeekDir (962)	Seek directory
TellDir (979)	Seek directory

B134 = \$0000004

B150 = \$0000005

B1800 = \$000000A

B19200 = \$000000E

B200 = \$0000006

B230400 = \$0001003

Table 23.7:

Name	Description
AssignPipe (910)	Create a pipe
AssignStream (911)	Create pipes to program's input and output
MkFifo (954)	Make a fifo
PClose (959)	Close a pipe
POpen (959)	Open a pipe for to program's input or output

Table 23.8:

Name	Description
Access (908)	Check access rights on file
BaseName (912)	Return name part of file
Chown (915)	Change owner of file
Chmod (914)	Change access rights on file
DirName (919)	Return directory part of file
FSplit (936)	Split filename in parts
FExpand (933)	Return full-grown filename
FLock (933)	Set lock on a file
FNMatch (934)	Match filename to searchpattern
FSearch (936)	Search for a file in a path
FStat (937)	Return filesystem information
FStat (938)	Return file information
FRename (935)	Rename file
LStat (952)	Return information on a link
Link (950)	Create a link
ReadLink (961)	Read contents of a symbolic link
SymLink (971)	Create a symbolic link
Umask (980)	Set the file creation mask
UnLink (980)	Remove a file
Utime (981)	Change file timestamps

B2400 = \$000000B

B300 = \$0000007

B38400 = \$000000F

B460800 = \$0001004

B4800 = \$000000C

B50 = \$0000001

B57600 = \$0001001

Table 23.9:

Name	Description
Dup (920)	Duplicate a file handle
Dup2 (920)	Copy one file handle to another
Fcntl (927)	General file control
fdClose (928)	Close file descriptor
fdFlush (928)	Flush file descriptor
fdOpen (929)	Open new file descriptor
fdRead (930)	Read from file descriptor
fdSeek (931)	Position in file
fdTruncate (931)	Truncate file
fdWrite (932)	Write to file descriptor
GetFS (942)	Get file descriptor of pascal file
Select (962)	Wait for input from file descriptor
SelectText (964)	Wait for input from pascal file

B600 = \$0000008

B75 = \$0000002

B9600 = \$000000D

BRKINT = \$0000002

BS0 = \$0000000

BS1 = \$0002000

BSDLY = \$0002000

CBAUD = \$000100F

CBAUDEX = \$0001000

CIBAUD = \$100F0000

CLOCAL = \$0000800

CLONE_FILES = \$00000400

Clone (916) option: open files shared between processes

CLONE_FS = \$00000200

Clone (916) option: fs info shared between processes

CLONE_PID = \$00001000

Clone (916) option: PID shared between processes

CLONE_SIGHAND = \$00000800

Clone (916) option: signal handlers shared between processes

CLONE_VM = \$00000100

Clone (916) option: VM shared between processes

CMSPAR = \$40000000

CR0 = \$00000000

CR1 = \$0000200

CR2 = \$0000400

CR3 = \$0000600

CRDLY = \$0000600

CREAD = \$0000080

CRTSCTS = \$80000000

CS5 = \$0000000

CS6 = \$0000010

CS7 = \$0000020

CS8 = \$0000030

CSIGNAL = \$000000ff

Clone (916) option: Signal mask to be sent at exit

CSize = \$0000030

CStopB = \$0000040

ECHO = \$0000008

ECHOCTL = \$0000200

ECHOE = \$0000010

ECHOK = \$0000020

ECHOKE = \$0000800

ECHONL = \$0000040

ECHOPRT = \$0000400

EXTA = B19200

EXTB = B38400

FF0 = \$0000000

FF1 = \$0008000

FFDLY = \$0008000

FIOASYNC = \$5452

FIOCLEX = \$5451

FIONBIO = \$5421

FIONCLEX = \$5450

FIONREAD = \$541B

FLUSHO = \$0001000

fs_ext = \$137d

File system type (FSStat (937)): (ext) Extended

fs_ext2 = \$ef53

File system type (FSStat (937)): (ext2) Second extended

fs_iso = \$9660

File system type (FSStat (937)): ISO 9660

fs_minix = \$137f

File system type (FSStat (937)): Minix

fs_minix_30 = \$138f

File system type (FSStat (937)): Minix 3.0

fs_minux_V2 = \$2468

File system type (FSStat (937)): Minix V2

fs_msdos = \$4d44

File system type (FSStat (937)): MSDOS (FAT)

fs_nfs = \$6969

File system type (FSStat (937)): NFS

fs_old_ext2 = \$ef51

File system type (FSStat (937)): (ext2) Old second extended

fs_proc = \$9fa0

File system type (FSStat (937)): PROC fs

fs_xia = \$012FD16D

File system type (FSStat (937)): XIA

F_GetFd = 1

FCntl (927) command: Get close-on-exec flag

F_GetFl = 3

FCntl (927) command: Get filedescriptor flags

F_GetLk = 5

FCntl (927) command: Get lock

F_GetOwn = 9

FCntl (927) command: get owner of filedescriptor events

F_OK = 0

Access (908) call test: file exists.

F_SetFd = 2

FCntl (927) command: Set close-on-exec flag

F_SetFl = 4

FCntl (927) command: Set filedescriptor flags

F_SetLk = 6

FCntl (927) command: Set lock

F_SetLkW = 7

FCntl (927) command: Test lock

F_SetOwn = 8

FCntl (927) command: Set owner of filedescriptor events

HUPCL = \$0000400

ICANON = \$0000002

ICRNL = \$0000100

IEXTEN = \$0008000

IGNBRK = \$0000001

IGNCR = \$00000080

IGNPAR = \$00000004

IMAXBEL = \$00020000

INLCR = \$00000040

INPCK = \$00000010

IOctl_TCGETS = \$5401

IOCTL call number: get Terminal Control settings

ISIG = \$00000001

ISTRIP = \$00000020

IUCLC = \$00002000

IXANY = \$00008000

IXOFF = \$00010000

IXON = \$00004000

LOCK_EX = 2

Flock (933) Exclusive lock

LOCK_NB = 4

Flock (933) Non-blocking operation

LOCK_SH = 1

Flock (933) Shared lock

LOCK_UN = 8

Flock (933) unlock

MAP_ANONYMOUS = \$20

MMap (954) map type: Don't use a file

MAP_DENYWRITE = 800

MMap (954) option: Ignored.

MAP_EXECUTABLE = 1000

MMap (954) option: Ignored.

MAP_FIXED = 10

MMap (954) map type: Interpret addr exactly

MAP_GROWSDOWN = 100

MMap (954) option: Memory grows downward (like a stack)

MAP_LOCKED = 2000

MMap (954) option: lock the pages in memory.

MAP_NORESERVE = 4000

MMap (954) option: Do not reserve swap pages for this memory.

MAP_PRIVATE = 2

MMap (954) map type: Changes are private

MAP_SHARED = 1

MMap (954) map type: Share changes

MAP_TYPE = f

MMap (954) map type: Bitmask for type of mapping

MINSIGSTKSZ = 2048

NCC = 8

Number of control characters in termio (904) record.

NCCS = 32

Number of control characters in termios (905) record.

NL0 = 00000000

NL1 = \$0000100

NLDLY = \$0000100

NOFLSH = \$0000080

OCRNL = \$0000008

OFDEL = \$0000080

OFILL = \$0000040

OLCUC = \$0000002

ONLCR = \$0000004

ONLRET = \$0000020

ONOCR = \$0000010

Open_Accmode = 3

Bitmask to determine access mode in open flags.

Open_Append = 2 shl 9

File open mode: Append to file

Open_Creat = 1 shl 6

File open mode: Create if file does not yet exist.

Open_Direct = 4 shl 12

File open mode: Minimize caching effects

Open_Directory = 2 shl 15

File open mode: File must be directory.

Open_Excl = 2 shl 6

File open mode: Open exclusively

`Open_LargeFile = 1 shl 15`

File open mode: Open for 64-bit I/O

`Open_NDelay = Open_NonBlock`

File open mode: Alias for `Open_NonBlock` (870)

`Open_NoCtty = 4 shl 6`

File open mode: No TTY control.

`Open_NoFollow = 4 shl 15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4 shl 9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1 shl 12`

File open mode: Write to disc at once

`Open_Trunc = 1 shl 9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`OPOST = $0000001`

`PARENB = $0000100`

`PARMRK = $0000008`

`PARODD = $0000200`

PENDIN = \$0004000

Prio_PGrp = 1

Get/set process group priority

Prio_Process = 0

Get/Set process priority

Prio_User = 2

Get/set user priority

PROT_EXEC = \$4

MMap (954) memory access: page can be executed

PROT_NONE = \$0

MMap (954) memory access: page can not be accessed

PROT_READ = \$1

MMap (954) memory access: page can be read

PROT_WRITE = \$2

MMap (954) memory access: page can be written

P_IN = 1

Input file descriptor of pipe pair.

P_OUT = 2

Output file descriptor of pipe pair.

R_OK = 4

Access (908) call test: read allowed

SA_INTERRUPT = \$20000000

Sigaction options: ?

SA_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA_NOMASK = \$40000000

Sigaction options: Do not prevent the signal from being received when it is handled.

SA_ONESHOT = \$80000000

Sigaction options: Restore the signal action to the default state.

SA_ONSTACK = SA_STACK

Socket option

SA_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA_SHIRQ = \$04000000

Sigaction options: ?

SA_STACK = \$08000000

Sigaction options: Call the signal handler on an alternate signal stack.

Seek_Cur = 1

Seek option: Set position relative to current position.

Seek_End = 2

Seek option: Set position relative to end of file.

Seek_set = 0

Seek option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTKSZ = 8192

Signal Stack size error

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTerm = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)

SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)

SIGUSR1 = 10

Signal: USR1 (User-defined signal 1)

SIGUSR2 = 12

Signal: USR2 (User-defined signal 2)

SIGVTALRM = 26

Signal: VTALRM (Virtual alarm clock)

SIGWINCH = 28

Signal: WINCH (Window/Terminal size change)

SIGXCPU = 24

Signal: XCPU (CPU limit exceeded)

SIGXFSZ = 25

Signal: XFSZ (File size limit exceeded)

SIG_BLOCK = 0

Sigprocmask flags: Add signals to the set of blocked signals.

SIG_DFL = 0

Signal handler: Default signal handler

SIG_ERR = -1

Signal handler: error

SIG_IGN = 1

Signal handler: Ignore signal

SIG_SETMASK = 2

Sigprocmask flags: Set of blocked signals is given.

SIG_UNBLOCK = 1

Sigprocmask flags: Remove signals from the set set of blocked signals.

SI_PAD_SIZE = ((128 / sizeof (longint)) - 3)

Signal information record pad bytes size. Do not use.

SS_DISABLE = 2

Socket options

SS_ONSTACK = 1

Socket options

STAT_IFBLK = \$6000

File (stat (903) record) mode: Block device

STAT_IFCHR = \$2000

File (stat (903) record) mode: Character device

STAT_IFDIR = \$4000

File (stat (903) record) mode: Directory

STAT_IFIFO = \$1000

File (stat (903) record) mode: FIFO

STAT_IFLNK = \$a000

File (stat (903) record) mode: Link

STAT_IFMT = \$f000

File (stat (903) record) mode: File type bit mask

STAT_IFREG = \$8000

File (stat (903) record) mode: Regular file

STAT_IFSOCK = \$c000

File (stat (903) record) mode: Socket

STAT_IRGRP = STAT_IROTH shl 3

File (stat (903) record) mode: Group read permission

STAT_IROTH = \$4

File (stat (903) record) mode: Other read permission

STAT_IRUSR = STAT_IROTH shl 6

File (stat (903) record) mode: Owner read permission

STAT_IRWXG = STAT_IRWXO shl 3

File (stat (903) record) mode: Group permission bits mask

STAT_IRWXO = \$7

File (stat (903) record) mode: Other permission bits mask

`STAT_IRWXU = STAT_IRWXO shl 6`

File (stat (903) record) mode: Owner permission bits mask

`STAT_ISGID = $0400`

File (stat (903) record) mode: GID bit set

`STAT_ISUID = $0800`

File (stat (903) record) mode: UID bit set

`STAT_ISVTX = $0200`

File (stat (903) record) mode: Sticky bit set

`STAT_IWGRP = STAT_IWOTH shl 3`

File (stat (903) record) mode: Group write permission

`STAT_IWOTH = $2`

File (stat (903) record) mode: Other write permission

`STAT_IWUSR = STAT_IWOTH shl 6`

File (stat (903) record) mode: Owner write permission

`STAT_IXGRP = STAT_IXOTH shl 3`

File (stat (903) record) mode: Others execute permission

`STAT_IXOTH = $1`

File (stat (903) record) mode: Others execute permission

`STAT_IXUSR = STAT_IXOTH shl 6`

File (stat (903) record) mode: Others execute permission

`syscall_nr_access = 33`

`syscall_nr_acct = 51`

`syscall_nr_adjtimex = 124`

`syscall_nr_afs_syscall = 137`

`syscall_nr_alarm = 27`

`syscall_nr_bdflush = 134`

`syscall_nr_break = 17`

`syscall_nr_brk = 45`

`syscall_nr_chdir = 12`

`syscall_nr_chmod = 15`

`syscall_nr_chown = 16`

`syscall_nr_chroot = 61`

`syscall_nr_clone = 120`

`syscall_nr_close = 6`

`syscall_nr_creat = 8`

`syscall_nr_create_module = 127`

`syscall_nr_delete_module = 129`

`syscall_nr_dup = 41`

`syscall_nr_dup2 = 63`

`syscall_nr_execve = 11`

`syscall_nr_exit = 1`

`syscall_nr_fchdir = 133`

`syscall_nr_fchmod = 94`

`syscall_nr_fchown = 95`

`syscall_nr_fcntl = 55`

`syscall_nr_fdatasync = 148`

`syscall_nr_flock = 143`

`syscall_nr_fork = 2`

`syscall_nr_fstat = 108`

`syscall_nr_fstatfs = 100`

`syscall_nr_fsync = 118`

`syscall_nr_ftime = 35`

`syscall_nr_ftruncate = 93`

`syscall_nr_getdents = 141`

`syscall_nr_getegid = 50`

`syscall_nr_geteuid = 49`

`syscall_nr_getgid = 47`

`syscall_nr_getgroups = 80`

`syscall_nr_getitimer = 105`

`syscall_nr_getpgid = 132`

`syscall_nr_getpgrp = 65`

`syscall_nr_getpid = 20`

syscall_nr_getppid = 64

syscall_nr_getpriority = 96

syscall_nr_getresuid = 165

syscall_nr_getrlimit = 76

syscall_nr_getrusage = 77

syscall_nr_getsid = 147

syscall_nr_gettimeofday = 78

syscall_nr_getuid = 24

syscall_nr_get_kernel_syms = 130

syscall_nr_gtty = 32

syscall_nr_idle = 112

syscall_nr_init_module = 128

syscall_nr_ioctl = 54

syscall_nr_ioperm = 101

syscall_nr_iopl = 110

syscall_nr_ipc = 117

syscall_nr_kill = 37

syscall_nr_link = 9

syscall_nr_lock = 53

`syscall_nr_lseek` = 19

`syscall_nr_lstat` = 107

`syscall_nr_mkdir` = 39

`syscall_nr_mknod` = 14

`syscall_nr_mlock` = 150

`syscall_nr_mlockall` = 152

`syscall_nr_mmap` = 90

`syscall_nr_modify_ldt` = 123

`syscall_nr_mount` = 21

`syscall_nr_mprotect` = 125

`syscall_nr_mpx` = 56

`syscall_nr_mremap` = 163

`syscall_nr_msync` = 144

`syscall_nr_munlock` = 151

`syscall_nr_munlockall` = 153

`syscall_nr_munmap` = 91

`syscall_nr_nanosleep` = 162

`syscall_nr_nice` = 34

`syscall_nr_oldfstat` = 28

```
syscall_nr_oldlstat = 84

syscall_nr_oldolduname = 59

syscall_nr_oldstat = 18

syscall_nr_olduname = 109

syscall_nr_open = 5

syscall_nr_pause = 29

syscall_nr_personality = 136

syscall_nr_phys = 52

syscall_nr_pipe = 42

syscall_nr_poll = 168

syscall_nr_prof = 44

syscall_nr_profil = 98

syscall_nr_ptrace = 26

syscall_nr_query_module = 167

syscall_nr_quotactl = 131

syscall_nr_read = 3

syscall_nr_readdir = 89

syscall_nr_readlink = 85

syscall_nr_readv = 145
```

`syscall_nr_reboot = 88`

`syscall_nr_rename = 38`

`syscall_nr_rmdir = 40`

`syscall_nr_sched_getparam = 155`

`syscall_nr_sched_getscheduler = 157`

`syscall_nr_sched_get_priority_max = 159`

`syscall_nr_sched_get_priority_min = 160`

`syscall_nr_sched_rr_get_interval = 161`

`syscall_nr_sched_setparam = 154`

`syscall_nr_sched_setscheduler = 156`

`syscall_nr_sched_yield = 158`

`syscall_nr_select = 82`

`syscall_nr_setdomainname = 121`

`syscall_nr_setfsgid = 139`

`syscall_nr_setfsuid = 138`

`syscall_nr_setgid = 46`

`syscall_nr_setgroups = 81`

`syscall_nr_sethostname = 74`

`syscall_nr_setitimer = 104`

syscall_nr_setpgid = 57

syscall_nr_setpriority = 97

syscall_nr_setregid = 71

syscall_nr_setresuid = 164

syscall_nr_setreuid = 70

syscall_nr_setrlimit = 75

syscall_nr_setsid = 66

syscall_nr_settimeofday = 79

syscall_nr_setuid = 23

syscall_nr_setup = 0

syscall_nr_sgetmask = 68

syscall_nr_sigaction = 67

syscall_nr_sigaltstack = 186

syscall_nr_signal = 48

syscall_nr_sigpending = 73

syscall_nr_sigprocmask = 126

syscall_nr_sigreturn = 119

syscall_nr_sigsuspend = 72

syscall_nr_socketcall = 102

syscall_nr_ssetmask = 69

syscall_nr_stat = 106

syscall_nr_statfs = 99

syscall_nr_stime = 25

syscall_nr_stty = 31

syscall_nr_swapoff = 115

syscall_nr_swapon = 87

syscall_nr_symlink = 83

syscall_nr_sync = 36

syscall_nr_sysfs = 135

syscall_nr_sysinfo = 116

syscall_nr_syslog = 103

syscall_nr_time = 13

syscall_nr_times = 43

syscall_nr_truncate = 92

syscall_nr_ulimit = 58

syscall_nr_umask = 60

syscall_nr_umount = 22

syscall_nr_uname = 122

syscall_nr_unlink = 10

syscall_nr_uselib = 86

syscall_nr_ustat = 62

syscall_nr_utime = 30

syscall_nr_vhangup = 111

syscall_nr_vm86 = 166

syscall_nr_vm86old = 113

syscall_nr_wait4 = 114

syscall_nr_waitpid = 7

syscall_nr_write = 4

syscall_nr_writev = 146

syscall_nr__llseek = 140

syscall_nr__newselect = 142

syscall_nr__sysctl = 149

Sys_E2BIG = 7

Sys_EACCES = 13

Sys_EADDRINUSE = 98

Sys_EADDRNOTAVAIL = 99

Sys_EADV = 68

`Sys_EAFNOSUPPORT = 97`

`Sys_EAGAIN = 11`

`Sys_EALREADY = 114`

`Sys_EBADE = 52`

`Sys_EBADF = 9`

`Sys_EBADFD = 77`

`Sys_EBADMSG = 74`

`Sys_EBADR = 53`

`Sys_EBADRQC = 56`

`Sys_EBADSLT = 57`

`Sys_EBFONT = 59`

`Sys_EBUSY = 16`

`Sys_ECHILD = 10`

`Sys_ECHRNG = 44`

`Sys_ECOMM = 70`

`Sys_ECONNABORTED = 103`

`Sys_ECONNREFUSED = 111`

`Sys_ECONNRESET = 104`

`Sys_EDEADLK = 35`

Sys_EDEADLOCK = 58

Sys_EDESTADDRREQ = 89

Sys_EDOM = 33

Sys_EDOTDOT = 73

Sys_EDQUOT = 122

Sys_EEXIST = 17

Sys_EFAULT = 14

Sys_EFBIG = 27

Sys_EHOSTDOWN = 112

Sys_EHOSTUNREACH = 113

Sys_EIDRM = 43

Sys_EILSEQ = 84

Sys_EINPROGRESS = 115

Sys_EINTR = 4

Sys_EINVAL = 22

Sys_EIO = 5

Sys_EISCONN = 106

Sys_EISDIR = 21

Sys_EISNAM = 120

Sys_EL2HLT = 51

Sys_EL2NSYNC = 45

Sys_EL3HLT = 46

Sys_EL3RST = 47

Sys_ELIBACC = 79

Sys_ELIBBAD = 80

Sys_ELIBEXEC = 83

Sys_ELIBMAX = 82

Sys_ELIBSCN = 81

Sys_ELN RNG = 48

Sys_ELOOP = 40

Sys_EMFILE = 24

Sys_EMLINK = 31

Sys_EMMSGSIZE = 90

Sys_EMULTIHOP = 72

Sys_ENAMETOOLONG = 36

Sys_ENAVAIL = 119

Sys_ENETDOWN = 100

Sys_ENETRESET = 102

Sys_ENETUNREACH = 101

Sys_ENFILE = 23

Sys_ENOANO = 55

Sys_ENOBUFS = 105

Sys_ENOCSI = 50

Sys_ENODATA = 61

Sys_ENODEV = 19

Sys_ENOENT = 2

Sys_ENOEXEC = 8

Sys_ENOLCK = 37

Sys_ENOLINK = 67

Sys_ENOMEM = 12

Sys_ENOMSG = 42

Sys_ENONET = 64

Sys_ENOPKG = 65

Sys_ENOPROTOOPT = 92

Sys_ENOSPC = 28

Sys_ENOSR = 63

Sys_ENOSTR = 60

Sys_ENOSYS = 38

Sys_ENOTBLK = 15

Sys_ENOTCONN = 107

Sys_ENOTDIR = 20

Sys_ENOTEMPTY = 39

Sys_ENOTNAM = 118

Sys_ENOTSOCK = 88

Sys_ENOTTY = 25

Sys_ENOTUNIQ = 76

Sys_ENXIO = 6

Sys_EOPNOTSUPP = 95

Sys_EOVERFLOW = 75

Sys_EPERM = 1

Sys_EPFNOSUPPORT = 96

Sys_EPIPE = 32

Sys_EPROTO = 71

Sys_EPROTONOSUPPORT = 93

Sys_EPROTOTYPE = 91

Sys_ERANGE = 34

Sys_EREMCHG = 78

Sys_EREMOTE = 66

Sys_EREMOTEIO = 121

Sys_ERESTART = 85

Sys_EROFS = 30

Sys_ERROR_MAX = \$fff

Sys_ESHUTDOWN = 108

Sys_ESOCKTNOSUPPORT = 94

Sys_ESPIPE = 29

Sys_ESRCH = 3

Sys_ESRMNT = 69

Sys_ESTALE = 116

Sys ESTRPIPE = 86

Sys_ETIME = 62

Sys_ETIMEDOUT = 110

Sys_ETOOMANYREFS = 109

Sys_ETXTBSY = 26

Sys_EUCLEAN = 117

Sys_EUNATCH = 49

Sys_EUSERS = 87

Sys_EWOULDBLOCK = Sys_EAGAIN

Sys_EXDEV = 18

Sys_EXFULL = 54

TAB0 = \$00000000

TAB1 = \$00008000

TAB2 = \$00010000

TAB3 = \$00018000

TABDLY = \$00018000

TCFLSH = \$540B

TCGETA = \$5405

TCGETS = \$5401

TCIFLUSH = 0

TCIOFF = 2

TCIOFLUSH = 2

TCION = 3

TCOFLUSH = 1

TCOOFF = 0

TCOON = 1

TCSADRAIN = 1

TCSAFLUSH = 2

TCSANOW = 0

TCSBRK = \$5409

TCSBRKP = \$5425

TCSETA = \$5406

TCSETAF = \$5408

TCSETAW = \$5407

TCSETS = \$5402

TCSETSF = \$5404

TCSETSW = \$5403

TCXONC = \$540A

TIOCCONS = \$541D

TIOCEXCL = \$540C

TIOCGETD = \$5424

TIOCGICOUNT = \$545D

TIOCGLOCKTRMIOS = \$5456

TIOCGPGRP = \$540F

TIOCGSERIAL = \$541E

TIOCGSOFTCAR = \$5419

TIOCGWINSZ = \$5413

TIOCINQ = FIONREAD

TIOCLINUX = \$541C

TIOCMBIC = \$5417

TIOCMBIS = \$5416

TIOCMGET = \$5415

TIOCMWAIT = \$545C

TIOCMSET = \$5418

TIOCM_CAR = \$040

TIOCM_CD = TIOCM_CAR

TIOCM_CTS = \$020

TIOCM_DSR = \$100

TIOCM_DTR = \$002

TIOCM_LE = \$001

TIOCM_OUT1 = \$2000

TIOCM_OUT2 = \$4000

TIOCM_RI = TIOCM_RNG

TIOCM_RNG = \$080

TIOCM_RTS = \$004

TIOCM_SR = \$010

TIOCM_ST = \$008

TIOCNOTTY = \$5422

TIOCNXCL = \$540D

TIOCOUTQ = \$5411

TIOCPKT = \$5420

TIOCPKT_DATA = 0

TIOCPKT_DOSTOP = 32

TIOCPKT_FLUSHREAD = 1

TIOCPKT_FLUSHWRITE = 2

TIOCPKT_NOSTOP = 16

TIOCPKT_START = 8

TIOCPKT_STOP = 4

TIOCSCTTY = \$540E

TIOCSEERCONFIG = \$5453

TIOCSEERGETLSR = \$5459

TIOCSEERGETMULTI = \$545A

TIOCSEERGSTRUCT = \$5458

TIOCSERGWILD = \$5454

TIOCSERSETMULTI = \$545B

TIOCSERSWILD = \$5455

TIOCSETD = \$5423

TIOCSLCKTRMIOS = \$5457

TIOCSPPGRP = \$5410

TIOCSSERIAL = \$541F

TIOCSSOFTCAR = \$541A

TIOCSTI = \$5412

TIOCSWINSZ = \$5414

TIOCTTYGSTRUCT = \$5426

TOSTOP = \$0000100

VDISCARD = 13

VEOF = 4

VEOL = 11

VEOL2 = 16

VERASE = 2

VINTR = 0

VKILL = 3

VLNEXT = 15

VMIN = 6

VQUIT = 1

VREPRINT = 12

VSTART = 8

VSTOP = 9

VSUSP = 10

VSWTC = 7

VT0 = \$00000000

VT1 = \$00040000

VTDLY = \$00040000

VTIME = 5

VWERASE = 14

Wait_Any = -1

WaitPID (982): Wait on any process

Wait_Clone = \$80000000

WaitPID (982): Wait on clone processes only.

Wait_MyPGRP = 0

WaitPID (982): Wait processes from current process group

Wait_NoHang = 1

WaitPID (982): Do not wait

Wait_UnTraced = 2

WaitPID (982): Also report stopped but untraced processes

WNOHANG = \$1

Waitpid (982) option: Do not wait for processes to terminate.

WUNTRACED = \$2

Waitpid (982) option: Also report children which were stopped but not yet reported

W_OK = 2

Access (908) call test: write allowed

XCASE = \$00000004

XTABS = \$0001800

X_OK = 1

Access (908) call test: execute allowed

__WCLONE = \$80000000

Waitpid option: Wait for clone children only

23.11.2 Types

ComStr =

Command-line string type.

dev_t = Word

Device descriptor type

```
dirent = packed record
  ino : LongInt;
  off : LongInt;
  reclen : Word;
  name : Array[0..255] of Char;
end
```

Record used in the ReadDir (960) function to return files in a directory.

DirStr =

Filename directory part string type.

ExtStr =

Filename extension part string type.

fdSet = Array[0..7] of LongInt

Array containing file descriptor bitmask for the Select (962) call.

NameStr =

Filename name part string type.

PathStr =

Filename path part string type.

PDir = ^TDir

Pointer to TDir (904) record

pdirent = ^dirent

Pointer to Dirent (899) record.

pfdsset = ^fdSet

Pointer to FDSet (932) array.

pfpstate = ^tfpstate

Pointer to tfpstate (905) record.

pglob = ^tglob

Pointer to TGlob (905) record.

PSigActionRec = ^SigActionRec

Pointer to SigActionRec (902) record.

PSigAltStack = ^SigAltStack

Pointer to SigAltStack (902) record

PSigContextRec = ^SigContextRec

Pointer to SigContextRec (902) record

PSignalHandler = ^SignalHandler

Pointer to SignalHandler (902) type.

```
PSignalRestorer = ^SignalRestorer
```

Pointer to SignalRestorer (902) type

```
PSigSet = ^SigSet
```

Pointer to signal set.

```
pstack_t = ^stack_t
```

Pointer to stack_t (903) record

```
PStat = ^Stat
```

Pointer to Stat (903) record.

```
PStatFS = ^Statfs
```

Pointer to StatFS (903) record.

```
PSysCallRegs = ^SysCallRegs
```

Pointer to SysCallRegs (904) record.

```
PSysInfo = ^TSysinfo
```

Pointer to TSysInfo (907) record.

```
ptimeval = ^timeval
```

Pointer to TTimeVal (907) record

```
ptimezone = ^timezone
```

Pointer to TimeZone (906) record.

```
PUTimeBuf = ^UTimeBuf
```

Pointer to UTimeBuf (907) record

```
PUTSName = ^utsname
```

Pointer to UTSName (908) record.

```
SigActionRec = packed record
  Handler : record
  end;
  Sa_Mask : SigSet;
  Sa_Flags : LongInt;
  Sa_restorer : SignalRestorer;
end
```

Record used in SigAction (966) call.

```
SigAltStack = record
  ss_sp : pointer;
  ss_flags : LongInt;
  ss_size : Size_T;
end
```

Alternate stack registers record

```
SigContextRec = record
  gs : Word;
  __gsh : Word;
  fs : Word;
  __fsh : Word;
  es : Word;
  __esh : Word;
  ds : Word;
  __dsh : Word;
  edi : cardinal;
  esi : cardinal;
  ebp : cardinal;
  esp : cardinal;
  ebx : cardinal;
  edx : cardinal;
  ecx : cardinal;
  eax : cardinal;
  trapno : cardinal;
  err : cardinal;
  eip : cardinal;
  cs : Word;
  __csh : Word;
  eflags : cardinal;
  esp_at_signal : cardinal;
  ss : Word;
  __ssh : Word;
  fpstate : pfpstate;
  oldmask : cardinal;
  cr2 : cardinal;
end
```

The above records contain information about the processor state and process state at the moment a signal is sent to your program.

```
SignalHandler = procedure(Sig: LongInt)
```

Function prototype for the Signal (967) call.

```
SignalRestorer = procedure
```

Signal restorer function prototype

```
SigSet = LongInt
```

Signal set type

```
Size_T = cardinal
```

Size type

```
stack_t = SigAltStack
```

Alias for SigAltStack (902) type

```
Stat = packed record
  dev : dev_t;
  pad1 : Word;
  ino : LongInt;
  mode : Word;
  nlink : Word;
  uid : Word;
  gid : Word;
  rdev : dev_t;
  pad2 : Word;
  size : LongInt;
  blksize : LongInt;
  blocks : LongInt;
  atime : LongInt;
  unused1 : LongInt;
  mtime : LongInt;
  unused2 : LongInt;
  ctime : LongInt;
  unused3 : LongInt;
  unused4 : LongInt;
  unused5 : LongInt;
end
```

Record describing an inode (file) in the fstat (938) call.

```
Statfs = packed record
  fstype : LongInt;
  bsize : LongInt;
  blocks : LongInt;
  bfree : LongInt;
  bavail : LongInt;
  files : LongInt;
  ffree : LongInt;
  fsid : LongInt;
  namelen : LongInt;
  spare : Array[0..6] of LongInt;
end
```

Record describing a file system in the fsstat (937) call.

```

SysCallRegs = record
  reg1 : LongInt;
  reg2 : LongInt;
  reg3 : LongInt;
  reg4 : LongInt;
  reg5 : LongInt;
  reg6 : LongInt;
end

```

Register describing system calls.

```

TCloneFunc = function(args: pointer) : LongInt

```

Clone function prototype.

```

TDir = packed record
  fd : Integer;
  loc : LongInt;
  size : Integer;
  buf : dirent;
  nextoff : LongInt;
  dd_max : Integer;
  lock : pointer;
end

```

Record used in [OpenDir \(958\)](#) and [ReadDir \(960\)](#) calls

```

TDirEnt = dirent

```

Alias for [DirEnt \(899\)](#) record

```

Termio = packed record
  c_iflag : Word;
  c_oflag : Word;
  c_cflag : Word;
  c_lflag : Word;
  c_line : Word;
  c_cc : Array[0..NCC-1] of Char;
end

```

Terminal I/O description record (small)

```

Termios = record
  c_iflag : Cardinal;
  c_oflag : Cardinal;
  c_cflag : Cardinal;
  c_lflag : Cardinal;
  c_line : Char;
  c_cc : Array[0..NCCS-1] of Byte;

```

```

    c_ispeed : LongInt;
    c_ospeed : LongInt;
end

```

Terminal I/O description record

```
TFDSet = fdSet
```

Alias for FDSets (932) type.

```

tfpreg = record
    significand : Array[0..3] of Word;
    exponent : Word;
end

```

Record describing floating point register in signal handler.

```

tfpstate = record
    cw : cardinal;
    sw : cardinal;
    tag : cardinal;
    ipoff : cardinal;
    cssel : cardinal;
    dataoff : cardinal;
    datasel : cardinal;
    st : Array[0..7] of tfpreg;
    status : cardinal;
end

```

Record describing floating point unit in signal handler.

```

tglob = record
    name : pchar;
    next : pglob;
end

```

Record containing one entry in the result of Glob (947)

```

timespec = packed record
    tv_sec : LongInt;
    tv_nsec : LongInt;
end

```

Time interval for the NanoSleep (956) function.

```

timeval = packed record
    sec : LongInt;
    usec : LongInt;
end

```

Record specifying a time interval.

```
timezone = packed record
  minuteswest : LongInt;
  dsttime : LongInt;
end
```

Record describing a timezone

```
tmapargs = record
  address : LongInt;
  size : LongInt;
  prot : LongInt;
  flags : LongInt;
  fd : LongInt;
  offset : LongInt;
end
```

Record containing mmap args.

```
Tpipe = Array[1..2] of LongInt
```

Array describing a pipe pair of filedescriptors.

```
TSigAction = procedure(Sig: LongInt; SigContext: SigContextRec)
```

Function prototype for SigAction (966) call.

```
TStat = Stat
```

Alias for Stat (903) record.

```
TStatFS = Statfs
```

Alias for StatFS (903) type.

```
TSysCallRegs = SysCallRegs
```

Alias for SysCallRegs (904) record

```
TSysinfo = packed record
  uptime : LongInt;
  loads : Array[1..3] of LongInt;
  totalram : LongInt;
  freeram : LongInt;
  sharedram : LongInt;
  bufferram : LongInt;
  totalswap : LongInt;
  freeswap : LongInt;
  procs : Integer;
  s : String;
end
```

Record with system information, used by the SysInfo (972) call.

```
TTermio = Termio
```

Alias for TermIO (904) record

```
TTermios = Termios
```

Alias for Termios (905) record.

```
TTimeVal = timeval
```

Alias for TimeVal (906) record.

```
TTimeZone = timezone
```

Alias for TimeZone (906) record.

```
TUTimeBuf = UTimeBuf
```

Alias for UTimBuf (907) record.

```
TUTSName = utsname
```

Alias for UTSName (908) record.

```
TWinSize = winsize
```

Alias for WinSize (908) record.

```
UTimBuf = packed record
  actime : LongInt;
  modtime : LongInt;
end
```

Record used in Utime (981) to set file access and modification times.

```
UTimeBuf = UTimBuf
```

Alias for UTimBuf (907) record.

```
utsname = packed record
  sysname : Array[0..64] of Char;
  nodename : Array[0..64] of Char;
  release : Array[0..64] of Char;
  version : Array[0..64] of Char;
  machine : Array[0..64] of Char;
  domainname : Array[0..64] of Char;
end
```


The elements of this record are null-terminated C style strings, you cannot access them directly.

```
winsize = packed record
  ws_row : Word;
  ws_col : Word;
  ws_xpixel : Word;
  ws_ypixel : Word;
end
```

Record describing terminal window size.

23.11.3 Variables

`ErrNo` : LongInt

Error number of last operation.

`LinuxError` : LongInt

`Linuxerror` is the variable in which the procedures in the linux unit report errors.

`tzdaylight` : Boolean

Indicates whether daylight savings time is active.

`tzname` : Array[boolean] of pchar

Timezone name.

`tzseconds` : LongInt

Seconds west of GMT

23.12 Procedures and functions

23.12.1 Access

Synopsis: Check file access

Declaration: `function Access(Path: PathStr; mode: Integer) : Boolean`

Visibility: default

Description: `Access` tests user's access rights on the specified file. `Mode` is a mask existing of one or more of the following:

R_OKUser has read rights.

W_OKUser has write rights.

X_OKUser has execute rights.

F_OKFile exists.

The test is done with the real user ID, instead of the effective user ID. If access is denied, or an error occurred, `False` is returned.

Errors: `LinuxError` is used to report errors:

sys_eaccess The requested access is denied, either to the file or one of the directories in its path.

sys_einval Mode was incorrect.

sys_enoent A directory component in `Path` doesn't exist or is a dangling symbolic link.

sys_enotdir A directory component in `Path` is not a directory.

sys_enomem Insufficient kernel memory.

sys_eloop `Path` has a circular symbolic link.

See also: `Chown` (915), `Chmod` (914)

Listing: `./olinuxex/ex26.pp`

Program `Example26`;

{ Program to demonstrate the Access function. }

Uses `oldlinux`;

begin

if `Access ('/etc/passwd', W_OK)` **then**

begin

WriteLn ('Better check your system.');

WriteLn ('I can write to the /etc/passwd file !');

end;

end.

23.12.2 Alarm

Synopsis: Schedule an alarm signal to be delivered

Declaration: `function Alarm(Sec: LongInt) : LongInt`

Visibility: `default`

Description: `Alarm` schedules an alarm signal to be delivered to your process in `Sec` seconds. When `Sec` seconds have elapsed, Linux will send a `SIGALRM` signal to the current process. If `Sec` is zero, then no new alarm will be set. Whatever the value of `Sec`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none.

See also: `SigAction` (966)

Listing: `./olinuxex/ex59.pp`

Program `Example59`;

{ Program to demonstrate the Alarm function. }

Uses `oldlinux`;

Procedure `AlarmHandler(Sig : longint); cdecl`;

```

begin
  Writeln ( 'Got to alarm handler' );
end;

begin
  Writeln ( 'Setting alarm handler' );
  Signal (SIGALRM, @AlarmHandler);
  Writeln ( 'Scheduling Alarm in 10 seconds' );
  Alarm (10);
  Writeln ( 'Pausing' );
  Pause;
  Writeln ( 'Pause returned' );
end.

```

23.12.3 AssignPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function AssignPipe (var pipe_in: LongInt; var pipe_out: LongInt) : Boolean`
`function AssignPipe (var pipe_in: text; var pipe_out: text) : Boolean`
`function AssignPipe (var pipe_in: file; var pipe_out: file) : Boolean`

Visibility: default

Description: `AssignPipe` creates a pipe, i.e. two file objects, one for input, one for output. What is written to `Pipe_out`, can be read from `Pipe_in`.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual `Readln (Pipe_in, ...)` and `Writeln (Pipe_out, ...)` procedures.

The function returns `True` if everything went successfully, `False` otherwise.

Errors: In case the function fails and returns `False`, `LinuxError` is used to report errors:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `POpen` ([959](#)), `MkFifo` ([954](#))

Listing: `./olinuxex/ex36.pp`

Program `Example36`;

{ Program to demonstrate the AssignPipe function. }

Uses `oldlinux`;

Var `pipi, pipo : Text`;
`s : String`;

begin
`Writeln ('Assigning Pipes.');`
`If Not assignpipe (pipi, pipo) then`

```

    Writeln('Error assigning pipes !',LinuxError);
    Writeln ('Writing to pipe, and flushing. ');
    Writeln (pipo,'This is a textstring');close(pipo);
    Writeln ('Reading from pipe. ');
    While not eof(pipi) do
    begin
        Readln (pipi,s);
        Writeln ('Read from pipe : ',s);
    end;
    close (pipi);
    writeln ('Closed pipes. ');
    writeln
end.

```

23.12.4 AssignStream

Synopsis: Assign stream for in and output to a program

Declaration: `function AssignStream(var StreamIn: text;var Streamout: text; const Prog: String) : LongInt`
`function AssignStream(var StreamIn: Text;var StreamOut: Text; var StreamErr: Text;const prog: String) : LongInt`

Visibility: default

Description: AssignStream creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output,(and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of Prog. Prog is the name of a program (including path) with options, which will be executed.

What is written to StreamOut, will go to the standard input of Prog. Whatever is written by Prog to it's standard output can be read from StreamIn. Whatever is written by Prog to it's standard error read from StreamErr, if present.

Reading and writing happens through the usual Readln(StreamIn,...) and Writeln (StreamOut,...) procedures.

Remark: You should *not* use Reset or Rewrite on a file opened with POpen. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: In case of error (return value -1) LinuxError is used to report errors:

sys_enfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

Other errors include the ones by the fork and exec programs

See also: AssignPipe ([910](#)), POpen ([959](#))

Listing: ./olinuxex/ex38.pp

Program Example38;

{ Program to demonstrate the AssignStream function. }

Uses oldlinux;

```

Var Si,So : Text;
      S : String;
      i : longint;

begin
  if not (paramstr(1)='-son') then
    begin
      Writeln ('Calling son');
      Assignstream (Si,So,'./ex38 -son');
      if linuxerror<>0 then
        begin
          writeln ('AssignStream failed !');
          halt(1);
        end;
      Writeln ('Speaking to son');
      For i:=1 to 10 do
        begin
          writeln (so,'Hello son !');
          if ioresult<>0 then writeln ('Can''t speak to son...');
        end;
      For i:=1 to 3 do writeln (so,'Hello chap !');
      close (so);
      while not eof(si) do
        begin
          readln (si,s);
          writeln ('Father: Son said : ',S);
        end;
      Writeln ('Stopped conversation');
      Close (Si);
      Writeln ('Put down phone');
    end
  Else
    begin
      Writeln ('This is the son ');
      While not eof (input) do
        begin
          readln (s);
          if pos ('Hello son !',S)<>0 then
            Writeln ('Hello Dad !')
          else
            writeln ('Who are you ?');
          end;
        close (output);
      end
    end.

```

23.12.5 Basename

Synopsis: Return basename of a file

Declaration: `function Basename(const path: PathStr;const suf: PathStr) : PathStr`

Visibility: default

Description: Returns the filename part of Path, stripping off Suf if it exists. The filename part is the whole name if Path contains no slash, or the part of Path after the last slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: [DirName \(919\)](#), [FExpand \(933\)](#)

Listing: ./olinuxex/ex48.pp

Program Example48;

{ Program to demonstrate the BaseName function. }

Uses oldlinux;

Var S : **String**;

begin

S:=FExpand(**Paramstr**(0));

WriteLn ('This program is called : ', Basename(S, ''));

end.

23.12.6 CFMakeRaw

Synopsis: Sets flags in Termios ([905](#)) record.

Declaration: `procedure CFMakeRaw(var tios: Termios)`

Visibility: default

Description: CFMakeRaw sets the flags in the Termios structure Tios to a state so that the terminal will function in Raw Mode.

For an example, see TCGetAttr ([977](#)).

Errors: None.

See also: [CFSetOSpeed \(913\)](#), [CFSetISpeed \(913\)](#)

23.12.7 CFSetISpeed

Synopsis: Set input baud rate in Termios ([905](#)) record

Declaration: `procedure CFSetISpeed(var tios: Termios; speed: Cardinal)`

Visibility: default

Description: CFSetISpeed Sets the input baudrate in the TermIOS structure Tios to Speed.

Errors: None.

See also: [CFSetOSpeed \(913\)](#), [CFMakeRaw \(913\)](#)

23.12.8 CFSetOSpeed

Synopsis: Set output baud rate in Termios ([905](#)) record

Declaration: `procedure CFSetOSpeed(var tios: Termios; speed: Cardinal)`

Visibility: default

Description: `CFSetOSpeed` Sets the output baudrate in the `Termios` structure `Tios` to `Speed`.

Errors: None.

See also: `CFSetISpeed` (913), `CFMakeRaw` (913)

23.12.9 Chmod

Synopsis: Change file permission bits

Declaration: `function Chmod(path: PathStr; Newmode: LongInt) : Boolean`

Visibility: default

Description: `Chmod` Sets the Mode bits of the file in `Path` to `NewMode`. `Newmode` can be specified by 'or'-ing the following:

- `S_ISUID` Set user ID on execution.
- `S_ISGID` Set Group ID on execution.
- `S_ISVTX` Set sticky bit.
- `S_IRUSR` Read by owner.
- `S_IWUSR` Write by owner.
- `S_IXUSR` Execute by owner.
- `S_IRGRP` Read by group.
- `S_IWGRP` Write by group.
- `S_IXGRP` Execute by group.
- `S_IROTH` Read by others.
- `S_IWOTH` Write by others.
- `S_IXOTH` Execute by others.
- `S_IRWXO` Read, write, execute by others.
- `S_IRWXG` Read, write, execute by groups.
- `S_IRWXU` Read, write, execute by user.

Errors: Errors are returned in `LinuxError`.

sys_eperm The effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccess One of the directories in `Path` has no search (=execute) permission.

sys_enoent A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomem Insufficient kernel memory.

sys_erofs The file is on a read-only filesystem.

sys_eloop `Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `Chown` (915), `Access` (908), `Octal` (957)

Listing: `./olinuxex/ex23.pp`

```

Program Example23;

{ Program to demonstrate the Chmod function. }

Uses oldlinux;

Var F : Text;

begin
  { Create a file }
  Assign (f, 'testex21');
  Rewrite (F);
  WriteLn (f, '#!/bin/sh');
  WriteLn (f, 'echo Some text for this file');
  Close (F);
  { Octal() makes the correct number from a
    number that LOOKS octal }
  Chmod ('testex21', octal (777));
  { File is now executable }
  execl ( './testex21' );
end.

```

23.12.10 Chown

Synopsis: Change owner of file

Declaration: `function Chown(path: PathStr; NewUid: LongInt; NewGid: LongInt) : Boolean`

Visibility: default

Description: Chown sets the User ID and Group ID of the file in Path to NewUid, NewGid The function returns True if the call was succesfull, False if the call failed.

Errors: Errors are returned in `LinuxError`.

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in Path has no search (=execute) permission.

sys_enoentA directory entry in Path does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only filesystem.

sys_eloopPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: Chmod ([914](#)), Access ([908](#))

Listing: ./olinuxex/ex24.pp

```

Program Example24;

{ Program to demonstrate the Chown function. }

Uses oldlinux;

```



```

Var UID,GID : Longint;
      F : Text;

begin

  Writeln ('This will only work if you are root. ');
  Write ('Enter a UID : '); readln(UID);
  Write ('Enter a GID : '); readln(GID);
  Assign (f, 'test.txt');
  Rewrite (f);
  Writeln (f, 'The owner of this file should become : ');
  Writeln (f, 'UID : ',UID);
  Writeln (f, 'GID : ',GID);
  Close (F);
  if not Chown ('test.txt',UID,GID) then
    if LinuxError=Sys_EPERM then
      Writeln ('You are not root !')
    else
      Writeln ('Chmod failed with exit code : ',LinuxError)
    else
      Writeln ('Changed owner successfully !');
end.

```

23.12.11 Clone

Synopsis: Clone current process (create new thread)

Declaration: `function Clone(func: TCloneFunc; sp: pointer; flags: LongInt;
args: pointer) : LongInt`

Visibility: default

Description: `Clone` creates a child process which is a copy of the parent process, just like `Fork` (935) does. In difference with `Fork`, however, the child process shares some parts of it's execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

CLONE_VMParent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

CLONE_FSParent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

CLONE_FILESthe file descriptor table of parent and child is shared.

CLONE_SIGHANDthe parent and child share the same table of signal handlers. The signal masks are different, though.

CLONE_PIDParent and child have the same process ID.

Clone returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainToo many processes are running.

sys_enomemNot enough memory to create child process.

See also: Fork ([935](#))

Listing: ./olinuxex/ex71.pp

```

program TestC{clone};

uses
    oldlinux , Errors , crt;

const
    Ready : Boolean = false;
    aChar : Char    = 'a';

function CloneProc( Arg: Pointer ): LongInt; Cdecl;
begin
    WriteLn('Hello from the clone ',PChar(Arg));
    repeat
        Write(aChar);
        Select(0,Nil,Nil,Nil,Nil);
    until Ready;
    WriteLn('Clone finished. ');
    CloneProc := 1;
end;

var
    PID : LongInt;

procedure MainProc;
begin
    WriteLn('cloned process PID: ', PID );
    WriteLn('Press <ESC> to kill ... ');
    repeat
        Write(' ');
        Select(0,Nil,Nil,Nil,Nil);
        if KeyPressed then
            case ReadKey of
                #27: Ready := true;
                'a': aChar := 'A';
                'A': aChar := 'a';
                'b': aChar := 'b';
                'B': aChar := 'B';
            end;
        until Ready;
    WriteLn('Ready. ');
end;

const
    StackSize = 16384;
    theFlags = CLONE_VM+CLONE_FS+CLONE_FILES+CLONE_SIGHAND;

```

```

aMsg      : PChar = 'Oops !';

var
  theStack : Pointer;
  ExitStat : LongInt;

begin
  GetMem(theStack, StackSize);
  PID := Clone(@CloneProc,
               Pointer(LongInt(theStack)+StackSize),
               theFlags,
               aMsg);
  if PID < 0 then
    WriteLn('Error : ', LinuxError, ' when cloning.')
  else
    begin
      MainProc;
      case WaitPID(0, @ExitStat, Wait_Untraced or wait_clone) of
        -1: WriteLn('error: ', LinuxError, '; ', StrError(LinuxError));
        0: WriteLn('error: ', LinuxError, '; ', StrError(LinuxError));
      else
        WriteLn('Clone exited with: ', ExitStat shr 8);
      end;
    end;
  FreeMem(theStack, StackSize);
end.

```

23.12.12 CloseDir

Synopsis: Close directory file descriptor

Declaration: `function CloseDir(p: PDir) : Integer`

Visibility: default

Description: `CloseDir` closes the directory pointed to by `p`. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see `OpenDir` ([958](#)).

Errors: Errors are returned in `LinuxError`.

See also: `OpenDir` ([958](#)), `ReadDir` ([960](#)), `SeekDir` ([962](#)), `TellDir` ([979](#))

23.12.13 CreateShellArgV

Synopsis: Create an array of null-terminated strings

Declaration: `function CreateShellArgV(const prog: String) : ppchar`
`function CreateShellArgV(const prog: Ansistring) : ppchar`

Visibility: default

Description: `CreateShellArgV` creates an array of 3 `PChar` pointers that can be used as arguments to `ExecVE` the first elements in the array will contain `/bin/sh`, the second will contain `-c`, and the third will contain `prog`.

The function returns a pointer to this array, of type `PPChar`.

Errors: None.

See also: Shell ([965](#))

Listing: ./olinuxex/ex61.pp

```

Program ex61;

{ Example program to demonstrate the CreateShellArgV function }

uses oldlinux;

Var
  S: String;
  PP : PPchar;
  I : longint;

begin
  S:= 'script -a -b -c -d -e fghijk';
  PP:=CreateShellArgV(S);
  I:=0;
  If PP<>Nil then
    While PP[I]<>Nil do
      begin
        WriteLn ( 'Got : " ',PP[I], '" ');
        Inc(I);
      end;
    end.

```

23.12.14 Dirname

Synopsis: Extract directory part from filename

Declaration: `function Dirname(const path: PathStr) : PathStr`

Visibility: default

Description: Returns the directory part of `Path`. The directory is the part of `Path` before the last slash, or empty if there is no slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: BaseName ([912](#)), FExpand ([933](#))

Listing: ./olinuxex/ex47.pp

```

Program Example47;

{ Program to demonstrate the DirName function. }

Uses oldlinux;

Var S : String;

begin
  S:=FExpand(Paramstr(0));
  WriteLn ( 'This program is in directory : ',Dirname(S));
end.

```

23.12.15 Dup

Synopsis: Duplicate a file handle

Declaration: `function Dup(oldfile: LongInt;var newfile: LongInt) : Boolean`
`function Dup(var oldfile: text;var newfile: text) : Boolean`
`function Dup(var oldfile: file;var newfile: file) : Boolean`

Visibility: default

Description: Makes `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a `Text` file or untyped file. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns `False` in case of an error, `True` if successful.

Errors: In case of errors, `Linuxerror` is used to report errors.

`sys_ebadf``OldFile` hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: `Dup2` ([920](#))

Listing: `./olinuxex/ex31.pp`

program `Example31` ;

{ Program to demonstrate the Dup function. }

uses `oldlinux` ;

var `f` : `text` ;

begin

if not `dup (output,f)` **then**

Writeln ('Dup Failed !');

writeln ('This is written to stdout.');

writeln (f, 'This is written to the dup file , and flushed'); **flush** (f);

writeln

end.

23.12.16 Dup2

Synopsis: Duplicate one filehandle to another

Declaration: `function Dup2(oldfile: LongInt;newfile: LongInt) : Boolean`
`function Dup2(var oldfile: text;var newfile: text) : Boolean`
`function Dup2(var oldfile: file;var newfile: file) : Boolean`

Visibility: default

Description: Makes `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in the case of `text` or untyped files.

`NewFile` can be an assigned file. If `newfile` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal

buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an lseek will, however, work as in C, i.e. doing a lseek will change the fileposition in both files.

The function returns `True` if succesful, false otherwise.

Errors: In case of error, `Linuxerror` is used to report errors.

sys_ebadfOldFile hasn't been assigned.

sys_emfileMaximum number of open files for the process is reached.

See also: Dup ([920](#))

Listing: ./olinuxex/ex32.pp

```

program Example31 ;

{ Program to demonstrate the Dup function. }

uses oldlinux ;

var f : text ;
    i : longint ;

begin
  Assign ( f , 'text.txt' ) ;
  Rewrite ( F ) ;
  For i:=1 to 10 do writeln ( F , 'Line : ', i ) ;
  if not dup2 ( output , f ) then
    Writeln ( 'Dup2 Failed !' ) ;
  writeln ( 'This is written to stdout.' ) ;
  writeln ( f , 'This is written to the dup file , and flushed' ) ;
  flush ( f ) ;
  writeln ;
  { Remove file . Comment this if you want to check flushing . }
  Unlink ( 'text.txt' ) ;
end.

```

23.12.17 EpochToLocal

Synopsis: Convert epoch time to local time

Declaration: `procedure EpochToLocal (epoch: LongInt; var year: Word; var month: Word; var day: Word; var hour: Word; var minute: Word; var second: Word)`

Visibility: default

Description: Converts the epoch time (=Number of seconds since 00:00:00 , January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timzeone settings of your system.

Errors: None

See also: GetEpochTime ([941](#)), LocalToEpoch ([951](#)), GetTime ([946](#)), GetDate ([939](#))

Listing: ./olinuxex/ex3.pp

Program Example3;

{ Program to demonstrate the EpochToLocal function. }

Uses oldlinux;

Var Year, month, day, hour, minute, seconds : Word;

begin

EpochToLocal (GetEpochTime, Year, month, day, hour, minute, seconds);

WriteLn ('Current date : ', Day:2, '/', Month:2, '/', Year:4);

WriteLn ('Current time : ', Hour:2, ':', minute:2, ':', seconds:2);

end.

23.12.18 Execl

Synopsis: Execute process (using argument list)

Declaration: `procedure Execl(const Todo: String)`
`procedure Execl(const Todo: Ansistring)`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. `Path` is split into a command and it's options. The executable in `path` is NOT searched in the `path`. The current environment is passed to the program. On success, `execl` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `Execve` (925), `Execv` (924), `Execvp` (926), `Execl` (923), `Execlp` (923), `Fork` (935)

Listing: ./olinuxex/ex10.pp

Program Example10;

{ Program to demonstrate the Execl function. }

Uses oldlinux, strings;

begin

{ Execute 'ls -l', with current environment. }

{ 'ls' is NOT looked for in PATH environment variable. }

Execl ('/bin/ls -l');

end.

23.12.19 Execle

Synopsis: Execute process (using argument list, environment)

Declaration: `procedure Execle(Todo: String;Ep: ppchar)`
`procedure Execle(Todo: AnsiString;Ep: ppchar)`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. `Path` is split into a command and it's options. The executable in `path` is searched in the `path`, if it isn't an absolute filename. The environment in `ep` is passed to the program. On success, `execle` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `Execve` (925), `Execv` (924), `Execvp` (926), `Execl` (922), `Execlp` (923), `Fork` (935)

Listing: `./olinuxex/ex11.pp`

Program `Example11`;

{ Program to demonstrate the Execle function. }

Uses `oldlinux` , `strings`;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is NOT looked for in PATH environment variable. }
{ envp is defined in the system unit. }
`Execle ('/bin/ls -l',envp);`

end.

23.12.20 Execlp

Synopsis: Execute process (using argument list, environment; search path)

Declaration: `procedure Execlp(Todo: String;Ep: ppchar)`
`procedure Execlp(Todo: AnsiString;Ep: ppchar)`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. `Path` is split into a command and it's options. The executable in `path` is searched in the `path`, if it isn't an absolute filename. The current environment is passed to the program. On success, `execlp` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.
sys_epermThe file system is mounted *noexec*.
sys_e2bigArgument list too big.
sys_enoexecThe magic number in the file is incorrect.
sys_enoentThe file does not exist.
sys_enomemNot enough memory for kernel, or to split command line.
sys_enotdirA component of the path is not a directory.
sys_eloopThe path contains a circular reference (via symlinks).

See also: `Execve` (925), `Execv` (924), `Execvp` (926), `Execle` (923), `Execl` (922), `Fork` (935)

Listing: `./olinuxex/ex12.pp`

Program `Example12`;

{ Program to demonstrate the Execlp function. }

Uses `oldlinux` , `strings`;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
{ envp is defined in the system unit. }
`Execlp ('ls -l',envp);`

end.

23.12.21 Execv

Synopsis: Execute process

Declaration: `procedure Execv(const path: PathStr;args: ppchar)`
`procedure Execv(const path: AnsiString;args: ppchar)`

Visibility: `default`

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.
sys_epermThe file system is mounted *noexec*.
sys_e2bigArgument list too big.
sys_enoexecThe magic number in the file is incorrect.
sys_enoentThe file does not exist.
sys_enomemNot enough memory for kernel.

sys_enotdir A component of the path is not a directory.

sys_eloop The path contains a circular reference (via symlinks).

See also: [Execve \(925\)](#), [Execvp \(926\)](#), [Execle \(923\)](#), [Execl \(922\)](#), [Execlp \(923\)](#), [Fork \(935\)](#)

Listing: ./olinuxex/ex8.pp

Program Example8;

{ Program to demonstrate the Execv function. }

Uses oldlinux , strings ;

Const Arg0 : PChar = '/bin/l\$';
Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP,3*SizeOf(Pchar));

PP[0]:=Arg0;

PP[1]:=Arg1;

PP[3]:=Nil;

{ Execute '/bin/l\$ -l', with current environment }

Execv ('/bin/l\$',pp);

end.

23.12.22 Execve

Synopsis: Execute process using environment

Declaration: `procedure Execve(Path: PathStr;args: ppchar;ep: ppchar)`
`procedure Execve(Path: AnsiString;args: ppchar;ep: ppchar)`
`procedure Execve(path: pchar;args: ppchar;ep: ppchar)`

Visibility: default

Description: Replaces the currently running program with the program, specified in path. It gives the program the options in args, and the environment in ep. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be nil. On success, `execve` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccess File is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_eperm The file system is mounted *noexec*.

sys_e2big Argument list too big.

sys_enoexec The magic number in the file is incorrect.

sys_enoent The file does not exist.

sys_enomem Not enough memory for kernel.

sys_enotdir A component of the path is not a directory.

sys_eloop The path contains a circular reference (via symlinks).

See also: [Execve \(925\)](#), [Execl \(922\)](#), [Execlp \(923\)](#), [Execl \(922\)](#), [Execlp \(923\)](#), [Fork \(935\)](#)

Listing: ./olinuxex/ex7.pp

Program Example7;

{ Program to demonstrate the Execve function . }

Uses oldlinux , strings ;

Const Arg0 : PChar = '/bin/lS';
Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP,3*SizeOf (Pchar));

PP[0]:=Arg0;

PP[1]:=Arg1;

PP[3]:=Nil;

{ Execute '/bin/lS -l', with current environment }

{ Env is defined in system.inc }

ExecVe ('/bin/lS',pp,envp);

end.

23.12.23 Execvp

Synopsis: Execute process, search path

Declaration: procedure Execvp(Path: PathStr;Args: ppchar;Ep: ppchar)
procedure Execvp(Path: AnsiString;Args: ppchar;Ep: ppchar)

Visibility: default

Description: Replaces the currently running program with the program, specified in path. The executable in path is searched in the path, if it isn't an absolute filename. It gives the program the options in args. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, execvp does not return.

Errors: Errors are reported in LinuxError:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [Execve \(925\)](#), [Execl \(922\)](#), [Execlp \(923\)](#), [Execl \(922\)](#), [Execlp \(923\)](#), [Fork \(935\)](#)

Listing: ./olinuxex/ex9.pp

Program Example9;

{ Program to demonstrate the Execvp function. }

Uses oldlinux , strings ;

Const Arg0 : PChar = 'ls' ;
 Arg1 : Pchar = '-l' ;

Var PP : PPchar ;

begin

GetMem (PP,3***SizeOf**(Pchar));
 PP[0]:=Arg0;
 PP[1]:=Arg1;
 PP[3]:=Nil;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
{ Env is defined in the system unit. }
 Execvp ('ls',pp,envp);

end.

23.12.24 ExitProcess

Synopsis: Exit the current process

Declaration: procedure ExitProcess(val: LongInt)

Visibility: default

Description: ExitProcess exits the currently running process, and report Val as the exit status.

Remark: If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the Halt call instead.

Errors: None.

See also: Fork ([935](#)), ExecVE ([925](#))

23.12.25 Fcntl

Synopsis: File control operations.

Declaration: function Fcntl(Fd: LongInt;Cmd: LongInt) : LongInt
 procedure Fcntl(Fd: LongInt;Cmd: LongInt;Arg: LongInt)
 function Fcntl(var Fd: Text;Cmd: LongInt) : LongInt
 procedure Fcntl(var Fd: Text;Cmd: LongInt;Arg: LongInt)

Visibility: default

Description: Read a file's attributes. Fd is an assigned file, or a valid file descriptor. Cmd specifies what to do, and is one of the following:

F_GetFdRead the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

F_GetFlRead the descriptor's flags.

F_GetOwnGet the Process ID of the owner of a socket.

F_SetFdSet the `close_on_exec` flag of `Fd`. (only the least significant bit is used).

F_GetLkReturn the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock of there is no obstruction. `Arg` is a pointer to a flock record.

F_SetLkSet the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

F_GetLkwSame as for **F_Setlk**, but wait until the lock is released.

F_SetOwnSet the Process or process group that owns a socket.

Errors: `LinuxError` is used to report errors.

sys_ebadf`Fd` has a bad file descriptor.

sys_eagain or **sys_eaccess**For **F_SetLk**, if the lock is held by another process.

23.12.26 fdClose

Synopsis: Close file descriptor

Declaration: `function fdClose(fd: LongInt) : Boolean`

Visibility: default

Description: `fdClose` closes a file with file descriptor `Fd`. The function returns `True` if the file was closed successfully, `False` otherwise.

For an example, see `fdOpen` (929).

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` (929), `fdRead` (930), `fdWrite` (932), `fdTruncate` (931), `fdFlush` (928), `fdSeek` (931)

23.12.27 fdFlush

Synopsis: Flush kernel file buffer

Declaration: `function fdFlush(fd: LongInt) : Boolean`

Visibility: default

Description: `fdflush` flushes the Linux kernel file buffer, so the file is actually written to disk. This is NOT the same as the internal buffer, maintained by Free Pascal. The function returns `True` if the call was successful, `false` if an error occurred.

For an example, see `fdRead` (930).

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` (929), `fdClose` (928), `fdRead` (930), `fdWrite` (932), `fdTruncate` (931), `fdSeek` (931)

23.12.28 fdOpen

Synopsis: Open file and return file descriptor

Declaration: `function fdOpen(pathname: String; flags: LongInt) : LongInt`
`function fdOpen(pathname: String; flags: LongInt; mode: LongInt) : LongInt`
`function fdOpen(pathname: pchar; flags: LongInt) : LongInt`
`function fdOpen(pathname: pchar; flags: LongInt; mode: LongInt) : LongInt`

Visibility: default

Description: `fdOpen` opens a file in `PathName` with flags `flags` One of the following:

Open_RdOnlyFile is opened Read-only

Open_WrOnlyFile is opened Write-only

Open_RdWrFile is opened Read-Write

The flags may be OR-ed with one of the following constants:

Open_CreatFile is created if it doesn't exist.

Open_ExclIf the file is opened with `Open_Creat` and it already exists, the call will fail.

Open_NoCttyIf the file is a terminal device, it will NOT become the process' controlling terminal.

Open_TruncIf the file exists, it will be truncated.

Open_Append the file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

Open_NonBlock The file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

Open_NDelay Idem as `Open_NonBlock`

Open_Sync The file is opened for synchronous IO. Any write operation on the file will not return until the data is physically written to disk.

Open_NoFollow if the file is a symbolic link, the open fails. (linux 2.1.126 and higher only)

Open_Directory if the file is not a directory, the open fails. (linux 2.1.126 and higher only)

`PathName` can be of type `PChar` or `String`. The optional `mode` argument specifies the permissions to set when opening the file. This is modified by the `umask` setting. The real permissions are `Mode` and not `umask`. The return value of the function is the file descriptor, or a negative value if there was an error.

Errors: Errors are returned in `LinuxError`.

See also: `fdClose` (928), `fdRead` (930), `fdWrite` (932), `fdTruncate` (931), `fdFlush` (928), `fdSeek` (931)

Listing: `./olinuxex/ex19.pp`

Program Example19;

{ Program to demonstrate the fdOpen, fdwrite and fdCLose functions. }

Uses oldlinux;

Const Line : **String**[80] = 'This is easy writing !';

Var FD : Longint;

begin

```

FD:=fdOpen ( 'Test.dat',Open_WrOnly or Open_Creat);
if FD>0 then
begin
  if length(Line)<>fdwrite (FD,Line[1],Length(Line)) then
    WriteLn ( 'Error when writing to file !');
  fdClose(FD);
end;
end.

```

23.12.29 fdRead

Synopsis: Read data from file descriptor

Declaration: `function fdRead(fd: LongInt;var buf;size: LongInt) : LongInt`

Visibility: default

Description: `fdRead` reads at most `size` bytes from the file descriptor `fd`, and stores them in `buf`. The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of `buf` is done.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([929](#)), `fdClose` ([928](#)), `fdWrite` ([932](#)), `fdTruncate` ([931](#)), `fdFlush` ([928](#)), `fdSeek` ([931](#))

Listing: `./olinuxex/ex20.pp`

Program `Example20`;

{ Program to demonstrate the fdRead and fdTruncate functions. }

Uses `oldlinux`;

Const `Data : string[10] = '12345687890'`;

Var `FD : Longint;`
`l : longint;`

```

begin
  FD:=fdOpen('test.dat',open_wronly or open_creat,octal(666));
  if fd>0 then
  begin
    { Fill file with data }
    for l:=1 to 10 do
      if fdWrite (FD,Data[l],10)<>10 then
      begin
        writeLn ( 'Error when writing !');
        halt(1);
      end;
    fdClose(FD);
    FD:=fdOpen('test.dat',open_rdonly);
    { Read data again }
    If FD>0 then
    begin
      For l:=1 to 5 do
        if fdRead (FD,Data[l],10)<>10 then
        begin
          WriteLn ( 'Error when Reading !');

```

```

        Halt (2);
    end;
    fdClose(FD);
    { Truncating file at 60 bytes }
    { For truncating , file must be open or write }
    FD:=fdOpen('test.dat',open_wronly,octal(666));
    if FD>0 then
        begin
            if not fdTruncate(FD,60) then
                Writeln('Error when truncating !');
            fdClose (FD);
        end;
    end;
end.

```

23.12.30 fdSeek

Synopsis: Set file pointer position.

Declaration: `function fdSeek(fd: LongInt;pos: LongInt;seektype: LongInt) : LongInt`

Visibility: default

Description: `fdSeek` sets the current fileposition of file `fd` to `Pos`, starting from `SeekType`, which can be one of the following:

Seek_SetPos is the absolute position in the file.

Seek_CurPos is relative to the current position.

Seek_endPos is relative to the end of the file.

The function returns the new fileposition, or -1 of an error occurred.

For an example, see `fdOpen` (929).

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` (929), `fdWrite` (932), `fdClose` (928), `fdRead` (930), `fdTruncate` (931), `fdFlush` (928)

23.12.31 fdTruncate

Synopsis: Truncate file on certain size.

Declaration: `function fdTruncate(fd: LongInt;size: LongInt) : Boolean`

Visibility: default

Description: `fdTruncate` sets the length of a file in `fd` on `size` bytes, where `size` must be less than or equal to the current length of the file in `fd`. The function returns `True` if the call was successful, `false` if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` (929), `fdClose` (928), `fdRead` (930), `fdWrite` (932), `fdFlush` (928), `fdSeek` (931)

23.12.32 fdWrite

Synopsis: Write data to file descriptor

Declaration: `function fdWrite(fd: LongInt; const buf; size: LongInt) : LongInt`

Visibility: default

Description: `fdWrite` writes at most `size` bytes from `buf` to file descriptor `fd`. The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` (929), `fdClose` (928), `fdRead` (930), `fdTruncate` (931), `fdSeek` (931), `fdFlush` (928)

23.12.33 FD_Clr

Synopsis: Clears a filedescriptor in a set

Declaration: `procedure FD_Clr(fd: LongInt; var fds: fdSet)`

Visibility: default

Description: `FD_Clr` clears file descriptor `fd` in filedescriptor set `fds`.

For an example, see `Select` (962).

Errors: None.

See also: `Select` (962), `SelectText` (964), `GetFS` (942), `FD_ZERO` (933), `FD_Set` (932), `FD_IsSet` (932)

23.12.34 FD_IsSet

Synopsis: Check whether a filedescriptor is set

Declaration: `function FD_IsSet(fd: LongInt; var fds: fdSet) : Boolean`

Visibility: default

Description: `FD_Set` Checks whether file descriptor `fd` in filedescriptor set `fds` is set.

For an example, see `Select` (962).

Errors: None.

See also: `Select` (962), `SelectText` (964), `GetFS` (942), `FD_ZERO` (933), `FD_Clr` (932), `FD_Set` (932)

23.12.35 FD_Set

Synopsis: Set a filedescriptor in a set

Declaration: `procedure FD_Set(fd: LongInt; var fds: fdSet)`

Visibility: default

Description: `FD_Set` sets file descriptor `fd` in filedescriptor set `fds`.

For an example, see `Select` (962).

Errors: None.

See also: `Select` (962), `SelectText` (964), `GetFS` (942), `FD_ZERO` (933), `FD_Clr` (932), `FD_IsSet` (932)

23.12.36 FD_Zero

Synopsis: Clear all file descriptors in set

Declaration: `procedure FD_Zero(var fds: fdSet)`

Visibility: default

Description: `FD_ZERO` clears all the filedescriptors in the file descriptor set `fds`.

For an example, see [Select \(962\)](#).

Errors: None.

See also: [Select \(962\)](#), [SelectText \(964\)](#), [GetFS \(942\)](#), [FD_Clr \(932\)](#), [FD_Set \(932\)](#), [FD_IsSet \(932\)](#)

23.12.37 FExpand

Synopsis: Expand filename to fully qualified path

Declaration: `function FExpand(const Path: PathStr) : PathStr`

Visibility: default

Description: `FExpand` expands `Path` to a full path, starting from root, eliminating directory references such as `.` and `..` from the result.

Errors: None

See also: [BaseName \(912\)](#), [DirName \(919\)](#)

Listing: `./olinuxex/ex45.pp`

Program `Example45;`

{ Program to demonstrate the FExpand function. }

Uses `oldlinux;`

begin

`WriteLn ('This program is in : ',FExpand(Paramstr(0)));`
end.

23.12.38 Flock

Synopsis: Lock a file (advisory lock)

Declaration: `function Flock(fd: LongInt;mode: LongInt) : Boolean`
`function Flock(var T: text;mode: LongInt) : Boolean`
`function Flock(var F: File;mode: LongInt) : Boolean`

Visibility: default

Description: `FLock` implements file locking. it sets or removes a lock on the file `F`. `F` can be of type `Text` or `File`, or it can be a linux filedescriptor (a longint) `Mode` can be one of the following constants :

LOCK_SHsets a shared lock.

LOCK_EXsets an exclusive lock.

LOCK_UN unlocks the file.

LOCK_NB This can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns `True` if successful, `False` otherwise.

Errors: If an error occurs, it is reported in `LinuxError`.

See also: `Fcntl` ([927](#))

23.12.39 FNMatch

Synopsis: Check whether filename matches wildcard specification

Declaration: `function FNMatch(const Pattern: String;const Name: String) : Boolean`

Visibility: `default`

Description: `FNMatch` returns `True` if the filename in `Name` matches the wildcard pattern in `Pattern`, `False` otherwise.

`Pattern` can contain the wildcards `*` (match zero or more arbitrary characters) or `?` (match a single character).

Errors: None.

See also: `FSearch` ([936](#)), `FExpand` ([933](#))

Listing: `./olinuxex/ex69.pp`

Program `Example69;`

{ Program to demonstrate the FNMatch function. }

Uses `oldlinux;`

Procedure `TestMatch(Pattern,Name : String);`

begin

`Write ('"',Name,'" ');`

`If FNMatch (Pattern,Name) then`

`Write (' matches')`

`else`

`Write ('does not match');`

`Writeln ('"',Pattern,'"');`

`end;`

begin

`TestMatch ('*', 'FileName');`

`TestMatch ('.*', 'FileName');`

`TestMatch ('*a*', 'FileName');`

`TestMatch ('?ile*', 'FileName');`

`TestMatch ('?', 'FileName');`

`TestMatch ('.?', 'FileName');`

`TestMatch ('?a*', 'FileName');`

`TestMatch ('??*me?', 'FileName');`

`end.`

23.12.40 Fork

Synopsis: Create child process

Declaration: `function Fork : LongInt`

Visibility: default

Description: `Fork` creates a child process which is a copy of the parent process. `Fork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `GetPPid` (945)).

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainNot enough memory to create child process.

See also: `Execve` (925), `Clone` (916)

23.12.41 FReName

Synopsis: Rename file

Declaration: `function FReName (OldName: Pchar; NewName: Pchar) : Boolean`
`function FReName (OldName: String; NewName: String) : Boolean`

Visibility: default

Description: `FReName` renames the file `OldName` to `NewName`. `NewName` can be in a different directory than `OldName`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `OldName` file will be preserved.

The function returns `True` on succes, `False` on failure.

Errors: On error, errors are reported in `LinuxError`. Possible errors include:

sys_eisdir`NewName` exists and is a directory, but `OldName` is not a directory.

sys_exdev`NewName` and `OldName` are on different devices.

sys_enotempty or sys_eexist`NewName` is an existing, non-empty directory.

sys_ebusy`OldName` or `NewName` is a directory and is in use by another process.

sys_einval`NewName` is part of `OldName`.

sys_emlink`OldPath` or `NewPath` already have the maximum amount of links pointing to them.

sys_enotdirpart of `OldName` or `NewName` is not directory.

sys_efaultFor the `pchar` case: One of the pointers points to an invalid address.

sys_eaccessaccess is denied when attempting to move the file.

sys_enametoolongEither `OldName` or `NewName` is too long.

sys_enoenta directory component in `OldName` or `NewName` didn't exist.

sys_enomemnot enough kernel memory.

sys_erofs`NewName` or `OldName` is on a read-only file system.

sys_elooptoo many symbolic links were encountered trying to expand `OldName` or `NewName`

sys_enospcthe filesystem has no room for the new directory entry.

See also: `UnLink` (980)

23.12.42 FSearch

Synopsis: Search for file in search path.

Declaration: `function FSearch(const path: PathStr;dirlist: String) : PathStr`

Visibility: default

Description: `FSearch` searches in `DirList`, a colon separated list of directories, for a file named `Path`. It then returns a path to the found file.

Errors: An empty string if no such file was found.

See also: `BaseName` ([912](#)), `DirName` ([919](#)), `FExpand` ([933](#)), `FNMatch` ([934](#))

Listing: `./olinuxex/ex46.pp`

Program `Example46;`

{ Program to demonstrate the FSearch function. }

Uses `oldlinux, strings;`

begin

`WriteLn ('Is is in : ',FSearch ('Is ',strpas (Getenv ('PATH'))));`
end.

23.12.43 FSplit

Synopsis: Split filename into path, name and extension

Declaration: `procedure FSplit(const Path: PathStr;var Dir: DirStr;var Name: NameStr;
 var Ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A `Path`, a `Name` and an extension (in `ext`). The extension is taken to be all letters after the last dot (.).

Errors: None.

See also: `FSearch` ([936](#))

Listing: `./olinuxex/ex67.pp`

Program `Example67;`

uses `oldlinux;`

{ Program to demonstrate the FSplit function. }

var

`Path,Name,Ext : string;`

begin

`FSplit (ParamStr (1),Path,Name,Ext);`
`WriteLn (' Split ',ParamStr (1), ' in: ');`
`WriteLn (' Path : ',Path);`
`WriteLn (' Name : ',Name);`
`WriteLn (' Extension: ',Ext);`
end.

23.12.44 FSStat

Synopsis: Retrieve filesystem information.

Declaration: `function FSStat (Path: PathStr; var Info: Statfs) : Boolean`
`function FSStat (Fd: LongInt; var Info: Statfs) : Boolean`

Visibility: default

Description: `FSStat` returns in `Info` information about the filesystem on which the file `Path` resides, or on which the file with file descriptor `fd` resides. `Info` is of type `statfs`. The function returns `True` if the call was successful, `False` if the call failed.

Errors: `LinuxError` is used to report errors.

`sys_enotdir` A component of `Path` is not a directory.

`sys_einval` Invalid character in `Path`.

`sys_enoent` `Path` does not exist.

`sys_eaccess` Search permission is denied for component in `Path`.

`sys_eloop` A circular symbolic link was encountered in `Path`.

`sys_eio` An error occurred while reading from the filesystem.

See also: `FStat` ([938](#)), `LStat` ([952](#))

Listing: `./olinuxex/ex30.pp`

```

program Example30;

{ Program to demonstrate the FSStat function. }

uses oldlinux;

var s : string;
    info : statfs;

begin
  writeln ('Info about current partition : ');
  s := '.';
  while s <> 'q' do
    begin
      if not fsstat (s, info) then
        begin
          writeln ('Fstat failed. Errno : ', linuxerror);
          halt (1);
        end;
      writeln;
      writeln ('Result of fsstat on file ''', s, '''');
      writeln ('fstype   : ', info.fstype);
      writeln ('bsize    : ', info.bsize);
      writeln ('bfree     : ', info.bfree);
      writeln ('bavail    : ', info.bavail);
      writeln ('files     : ', info.files);
      writeln ('ffree     : ', info.ffree);
      writeln ('fsid      : ', info.fsid);
      writeln ('Namelen   : ', info.namelen);
      write ('Type name of file to do fsstat. (q quits) : ');
      readln (s);
    end;
  end.

```

23.12.45 FStat

Synopsis: Retrieve information about a file

Declaration: `function FStat (Path: PathStr; var Info: Stat) : Boolean`
`function FStat (Fd: LongInt; var Info: Stat) : Boolean`
`function FStat (var F: Text; var Info: Stat) : Boolean`
`function FStat (var F: File; var Info: Stat) : Boolean`

Visibility: default

Description: `FStat` gets information about the file specified in one of the following:

Patha file on the filesystem.

Fda valid file descriptor.

Fan opened text file or untyped file.

and stores it in `Info`, which is of type `stat`. The function returns `True` if the call was successful, `False` if the call failed.

Errors: `LinuxError` is used to report errors.

`sys_enoent`Path does not exist.

See also: `FSSStat` ([937](#)), `LStat` ([952](#))

Listing: `./olinuxex/ex28.pp`

```

program example28;

  { Program to demonstrate the FStat function. }

uses oldlinux;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil ');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if not fstat ('test.fil ', info) then
    begin
      writeln ('Fstat failed. Errno : ', linuxerror);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil ''.');
  writeln ('Inode      : ', info.ino);
  writeln ('Mode       : ', info.mode);
  writeln ('nlink      : ', info.nlink);
  writeln ('uid        : ', info.uid);
  writeln ('gid        : ', info.gid);
  writeln ('rdev       : ', info.rdev);
  writeln ('Size       : ', info.size);

```

```

writeln ( 'Blksize : ',info.blksize);
writeln ( 'Blocks : ',info.blocks);
writeln ( 'atime : ',info.atime);
writeln ( 'mtime : ',info.mtime);
writeln ( 'ctime : ',info.ctime);
  { Remove file }
  erase (f);
end .

```

23.12.46 GetDate

Synopsis: Return the system date

Declaration: `procedure GetDate(var Year: Word;var Month: Word;var Day: Word)`

Visibility: default

Description: Returns the current date.

Errors: None

See also: [GetEpochTime \(941\)](#), [GetTime \(946\)](#), [GetDateTime \(939\)](#), [EpochToLocal \(921\)](#)

Listing: ./olinuxex/ex6.pp

Program Example6;

{ Program to demonstrate the GetDate function. }

Uses oldlinux;

Var Year, Month, Day : Word;

begin

 GetDate (Year, Month, Day);

Writeln ('Date : ',Day:2,'/',Month:2,'/',Year:4);

end .

23.12.47 GetDateTime

Synopsis: Return system date and time

Declaration: `procedure GetDateTime(var Year: Word;var Month: Word;var Day: Word;
var hour: Word;var minute: Word;var second: Word)`

Visibility: default

Description: Returns the current date and time. The time is corrected for the local time zone. This procedure is equivalent to the [GetDate \(939\)](#) and [GetTime](#) calls.

Errors: None

See also: [GetEpochTime \(941\)](#), [GetTime \(946\)](#), [EpochToLocal \(921\)](#), [GetDate \(939\)](#)

Listing: ./olinuxex/ex60.pp

```

Program Example6;

{ Program to demonstrate the GetDateTime function. }

Uses oldlinux;

Var Year, Month, Day, Hour, min, sec : Word;

begin
  GetDateTime (Year, Month, Day, Hour, min, sec);
  WriteIn ( 'Date : ',Day:2,'/',Month:2,'/',Year:4);
  WriteIn ( 'Time : ',Hour:2,':',Min:2,':',Sec:2);
end.

```

23.12.48 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : String`

Visibility: default

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` ([943](#))

Listing: ./olinuxex/ex39.pp

```

Program Example39;

{ Program to demonstrate the GetDomainName function. }

Uses oldlinux;

begin
  WriteIn ( 'Domain name of this machine is : ',GetDomainName);
end.

```

23.12.49 GetEGid

Synopsis: Return effective group ID

Declaration: `function GetEGid : LongInt`

Visibility: default

Description: Get the effective group ID of the currently running process.

Errors: None.

See also: `GetGid` ([943](#))

Listing: ./olinuxex/ex18.pp

Program Example18;

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses oldlinux;

begin

writeln ('Group Id = ',getgid,' Effective group Id = ',getegid);

end.

23.12.50 GetEnv

Synopsis: Return value of environment variable.

Declaration: `function GetEnv(P: String) : PChar`

Visibility: default

Description: `GetEnv` returns the value of the environment variable in `P`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accomodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

Errors: None.

Listing: ./olinuxex/ex41.pp

Program Example41;

{ Program to demonstrate the GetEnv function. }

Uses oldlinux;

begin

Writeln ('Path is : ',Getenv('PATH'));

end.

23.12.51 GetEpochTime

Synopsis: Return the current unix time

Declaration: `function GetEpochTime : LongInt`

Visibility: default

Description: returns the number of seconds since 00:00:00 gmt, january 1, 1970. it is adjusted to the local time zone, but not to DST.

Errors: no errors

See also: [EpochToLocal \(921\)](#), [GetTime \(946\)](#)

Listing: ./olinuxex/ex1.pp

```

Program Example1;

{ Program to demonstrate the GetEpochTime function. }

Uses oldlinux;

begin
  Write ( 'Secs past the start of the Epoch (00:00 1/1/1980) : ');
  WriteLn ( GetEpochTime );
end.

```

23.12.52 GetEUid

Synopsis: Return effective user ID

Declaration: `function GetEUid : LongInt`

Visibility: default

Description: Get the effective user ID of the currently running process.

Errors: None.

See also: `GetUid` ([947](#))

Listing: ./olinuxex/ex17.pp

```

Program Example17;

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses oldlinux;

begin
  writeln ( 'User Id = ',getuid, ' Effective user Id = ',geteuid);
end.

```

23.12.53 GetFS

Synopsis: Return file selector

Declaration: `function GetFS(var T: Text) : LongInt`
`function GetFS(var F: File) : LongInt`

Visibility: default

Description: `GetFS` returns the file selector that the kernel provided for your file. In principle you don't need this file selector. Only for some calls it is needed, such as the `Select` ([962](#)) call or so.

Errors: In case the file was not opened, then -1 is returned.

See also: `Select` ([962](#))

Listing: ./olinuxex/ex34.pp

Program Example33;

{ Program to demonstrate the SelectText function. }

Uses oldlinux;

Var tv : TimeVal;

begin

Writeln ('Press the <ENTER> to continue the program.');

{ Wait until File descriptor 0 (=Input) changes }

 SelectText (Input, nil);

{ Get rid of <ENTER> in buffer }

readln;

Writeln ('Press <ENTER> key in less than 2 seconds...');

 tv.sec:=2;

 tv.usec:=0;

if SelectText (Input, @tv) > 0 **then**

Writeln ('Thank you !')

else

Writeln ('Too late !');

end.

23.12.54 GetGid

Synopsis: Return real group ID

Declaration: `function GetGid : LongInt`

Visibility: default

Description: Get the real group ID of the currently running process.

Errors: None.

See also: GetEGid ([940](#))

Listing: ./olinuxex/ex18.pp

Program Example18;

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses oldlinux;

begin

writeln ('Group Id = ', getgid, ' Effective group Id = ', getegid);

end.

23.12.55 GetHostName

Synopsis: Return host name

Declaration: `function GetHostName : String`

Visibility: default

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: `GetDomainName` ([940](#))

Listing: `./olinuxex/ex40.pp`

Program `Example40;`

{ Program to demonstrate the GetHostName function. }

Uses `oldlinux;`

begin

WriteLn ('Name of this machine is : ',GetHostName);
end.

23.12.56 GetLocalTimezone

Synopsis: Return local timezone information

Declaration:

```
procedure GetLocalTimezone(timer: LongInt;var leap_correct: LongInt;
                           var leap_hit: LongInt)
procedure GetLocalTimezone(timer: LongInt)
```

Visibility: `default`

Description: `GetLocalTimezone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` ([947](#)), `ReadTimezoneFile` ([962](#))

23.12.57 GetPid

Synopsis: Return current process ID

Declaration: `function GetPid : LongInt`

Visibility: `default`

Description: Get the Process ID of the currently running process.

Errors: None.

See also: `GetPPid` ([945](#))

Listing: `./olinuxex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid , GetPPid function. }

Uses `oldlinux;`

```
begin
  WriteLn ( 'Process Id = ',getpid, ' Parent process Id = ',getppid);
end.
```

23.12.58 GetPPid

Synopsis: Return parent process ID

Declaration: `function GetPPid : LongInt`

Visibility: default

Description: Get the Process ID of the parent process.

Errors: None.

See also: [GetPid \(944\)](#)

Listing: `./olinuxex/ex16.pp`

Program Example16;

{ Program to demonstrate the GetPid , GetPPid function . }

Uses oldlinux;

```
begin
  WriteLn ( 'Process Id = ',getpid, ' Parent process Id = ',getppid);
end.
```

23.12.59 GetPriority

Synopsis: Return process priority

Declaration: `function GetPriority(Which: Integer;Who: Integer) : Integer`

Visibility: default

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined Prio_Process, Prio_PGrp, Prio_User, in which case Who is the process ID, Process group ID or User ID, respectively.

For an example, see [Nice \(957\)](#).

Errors: Error checking must be done on `LinuxError`, since a priority can be negative.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

See also: [SetPriority \(965\)](#), [Nice \(957\)](#)

23.12.60 GetTime

Synopsis: Return current system time

Declaration: `procedure GetTime(var hour: Word; var min: Word; var sec: Word;
var msec: Word; var usec: Word)
procedure GetTime(var hour: Word; var min: Word; var sec: Word;
var sec100: Word)
procedure GetTime(var hour: Word; var min: Word; var sec: Word)`

Visibility: default

Description: Returns the current time of the day, adjusted to local time. Upon return, the parameters are filled with

hourHours since 00:00 today.

minminutes in current hour.

secseconds in current minute.

sec100hundreds of seconds in current second.

msecmilliseconds in current second.

usecmicroseconds in current second.

Errors: None

See also: [GetEpochTime \(941\)](#), [GetDate \(939\)](#), [GetDateTime \(939\)](#), [EpochToLocal \(921\)](#)

Listing: ./olinuxex/ex5.pp

Program Example5;

{ Program to demonstrate the GetTime function. }

Uses oldlinux;

Var Hour, Minute, Second : Word;

begin

GetTime (Hour, Minute, Second);

WriteLn ('Time : ', Hour:2, ': ', Minute:2, ': ', Second:2);

end.

23.12.61 GetTimeOfDay

Synopsis: Return kernel time of day in GMT

Declaration: `procedure GetTimeOfDay(var tv: timeval)
function GetTimeOfDay : LongInt`

Visibility: default

Description: `GetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call. To get the local time, [GetTime \(946\)](#).

Errors: None.

See also: [GetTime \(946\)](#), [GetTimeOfDay \(946\)](#)

23.12.62 GetTimezoneFile

Synopsis: Return name of timezone information file

Declaration: `function GetTimezoneFile : String`

Visibility: default

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` ([962](#))

23.12.63 GetUid

Synopsis: Return current user ID

Declaration: `function GetUid : LongInt`

Visibility: default

Description: Get the real user ID of the currently running process.

Errors: None.

See also: `GetEUid` ([942](#))

Listing: `./olinuxex/ex17.pp`

Program `Example17;`

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses `oldlinux;`

begin

`writeln ('User Id = ',getuid, ' Effective user Id = ',geteuid);`
end.

23.12.64 Glob

Synopsis: Find filenames matching a wildcard pattern

Declaration: `function Glob(const path: PathStr) : pglob`

Visibility: default

Description: `Glob` returns a pointer to a glob structure which contains all filenames which exist and match the pattern in `Path`. The pattern can contain wildcard characters, which have their usual meaning.

Errors: Returns nil on error, and `LinuxError` is set.

sys_enomem No memory on heap for glob structure.

others As returned by the `opendir` call, and `sys_readdir`.

See also: `GlobFree` (948)

Listing: `./olinuxex/ex49.pp`

Program `Example49`;

{ Program to demonstrate the Glob and GlobFree functions. }

Uses `oldlinux`;

Var `G1,G2 : PGlob`;

begin

`G1:=Glob ('*');`

`if LinuxError=0 then`

`begin`

`G2:=G1;`

`Writeln ('Files in this directory : ');`

`While g2<>Nil do`

`begin`

`Writeln (g2^.name);`

`g2:=g2^.next;`

`end;`

`GlobFree (g1);`

`end;`

`end.`

23.12.65 Globfree

Synopsis: Free result of `Glob` (947) call

Declaration: `procedure Globfree (var p: pglob)`

Visibility: default

Description: Releases the memory, occupied by a `pglob` structure. `P` is set to nil.

For an example, see `Glob` (947).

Errors: None

See also: `Glob` (947)

23.12.66 IOCtl

Synopsis: General kernel IOCTL call.

Declaration: `function IOCtl (Handle: LongInt; Ndx: LongInt; Data: Pointer) : Boolean`

Visibility: default

Description: This is a general interface to the Unix/ linux ioctl call. It performs various operations on the filedescriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under linux.

Errors: Errors are reported in `LinuxError`. They are very dependent on the used function, that's why we don't list them here

Listing: `./olinuxex/ex54.pp`

Program `Example54`;

uses `oldlinux`;

{ Program to demonstrate the IOCTL function. }

var

`tios` : `Termios`;

begin

`IOctl(1,TCGETS,@tios);`

`WriteLn('Input Flags : $',hexstr(tios.c_iflag,8));`

`WriteLn('Output Flags : $',hexstr(tios.c_oflag,8));`

`WriteLn('Line Flags : $',hexstr(tios.c_lflag,8));`

`WriteLn('Control Flags: $',hexstr(tios.c_cflag,8));`

end.

23.12.67 IOperm

Synopsis: Set permission on IO ports

Declaration: `function IOperm(From: Cardinal;Num: Cardinal;Value: LongInt) : Boolean`

Visibility: `default`

Description: `IOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns `True` if the call was successfull, `False` otherwise.

Note:

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `Fork` (935), the permissions are reset. When doing a `Execve` (925) they are kept.

Errors: Errors are returned in `LinuxError`

23.12.68 IoPL

Synopsis: Set I/O privilege level

Declaration: `function IoPL(Level: LongInt) : Boolean`

Visibility: `default`

Description: `IoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

23.12.69 IsATTY

Synopsis: Check if filehandle is a TTY (terminal)

Declaration: `function IsATTY(Handle: LongInt) : Boolean`
`function IsATTY(var f: text) : Boolean`

Visibility: default

Description: Check if the filehandle described by `f` is a terminal. `f` can be of type

1. `longint` for file handles;
2. Text for text variables such as input etc.

Returns `True` if `f` is a terminal, `False` otherwise.

Errors: No errors are reported

See also: [IOCtl \(948\)](#), [TTYName \(979\)](#)

23.12.70 Kill

Synopsis: Send a signal to a process

Declaration: `function Kill(Pid: LongInt; Sig: LongInt) : Integer`

Visibility: default

Description: Send a signal `Sig` to a process or process group. If `Pid > 0` then the signal is sent to `Pid`, if it equals `-1`, then the signal is sent to all processes except process 1. If `Pid < -1` then the signal is sent to process group `-Pid`. The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: `LinuxError` is used to report errors:

sys_einval An invalid signal is sent.

sys_esrch The `Pid` or process group don't exist.

sys_eperm The effective userid of the current process doesn't match the one of process `Pid`.

See also: [SigAction \(966\)](#), [Signal \(967\)](#)

23.12.71 Link

Synopsis: Create a hard link to a file

Declaration: `function Link(OldPath: PathStr; NewPath: PathStr) : Boolean`

Visibility: default

Description: `Link` makes `NewPath` point to the same file as `OldPath`. The two files then have the same inode number. This is known as a 'hard' link. The function returns `True` if the call was successful, `False` if the call failed.

Errors: Errors are returned in `LinuxError`.

sys_exdev `OldPath` and `NewPath` are not on the same filesystem.

sys_eperm The filesystem containing `oldpath` and `newpath` doesn't support linking files.

sys_eaccess Write access for the directory containing `NewPath` is disallowed, or one of the directories in `OldPath` or `{NewPath}` has no search (=execute) permission.

sys_enoent A directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdir A directory entry in `OldPath` or `NewPath` is not a directory.

sys_enomem Insufficient kernel memory.

sys_erofs The files are on a read-only filesystem.

sys_eexist `NewPath` already exists.

sys_mlink `OldPath` has reached maximal link count.

sys_eloop `OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospc The device containing `NewPath` has no room for another entry.

sys_eperm `OldPath` points to `.` or `..` of a directory.

See also: [SymLink \(971\)](#), [UnLink \(980\)](#)

Listing: `./olinuxex/ex21.pp`

Program `Example21;`

{ Program to demonstrate the Link and UnLink functions. }

Uses `oldlinux;`

Var `F : Text;`

`S : String;`

begin

`Assign (F, 'test.txt');`

`Rewrite (F);`

`Writeln (F, 'This is written to test.txt');`

`Close(f);`

{ new.txt and test.txt are now the same file }

if not `Link ('test.txt', 'new.txt')` **then**

`writeln ('Error when linking !');`

{ Removing test.txt still leaves new.txt }

If not `Unlink ('test.txt')` **then**

`Writeln ('Error when unlinking !');`

`Assign (f, 'new.txt');`

`Reset (F);`

While not `EOF(f)` **do**

begin

`Readln(F,S);`

`Writeln ('> ',s);`

end;

`Close (f);`

{ Remove new.txt also }

If not `Unlink ('new.txt')` **then**

`Writeln ('Error when unlinking !');`

end.

23.12.72 LocalToEpoch

Synopsis: Convert local time to epoch (unix) time

Declaration: `function LocalToEpoch(year: Word;month: Word;day: Word;hour: Word;
minute: Word;second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00 , January 1, 1970).

Errors: None

See also: [GetEpochTime \(941\)](#), [EpochToLocal \(921\)](#), [GetTime \(946\)](#), [GetDate \(939\)](#)

Listing: ./olinuxex/ex4.pp

Program Example4;

{ Program to demonstrate the LocalToEpoch function. }

Uses oldlinux;

Var year, month, day, hour, minute, second : Word;

begin

```
Write ( 'Year      : ' ); readln (Year);
Write ( 'Month     : ' ); readln (Month);
Write ( 'Day       : ' ); readln (Day);
Write ( 'Hour      : ' ); readln (Hour);
Write ( 'Minute    : ' ); readln (Minute);
Write ( 'Seconds   : ' ); readln (Second);
Write ( 'This is   : ' );
Write ( LocalToEpoch(year, month, day, hour, minute, second));
Writeln ( ' seconds past 00:00 1/1/1980 ' );
```

end.

23.12.73 Lstat

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function Lstat (Filename: PathStr;var Info: Stat) : Boolean`

Visibility: default

Description: LStat gets information about the link specified in Path, and stores it in Info, which is of type stat. Contrary to FStat, it stores information about the link, not about the file the link points to. The function returns True if the call was succesfull, False if the call failed.

Errors: LinuxError is used to report errors.

sys_enoentPath does not exist.

See also: [FStat \(938\)](#), [FSStat \(937\)](#)

Listing: ./olinuxex/ex29.pp

program example29;

{ Program to demonstrate the LStat function. }

uses oldlinux;

```

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil ');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if not fstat ('test.fil ', info) then
    begin
      writeln('Fstat failed. Errno : ', linuxerror);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil ''');
  writeln ('Inode      : ', info.ino);
  writeln ('Mode       : ', info.mode);
  writeln ('nlink      : ', info.nlink);
  writeln ('uid        : ', info.uid);
  writeln ('gid        : ', info.gid);
  writeln ('rdev       : ', info.rdev);
  writeln ('Size       : ', info.size);
  writeln ('Blksize    : ', info.blksize);
  writeln ('Blocks     : ', info.blocks);
  writeln ('atime      : ', info.atime);
  writeln ('mtime      : ', info.mtime);
  writeln ('ctime      : ', info.ctime);

  If not SymLink ('test.fil ', 'test.lnk') then
    writeln ('Link failed ! Errno : ', linuxerror);

  if not lstat ('test.lnk', info) then
    begin
      writeln('LStat failed. Errno : ', linuxerror);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.lnk ''');
  writeln ('Inode      : ', info.ino);
  writeln ('Mode       : ', info.mode);
  writeln ('nlink      : ', info.nlink);
  writeln ('uid        : ', info.uid);
  writeln ('gid        : ', info.gid);
  writeln ('rdev       : ', info.rdev);
  writeln ('Size       : ', info.size);
  writeln ('Blksize    : ', info.blksize);
  writeln ('Blocks     : ', info.blocks);
  writeln ('atime      : ', info.atime);
  writeln ('mtime      : ', info.mtime);
  writeln ('ctime      : ', info.ctime);
  { Remove file and link }
  erase (f);
  unlink ('test.lnk');
end.

```

23.12.74 mkFifo

Synopsis: Create FIFO (named pipe) in file system

Declaration: `function mkFifo(pathname: String; mode: LongInt) : Boolean`

Visibility: default

Description: `MkFifo` creates named a named pipe in the filesystem, with name `PathName` and mode `Mode`.

Errors: `LinuxError` is used to report errors:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `POpen` (959), `MkFifo` (954)

23.12.75 MMap

Synopsis: Create memory map of a file

Declaration: `function MMap(const m: tmmmapargs) : LongInt`

Visibility: default

Description: `MMap` maps or unmaps files or devices into memory. The different fields of the argument `m` determine what and how the `mmap` maps this:

address Address where to `mmap` the device. This address is a hint, and may not be followed.

size Size (in bytes) of area to be mapped.

prot Protection of mapped memory. This is a OR-ed combination of the following constants:

PROT_EXEC The memory can be executed.

PROT_READ The memory can be read.

PROT_WRITE The memory can be written.

PROT_NONE The memory can not be accessed.

flags Contains some options for the `mmap` call. It is an OR-ed combination of the following constants:

MAP_FIXED Do not map at another address than the given address. If the address cannot be used, `MMap` will fail.

MAP_SHARED Share this map with other processes that map this object.

MAP_PRIVATE Create a private map with copy-on-write semantics.

MAP_ANONYMOUS `fd` does not have to be a file descriptor.

One of the options `MAP_SHARED` and `MAP_PRIVATE` must be present, but not both at the same time.

fd File descriptor from which to map.

offset Offset to be used in file descriptor `fd`.

The function returns a pointer to the mapped memory, or a -1 in case of an error.

Errors: On error, -1 is returned and `LinuxError` is set to the error code:

Sys_EBADF `fd` is not a valid file descriptor and `MAP_ANONYMOUS` was not specified.

Sys_EACCES `MAP_PRIVATE` was specified, but `fd` is not open for reading. Or `MAP_SHARED` was asked and `PROT_WRITE` is set, `fd` is not open for writing

Sys_EINVAL One of the record fields `Start`, `length` or `offset` is invalid.

Sys_ETXTBUSY `MAP_DENYWRITE` was set but the object specified by `fd` is open for writing.

Sys_EAGAIN `fd` is locked, or too much memory is locked.

Sys_ENOMEM Not enough memory for this operation.

See also: `MUnMap` ([955](#))

Listing: `./olinuxex/ex66.pp`

Program `Example66`;

{ Program to demonstrate the MMap function. }

Uses `oldlinux`;

Var `S : String`;
 `fd, Len : Longint`;
 `args : tmapargs`;
 `P : PChar`;

begin
 `S := 'This is a string'#0`;
 `Len := Length(S)`;
 `fd := fdOpen('testfile.txt', Open_wrOnly or open_creat)`;
 If `fd = -1` **then**
 Halt(1);
 If `fdWrite(fd, S[1], Len) = -1` **then**
 Halt(2);
 `fdClose(fd)`;
 `fdOpen('testfile.txt', Open_rdOnly)`;
 if `fd = -1` **then**
 Halt(3);
 `args.address := 0`;
 `args.offset := 0`;
 `args.size := Len + 1`;
 `args.fd := fd`;
 `args.flags := MAP_PRIVATE`;
 `args.prot := PROT_READ or PROT_WRITE`;
 `P := PChar(mmap(args))`;
 If `longint(P) = -1` **then**
 Halt(4);
 WriteIn('Read in memory :', P);
 `fdclose(fd)`;
 if Not `MUnMap(P, Len)` **Then**
 Halt(LinuxError);
end.

23.12.76 MUnMap

Synopsis: Unmap previously mapped memory block

Declaration: `function MUnMap(P: Pointer; Size: LongInt) : Boolean`

Visibility: default

Description: `MUnMap` unmaps the memory block of size `Size`, pointed to by `P`, which was previously allocated with `MMap` (954).

The function returns `True` if successful, `False` otherwise.

For an example, see `MMap` (954).

Errors: In case of error the function returns `False` and `LinuxError` is set to an error value. See `MMap` (954) for possible error values.

See also: `MMap` (954)

23.12.77 NanoSleep

Synopsis: Suspend process for a short time

Declaration: `function NanoSleep(const req: timespec; var rem: timespec) : LongInt`

Visibility: default

Description: `NanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be `-1`, and `LinuxError` will be set to `EINTR`.

If the function returns without error, the return value is zero.

Errors: If the call was interrupted, `-1` is returned, and `LinuxError` is set to `EINTR`. If invalid time values were specified, then `-1` is returned and `LinuxError` is set to `EINVAL`.

See also: `Pause` (959), `Alarm` (909)

Listing: `./olinuxex/ex72.pp`

```

program example72;

{ Program to demonstrate the NanoSleep function. }

uses oldlinux;

Var
  Req, Rem : TimeSpec;
  Res : Longint;

begin
  With Req do
    begin
      tv_sec:=10;
      tv_nsec:=100;
    end;
  Write( 'NanoSleep returned : ');
  Flush( Output );
  Res:=( NanoSleep( Req, rem ) );
  WriteLn( res );
  If ( res<>0) then
    With rem do
      begin
        WriteLn( 'Remaining seconds      : ', tv_sec );
        WriteLn( 'Remaining nanoseconds : ', tv_nsec );
      end;
end.
```

23.12.78 Nice

Synopsis: Set process priority

Declaration: `procedure Nice(N: Integer)`

Visibility: default

Description: `Nice` adds $-N$ to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative N , i.e. increase the rate at which the process is run.

Errors: Errors are returned in `LinuxError`

sys_eperm A non-superuser tried to specify a negative N , i.e. do a priority increase.

See also: [GetPriority \(945\)](#), [SetPriority \(965\)](#)

Listing: `./olinuxex/ex15.pp`

Program `Example15;`

{ Program to demonstrate the Nice and Get/SetPriority functions. }

Uses `oldlinux;`

begin

```
writeln ('Setting priority to 5');
setpriority (prio_process, getpid, 5);
writeln ('New priority = ', getpriority (prio_process, getpid));
writeln ('Doing nice 10');
nice (10);
writeln ('New Priority = ', getpriority (prio_process, getpid));
```

end.

23.12.79 Octal

Synopsis: Convert octal to decimal value

Declaration: `function Octal(l: LongInt) : LongInt`

Visibility: default

Description: `Octal` will convert a number specified as an octal number to its decimal value.

This is useful for the `Chmod` ([914](#)) call, where permissions are specified as octal numbers.

Errors: No checking is performed whether the given number is a correct Octal number. e.g. specifying 998 is possible; the result will be wrong in that case.

See also: `Chmod` ([914](#))

Listing: `./olinuxex/ex68.pp`

Program `Example68;`

{ Program to demonstrate the Octal function. }

Uses `oldlinux;`

```

begin
  Writeln ( 'Mode 777 : ', Octal(777));
  Writeln ( 'Mode 644 : ', Octal(644));
  Writeln ( 'Mode 755 : ', Octal(755));
end.

```

23.12.80 OpenDir

Synopsis: Open directory for reading

Declaration: `function OpenDir(f: pchar) : PDir`
`function OpenDir(f: String) : PDir`

Visibility: default

Description: `OpenDir` opens the directory `f`, and returns a `pdir` pointer to a `Dir` record, which can be used to read the directory structure. If the directory cannot be opened, `nil` is returned.

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` (918), `ReadDir` (960), `SeekDir` (962), `TellDir` (979)

Listing: `./olinuxex/ex35.pp`

Program `Example35`;

```

{ Program to demonstrate the
  OpenDir, ReadDir, SeekDir and TellDir functions. }

```

Uses `oldlinux`;

```

Var TheDir : PDir;
    ADirent : PDirent;
    Entry : Longint;

```

```

begin
  TheDir:=OpenDir( './. ' );
  Repeat
    Entry:=TellDir(TheDir);
    ADirent:=ReadDir ( TheDir);
    If ADirent<>Nil then
      With ADirent^ do
        begin
          Writeln ( 'Entry No : ',Entry);
          Writeln ( 'Inode      : ',ino);
          Writeln ( 'Offset     : ',off);
          Writeln ( 'Reclen    : ',reclen);
          Writeln ( 'Name       : ',pchar(@name[0]));
        end;
  Until ADirent=Nil;
  Repeat
    Write ( 'Entry No. you would like to see again (-1 to stop): ');
    ReadLn ( Entry);
    If Entry<>-1 then
      begin
        SeekDir ( TheDir, Entry);
        ADirent:=ReadDir ( TheDir);

```

```

    If ADirent<>Nil then
      With ADirent^ do
        begin
          Writeln ( 'Entry No : ',Entry );
          Writeln ( 'Inode   : ',ino );
          Writeln ( 'Offset  : ',off );
          Writeln ( 'Reclen  : ',reclen );
          Writeln ( 'Name    : ',pchar(@name[0]));
        end;
      end;
    Until Entry=-1;
    CloseDir ( TheDir );
end.

```

23.12.81 Pause

Synopsis: Wait for a signal

Declaration: `procedure Pause`

Visibility: default

Description: `Pause` puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

For an example, see `Alarm` (909).

23.12.82 PClose

Synopsis: Close file opened with `POpen` (959)

Declaration: `function PClose(var F: text) : LongInt`
`function PClose(var F: file) : LongInt`

Visibility: default

Description: `PClose` closes a file opened with `POpen` (959). It waits for the command to complete, and then returns the exit status of the command.

For an example, see `POpen` (959)

Errors: `LinuxError` is used to report errors. If it is different from zero, the exit status is not valid.

See also: `POpen` (959)

23.12.83 POpen

Synopsis: Pipe file to standard input/output of program

Declaration: `procedure POpen(var F: text;const Prog: String;rw: Char)`
`procedure POpen(var F: file;const Prog: String;rw: Char)`

Visibility: default

Description: `POpen` runs the command specified in `Cmd`, and redirects the standard in or output of the command to the other end of the pipe `F`. The parameter `rw` indicates the direction of the pipe. If it is set to 'W', then `F` can be used to write data, which will then be read by the command from `stdin`. If it is set to 'R', then the standard output of the command can be read from `F`. `F` should be reset or rewritten prior to using it. `F` can be of type `Text` or `File`. A file opened with `POpen` can be closed with `Close`, but also with `PClose` (959). The result is the same, but `PClose` returns the exit status of the command `Cmd`.

Errors: Errors are reported in `LinuxError` and are essentially those of the `Execve`, `Dup` and `AssignPipe` commands.

See also: `AssignPipe` (910), `PClose` (959)

Listing: `./olinuxex/ex37.pp`

Program `Example37`;

```
{ Program to demonstrate the Popen function. }

uses oldlinux;

var f : text;
    i : longint;

begin
  writeln ('Creating a shell script to which echoes its arguments');
  writeln ('and input back to stdout');
  assign (f, 'test21a');
  rewrite (f);
  writeln (f, '#!/bin/sh');
  writeln (f, 'echo this is the child speaking.... ');
  writeln (f, 'echo got arguments \*"${*}"\*');
  writeln (f, 'cat');
  writeln (f, 'exit 2');
  writeln (f);
  close (f);
  chmod ('test21a', octal (755));
  popen (f, './test21a arg1 arg2', 'W');
  if linuxerror <> 0 then
    writeln ('error from POpen : Linuxerror : ', Linuxerror);
  for i:=1 to 10 do
    writeln (f, 'This is written to the pipe, and should appear on stdout. ');
  Flush(f);
  Writeln ('The script exited with status : ', PClose (f));
  writeln;
  writeln ('Press <return> to remove shell script. ');
  readln;
  assign (f, 'test21a');
  erase (f)
end.
```

23.12.84 ReadDir

Synopsis: Read entry from directory

Declaration: `function ReadDir(p: PDir) : pdirent`

Visibility: default

Description: `ReadDir` reads the next entry in the directory pointed to by `p`. It returns a `pdirent` pointer to a structure describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `OpenDir` (958).

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` (918), `OpenDir` (958), `SeekDir` (962), `TellDir` (979)

23.12.85 ReadLink

Synopsis: Read destination of symbolic link

Declaration: `function ReadLink(name: pchar; linkname: pchar; maxlen: LongInt) : LongInt`
`function ReadLink(name: PathStr) : PathStr`

Visibility: default

Description: `ReadLink` returns the file the symbolic link `name` is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. `LinuxError` is set to report errors:

SYS_ENOTDIRA part of the path in `Name` is not a directory.

SYS_EINVAL`maxlen` is not positive, or the file is not a symbolic link.

SYS_ENAMETOOLONGA pathname, or a component of a pathname, was too long.

SYS_ENOENTthe link `name` does not exist.

SYS_EACCESNo permission to search a directory in the path

SYS_ELOOPToo many symbolic links were encountered in translating the pathname.

SYS_EIOAn I/O error occurred while reading from the file system.

SYS_EFAULTThe buffer is not part of the process's memory space.

SYS_ENOMEMNot enough kernel memory was available.

See also: `SymLink` (971)

Listing: `./olinuxex/ex62.pp`

Program `Example62`;

{ Program to demonstrate the ReadLink function. }

Uses `oldlinux`;

Var `F : Text`;
`S : String`;

begin
`Assign (F, 'test.txt');`
`Rewrite (F);`
`WriteLn (F, 'This is written to test.txt');`

```

Close(f);
{ new.txt and test.txt are now the same file }
if not SymLink ('test.txt', 'new.txt') then
  writeln ('Error when symlinking !');
S:=ReadLink('new.txt');
If S='' then
  Writeln ('Error reading link !')
Else
  Writeln ('Link points to : ',S);
{ Now remove links }
If not Unlink ('new.txt') then
  Writeln ('Error when unlinking !');
If not Unlink ('test.txt') then
  Writeln ('Error when unlinking !');
end.

```

23.12.86 ReadTimezoneFile

Synopsis: Read the timezone file and initialize time routines

Declaration: `procedure ReadTimezoneFile(fn: String)`

Visibility: default

Description: `ReadTimezoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimezoneFile` ([947](#)), `GetLocalTimezone` ([944](#))

23.12.87 SeekDir

Synopsis: Seek to position in directory

Declaration: `procedure SeekDir(p: PDir; off: LongInt)`

Visibility: default

Description: `SeekDir` sets the directory pointer to the `off`-th entry in the directory structure pointed to by `p`.

For an example, see `OpenDir` ([958](#)).

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` ([918](#)), `ReadDir` ([960](#)), `OpenDir` ([958](#)), `TellDir` ([979](#))

23.12.88 Select

Synopsis: Wait for events on file descriptors

Declaration: `function Select(N: LongInt; readfds: pfdset; writefds: pfdset; exceptfds: pfdset; Timeout: ptimeval) : LongInt`
`function Select(N: LongInt; readfds: pfdset; writefds: pfdset; exceptfds: pfdset; Timeout: LongInt) : LongInt`

Visibility: default

Description: `Select` checks one of the file descriptors in the `FDSet`s to see if its status changed.

`readfds`, `writfds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if characters become available for reading. The entries in `writfds` are checked to see if it is OK to write to them, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions `FD_ZERO` (933), `FD_Clr` (932), `FD_Set` (932) or `FD_IsSet` (932) to manipulate the individual elements of a set.

The pointers can be `Nil`.

`N` is the largest index of a nonzero entry plus 1. (= the largest file-descriptor + 1).

`TimeOut` can be used to set a time limit. If `TimeOut` can be two types :

1. `TimeOut` is of type `PTime` and contains a zero time, the call returns immediately. If `TimeOut` is `Nil`, the kernel will wait forever, or until a status changed.
2. `TimeOut` is of type `Longint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `TimeOut` contains a time in milliseconds.

When the `TimeOut` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

Errors: On error, the function returns -1, and Errors are reported in `LinuxError` :

SYS_EBADF An invalid descriptor was specified in one of the sets.

SYS_EINTR A non blocked signal was caught.

SYS_EINVAL `N` is negative or too big.

SYS_ENOMEM `Select` was unable to allocate memory for its internal tables.

See also: `SelectText` (964), `GetFS` (942), `FD_ZERO` (933), `FD_Clr` (932), `FD_Set` (932), `FD_IsSet` (932)

Listing: `./olinuxex/ex33.pp`

Program `Example33`;

{ Program to demonstrate the Select function. }

Uses `oldlinux`;

Var `FDS` : `FDSet`;

begin

```

  FD_Zero (FDS);
  FD_Set (0,FDS);
  Writeln ( 'Press the <ENTER> to continue the program.' );
  { Wait until File descriptor 0 (=Input) changes }
  Select (1,@FDS,nil,nil,nil);
  { Get rid of <ENTER> in buffer }
  readln;
  Writeln ( 'Press <ENTER> key in less than 2 seconds...' );
  FD_Zero (FDS);
  FD_Set (0,FDS);

```

```

if Select (1,@FDS,nil ,nil ,2000)>0 then
  Writeln ( 'Thank you !')
  { FD_ISSET(0,FDS) would be true here. }
else
  Writeln ( 'Too late !');
end.

```

23.12.89 SelectText

Synopsis: Wait for event on typed ontyped file.

Declaration: `function SelectText (var T: Text; Timeout: ptimeval) : LongInt`
`function SelectText (var T: Text; Timeout: LongInt) : LongInt`

Visibility: default

Description: `SelectText` executes the `Select` (962) call on a file of type `Text`. You can specify a timeout in `Timeout`. The `SelectText` call determines itself whether it should check for read or write, depending on how the file was opened : With `Reset` it is checked for reading, with `Rewrite` and `Append` it is checked for writing.

Errors: See `Select` (962). `SYS_EBADF` can also mean that the file wasn't opened.

See also: `Select` (962), `GetFS` (942)

23.12.90 SetDate

Synopsis: Set the current system date.

Declaration: `function SetDate (Year: Word; Month: Word; Day: Word) : Boolean`

Visibility: default

Description: `SetDate` sets the system date to year, month, day. This is the kernel date, so it is in GMT. The time is not touched. The function returns `True` if the call was executed correctly, `False` otherwise.

Remark: You must be root to execute this call.

Errors: Errors are returned in `LinuxError` (908)

See also: `GetDate` (939), `SetTime` (965), `SetDateTime` (964)

23.12.91 SetDateTime

Synopsis: Set the current system date and time

Declaration: `function SetDateTime (Year: Word; Month: Word; Day: Word; hour: Word;`
`minute: Word; second: Word) : Boolean`

Visibility: default

Description: `SetDate` sets the system date and time to year, month, day, hour, min, Sec. This is the kernel date/time, so it is in GMT. The time is not touched. The function returns `True` if the call was executed correctly, `False` otherwise.

Remark: You must be root to execute this call.

Errors: Errors are returned in `LinuxError` (908)

See also: `SetDate` (964), `SetTime` (965), `GetDateTime` (939)

23.12.92 SetPriority

Synopsis: Set process priority

Declaration: `procedure SetPriority(Which: Integer;Who: Integer;What: Integer)`

Visibility: default

Description: SetPriority sets the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined constants:

Prio_ProcessWho is interpreted as process ID

Prio_PGrpWho is interpreted as process group ID

Prio_UserWho is interpreted as user ID

Prio is a value in the range -20 to 20.

For an example, see Nice (957).

Errors: Error checking must be done on LinuxError, since a priority can be negative.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

sys_epermA process was found, but neither its effective or real user ID match the effective user ID of the caller.

sys_eaccessA non-superuser tried to a priority increase.

See also: GetPriority (945), Nice (957)

23.12.93 SetTime

Synopsis: Set the current system time.

Declaration: `function SetTime(Hour: Word;Min: Word;Sec: Word) : Boolean`

Visibility: default

Description: SetTime sets the system time to hour, min, Sec. This is the kernel time, so it is in GMT. The date is not touched. The function returns True if the call was executed correctly, False otherwise.

Remark: You must be root to execute this call.

Errors: Errors are returned in LinuxError (908)

See also: GetTime (946), SetDate (964), SetDateTime (964)

23.12.94 Shell

Synopsis: Execute and feed command to system shell

Declaration: `function Shell(const Command: String) : LongInt`
`function Shell(const Command: AnsiString) : LongInt`

Visibility: default

Description: Shell invokes the bash shell (/bin/sh), and feeds it the command Command (using the -c option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the Fork (935) or Execve (925) calls.

Errors: Errors are reported in `LinuxError`.

See also: `POpen` (959), `Fork` (935), `Execve` (925)

Listing: `./olinuxex/ex56.pp`

```

program example56;

uses oldlinux;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  WriteLn ( 'Output of ls -l *.pp' );
  S:=Shell ( 'ls -l *.pp' );
  WriteLn ( 'Command exited with status : ',S);
end.

```

23.12.95 SigAction

Synopsis: Install signal handler

Declaration: `procedure SigAction(Signum: LongInt; Act: PSigActionRec;
OldAct: PSigActionRec)`

Visibility: default

Description: Changes the action to take upon receipt of a signal. `Act` and `Oldact` are pointers to a `SigActionRec` record. `SigNum` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `SigNum` is taken from it. If `OldAct` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

SA_NOCLDSTOP If `signum` is **SIGCHLD** do not receive notification when child processes stop.

SA_ONESHOT or **SA_RESETHAND** Restore the signal action to the default state once the signal handler has been called.

SA_RESTART For compatibility with BSD signals.

SA_NOMASK or **SA_NODEFER** Do not prevent the signal from being received from within its own signal handler.

Errors: `LinuxError` is used to report errors.

sys_einval an invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

sys_efault `Act`, `OldAct` point outside this process address space

sys_eintr System call was interrupted.

See also: `SigProcMask` (968), `SigPending` (968), `SigSuspend` (970), `Kill` (950)

Listing: `./olinuxex/ex57.pp`

```

Program example57;

{ Program to demonstrate the SigAction function.}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses oldlinux;

Var
    oa, na : PSigActionRec;

Procedure DoSig(sig : Longint); cdecl;

begin
    writeln ( 'Receiving signal: ', sig );
end;

begin
    new(na);
    new(oa);
    na^.Handler.sh:=@DoSig;
    na^.Sa_Mask:=0;
    na^.Sa_Flags:=0;
    na^.Sa_Restorer:=Nil;
    SigAction (SigUsr1, na, oa);
    if LinuxError <> 0 then
        begin
            writeln ( 'Error: ', linuxerror, '.' );
            halt (1);
        end;
    Writeln ( 'Send USR1 signal or press <ENTER> to exit' );
    readln;
end.

```

23.12.96 Signal

Synopsis: Install signal handler (deprecated)

Declaration: `function Signal(Signum: LongInt; Handler: SignalHandler) : SignalHandler`

Visibility: default

Description: `Signal` installs a new signal handler for signal `SigNum`. This call has the same functionality as the **SigAction** call. The return value for `Signal` is the old signal handler, or nil on error.

Errors: `LinuxError` is used to report errors :

SIG_ERR An error occurred.

See also: `SigAction` ([966](#)), `Kill` ([950](#))

Listing: ./olinuxex/ex58.pp

Program example58;

```
{ Program to demonstrate the Signal function.}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses oldlinux;

Procedure DoSig(sig : Longint);cdecl;

begin
  writeln('Receiving signal: ',sig);
end;

begin
  SigNal(SigUsr1,@DoSig);
  if LinuxError<>0 then
    begin
      writeln('Error: ',linuxerror, '.');
      halt(1);
    end;
  Writeln ('Send USR1 signal or press <ENTER> to exit');
  readln;
end.
```

23.12.97 SigPending

Synopsis: Return set of currently pending signals

Declaration: `function SigPending : SigSet`

Visibility: default

Description: Sigpending allows the examination of pending signals (which have been raised while blocked.) The signal mask of pending signals is returned.

Errors: None

See also: SigAction (966), SigProcMask (968), SigSuspend (970), Signal (967), Kill (950)

23.12.98 SigProcMask

Synopsis: Set list of blocked signals

Declaration: `procedure SigProcMask(How: LongInt; SSet: PSigSet; OldSSet: PSigSet)`

Visibility: default

Description: Changes the list of currently blocked signals. The behaviour of the call depends on How :

SIG_BLOCKThe set of blocked signals is the union of the current set and the SSet argument.

SIG_UNBLOCKThe signals in SSet are removed from the set of currently blocked signals.

SIG_SETMASKThe list of blocked signals is set so SSet.

If OldSSet is non-nil, then the old set is stored in it.

Errors: LinuxError is used to report errors.

sys_efaultSSet or OldSSet point to an adress outside the range of the process.

sys_eintrSystem call was interrupted.

See also: SigAction (966), SigPending (968), SigSuspend (970), Kill (950)

23.12.99 SigRaise

Synopsis: Raise a signal (send to current process)

Declaration: procedure SigRaise(Sig: Integer)

Visibility: default

Description: SigRaise sends a Sig signal to the current process.

Errors: None.

See also: Kill (950), GetPid (944)

Listing: ./olinuxex/ex65.pp

Program example64;

{ Program to demonstrate the SigRaise function. }

uses oldlinux;

Var

oa, na : PSigActionRec;

Procedure DoSig(sig : Longint); **cdecl**;

begin

writeln('Receiving signal: ', sig);

end;

begin

new(na);

new(oa);

na^.handler.sh:=@DoSig;

na^.Sa_Mask:=0;

na^.Sa_Flags:=0;

na^.Sa_Restorer:= Nil;

SigAction(SigUsr1, na, oa);

if LinuxError <> 0 **then**

begin

writeln('Error: ', linuxerror, ' ');

halt(1);

end;

Writeln('Sending USR1 (', sigusr1, ') signal to self. ');

SigRaise(sigusr1);

end.

23.12.100 SigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration: `procedure SigSuspend(Mask: SigSet)`

Visibility: default

Description: SigSuspend temporarily replaces the signal mask for the process with the one given in Mask, and then suspends the process until a signal is received.

Errors: None

See also: SigAction (966), SigProcMask (968), SigPending (968), Signal (967), Kill (950)

23.12.101 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: `function StringToPPChar(var S: String) : ppchar`
`function StringToPPChar(var S: AnsiString) : ppchar`
`function StringToPPChar(S: Pchar) : ppchar`

Visibility: default

Description: StringToPPChar splits the string S in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in S. This array is terminated by a Nil pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of PChar; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various Exec calls.

Errors: None.

See also: CreateShellArgV (918), Execve (925), Execv (924)

Listing: ./olinuxex/ex70.pp

Program Example70;

{ Program to demonstrate the StringToPPchar function. }

Uses oldlinux;

Var S : **String**;
P : PPChar;
I : longint;

begin
// remark whitespace at end.
S:= 'This is a string with words. ';
P:= StringToPPChar(S);
I:=0;
While P[I]<>Nil **do**
 begin
 Writeln('Word ',I, ' : ',P[I]);
 Inc(I);
 end

```

    end;
    FreeMem(P, i*SizeOf(Pchar));
end.

```

23.12.102 SymLink

Synopsis: Create a symbolic link

Declaration: `function SymLink(OldPath: PathStr; NewPath: PathStr) : Boolean`

Visibility: default

Description: `SymLink` makes `Newpath` point to the file in `OldPath`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: Errors are returned in `LinuxError`.

sys_eperm The filesystem containing `oldpath` and `newpath` does not support linking files.

sys_eaccess Write access for the directory containing `Newpath` is disallowed, or one of the directories in `OldPath` or `NewPath` has no search (=execute) permission.

sys_enoent A directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdir A directory entry in `OldPath` or `NewPath` is nor a directory.

sys_enomem Insufficient kernel memory.

sys_erofs The files are on a read-only filesystem.

sys_eexist `NewPath` already exists.

sys_eloop `OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospc The device containing `NewPath` has no room for another entry.

See also: [Link \(950\)](#), [UnLink \(980\)](#), [ReadLink \(961\)](#)

Listing: `./olinuxex/ex22.pp`

Program `Example22;`

{ Program to demonstrate the SymLink and UnLink functions. }

Uses `oldlinux;`

Var `F : Text;`
`S : String;`

begin
`Assign (F, 'test.txt');`
`Rewrite (F);`
`Writeln (F, 'This is written to test.txt');`
`Close(f);`
{ new.txt and test.txt are now the same file }
if not `SymLink ('test.txt', 'new.txt')` **then**

```

    writeln ( 'Error when symlinking !' );
    { Removing test.txt still leaves new.txt
      Pointing now to a non-existent file ! }
    If not Unlink ( 'test.txt' ) then
        Writeln ( 'Error when unlinking !' );
    Assign ( f, 'new.txt' );
    { This should fail, since the symbolic link
      points to a non-existent file ! }
    { $i- }
    Reset ( F );
    { $i+ }
    If IOResult=0 then
        Writeln ( 'This shouldn't happen' );
    { Now remove new.txt also }
    If not Unlink ( 'new.txt' ) then
        Writeln ( 'Error when unlinking !' );
end.

```

23.12.103 SysCall

Synopsis: Execute system call.

Declaration: `function SysCall(callnr: LongInt; var regs: SysCallRegs) : LongInt`

Visibility: default

Description: `SysCall` can be used to execute a direct system call. The call parameters must be encoded in `regs` and the call number must be specified by `callnr`. The call result is returned, and any modified registers are in `regs`

Errors: None.

See also: `SysCallRegs` ([904](#))

23.12.104 Sysinfo

Synopsis: Return kernel system information

Declaration: `function Sysinfo(var Info: TSysinfo) : Boolean`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

uptime Number of seconds since boot.

loads 1, 5 and 15 minute load averages.

totalram total amount of main memory.

freeram amount of free memory.

sharedram amount of shared memory.

bufferram amount of memory used by buffers.

totalswap total amount of swapspace.

freeswap amount of free swapspace.

procs number of current processes.

Errors: None.

See also: [Uname \(980\)](#)

Listing: ./olinuxex/ex64.pp

```

program Example64;

{ Example to demonstrate the SysInfo function }

Uses oldlinux;

Function Mb(L : Longint) : longint;

begin
  Mb:=L div (1024*1024);
end;

Var Info : TSysInfo;
      D,M,Secs,H : longint;

begin
  If Not SysInfo(Info) then
    Halt(1);
  With Info do
    begin
      D:=Uptime div (3600*24);
      UpTime:=UpTime mod (3600*24);
      h:=uptime div 3600;
      uptime:=uptime mod 3600;
      m:=uptime div 60;
      secs:=uptime mod 60;
      Writeln( 'Uptime : ',d,'days', 'h,' hours', 'm,' min', 'secs,' s.' );
      Writeln( 'Loads   : ',Loads[1], '/' ,Loads[2], '/' ,Loads[3]);
      Writeln( 'Total Ram   : ',Mb(totalram), 'Mb.' );
      Writeln( 'Free Ram    : ',Mb(freeram), 'Mb.' );
      Writeln( 'Shared Ram  : ',Mb(sharedram), 'Mb.' );
      Writeln( 'Buffer Ram  : ',Mb(bufferram), 'Mb.' );
      Writeln( 'Total Swap  : ',Mb(totalswap), 'Mb.' );
      Writeln( 'Free Swap   : ',Mb(freeswap), 'Mb.' );
    end;
  end.

```

23.12.105 S_ISBLK

Synopsis: Is file a block device

Declaration: `function S_ISBLK(m: Word) : Boolean`

Visibility: default

Description: S_ISBLK checks the file mode m to see whether the file is a block device file. If so it returns True.

See also: [FStat \(938\)](#), [S_ISLNK \(974\)](#), [S_ISREG \(975\)](#), [S_ISDIR \(974\)](#), [S_ISCHR \(974\)](#), [S_ISFIFO \(974\)](#), [S_ISSOCK \(975\)](#)

23.12.106 S_ISCHR

Synopsis: Is file a character device

Declaration: `function S_ISCHR(m: Word) : Boolean`

Visibility: default

Description: `S_ISCHR` checks the file mode `m` to see whether the file is a character device file. If so it returns `True`.

See also: `FStat` (938), `S_ISLNK` (974), `S_ISREG` (975), `S_ISDIR` (974), `S_ISBLK` (973), `S_ISFIFO` (974), `S_ISSOCK` (975)

23.12.107 S_ISDIR

Synopsis: Is file a directory

Declaration: `function S_ISDIR(m: Word) : Boolean`

Visibility: default

Description: `S_ISDIR` checks the file mode `m` to see whether the file is a directory. If so it returns `True`

See also: `FStat` (938), `S_ISLNK` (974), `S_ISREG` (975), `S_ISCHR` (974), `S_ISBLK` (973), `S_ISFIFO` (974), `S_ISSOCK` (975)

23.12.108 S_ISFIFO

Synopsis: Is file a FIFO

Declaration: `function S_ISFIFO(m: Word) : Boolean`

Visibility: default

Description: `S_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FStat` (938), `S_ISLNK` (974), `S_ISREG` (975), `S_ISCHR` (974), `S_ISBLK` (973), `S_ISDIR` (974), `S_ISSOCK` (975)

23.12.109 S_ISLNK

Synopsis: Is file a symbolic link

Declaration: `function S_ISLNK(m: Word) : Boolean`

Visibility: default

Description: `S_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FStat` (938), `S_ISFIFO` (974), `S_ISREG` (975), `S_ISCHR` (974), `S_ISBLK` (973), `S_ISDIR` (974), `S_ISSOCK` (975)

Listing: `./olinuxex/ex53.pp`

```

Program Example53;

{ Program to demonstrate the S_ISLNK function. }

Uses oldlinux;

Var Info : Stat;

begin
  if LStat (paramstr(1),info) then
    begin
      if S_ISLNK(info.mode) then
        Writeln ('File is a link');
      if S_ISREG(info.mode) then
        Writeln ('File is a regular file');
      if S_ISDIR(info.mode) then
        Writeln ('File is a directory');
      if S_ISCHR(info.mode) then
        Writeln ('File is a character device file');
      if S_ISBLK(info.mode) then
        Writeln ('File is a block device file');
      if S_ISFIFO(info.mode) then
        Writeln ('File is a named pipe (FIFO)');
      if S_ISSOCK(info.mode) then
        Writeln ('File is a socket');
      end;
    end.

```

23.12.110 S_ISREG

Synopsis: Is file a regular file

Declaration: `function S_ISREG(m: Word) : Boolean`

Visibility: default

Description: S_ISREG checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: FStat ([938](#)), S_ISFIFO ([974](#)), S_ISLNK ([974](#)), S_ISCHR ([974](#)), S_ISBLK ([973](#)), S_ISDIR ([974](#)), S_ISSOCK ([975](#))

23.12.111 S_ISSOCK

Synopsis: Is file a unix socket

Declaration: `function S_ISSOCK(m: Word) : Boolean`

Visibility: default

Description: S_ISSOCK checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: FStat ([938](#)), S_ISFIFO ([974](#)), S_ISLNK ([974](#)), S_ISCHR ([974](#)), S_ISBLK ([973](#)), S_ISDIR ([974](#)), S_ISREG ([975](#))

23.12.112 TCDrain

Synopsis: Terminal control: Wait till all data was transmitted

Declaration: `function TCDrain(fd: LongInt) : Boolean`

Visibility: default

Description: `TCDrain` waits until all data to file descriptor `Fd` is transmitted.

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`

See also: `TCFlow` (976), `TCFlush` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

23.12.113 TCFlow

Synopsis: Terminal control: Suspend transmission of data

Declaration: `function TCFlow(fd: LongInt;act: LongInt) : Boolean`

Visibility: default

Description: `TCFlow` suspends/resumes transmission or reception of data to or from the file descriptor `Fd`, depending on the action `Act`.

This can be one of the following pre-defined values:

TCOOFFsuspend reception/transmission

TCOONresume reception/transmission

TCIOFFtransmit a stop character to stop input from the terminal

TCIONtransmit start to resume input from the terminal.

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (976), `TCFlow` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

23.12.114 TCFlush

Synopsis: Terminal control: Discard data buffer

Declaration: `function TCFlush(fd: LongInt;qsel: LongInt) : Boolean`

Visibility: default

Description: `TCFlush` discards all data sent or received to/from file descriptor `fd`. `QSel` indicates which queue should be discard. It can be one of the following pre-defined values :

TCIFLUSHinput buffer

TCOFLUSHoutput buffer

TCIOFLUSHboth input and output buffers

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (976), `TCFlow` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

23.12.115 TCGetAttr

Synopsis: Terminal Control: Get terminal attributes

Declaration: `function TCGetAttr(fd: LongInt; var tios: Termios) : Boolean`

Visibility: default

Description: `TCGetAttr` gets the terminal parameters from the terminal referred to by the file descriptor `fd` and returns them in a `TermIOS` structure `tios`. The function returns `True` if the call was successful, `False` otherwise.

Errors: Errors are reported in `LinuxError`

See also: `TCDrain` (976), `TCFlow` (976), `TCFlush` (976), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

Listing: `./olinuxex/ex55.pp`

Program `Example55`;

`uses` `oldlinux`;

{ Program to demonstrate the TCGetAttr/TCSetAttr/CFMakeRaw functions. }

procedure `ShowTermios`(**var** `tios`:`Termios`);

begin

WriteLn('Input Flags : \$', `hexstr(tios.c_iflag,8)+#13`);

WriteLn('Output Flags : \$', `hexstr(tios.c_oflag,8)`);

WriteLn('Line Flags : \$', `hexstr(tios.c_lflag,8)`);

WriteLn('Control Flags: \$', `hexstr(tios.c_cflag,8)`);

end;

var

`oldios` ,

`tios` : `Termios`;

begin

WriteLn('Old attributes:');

`TCGetAttr`(1,`tios`);

`ShowTermios`(`tios`);

`oldios:=tios`;

WriteLn('Setting raw terminal mode');

`CFMakeRaw`(`tios`);

`TCSetAttr`(1,`TCSANOW`,`tios`);

WriteLn('Current attributes:');

`TCGetAttr`(1,`tios`);

`ShowTermios`(`tios`);

`TCSetAttr`(1,`TCSANOW`,`oldios`);

end.

23.12.116 TCGetPGrp

Synopsis: Terminal control: Get process group

Declaration: `function TCGetPGrp(fd: LongInt; var id: LongInt) : Boolean`

Visibility: default

Description: `TCGetPGrp` returns the process group ID of a foreground process group in `Id`. The function returns `True` if the call was successful, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (976), `TCFlow` (976), `TCFlush` (976), `TCGetAttr` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

23.12.117 TCSendBreak

Synopsis: Terminal control: Send break

Declaration: `function TCSendBreak(fd: LongInt;duration: LongInt) : Boolean`

Visibility: default

Description: `TCSendBreak` Sends zero-valued bits on an asynchrone serial connection described by file-descriptor `Fd`, for duration `Duration`. The function returns `True` if the action was performed successfully, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (976), `TCFlow` (976), `TCFlush` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSetAttr` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

23.12.118 TCSetAttr

Synopsis: Terminal control: Set attributes

Declaration: `function TCSetAttr(fd: LongInt;OptAct: LongInt;const tios: Termios) : Boolean`

Visibility: default

Description: `TCSetAttr` sets the terminal parameters you specify in a `TermIOS` structure `Tios` for the terminal referred to by the file descriptor `Fd`.

`OptAct` specifies an optional action when the set need to be done, this could be one of the following pre-defined values:

TCSANOW set immediately.

TCSADRAIN wait for output.

TCSAFLUSH wait for output and discard all input not yet read.

The function Returns `True` if the call was successful, `False` otherwise.

For an example, see `TCGetAttr` (977).

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (976), `TCFlow` (976), `TCFlush` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetPGrp` (979), `TTYName` (979), `IsATTY` (950)

23.12.119 TCSetsPGrp

Synopsis: Terminal control: Set process group

Declaration: `function TCSetsPGrp(fd: LongInt;id: LongInt) : Boolean`

Visibility: default

Description: `TCSetsPGrp` Sets the Process Group Id to `Id`. The function returns `True` if the call was successful, `False` otherwise.

For an example, see `TCGetPGrp` (977).

Errors: Errors are returned in `LinuxError`.

See also: `TCDrain` (976), `TCFlow` (976), `TCFlush` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TTYName` (979), `IsATTY` (950)

23.12.120 Telldir

Synopsis: Return current location in a directory

Declaration: `function Telldir(p: PDir) : LongInt`

Visibility: default

Description: `Telldir` returns the current location in the directory structure pointed to by `p`. It returns `-1` on failure.

For an example, see `OpenDir` (958).

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` (918), `ReadDir` (960), `SeekDir` (962), `OpenDir` (958)

23.12.121 TTYname

Synopsis: Terminal control: Get terminal name

Declaration: `function TTYname(Handle: LongInt) : String`
`function TTYname(var F: Text) : String`

Visibility: default

Description: `TTYName` Returns the name of the terminal pointed to by `f`. `f` must be a terminal. `f` can be of type:

1. `longint` for file handles;
2. `Text` for text variables such as `input` etc.

Errors: Returns an empty string in case of an error. `Linuxerror` may be set to indicate what error occurred, but this is uncertain.

See also: `TCDrain` (976), `TCFlow` (976), `TCFlush` (976), `TCGetAttr` (977), `TCGetPGrp` (977), `TCSendBreak` (978), `TCSetAttr` (978), `TCSetPGrp` (979), `IsATTY` (950), `IOctl` (948)

23.12.122 Umask

Synopsis: Set file creation mask.

Declaration: `function Umask(Mask: Integer) : Integer`

Visibility: default

Description: Change the file creation mask for the current user to `Mask`. The current mask is returned.

See also: `Chmod` ([914](#))

Listing: `./olinuxex/ex27.pp`

Program `Example27;`

{ Program to demonstrate the Umask function. }

Uses `oldlinux;`

begin

WriteLn ('Old Umask was : ', Umask(Octal(111)));

WRiteLn ('New Umask is : ', Octal(111));

end.

23.12.123 Uname

Synopsis: Return system name.

Declaration: `function Uname(var unamerec: utsname) : Boolean`

Visibility: default

Description: `Uname` gets the name and configuration of the current linux kernel, and returns it in `unamerec`.

Errors: `LinuxError` is used to report errors.

See also: `GetHostName` ([943](#)), `GetDomainName` ([940](#))

23.12.124 UnLink

Synopsis: `Unlink` (i.e. remove) a file.

Declaration: `function UnLink(Path: PathStr) : Boolean`
`function UnLink(Path: pchar) : Boolean`

Visibility: default

Description: `UnLink` decreases the link count on file `Path`. `Path` can be of type `PathStr` or `PChar`. If the link count is zero, the file is removed from the disk. The function returns `True` if the call was succesfull, `False` if the call failed.

For an example, see `Link` ([950](#)).

Errors: Errors are returned in `LinuxError`.

sys_eaccess You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

sys_epermThe directory containing pathname has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

sys_enoentA component of the path doesn't exist.

sys_enotdirA directory component of the path is not a directory.

sys_eisdirPath refers to a directory.

sys_enomemInsufficient kernel memory.

sys_erofsPath is on a read-only filesystem.

See also: [Link \(950\)](#), [SymLink \(971\)](#)

23.12.125 Utime

Synopsis: Set access and modification times of a file (touch).

Declaration: `function Utime(const path: PathStr; utim: UTimeBuf) : Boolean`

Visibility: default

Description: `Utime` sets the access and modification times of a file. the `utimbuf` record contains 2 fields, `actime`, and `modtime`, both of type `Longint`. They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

Errors: Errors are returned in `LinuxError`.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: [GetEpochTime \(941\)](#), [Chown \(915\)](#), [Access \(908\)](#)

Listing: `./olinuxex/ex25.pp`

Program `Example25;`

{ Program to demonstrate the UTime function. }

Uses `oldlinux;`

Var `utim : utimbuf;`
`year, month, day, hour, minute, second : Word;`

begin
{ Set access and modification time of executable source }
`GetTime (hour, minute, second);`
`GetDate (year, month, day);`
`utim.actime := LocalToEpoch (year, month, day, hour, minute, second);`
`utim.modtime := utim.actime;`
if not `Utime ('ex25.pp', utim) then`
 `writeln ('Call to UTime failed !')`
else
 begin
 `Write ('Set access and modification times to : ');`
 `Write (Hour:2, ': ', minute:2, ': ', second, ' ', ');`
 end

```

    Writeln (Day:2, ' / ', month:2, ' / ', year:4);
end;
end.

```

23.12.126 WaitPid

Synopsis: Wait for a process to terminate

Declaration: `function WaitPid(Pid: LongInt; Status: pointer; Options: LongInt) : LongInt`

Visibility: default

Description: `WaitPid` waits for a child process with process ID `Pid` to exit. The value of `Pid` can be one of the following:

Pid < -1 Causes `WaitPid` to wait for any child process whose process group ID equals the absolute value of `pid`.

Pid = -1 Causes `WaitPid` to wait for any child process.

Pid = 0 Causes `WaitPid` to wait for any child process whose process group ID equals the one of the calling process.

Pid > 0 Causes `WaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `WaitPid` behaves:

WNOHANG Causes `Waitpid` to return immediately if no child has exited.

WUNTRACED Causes `WaitPid` to return also for children which are stopped, but whose status has not yet been reported.

__WCLONE Causes `WaitPid` also to wait for threads created by the [Clone \(916\)](#) call.

Upon return, it returns the exit status of the process, or -1 in case of failure.

For an example, see [Fork \(935\)](#).

Errors: Errors are returned in `LinuxError`.

See also: [Fork \(935\)](#), [Execve \(925\)](#)

23.12.127 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: `function WaitProcess(Pid: LongInt) : LongInt`

Visibility: default

Description: `WaitProcess` waits for process `PID` to exit. `WaitProcess` is equivalent to the [WaitPID \(982\)](#) call:

```
WaitPid(PID, @result, 0)
```

Handles of Signal interrupts (`errno=EINTR`), and returns the Exitcode of Process `PID` (`>=0`) or - Status if it was terminated

Errors: None.

See also: [WaitPID \(982\)](#), [WTERMSIG \(984\)](#), [WSTOPSIG \(984\)](#), [WIFEXITED \(983\)](#), [WIFSTOPPED \(983\)](#), [WIFSIGNALED \(983\)](#), [W_EXITCODE \(984\)](#), [W_STOPCODE \(984\)](#), [WEXITSTATUS \(983\)](#)

23.12.128 WEXITSTATUS

Synopsis: Extract the exit status from the `WaitPID` (982) result.

Declaration: `function WEXITSTATUS (Status: Integer) : Integer`

Visibility: default

Description: `WEXITSTATUS` can be used to extract the exit status from `Status`, the result of the `WaitPID` (982) call.

See also: `WaitPID` (982), `WaitProcess` (982), `WTERMSIG` (984), `WSTOPSIG` (984), `WIFEXITED` (983), `WIFSTOPPED` (983), `WIFSIGNALED` (983), `W_EXITCODE` (984), `W_STOPCODE` (984)

23.12.129 WIFEXITED

Synopsis: Check whether the process exited normally

Declaration: `function WIFEXITED (Status: Integer) : Boolean`

Visibility: default

Description: `WIFEXITED` checks `Status` and returns `True` if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: `WaitPID` (982), `WaitProcess` (982), `WTERMSIG` (984), `WSTOPSIG` (984), `WIFSTOPPED` (983), `WIFSIGNALED` (983), `W_EXITCODE` (984), `W_STOPCODE` (984), `WEXITSTATUS` (983)

23.12.130 WIFSIGNALED

Synopsis: Check whether the process was exited by a signal.

Declaration: `function WIFSIGNALED (Status: Integer) : Boolean`

Visibility: default

Description: `WIFSIGNALED` returns `True` if `Status` indicates that the process exited because it received a signal.

See also: `WaitPID` (982), `WaitProcess` (982), `WTERMSIG` (984), `WSTOPSIG` (984), `WIFEXITED` (983), `WIFSTOPPED` (983), `W_EXITCODE` (984), `W_STOPCODE` (984), `WEXITSTATUS` (983)

23.12.131 WIFSTOPPED

Synopsis: Check whether the process is currently stopped.

Declaration: `function WIFSTOPPED (Status: Integer) : Boolean`

Visibility: default

Description: `WIFSTOPPED` checks `Status` and returns `true` if the process is currently stopped. This is only possible if `WUNTRACED` was specified in the options of `WaitPID` (982).

See also: `WaitPID` (982), `WaitProcess` (982), `WTERMSIG` (984), `WSTOPSIG` (984), `WIFEXITED` (983), `WIFSIGNALED` (983), `W_EXITCODE` (984), `W_STOPCODE` (984), `WEXITSTATUS` (983)

23.12.132 WSTOPSIG

Synopsis: Return the exit code from the process.

Declaration: `function WSTOPSIG(Status: Integer) : Integer`

Visibility: default

Description: WSTOPSIG is an alias for WEXITSTATUS (983).

See also: WaitPID (982), WaitProcess (982), WTERMSIG (984), WIFEXITED (983), WIFSTOPPED (983), WIFSIGNALED (983), W_EXITCODE (984), W_STOPCODE (984), WEXITSTATUS (983)

23.12.133 WTERMSIG

Synopsis: Return the signal that caused a process to exit.

Declaration: `function WTERMSIG(Status: Integer) : Integer`

Visibility: default

Description: WTERMSIG extracts from Status the signal number which caused the process to exit.

See also: WaitPID (982), WaitProcess (982), WSTOPSIG (984), WIFEXITED (983), WIFSTOPPED (983), WIFSIGNALED (983), W_EXITCODE (984), W_STOPCODE (984), WEXITSTATUS (983)

23.12.134 W_EXITCODE

Synopsis: Construct an exit status based on an return code and signal.

Declaration: `function W_EXITCODE(ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

Description: W_EXITCODE combines ReturnCode and Signal to a status code fit for WaitPid.

See also: WaitPID (982), WaitProcess (982), WTERMSIG (984), WSTOPSIG (984), WIFEXITED (983), WIFSTOPPED (983), WIFSIGNALED (983), W_STOPCODE (984), WEXITSTATUS (983)

23.12.135 W_STOPCODE

Synopsis: Construct an exit status based on a signal.

Declaration: `function W_STOPCODE(Signal: Integer) : Integer`

Visibility: default

Description: W_STOPCODE constructs an exit status based on Signal, which will cause WIFSIGNALED (983) to return True

See also: WaitPID (982), WaitProcess (982), WTERMSIG (984), WSTOPSIG (984), WIFEXITED (983), WIFSTOPPED (983), WIFSIGNALED (983), W_EXITCODE (984), WEXITSTATUS (983)

Chapter 24

Reference for unit 'ports'

24.1 Overview

The ports unit implements the `port` constructs found in Turbo Pascal. It uses classes and default array properties to do this.

The unit exists on linux, os/2 and dos. It is implemented only for compatibility with Turbo Pascal. It's usage is discouraged, because using ports is not portable programming, and the operating system may not even allow it (for instance Windows).

Under linux, your program must be run as root, or the `IOPerm` call must be set in order to set appropriate permissions on the port access.

24.2 Constants, types and variables

24.2.1 Variables

`port : tport`

Default instance of type `TPort` (986). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
port[221]:=12;
```

Will result in the integer 12 being written to port 221, if port is defined as a variable of type `tport`

`portb : tport`

Default instance of type `TPort` (986). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portb[221]:=12;
```

Will result in the byte 12 being written to port 221, if port is defined as a variable of type `tport`

```
portl : tportl
```

Default instance of type TPortL ([986](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portl[221]:=12;
```

Will result in the longint 12 being written to port 221, if port is defined as a variable of type tport

```
portw : tportw
```

Default instance of type TPortW ([987](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portb[221]:=12;
```

Will result in the word 12 being written to port 221, if port is defined as a variable of type tport

24.3 tport

24.3.1 Description

The TPort type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

24.3.2 Property overview

Page	Property	Access	Description
986	pp	rw	Access integer-sized port by port number

24.3.3 tport.pp

Synopsis: Access integer-sized port by port number

Declaration: Property pp[w: LongInt]: Byte; default

Visibility: public

Access: Read,Write

Description: Access integer-sized port by port number

24.4 tportl

24.4.1 Description

The TPortL type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

24.4.2 Property overview

Page	Property	Access	Description
987	pp	rw	Access Longint-sized port by port number

24.4.3 tportl.pp

Synopsis: Access Longint-sized port by port number

Declaration: `Property pp[w: LongInt]: LongInt; default`

Visibility: `public`

Access: `Read,Write`

Description: Access Longint-sized port by port number

24.5 tportw

24.5.1 Description

The `TPortW` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

24.5.2 Property overview

Page	Property	Access	Description
987	pp	rw	Access word-sized port by port number

24.5.3 tportw.pp

Synopsis: Access word-sized port by port number

Declaration: `Property pp[w: LongInt]: Word; default`

Visibility: `public`

Access: `Read,Write`

Description: Access word-sized port by port number

Chapter 25

Reference for unit 'printer'

25.1 Overview

This chapter describes the PRINTER unit for Free Pascal. It was written for dos by Florian Klaempfl, and it was written for linux by Michael Van Canneyt, and has been ported to Windows and os/2 as well. Its basic functionality is the same for all supported systems, although there are minor differences on linux/unix.

25.2 Constants, types and variables

25.2.1 Variables

`Lst : text`

`Lst` is the standard printing device.

On linux, `Lst` is set up using `AssignLst ('/tmp/PID.lst')`.

25.3 Procedures and functions

25.3.1 AssignLst

Synopsis: Assign text file to printing device

Declaration: `procedure AssignLst (var F: text; ToFile: String)`

Visibility: default

Description: `AssignLst` Assigns to `F` a printing device - *Unix only*. `ToFile` is a string with the following form:

- `'|filename options'` : This sets up a pipe with the program filename, with the given options, such as in the `popen()` call.
- `'filename'` : Prints to file filename. Filename can contain the string 'PID' (No Quotes), which will be replaced by the PID of your program. When closing `lst`, the file will be sent to `lpr` and deleted. (`lpr` should be in `PATH`)
- `{'filename|'}` Idem as previous, only the file is NOT sent to `lpr`, nor is it deleted. (useful for opening `/dev/printer` or for later printing)

Errors: Errors are reported in `Linuxerror`.

See also: `lst` ([988](#))

Listing: `./printex/printex.pp`

```

program testprn;

uses printer;

var i : integer;
    f : text;

begin
  writeln ('Test of printer unit');
  writeln ('Writing to lst...');
  for i:=1 to 80 do writeln (lst, 'This is line ', i, '.' #13);
  close (lst);
  writeln ('Done. ');
  { $ifdef Unix }
  writeln ('Writing to pipe...');
  assign lst (f, '|/usr/bin/lpr -m');
  rewrite (f);
  for i:=1 to 80 do writeln (f, 'This is line ', i, '.' #13);
  close (f);
  writeln ('Done. ')
  { $endif }
end.

```

25.3.2 InitPrinter

Synopsis: Initialize the printer

Declaration: `procedure InitPrinter(const PrinterName: String)`

Visibility: default

Description: Initialize the printer

25.3.3 IsLstAvailable

Synopsis: Determine whether printer is available.

Declaration: `function IsLstAvailable : Boolean`

Visibility: default

Description: Determine whether printer is available.

Chapter 26

Reference for unit 'Sockets'

26.1 Used units

Table 26.1: Used units by unit 'Sockets'

Name	Page
UnixType	990

26.2 Overview

This document describes the SOCKETS unit for Free Pascal. it was written for linux by Michael Van Canneyt, and ported to Windows by Florian Klaempfl.

26.3 Constants, types and variables

26.3.1 Constants

`AF_APPLETALK = 16`

Socket domain: Appletalk DDP

`AF_ATM = 30`

Address family: ?

`AF_CCITT = 10`

Address family: ?

`AF_CHAOS = 5`

Address family: ?

AF_CNT = 21

Address family: ?

AF_COIP = 20

Address family: ?

AF_DATAKIT = 9

Address family: ?

AF_DECnet = 12

Address family: Reserved for DECnet project.

AF_DLI = 13

Address family: ?

AF_E164 = AF_ISDN

Address family: ?

AF_ECMA = 8

Address family: ?

AF_FILE = PF_FILE

Address family: Unix socket (alias)

AF_HYLINK = 15

Address family: ?

AF_IMPLINK = 3

Address family: ?

AF_INET = PF_INET

Socket domain: Internet IP Protocol

AF_INET6 = 28

Socket domain: IP version 6

AF_IPX = 23

Socket domain: Novell IPX

AF_ISDN = 26

Address family: ?

AF_ISO = 7

Address family: ?

AF_LAT = 14

Address family: ?

AF_LINK = 18

Address family: ?

AF_LOCAL = PF_LOCAL

Address family: Unix socket

AF_MAX = 33

Socket domain: Maximum value

AF_NATM = 29

Address family: ?

AF_NETGRAPH = 32

Address family: ?

AF_NS = 6

Address family: ?

AF_OSI = AF_ISO

Address family: ?

AF_PUP = 4

Address family: ?

AF_ROUTE = 17

Address family: Alias to emulate 4.4BSD.

AF_SIP = 24

Address family: ?

AF_SNA = 11

Address family: Linux SNA project

AF_UNIX = PF_UNIX

Socket domain: Unix domain sockets

AF_UNSPEC = PF_UNSPEC

Socket domain: Not specified

INADDR_ANY = CARDINAL (0)

Undocumented ?

INADDR_NONE = CARDINAL (\$FFFFFFFF)

Undocumented ?

IPPROTO_AH = 51

authentication header.

IPPROTO_COMP = 108

Compression Header Protocol.

IPPROTO_DSTOPTS = 60

IPv6 destination options.

IPPROTO_EGP = 8

Exterior Gateway Protocol.

IPPROTO_ENCAP = 98

Encapsulation Header.

IPPROTO_ESP = 50

encapsulating security payload.

IPPROTO_FRAGMENT = 44

IPv6 fragmentation header.

IPPROTO_GRE = 47

General Routing Encapsulation.

IPPROTO_HOPOPTS = 0

IPv6 Hop-by-Hop options.

IPPROTO_ICMP = 1

Internet Control Message Protocol.

IPPROTO_ICMPV6 = 58

ICMPv6.

IPPROTO_IDP = 22

XNS IDP protocol.

IPPROTO_IGMP = 2

Internet Group Management Protocol.

IPPROTO_IP = 0

Dummy protocol for TCP.

IPPROTO_IPIP = 4

IPIP tunnels (older KA9Q tunnels use 94).

IPPROTO_IPV6 = 41

IPv6 header.

IPPROTO_MAX = 255

Maximum value for IPPROTO options

IPPROTO_MTP = 92

Multicast Transport Protocol.

IPPROTO_NONE = 59

IPv6 no next header.

IPPROTO_PIM = 103

Protocol Independent Multicast.

IPPROTO_PUP = 12

PUP protocol.

IPPROTO_RAW = 255

Raw IP packets.

IPPROTO_ROUTING = 43

IPv6 routing header.

IPPROTO_RSVP = 46

Reservation Protocol.

IPPROTO_SCTP = 132

Stream Control Transmission Protocol.

IPPROTO_TCP = 6

Transmission Control Protocol.

IPPROTO_TP = 29

SO Transport Protocol Class 4.

IPPROTO_UDP = 17

User Datagram Protocol.

IPV6_ADDRFORM = 1

Undocumented Getsockopt option ?

IPV6_ADD_MEMBERSHIP = IPV6_JOIN_GROUP

Undocumented Getsockopt option ?

IPV6_AUTHHDR = 10

Undocumented Getsockopt option ?

IPV6_CHECKSUM = 7

Undocumented Getsockopt option ?

IPV6_DROP_MEMBERSHIP = IPV6_LEAVE_GROUP

Undocumented Getsockopt option ?

IPV6_DSTOPTS = 4

Undocumented Getsockopt option ?

IPV6_HOPLIMIT = 8

Undocumented Getsockopt option ?

IPV6_HOPOPTS = 3

Undocumented Getsockopt option ?

IPV6_IPSEC_POLICY = 34

Undocumented Getsockopt option ?

IPV6_JOIN_ANYCAST = 27

Undocumented Getsockopt option ?

IPV6_JOIN_GROUP = 20

Undocumented Getsockopt option ?

IPV6_LEAVE_ANYCAST = 28

Undocumented Getsockopt option ?

IPV6_LEAVE_GROUP = 21

Undocumented Getsockopt option ?

IPV6_MTU = 24

Undocumented Getsockopt option ?

IPV6_MTU_DISCOVER = 23

Undocumented Getsockopt option ?

IPV6_MULTICAST_HOPS = 18

Undocumented Getsockopt option ?

IPV6_MULTICAST_IF = 17

Undocumented Getsockopt option ?

IPV6_MULTICAST_LOOP = 19

Undocumented Getsockopt option ?

IPV6_NEXTHOP = 9

Undocumented Getsockopt option ?

IPV6_PKTINFO = 2

Undocumented Getsockopt option ?

IPV6_PKTOPTIONS = 6

Undocumented Getsockopt option ?

IPV6_PMTUDISC_DO = 2

Always DF.

IPV6_PMTUDISC_DONT = 0

Never send DF frames.

IPV6_PMTUDISC_WANT = 1

Use per route hints.

IPV6_RECVERR = 25

Undocumented Getsockopt option ?

IPV6_ROUTER_ALERT = 22

Undocumented Getsockopt option ?

IPV6_RTHDR = 5

Undocumented Getsockopt option ?

IPV6_RTHDR_LOOSE = 0

Hop doesn't need to be neighbour.

IPV6_RTHDR_STRICT = 1

Hop must be a neighbour.

IPV6_RTHDR_TYPE_0 = 0

IPv6 Routing header type 0.

IPV6_RXDSTOPTS = IPV6_DSTOPTS

Undocumented Getsockopt option ?

IPV6_RXHOPOPTS = IPV6_HOPOPTS

Undocumented Getsockopt option ?

IPV6_RXSRCRT = IPV6_RTHDR

Undocumented Getsockopt option ?

IPV6_UNICAST_HOPS = 16

Undocumented Getsockopt option ?

IPV6_V6ONLY = 26

Undocumented Getsockopt option ?

IPV6_XFRM_POLICY = 35

Undocumented Getsockopt option ?

IP_ADD_MEMBERSHIP = 35

add an IP group membership

IP_ADD_SOURCE_MEMBERSHIP = 39

join source group

IP_BLOCK_SOURCE = 38

block data from source

IP_DEFAULT_MULTICAST_LOOP = 1

Undocumented ?

IP_DEFAULT_MULTICAST_TTL = 1

Undocumented ?

IP_DROP_MEMBERSHIP = 36

drop an IP group membership

IP_DROP_SOURCE_MEMBERSHIP = 40

leave source group

IP_HDRINCL = 3

Header is included with data.

IP_MAX_MEMBERSHIPS = 20

Undocumented ?

IP_MSFILTER = 41

Undocumented ?

IP_MTU_DISCOVER = 10

Undocumented ?

IP_MULTICAST_IF = 32

set/get IP multicast i/f

IP_MULTICAST_LOOP = 34

set/get IP multicast loopback

IP_MULTICAST_TTL = 33

set/get IP multicast ttl

IP_OPTIONS = 4

IP per-packet options.

IP_PKTINFO = 8

Undocumented ?

IP_PKTOPTIONS = 9

Undocumented ?

IP_PMTUDISC = 10

Undocumented ?

IP_PMTUDISC_DO = 2

Always DF.

IP_PMTUDISC_DONT = 0

Never send DF frames.

IP_PMTUDISC_WANT = 1

Use per route hints.

IP_RECVERR = 11

Undocumented ?

IP_RECVOPTS = 6

Receive all IP options w/datagram.

IP_RECVRETOPTS = IP_RETOPTS

Receive IP options for response.

IP_RECVTOS = 13

Undocumented ?

IP_RECVTTL = 12

Undocumented ?

IP_RETOPTS = 7

Set/get IP per-packet options.

IP_ROUTER_ALERT = 5

Undocumented ?

IP_TOS = 1

IP type of service and precedence.

IP_TTL = 2

IP time to live.

IP_UNBLOCK_SOURCE = 37

unblock data from source

MCAST_BLOCK_SOURCE = 43

block from given group

MCAST_EXCLUDE = 0

Undocumented ?

MCAST_INCLUDE = 1

Undocumented ?

MCAST_JOIN_GROUP = 42

join any-source group

MCAST_JOIN_SOURCE_GROUP = 46

join source-spec group

MCAST_LEAVE_GROUP = 45

leave any-source group

MCAST_LEAVE_SOURCE_GROUP = 47

leave source-spec group

MCAST_MSFILTER = 48

Undocumented ?

MCAST_UNBLOCK_SOURCE = 44

unblock from given group

MSG_CONFIRM = 0800

Send flags: Conform connection

MSG_CTRUNC = 0008

Receive flags: Control Data was discarded (buffer too small)

MSG_DONTROUTE = 0004

Send flags: don't use gateway

MSG_DONTWAIT = 0040

Receive flags: Non-blocking operation request.

MSG_EOR = 0080

Receive flags: End of record

MSG_ERRQUEUE = 2000

Receive flags: ?

MSG_FIN = 0200

Receive flags: ?

MSG_MORE = 8000

Receive flags: ?

MSG_NOSIGNAL = \$4000

Receive flags: Suppress SIG_PIPE signal.

MSG_OOB = \$0001

Receive flags: receive out-of-band data.

MSG_PEEK = \$0002

Receive flags: peek at data, don't remove from buffer.

MSG_PROXY = \$0010

Receive flags: ?

MSG_RST = \$1000

Receive flags: ?

MSG_SYN = \$0400

Receive flags: ?

MSG_TRUNC = \$0020

Receive flags: packet Data was discarded (buffer too small)

MSG_TRYHARD = MSG_DONTROUTE

Receive flags: ?

MSG_WAITALL = \$0100

Receive flags: Wait till operation completed.

NoAddress : in_addr = (s_addr:0)

Constant indicating invalid (no) network address.

NoAddress6 : Tin6_addr = (u6_addr16: (0,0,0,0,0,0,0,0))

Constant indicating invalid (no) IPV6 network address.

NoNet : in_addr = (s_addr:0)

Constant indicating invalid (no) network address.

NoNet6 : Tin6_addr = (u6_addr16: (0,0,0,0,0,0,0,0))

Constant indicating invalid (no) IPV6 network address.

PF_APPLETALK = AF_APPLETALK

Protocol family: Appletalk DDP

PF_ATM = AF_ATM

Protocol Family: ?

PF_CCITT = AF_CCITT

Protocol Family: ?

PF_CHAOS = AF_CHAOS

Protocol Family: ?

PF_CNT = AF_CNT

Protocol Family: ?

PF_COIP = AF_COIP

Protocol Family: ?

PF_DATAKIT = AF_DATAKIT

Protocol Family: ?

PF_DECnet = AF_DECnet

Protocol Family: DECNET project

PF_DLI = AF_DLI

Protocol Family: ?

PF_ECMA = AF_ECMA

Protocol Family: ?

PF_FILE = PF_LOCAL

Protocol family: Unix socket (alias)

PF_HYLINK = AF_HYLINK

Protocol Family: ?

PF_IMPLINK = AF_IMPLINK

Protocol Family: ?

PF_INET = 2

Protocol family: Internet IP Protocol

PF_INET6 = AF_INET6

Protocol family: IP version 6

PF_IPX = AF_IPX

Protocol family: Novell IPX

PF_ISDN = AF_ISDN

Protocol Family: ?

PF_ISO = AF_ISO

Protocol Family: ?

PF_KEY = pseudo_AF_KEY

Protocol family: Key management API

PF_LAT = AF_LAT

Protocol Family: ?

PF_LINK = AF_LINK

Protocol Family: ?

PF_LOCAL = 1

Protocol family: Unix socket

PF_MAX = AF_MAX

Protocol family: Maximum value

PF_NATM = AF_NATM

Protocol Family: ?

PF_NETGRAPH = AF_NETGRAPH

Protocol Family: ?

PF_NS = AF_NS

Protocol Family: ?

PF_OSI = AF_ISO

Protocol Family: ?

PF_PIP = pseudo_AF_PIP

Protocol Family: ?

PF_PUP = AF_PUP

Protocol Family: ?

PF_ROUTE = AF_ROUTE

Protocol Family: ?

PF_RTIP = pseudo_AF_RTIP

Protocol Family: ?

PF_SIP = AF_SIP

Protocol Family: ?

PF_SNA = AF_SNA

Protocol Family: Linux SNA project

PF_UNIX = PF_LOCAL

Protocol family: Unix domain sockets

PF_UNSPEC = 0

Protocol family: Unspecified

PF_XTP = pseudo_AF_XTP

Protocol Family: ?

pseudo_AF_HDRCMPLT = 31

Address family: ?

pseudo_AF_KEY = 27

Address family: key management API.

pseudo_AF_PIP = 25

Address family: ?

`pseudo_AF_RTIP = 22`

Address family: ?

`pseudo_AF_XTP = 19`

Address family: ?

`SCM_SRCRT = IPV6_RXSRCRT`

Undocumented Getsockopt option ?

`SCM_TIMESTAMP = SO_TIMESTAMP`

Socket option: ?

`SHUT_RD = 0`

Shutdown read part of full duplex socket

`SHUT_RDWR = 2`

Shutdown read and write part of full duplex socket

`SHUT_WR = 1`

Shutdown write part of full duplex socket

`SOCK_DGRAM = 2`

Type of socket: datagram (conn.less) socket (UDP)

`SOCK_MAXADDRLLEN = 255`

Maximum socket address length for Bind ([1013](#)) call.

`SOCK_RAW = 3`

Type of socket: raw socket

`SOCK_RDM = 4`

Type of socket: reliably-delivered message

`SOCK_SEQPACKET = 5`

Type of socket: sequential packet socket

`SOCK_STREAM = 1`

Type of socket: stream (connection) type socket (TCP)

SOL_ICMPV6 = 58

Socket level values for IPv6: ICMPV6

SOL_IP = 0

Undocumented ?

SOL_IPV6 = 41

Socket level values for IPv6: IPV6

SOL_SOCKET = 1

Socket option level: Socket level

SO_ACCEPTCONN = 30

Socket option: ?

SO_ATTACH_FILTER = 26

Socket option: ?

SO_BINDTODEVICE = 25

Socket option: ?

SO_BROADCAST = 6

Socket option: Broadcast

SO_BSDCOMPAT = 14

Socket option: ?

SO_DEBUG = 1

Socket option level: debug

SO_DETACH_FILTER = 27

Socket option: ?

SO_DONTROUTE = 5

Socket option: Don't route

SO_ERROR = 4

Socket option: Error

SO_KEEPAIVE = 9

Socket option: keep alive

SO_LINGER = 13

Socket option: ?

SO_NO_CHECK = 11

Socket option: ?

SO_OOBLINLNE = 10

Socket option: ?

SO_PASSCRED = 16

Socket option: ?

SO_PEERCRECRED = 17

Socket option: ?

SO_PEERNAME = 28

Socket option: ?

SO_PRIORITY = 12

Socket option: ?

SO_RCVBUF = 8

Socket option: receive buffer

SO_RCVLOWAT = 18

Socket option: ?

SO_RCVTIMEO = 20

Socket option: ?

SO_REUSEADDR = 2

Socket option: Reuse address

SO_SECURITY_AUTHENTICATION = 22

Socket option: ?

SO_SECURITY_ENCRYPTION_NETWORK = 24

Socket option: ?

SO_SECURITY_ENCRYPTION_TRANSPORT = 23

Socket option: ?

SO_SNDBUF = 7

Socket option: Send buffer

SO_SNDLOWAT = 19

Socket option: ?

SO_SNDTIMEO = 21

Socket option: ?

SO_TIMESTAMP = 29

Socket option: ?

SO_TYPE = 3

Socket option: Type

S_IN = 0

Input socket in socket pair.

S_OUT = 1

Output socket in socket pair

26.3.2 Types

```
in_addr = packed record
end
```

General inet socket address.

```
in_addrbytes = packed Array[1..4] of Byte
```

in_addrbytes is used to typecast a in_addr (1009) record to an array of bytes.

```
pIn6_Addr = ^Tin6_addr
```

Pointer to Tin6_addr (1010)

```
pInetSockAddr = ^TInetSockAddr
```

Pointer to TInetSockAddr (1010)

```
pin_addr = ^in_addr
```

Pointer to in_addr (1009) record.

```
PSockAddr = ^TSockAddr
```

Pointer to TSockAddr (1011)

```
psockaddr_in6 = ^sockaddr_in6
```

Pointer to sockaddr_in6 (1010)

```
sa_family_t = cushort
```

Address family type

```
SockAddr = TSockAddr
```

Alias for TSockAddr (1011) record type.

```
sockaddr_in6 = TInetSockAddr6
```

Alias for TInetSockAddr6 (1011)

```
Tin6_addr = packed record
end
```

Alias for TInetSockAddr6 (1011)

```
TInAddr = in_addr
```

Alias for in_addr (1009) record type.

```
TInetSockAddr = packed record
end
```

TUnixSockAddr is used to store a INET socket address for the Bind (1013), Recv (1022) and Send (1023) calls.

```
TInetSockAddr6 = packed record
  sin6_family : sa_family_t;
  sin6_port   : cuint16;
  sin6_flowinfo : cuint32;
  sin6_addr   : Tin6_addr;
  sin6_scope_id : cuint32;
end
```

Record for IPV6 socket address.

```
TIn_addr = in_addr
```

Alias for in_addr (1009) record type.

```
TSockAddr = packed record
end
```

TUnixSockAddr is used to store a general socket address for the Bind (1013), Recv (1022) and Send (1023) calls.

```
TSockArray = Array[1..2] of LongInt
```

Type returned by the SocketPair (1026) call.

```
TSockPairArray = Array[0..1] of LongInt
```

Array of sockets, used in SocketPair (1026) call.

```
TUnixSockAddr = packed record
  family : sa_family_t;
  path : Array[0..107] of Char;
end
```

TUnixSockAddr is used to store a UNIX socket address for the Bind (1013), Recv (1022) and Send (1023) calls.

26.3.3 Variables

```
SocketError : cint
```

SocketError contains the error code for the last socket operation. It can be examined to return the last socket error.

26.4 Procedures and functions

26.4.1 Accept

Synopsis: Accept a connection from a socket.

Declaration:

```
function Accept(Sock: LongInt; var Addr; var Addrlen: LongInt) : LongInt
function Accept(Sock: LongInt; var addr: TInetSockAddr; var SockIn: File;
  var SockOut: File) : Boolean
function Accept(Sock: LongInt; var addr: TInetSockAddr; var SockIn: text;
  var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: String; var SockIn: text;
  var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: String; var SockIn: File;
  var SockOut: File) : Boolean
```


Visibility: default

Description: `FPAccept` accepts a connection from a socket `Sock`, which was listening for a connection. If a connection is accepted, a file descriptor is returned. On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addr`, and sets its length in `AddrLen`. `Addr` should be pointing to enough space, and `AddrLen` should be set to the amount of space available, prior to the call.

The alternate forms of the `Accept` (1011) command, with the `Text` or `File` parameters are equivalent to subsequently calling the regular `Accept` (1011) function and the `Sock2Text` (1025) or `Sock2File` (1025) functions. These functions return `True` if successful, `False` otherwise.

Errors: On error, `-1` is returned, and errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

SYS_EFAULT`Addr` points outside your address space.

SYS_EWOULDBLOCKThe requested operation would block the process.

See also: `Listen` (1020), `Connect` (1014), `Bind` (1013)

Listing: `./sockex/socksvr.pp`

Program `server`;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version , First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses `Sockets`;

Var

```
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;
```

```
procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;
```

begin

```
  S:=Socket (AF_INET,SOCK_STREAM,0);
  if SocketError<>0 then
    Perror ( 'Server : Socket : ' );
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(50000);
```

```

SAddr.sin_addr.s_addr:=0;
if not Bind(S,SAddr,sizeof(saddr)) then
  PError ('Server : Bind : ');
if not Listen (S,1) then
  PError ('Server : Listen : ');
WriteLn('Waiting for Connect from Client , run now sock_cli in an other tty');
if not Accept (S,FromName,Sin,Sout) then
  PError ('Server : Accept : '+fromname);
Reset(Sin);
ReWrite(Sout);
WriteLn(Sout, 'Message From Server ');
Flush(SOut);
while not eof(sin) do
  begin
    ReadLn(Sin, Buffer);
    WriteLn('Server : read : ',buffer);
  end;
end.

```

26.4.2 Bind

Synopsis: Bind a socket to an address.

Declaration: `function Bind(Sock: LongInt;const Addr;AddrLen: LongInt) : Boolean`
`function Bind(Sock: LongInt;const addr: String) : Boolean`

Visibility: default

Description: Bind binds the socket Sock to address Addr. Addr has length AddrLen. The function returns True if the call was succesful, False if not.

The form of the Bind command with the TUnixSockAddr (1011) is equivalent to subsequently calling Str2UnixSockAddr (1026) and the regular Bind function. The function returns True if successfull, False otherwise.

Errors: Errors are returned in SocketError and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_EINVALThe socket is already bound to an address,

SYS_EACCESSAddress is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: Socket (1025)

26.4.3 CloseSocket

Synopsis: Closes a socket handle.

Declaration: `function CloseSocket(Sock: LongInt) : LongInt`

Visibility: default

Description: CloseSocket closes a socket handle. It returns 0 if the socket was closed succesfully, -1 if it failed.

Errors: On error, -1 is returned.

See also: Socket (1025)

26.4.4 Connect

Synopsis: Open a connection to a server socket.

Declaration:

```
function Connect (Sock: LongInt; const Addr; Addrlen: LongInt) : Boolean
function Connect (Sock: LongInt; const addr: TInetSockAddr;
                  var SockIn: text; var SockOut: text) : Boolean
function Connect (Sock: LongInt; const addr: TInetSockAddr;
                  var SockIn: file; var SockOut: file) : Boolean
function Connect (Sock: LongInt; const addr: String; var SockIn: text;
                  var SockOut: text) : Boolean
function Connect (Sock: LongInt; const addr: String; var SockIn: file;
                  var SockOut: file) : Boolean
```

Visibility: default

Description: Connect opens a connection to a peer, whose address is described by Addr. AddrLen contains the length of the address. The type of Addr depends on the kind of connection you're trying to make, but is generally one of TSocketAddr or TUnixSocketAddr.

The forms of the Connect (1014) command with the Text or File arguments are equivalent to subsequently calling the regular Connect function and the Sock2Text (1025) or Sock2File (1025) functions. These functions return True if successful, False otherwise.

The Connect function returns a file descriptor if the call was successful, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in SocketError.

See also: Listen (1020), Bind (1013), Accept (1011)

Listing: ./sockex/sockcli.pp

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

Var

```
SAddr    : TInetSockAddr;
Buffer    : string [255];
S         : Longint;
Sin, Sout : Text;
i         : integer;
```

begin

```
S:=Socket (AF_INET, SOCK_STREAM, 0);
if SocketError<>0 then
  PError('Client : Socket : ');
```

```

SAddr.sin_family:=AF_INET;
{ port 50000 in network order }
SAddr.sin_port:=htons(50000);
{ localhost : 127.0.0.1 in network order }
SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
if not Connect (S,SAddr,Sin,Sout) then
  PError('Client : Connect : ');
Reset(Sin);
Rewrite(Sout);
Buffer:='This is a textstring sent by the Client.';
for i:=1 to 10 do
  Writeln(Sout,Buffer);
Flush(Sout);
Readln(Sin,Buffer);
WriteLn(Buffer);
Close(sout);
end.

```

Listing: ./sockex/pfinger.pp

```

program pfinger;

uses sockets, errors;

Var
  Addr : TInetSockAddr;
  S : Longint;
  Sin, Sout : Text;
  Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=Socket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,ADDR,SIN,SOUT) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
  rewrite (sout);
  reset(sin);
  writeln (sout,paramstr(1));
  flush(sout);
  while not eof(sin) do
    begin
      readln (Sin,line);
      writeln (line);
    end;
  Shutdown(s,2);
  close (sin);
  close (sout);
end.

```

26.4.5 fpaccept

Synopsis: Alias for the accept (1011) call

Declaration: `function fpaccept(s: cint;addrx: PSockAddr;addrlen: psocklen) : cint`

Visibility: default

26.4.6 fpbind

Synopsis: Alias for the bind (1013) call

Declaration: `function fpbind(s: cint;addrx: PSockAddr;addrlen: tsocklen) : cint`

Visibility: default

26.4.7 fpconnect

Synopsis: Alias for the connect (1014) call

Declaration: `function fpconnect(s: cint;name: PSockAddr;namelen: tsocklen) : cint`

Visibility: default

26.4.8 fpgetpeername

Synopsis: Alias for the GetPeerName (1018) call

Declaration: `function fpgetpeername(s: cint;name: PSockAddr;namelen: psocklen) : cint`

Visibility: default

26.4.9 fpgetsockname

Synopsis: Alias for the GetSocketName (1018) call

Declaration: `function fpgetsockname(s: cint;name: PSockAddr;namelen: psocklen) : cint`

Visibility: default

26.4.10 fpgetsockopt

Synopsis: Alias for the GetSocketOptions (1019) call

Declaration: `function fpgetsockopt(s: cint;level: cint;optname: cint;optval: pointer;
optlen: psocklen) : cint`

Visibility: default

26.4.11 fplisten

Synopsis: Alias for the listen (1020) call

Declaration: `function fplisten(s: cint;backlog: cint) : cint`

Visibility: default

26.4.12 fprecv

Synopsis: Alias for the `recv` (1022) call

Declaration: `function fprecv(s: cint;buf: pointer;len: size_t;flags: cint) : ssize_t`

Visibility: default

26.4.13 frecvfrom

Synopsis: Alias for the `recvfrom` (1022) call

Declaration: `function frecvfrom(s: cint;buf: pointer;len: size_t;flags: cint;
from: PSockAddr;fromlen: psocklen) : ssize_t`

Visibility: default

26.4.14 fpsend

Synopsis: Alias for the `send` (1023) call

Declaration: `function fpsend(s: cint;msg: pointer;len: size_t;flags: cint) : ssize_t`

Visibility: default

26.4.15 fpsendto

Synopsis: Alias for the `send` (1023) call

Declaration: `function fpsendto(s: cint;msg: pointer;len: size_t;flags: cint;
tox: PSockAddr;tolen: tsocklen) : ssize_t`

Visibility: default

26.4.16 fpsetsockopt

Synopsis: Alias for the `SetSocketOptions` (1023) call

Declaration: `function fpsetsockopt(s: cint;level: cint;optname: cint;optval: pointer;
optlen: tsocklen) : cint`

Visibility: default

26.4.17 fpshutdown

Synopsis: Alias for the `shutdown` (1024) call

Declaration: `function fpshutdown(s: cint;how: cint) : cint`

Visibility: default

26.4.18 fpsocket

Synopsis: Alias for the `socket` (1025) call

Declaration: `function fpsocket(domain: cint;xtype: cint;protocol: cint) : cint`

Visibility: default

26.4.19 fpsocketpair

Synopsis: Alias for the SocketPair ([1026](#)) call

Declaration: `function fpsocketpair(d: cint; xtype: cint; protocol: cint; sv: pcint)
: cint`

Visibility: default

26.4.20 GetPeerName

Synopsis: Return the name (address) of the connected peer.

Declaration: `function GetPeerName(Sock: LongInt; var Addr; var Addrlen: LongInt)
: LongInt`

Visibility: default

Description: `GetPeerName` returns the name of the entity connected to the specified socket `Sock`. The Socket must be connected for this call to work.

`Addr` should point to enough space to store the name, the amount of space pointed to should be set in `Addrlen`. When the function returns successfully, `Addr` will be filled with the name, and `Addrlen` will be set to the length of `Addr`.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOBUFSThe system doesn't have enough buffers to perform the operation.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULT`Addr` points outside your address space.

SYS_ENOTCONNThe socket isn't connected.

See also: `Connect` ([1014](#)), `Socket` ([1025](#))

26.4.21 GetSocketName

Synopsis: Return name of socket.

Declaration: `function GetSocketName(Sock: LongInt; var Addr; var Addrlen: LongInt)
: LongInt`

Visibility: default

Description: `GetSockName` returns the current name of the specified socket `Sock`. `Addr` should point to enough space to store the name, the amount of space pointed to should be set in `Addrlen`. When the function returns successfully, `Addr` will be filled with the name, and `Addrlen` will be set to the length of `Addr`.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOBUFSThe system doesn't have enough buffers to perform the operation.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULT`Addr` points outside your address space.

See also: `Bind` ([1013](#))

26.4.22 GetSocketOptions

Synopsis: Get current socket options

Declaration: `function GetSocketOptions(Sock: LongInt; Level: LongInt; OptName: LongInt;
var OptVal; var optlen: LongInt) : LongInt`

Visibility: default

Description: `GetSocketOptions` gets the connection options for socket `Sock`. The socket may be obtained from different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKET From the socket itself.

XXX set `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

For more information on this call, refer to the unix manual page `\seem{getsockopt}{2}`.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADF The socket descriptor is invalid.

SYS_ENOTSOCK The descriptor is not a socket.

SYS_EFAULT `OptVal` points outside your address space.

See also: `GetSocketOptions` ([1019](#))

26.4.23 HostAddrToStr

Synopsis: Convert a host address to a string.

Declaration: `function HostAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr` converts the host address in `Entry` to a string representation in human-readable form (a dotted quad).

Basically, it is the same as `NetAddrToStr` ([1021](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1021](#)), `StrToHostAddr` ([1026](#)), `StrToNetAddr` ([1027](#))

26.4.24 HostAddrToStr6

Synopsis: Convert a IPV6 host address to a string representation.

Declaration: `function HostAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr6` converts the IPV6 host address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` ([1021](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1021](#)), `StrToHostAddr` ([1026](#)), `StrToNetAddr` ([1027](#)), `StrToHostAddr6` ([1027](#))

26.4.25 HostToNet

Synopsis: Convert a host address to a network address

Declaration: `function HostToNet (Host: in_addr) : in_addr`
`function HostToNet (Host: LongInt) : LongInt`

Visibility: default

Description: `HostToNet` converts a host address to a network address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `NetToHost` ([1021](#)), `NToHS` ([1022](#)), `HToNS` ([1020](#)), `ShortHostToNet` ([1024](#)), `ShortNetToHost` ([1024](#))

26.4.26 htonl

Synopsis: Convert long integer from host ordered to network ordered

Declaration: `function htonl (host: LongInt) : LongInt`

Visibility: default

Description: `htonl` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htons` ([1020](#)), `ntohl` ([1021](#)), `ntohs` ([1022](#))

26.4.27 htons

Synopsis: Convert short integer from host ordered to network ordered

Declaration: `function htons (host: Word) : Word`

Visibility: default

Description: `htons` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htonl` ([1020](#)), `ntohl` ([1021](#)), `ntohs` ([1022](#))

26.4.28 Listen

Synopsis: Listen for connections on socket.

Declaration: `function Listen (Sock: LongInt; MaxConnect: LongInt) : Boolean`

Visibility: default

Description: `Listen` listens for up to `MaxConnect` connections from socket `Sock`. The socket `Sock` must be of type `SOCK_STREAM` or `Sock_SEQPACKET`.

The function returns `True` if a connection was accepted, `False` if an error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADF The socket descriptor is invalid.

SYS_ENOTSOCK The descriptor is not a socket.

SYS_EOPNOTSUPP The socket type doesn't support the `Listen` operation.

See also: `Socket` ([1025](#)), `Bind` ([1013](#)), `Connect` ([1014](#))

26.4.29 NetAddrToStr

Synopsis: Convert a network address to a string.

Declaration: `function NetAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr` converts the network address in `Entry` to a string representation in human-readable form (a dotted quad).

See also: `HostAddrToStr` (1019), `StrToNetAddr` (1027), `StrToHostAddr` (1026)

26.4.30 NetAddrToStr6

Synopsis: Convert a IPV6 network address to a string.

Declaration: `function NetAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr6` converts the IPV6 network address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` (1021), but with the bytes in correct order.

See also: `NetAddrToStr` (1021), `StrToHostAddr` (1026), `StrToNetAddr` (1027), `StrToHostAddr6` (1027)

26.4.31 NetToHost

Synopsis: Convert a network address to a host address.

Declaration: `function NetToHost(Net: in_addr) : in_addr`
`function NetToHost(Net: LongInt) : LongInt`

Visibility: default

Description: `NetToHost` converts a network address to a host address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `HostToNet` (1020), `NToHS` (1022), `HToNS` (1020), `ShortHostToNet` (1024), `ShortNetToHost` (1024)

26.4.32 NToHl

Synopsis: Convert long integer from network ordered to host ordered

Declaration: `function NToHl(Net: LongInt) : LongInt`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1020), `htons` (1020), `ntohs` (1022)

26.4.33 NToHs

Synopsis: Convert short integer from network ordered to host ordered

Declaration: `function NToHs(Net: Word) : Word`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` ([1020](#)), `htons` ([1020](#)), `ntohl` ([1021](#))

26.4.34 Recv

Synopsis: Receive data on socket

Declaration: `function Recv(Sock: LongInt; var Buf; BufLen: LongInt; Flags: LongInt)
: LongInt`

Visibility: default

Description: `Recv` reads at most `AddrLen` bytes from socket `Sock` into address `Addr`. The socket must be in a connected state. `Flags` can be one of the following:

1Process out-of band data.

4Bypass routing, use a direct interface.

??Wait for full request or report an error.

The function returns the number of bytes actually read from the socket, or -1 if a detectable error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTCONNThe socket isn't connected.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULTThe address is outside your address space.

SYS EMSGSIZEThe message cannot be sent atomically.

SYS_EWOULDBLOCKThe requested operation would block the process.

SYS_ENOBUFSThe system doesn't have enough free buffers available.

See also: `Send` ([1023](#))

26.4.35 RecvFrom

Synopsis: Receive data from an unconnected socket

Declaration: `function RecvFrom(Sock: LongInt; var Buf; Buflen: LongInt; Flags: LongInt;
var Addr; var AddrLen: LongInt) : LongInt`

Visibility: default

Description: `RecvFrom` receives data in buffer `Buf` with maximum length `BufLen` from socket `Sock`. Receipt is controlled by options in `Flags`. `Addr` will be filled with the address from the sender, and will have length `AddrLen`. The function returns the number of bytes received, or -1 on error.

Errors: On error, -1 is returned.

See also: `Socket` ([1025](#)), `recv` ([1022](#)), `RecvFrom` ([1022](#))

26.4.36 Send

Synopsis: Send data through socket

Declaration: `function Send(Sock: LongInt; const Buf; BufLen: LongInt; Flags: LongInt)
: LongInt`

Visibility: default

Description: `Send` sends `AddrLen` bytes starting from address `Addr` to socket `Sock`. `Sock` must be in a connected state. The function returns the number of bytes sent, or -1 if a detectable error occurred.

`Flags` can be one of the following:

1Process out-of band data.

4Bypass routing, use a direct interface.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULTThe address is outside your address space.

SYS_EMSGSIZEThe message cannot be sent atomically.

SYS_EWOULDBLOCKThe requested operation would block the process.

SYS_ENOBUFSThe system doesn't have enough free buffers available.

See also: `Recv` ([1022](#))

26.4.37 SendTo

Synopsis: Send data through an unconnected socket to an address.

Declaration: `function SendTo(Sock: LongInt; const Buf; BufLen: LongInt; Flags: LongInt;
var Addr; AddrLen: LongInt) : LongInt`

Visibility: default

Description: `SendTo` sends data from buffer `Buf` with length `BufLen` through socket `Sock` with options `Flags`. The data is sent to address `Addr`, which has length `AddrLen`

Errors: On error, -1 is returned.

See also: `Socket` ([1025](#)), `Send` ([1023](#)), `RecvFrom` ([1022](#))

26.4.38 SetSocketOptions

Synopsis: Set socket options.

Declaration: `function SetSocketOptions(Sock: LongInt; Level: LongInt; OptName: LongInt;
const OptVal; optlen: LongInt) : LongInt`

Visibility: default

Description: `SetSocketOptions` sets the connection options for socket `Sock`. The socket may be manipulated at different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETTo manipulate the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

For more information on this call, refer to the unix manual page `setsockopt`

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULT`OptVal` points outside your address space.

See also: `GetSocketOptions` ([1019](#))

26.4.39 ShortHostToNet

Synopsis: Convert a host port number to a network port number

Declaration: `function ShortHostToNet(Host: Word) : Word`

Visibility: `default`

Description: `ShortHostToNet` converts a host port number to a network port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1024](#)), `HostToNet` ([1020](#)), `NToHS` ([1022](#)), `HToNS` ([1020](#))

26.4.40 ShortNetToHost

Synopsis: Convert a network port number to a host port number

Declaration: `function ShortNetToHost(Net: Word) : Word`

Visibility: `default`

Description: `ShortNetToHost` converts a network port number to a host port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1024](#)), `HostToNet` ([1020](#)), `NToHS` ([1022](#)), `HToNS` ([1020](#))

26.4.41 Shutdown

Synopsis: Close one end of full duplex connection.

Declaration: `function Shutdown(Sock: LongInt;How: LongInt) : LongInt`

Visibility: `default`

Description: `ShutDown` closes one end of a full duplex socket connection, described by `Sock`. The parameter `How` determines how the connection will be shut down, and can be one of the following:

0Further receives are disallowed.

1Further sends are disallowed.

2Sending nor receiving are allowed.

On succes, the function returns 0, on error -1 is returned.

Errors: `SocketError` is used to report errors, and includes the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTCONNThe socket isn't connected.

SYS_ENOTSOCKThe descriptor is not a socket.

See also: `Socket` ([1025](#)), `Connect` ([1014](#))

26.4.42 Sock2File

Synopsis: Convert socket to untyped file descriptors

Declaration: `procedure Sock2File(Socket: LongInt; var SocketIn: File; var SocketOut: File)`

Visibility: default

Description: `Sock2File` transforms a socket `Socket` into 2 Pascal file descriptors of type `File`, one for reading from the socket (`SocketIn`), one for writing to the socket (`SocketOut`).

Errors: None.

See also: `Socket` ([1025](#)), `Sock2Text` ([1025](#))

26.4.43 Sock2Text

Synopsis: Convert socket to text file descriptors

Declaration: `procedure Sock2Text(Socket: LongInt; var SocketIn: Text; var SocketOut: Text)`

Visibility: default

Description: `Sock2Text` transforms a socket `Socket` into 2 Pascal file descriptors of type `Text`, one for reading from the socket (`SocketIn`), one for writing to the socket (`SocketOut`).

Errors: None.

See also: `Socket` ([1025](#)), `Sock2File` ([1025](#))

26.4.44 Socket

Synopsis: Create new socket

Declaration: `function Socket(Domain: LongInt; SocketType: LongInt; Protocol: LongInt) : LongInt`

Visibility: default

Description: `Socket` creates a new socket in domain `Domain`, from type `SocketType` using protocol `Protocol`.

The `Domain`, `Socket` type and `Protocol` can be specified using predefined constants (see the section on constants for available constants) If succesfull, the function returns a socket descriptor, which can be passed to a subsequent `Bind` ([1013](#)) call. If unsuccesfull, the function returns -1.

for an example, see `Accept` ([1011](#)).

Errors: Errors are returned in `SocketError`, and include the follwing:

SYS_EPROTONOSUPPORTThe protocol type or the specified protocol is not supported within this domain.

SYS_EMFILEThe per-process descriptor table is full.

SYS_ENFILEThe system file table is full.

SYS_EACCESSPermission to create a socket of the specified type and/or protocol is denied.

SYS_ENOBUFSInsufficient buffer space is available. The socket cannot be created until sufficient resources are freed.

See also: [SocketPair \(1026\)](#)

26.4.45 SocketPair

Synopsis: Create socket pair

Declaration: `function SocketPair(Domain: LongInt; SocketType: LongInt;
Protocol: LongInt; var Pair: TSockArray) : LongInt`

Visibility: default

Description: `SocketPair` creates 2 sockets in domain `Domain`, from type `SocketType` and using protocol `Protocol`. The pair is returned in `Pair`, and they are indistinguishable. The function returns -1 upon error and 0 upon success.

Errors: Errors are reported in `SocketError`, and are the same as in `Socket` ([1025](#))

See also: [Str2UnixSockAddr \(1026\)](#)

26.4.46 Str2UnixSockAddr

Synopsis: Convert path to `TUnixSockAddr` ([1011](#))

Declaration: `procedure Str2UnixSockAddr(const addr: String; var t: TUnixSockAddr;
var len: LongInt)`

Visibility: default

Description: `Str2UnixSockAddr` transforms a Unix socket address in a string to a `TUnixSockAddr` structure which can be passed to the `Bind` ([1013](#)) call.

Errors: None.

See also: `Socket` ([1025](#)), `Bind` ([1013](#))

26.4.47 StrToHostAddr

Synopsis: Convert a string to a host address.

Declaration: `function StrToHostAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToHostAddr` converts the string representation in `IP` to a host address and returns the host address.

Errors: On error, the host address is filled with zeroes.

See also: [NetAddrToStr \(1021\)](#), [HostAddrToStr \(1019\)](#), [StrToNetAddr \(1027\)](#)

26.4.48 StrToHostAddr6

Synopsis: Convert a string to a IPV6 host address.

Declaration: `function StrToHostAddr6(IP: String) : Tin6_addr`

Visibility: default

Description: `StrToHostAddr6` converts the string representation in `IP` to a IPV6 host address and returns the host address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1021](#)), `HostAddrToStr6` ([1019](#)), `StrToHostAddr` ([1026](#))

26.4.49 StrToNetAddr

Synopsis: Convert a string to a network address.

Declaration: `function StrToNetAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToNetAddr` converts the string representation in `IP` to a network address and returns the network address.

Errors: On error, the network address is filled with zeroes.

See also: `NetAddrToStr` ([1021](#)), `HostAddrToStr` ([1019](#)), `StrToHostAddr` ([1026](#))

26.4.50 StrToNetAddr6

Synopsis: Convert a string to a IPV6 network address

Declaration: `function StrToNetAddr6(IP: AnsiString) : Tin6_addr`

Visibility: default

Description: `StrToNetAddr6` converts the string representation in `IP` to a IPV6 network address and returns the network address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1021](#)), `HostAddrToStr6` ([1019](#)), `StrToHostAddr6` ([1027](#))

Chapter 27

Reference for unit 'strings'

27.1 Overview

This chapter describes the `STRINGS` unit for Free Pascal. This unit is system independent, and therefore works on all supported platforms.

27.2 Procedures and functions

27.2.1 `stralloc`

Synopsis: Allocate memory for a new null-terminated string on the heap

Declaration: `function stralloc(L: SizeInt) : pchar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Errors: If there is not enough memory, a run-time error occurs.

See also: `StrNew` ([1036](#)), `StrPCopy` ([1038](#))

27.2.2 `strcat`

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: pchar; source: pchar) : pchar`

Visibility: default

Description: Attaches `Source` to `Dest` and returns `Dest`.

Errors: No length checking is performed.

See also: `StrLCat` ([1032](#))

Listing: `./stringex/ex11.pp`

```

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin
  P2:= StrAlloc ( StrLen(P1)*2+1);
  StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }
  StrCat (P2,P1); { Append P2 once more }
  WriteLn ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

27.2.3 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: `function strcmp(str1: pchar;str2: pchar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrLComp ([1033](#)).

Errors: None.

See also: StrLComp ([1033](#)), StrIComp ([1032](#)), StrLComp ([1035](#))

27.2.4 strcpy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: pchar;source: pchar) : pchar`

Visibility: default

Description: Copy the null terminated string in Source to Dest, and returns a pointer to Dest. Dest needs enough room to contain Source, i.e. StrLen(Source)+1 bytes.

Errors: No length checking is performed.

See also: StrPCopy ([1038](#)), StrLCopy ([1034](#)), StrECopy ([1030](#))

Listing: ./stringex/ex4.pp

```

Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin
  PP:= StrAlloc (StrLen(P)+1);
  STrCopy (PP,P);
  If StrComp (PP,P)<>0 then
    Writeln ( 'Oh-oh problems...' )
  else
    Writeln ( 'All is well : PP=',PP);
  StrDispose(PP);
end.

```

27.2.5 strdispose

Synopsis: disposes of a null-terminated string on the heap

Declaration: `procedure strdispose(p: pchar)`

Visibility: default

Description: Removes the string in P from the heap and releases the memory.

Errors: None.

See also: StrNew ([1036](#))

Listing: ./stringex/ex17.pp

```

Program Example17;

Uses strings;

{ Program to demonstrate the StrDispose function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin
  P2:=StrNew (P1);
  Writeln ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

27.2.6 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy(dest: pchar;source: pchar) : pchar`

Visibility: default

Description: Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` ([1034](#)), `StrCopy` ([1029](#))

Listing: `./stringex/ex6.pp`

Program Example6;

Uses strings;

{ Program to demonstrate the StrECopy function. }

Const P : PChar = 'This is a PCHAR string.';

Var PP : PChar;

begin

PP:= StrAlloc (StrLen(P)+1);

If Longint(StrECopy(PP,P)) – Longint(PP) <> StrLen(P) **then**

 Writeln('Something is wrong here !')

else

 Writeln('PP= ',PP);

 StrDispose(PP);

end.

27.2.7 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the end of P. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1034](#))

Listing: `./stringex/ex7.pp`

Program Example6;

Uses strings;

{ Program to demonstrate the StrEnd function. }

Const P : PChar = 'This is a PCHAR string.';

begin

If Longint(StrEnd(P)) – Longint(P) <> StrLen(P) **then**

 Writeln('Something is wrong here !')

```

    else
      WriteLn ( 'All is well..' );
    end.

```

27.2.8 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: pchar;str2: pchar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrLComp ([1033](#)), StrComp ([1029](#)), StrLComp ([1035](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

```

Const P1 : PChar = 'This is the first string.';
      P2 : PChar = 'This is the second string.';

```

```

Var L : Longint;

```

```

begin

```

```

  Write ( 'P1 and P2 are ');
  If StrComp (P1,P2)<>0 then write ( 'NOT ');
  write ( 'equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc (L);
  dec(L);
  WriteLn (L,' characters are the same.');
```

```

end.

```

27.2.9 strlcat

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Adds MaxLen characters from Source to Dest, and adds a terminating null-character. Returns Dest.

Errors: None.

See also: StrCat ([1028](#))

Listing: ./stringex/ex12.pp

Program Example12;

Uses strings;

{ Program to demonstrate the StrLCat function. }

Const P1 : PChar = '1234567890';

Var P2 : PChar;

begin

 P2:=StrAlloc (StrLen(P1)*2+1);

 P2^:=#0; *{ Zero length }*

 StrCat (P2,P1);

 StrLCat (P2,P1,5);

 Writeln ('P2 = ',P2);

 StrDispose(P2)

end.

27.2.10 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: function strlcomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrComp ([1029](#)), StrIComp ([1032](#)), StrLIComp ([1035](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';

 P2 : PChar = 'This is the second string.';

Var L : Longint;

begin

```

Write ( 'P1 and P2 are ');
If StrComp (P1,P2)<>0 then write ( 'NOT ');
write ( 'equal. The first ');
L:=1;
While StrLComp(P1,P2,L)=0 do inc (L);
dec(L);
WriteLn (L, ' characters are the same. ');
end.

```

27.2.11 strcpy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strcpy(dest: pchar;source: pchar;maxlen: SizeInt) : pchar`

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([1029](#)), StrECopy ([1030](#))

Listing: ./stringex/ex5.pp

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin

PP:= StrAlloc(11);

WriteLn ('First 10 characters of P : ',StrLCopy (PP,P,10));

StrDispose(PP);

end.

27.2.12 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: pchar) : sizeint`

Visibility: default

Description: Returns the length of the null-terminated string P.

Errors: None.

See also: StrNew ([1036](#))

Listing: ./stringex/ex1.pp

```

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin
  WriteLn ( 'P          : ',p);
  WriteLn ( 'length(P) : ',StrLen(P));
end.

```

27.2.13 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrIComp ([1032](#))

Errors: None.

See also: StrLComp ([1033](#)), StrComp ([1029](#)), StrIComp ([1032](#))

27.2.14 strlower

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: StrUpper ([1040](#))

Listing: ./stringex/ex14.pp

```

Program Example14;

Uses strings;

{ Program to demonstrate the StrLower and StrUpper functions. }

```


Const

```
P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';
P2 : PChar = 'this is a lowercase string';
```

begin

```
  WriteLn ( 'Uppercase : ', StrUpper(P2));
  StrLower (P1);
  WriteLn ( 'Lowercase : ', P1);
```

```
end.
```

27.2.15 strmove

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: `StrLCopy` ([1034](#)), `StrCopy` ([1029](#))

Listing: `./stringex/ex10.pp`

Program `Example10;`

Uses `strings;`

{ Program to demonstrate the StrMove function. }

Const `P1 : PCHAR = 'This is a pchar string.';`

Var `P2 : Pchar;`

begin

```
P2:= StrAlloc (StrLen(P1)+1);
StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }
WriteLn ( 'P2 = ',P2);
StrDispose(P2);
```

```
end.
```

27.2.16 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: pchar) : pchar`

Visibility: default

Description: Copies `P` to the Heap, and returns a pointer to the copy.

Errors: Returns `Nil` if no memory was available for the copy.

See also: StrCopy ([1029](#)), StrDispose ([1030](#))

Listing: ./stringex/ex16.pp

Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin

 P2:=StrNew (P1);

If P1=P2 **then**

writeln ('This can't be happening...')

else

writeln ('P2 : ',P2);

StrDispose(P2);

end.

27.2.17 strpas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: function strpas(p: pchar) : shortstring

Visibility: default

Description: Converts a null terminated string in P to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

See also: StrPCopy ([1038](#))

Listing: ./stringex/ex3.pp

Program Example3;

Uses strings;

{ Program to demonstrate the StrPas function. }

Const P : PChar = 'This is a PCHAR string';

var S : **string**;

begin

 S:=StrPas (P);

Writeln ('S : ',S);

end.

27.2.18 strcpy

Synopsis: Copy a pascal string to a null-terminated string

Declaration: `function strcpy(d: pchar; const s: String) : pchar`

Visibility: default

Description: Converts the Pascal string in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No length checking is performed.

See also: `StrPas` ([1037](#))

Listing: `./stringex/ex2.pp`

Program `Example2;`

Uses `strings;`

{ Program to demonstrate the StrPCopy function. }

Const `S = 'This is a normal string.';`

Var `P : Pchar;`

begin

`p:= StrAlloc (length(S)+1);`

`if StrPCopy (P,S)<>P then`

`Writeln ('This is impossible !!')`

`else`

`writeln (P);`

`StrDispose(P);`

`end.`

27.2.19 strpos

Synopsis: Search for a null-terminated substring in a null-terminated string

Declaration: `function strpos(str1: pchar; str2: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of `S2` in `S1`. If `S2` does not occur in `S1`, returns `Nil`.

Errors: None.

See also: `StrScan` ([1039](#)), `StrRScan` ([1039](#))

Listing: `./stringex/ex15.pp`

Program `Example15;`

Uses `strings;`

{ Program to demonstrate the StrPos function. }

Const `P : PChar = 'This is a PChar string.';`

```

        S : Pchar = 'is';
begin
  WriteLn ( 'Position of ''is'' in P : ', longint(StrPos(P,S)) - Longint(P));
end.

```

27.2.20 strscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan ([1039](#)).

Errors: None.

See also: StrScan ([1039](#)), StrPos ([1038](#))

27.2.21 strscan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan ([1039](#)), StrPos ([1038](#))

Listing: ./stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

```

Const P : PChar = 'This is a PCHAR string.';
      S : Char = 's' ;

```

```

begin
  WriteLn ( 'P, starting from first ''s'' : ', StrScan(P,s));
  WriteLn ( 'P, starting from last ''s'' : ', StrRScan(P,s));
end.

```

27.2.22 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see StrLower ([1035](#))

Errors: None.

See also: StrLower ([1035](#))

Chapter 28

Reference for unit 'strutlils'

28.1 Used units

Table 28.1: Used units by unit 'strutlils'

Name	Page
SysUtils	1041

28.2 Constants, types and variables

28.2.1 Constants

```
AnsiResemblesProc : TCompareTextProc = @SoundexProc
```

This procedural variable is standard set to SoundexProc (1064) but can be overridden with a user-defined algorithm. This algorithm should return True if AText resembles AOtherText, or False otherwise. The standard routine compares the soundexes of the two strings and returns True if they are equal.

```
Brackets = [ '(' , ')' , '[' , ']' , '{' , '}' ]
```

Set of characters that contain all possible bracket characters

```
DigitChars = ['0'..'9']
```

Set of digit characters

```
StdSwitchChars = ['-','/']
```

Standard characters for the SwitchChars argument of GetCmdLineArg (1053).

```
StdWordDelims = [#0..' ', '/', '.', ':', '\', ',', "'", '"', '`'] + Brackets
```

Standard word delimiter values.

WordDelimiters : Set of Char = [#0..#255] - ['a'..'z','A'..'Z','1'..'9','0']

Standard word delimiters, used in the SearchBuf (1063) call.

28.2.2 Types

TCompareTextProc = function(const AText: String;const AOther: String)
: Boolean

Function prototype for comparing two string in AnsiResemblesText (1047)

TSoundexIntLength = 1..8

Range of allowed integer soundex lengths.

TSoundexLength = 1..MaxInt

Range of allowed soundex lengths.

TStringSeachOption = TStringSearchOption

There is an typo error in the original Borland StrUtils unit. This type just refers to the correct TStringSearchOption (1042) and is provided for compatibility only.

TStringSearchOption = (soDown, soMatchCase, soWholeWord)

Table 28.2: Enumeration values for type TStringSearchOption

Value	Explanation
soDown	Search in down direction.
soMatchCase	Match case
soWholeWord	Search whole words only.

Possible options for SearchBuf (1063) call.

TStringSearchOptions= Set of (soDown, soMatchCase, soWholeWord)

Set of options for SearchBuf (1063) call.

28.3 Procedures and functions

28.3.1 AddChar

Synopsis: Add characters to the left of a string till a certain length

Declaration: function AddChar(C: Char;const S: String;N: Integer) : String

Visibility: default

Description: AddChar adds characters (C) to the left of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N , then no characters are added. The resulting string can be thought of as a right-aligned version of S , with length N .

Errors: None

See also: AddCharR (1043), PadLeft (1059), PadRight (1059), PadCenter (1058)

28.3.2 AddCharR

Synopsis: Add chars at the end of a string till it reaches a certain length

Declaration: `function AddCharR(C: Char; const S: String; N: Integer) : String`

Visibility: default

Description: `AddCharR` adds characters (`C`) to the right of `S` till the length `N` is reached, and returns the resulting string. If the length of `S` is already equal to or larger than `N`, then no characters are added. The resulting string can be thought of as a left-aligned version of `S`, with length `N`.

Errors: None

See also: `AddChar` ([1042](#))

28.3.3 AnsiContainsStr

Synopsis: Checks whether a string contains a given substring

Declaration: `function AnsiContainsStr(const AText: String; const ASubText: String) : Boolean`

Visibility: default

Description: `AnsiContainsString` checks whether `AText` contains `ASubText`, and returns `True` if this is the case, or returns `False` otherwise. The search is performed case-sensitive.

Errors: None

See also: `AnsiContainsText` ([1043](#)), `AnsiEndsStr` ([1043](#)), `AnsiIndexStr` ([1044](#)), `AnsiStartsStr` ([1047](#))

28.3.4 AnsiContainsText

Synopsis: Check whether a string contains a certain substring, ignoring case.

Declaration: `function AnsiContainsText(const AText: String; const ASubText: String) : Boolean`

Visibility: default

Description: `AnsiContainsString` checks whether `AText` contains `ASubText`, and returns `True` if this is the case, or returns `False` otherwise. The search is performed case-insensitive.

Errors:

See also: `AnsiContainsStr` ([1043](#)), `AnsiEndsText` ([1044](#)), `AnsiIndexText` ([1044](#)), `AnsiStartsText` ([1048](#))

28.3.5 AnsiEndsStr

Synopsis: Check whether a string ends with a certain substring

Declaration: `function AnsiEndsStr(const ASubText: String; const AText: String) : Boolean`

Visibility: default

Description: `AnsiEndsStr` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

Errors: None.

See also: [AnsiEndsText \(1044\)](#), [AnsiStartsStr \(1047\)](#), [AnsiIndexStr \(1044\)](#), [AnsiContainsStr \(1043\)](#)

28.3.6 AnsiEndsText

Synopsis: Check whether a string ends with a certain substring, ignoring case.

Declaration:

```
function AnsiEndsText(const ASubText: String;const AText: String)
                    : Boolean
```

Visibility: default

Description: `AnsiEndsStr` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

Errors: None

See also: [AnsiStartsText \(1048\)](#), [AnsiEndsStr \(1043\)](#), [AnsiIndexText \(1044\)](#), [AnsiContainsText \(1043\)](#)

28.3.7 AnsiIndexStr

Synopsis: Searches, observing case, for a string in an array of strings.

Declaration:

```
function AnsiIndexStr(const AText: String;
                    const AValues: Array[] of String) : Integer
```

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched observing case.

Errors: None.

See also: [AnsiIndexText \(1044\)](#), [AnsiMatchStr \(1045\)](#), [AnsiMatchText \(1045\)](#)

28.3.8 AnsiIndexText

Synopsis: Searches, case insensitive, for a string in an array of strings.

Declaration:

```
function AnsiIndexText(const AText: String;
                    const AValues: Array[] of String) : Integer
```

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched ignoring case.

Errors: None

See also: [AnsiIndexStr \(1044\)](#), [AnsiMatchStr \(1045\)](#), [AnsiMatchText \(1045\)](#)

28.3.9 AnsiLeftStr

Synopsis: Copies a number of characters starting at the left of a string

Declaration: `function AnsiLeftStr(const AText: AnsiString; const ACount: Integer)
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` leftmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes. This function corresponds to the Visual Basic `LeftStr` function.

Errors: None.

See also: `AnsiMidStr` (1045), `AnsiRightStr` (1047), `LeftStr` (1056), `RightStr` (1062), `MidStr` (1057), `LeftBStr` (1056), `RightBStr` (1061), `MidBStr` (1057)

28.3.10 AnsiMatchStr

Synopsis: Check whether a string occurs in an array of strings, observing case.

Declaration: `function AnsiMatchStr(const AText: String;
const AValues: Array[] of String) : Boolean`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched observing case. This function simply calls `AnsiIndexStr` (1044) and checks whether it returns -1 or not.

Errors:

28.3.11 AnsiMatchText

Synopsis: Check whether a string occurs in an array of strings, disregarding case.

Declaration: `function AnsiMatchText(const AText: String;
const AValues: Array[] of String) : Boolean`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched ignoring case. This function simply calls `AnsiIndexText` (1044) and checks whether it returns -1 or not.

Errors:

28.3.12 AnsiMidStr

Synopsis: Returns a number of characters copied from a given location in a string

Declaration: `function AnsiMidStr(const AText: AnsiString; const AStart: Integer;
const ACount: Integer) : AnsiString`

Visibility: default

Description: `AnsiMidStr` returns `ACount` characters from `AText`, starting at position `AStart`. If `AStart+ACount` is larger than the length of `AText`, only as much characters as available in `AText` (starting from `AStart`) will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.

This function corresponds to the Visual Basic `MidStr` function.

Errors: None

See also: `AnsiLeftStr` (1045), `AnsiRightStr` (1047), `LeftStr` (1056), `RightStr` (1062), `MidStr` (1057), `LeftBStr` (1056), `RightBStr` (1061), `MidBStr` (1057)

28.3.13 `AnsiProperCase`

Synopsis: Pretty-Print a string: make lowercase and capitalize first letters of words

Declaration: `function AnsiProperCase(const S: String;const WordDelims: TSysCharSet) : String`

Visibility: default

Description: `AnsiProperCase` converts `S` to an all lowercase string, but capitalizes the first letter of every word in the string, and returns the resulting string. When searching for words, the characters in `WordDelimiters` are used to determine the boundaries of words. The constant `StdWordDelims` (1041) can be used for this.

Errors:

28.3.14 `AnsiReplaceStr`

Synopsis: Search and replace all occurrences of a string, case sensitive.

Declaration: `function AnsiReplaceStr(const AText: String;const AFromText: String;const AToText: String) : String`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed observing case.

Errors: None.

See also: `AnsiReplaceText` (1046), `SearchBuf` (1063)

28.3.15 `AnsiReplaceText`

Synopsis: Search and replace all occurrences of a string, case insensitive.

Declaration: `function AnsiReplaceText(const AText: String;const AFromText: String;const AToText: String) : String`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed ignoring case.

Errors: None.

See also: `AnsiReplaceStr` (1046), `SearchBuf` (1063)

28.3.16 AnsiResemblesText

Synopsis: Check whether 2 strings resemble each other.

Declaration: `function AnsiResemblesText(const AText: String;const AOther: String)
: Boolean`

Visibility: default

Description: `AnsiResemblesText` will check whether `AnsiResemblesProc` (1041) is set. If it is not set, `False` is returned. If it is set, `AText` and `AOtherText` are passed to it and it's result is returned.

Errors: None.

See also: `AnsiResemblesProc` (1041), `SoundexProc` (1064)

28.3.17 AnsiReverseString

Synopsis: Reverse the letters in a string.

Declaration: `function AnsiReverseString(const AText: AnsiString) : AnsiString`

Visibility: default

Description: `AnsiReverseString` returns a string with all characters of `AText` in reverse order.
if the result of this function equals `AText`, `AText` is called an anagram.

Errors: None.

28.3.18 AnsiRightStr

Synopsis: Copies a number of characters starting at the right of a string

Declaration: `function AnsiRightStr(const AText: AnsiString;const ACount: Integer)
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` rightmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.
This function corresponds to the Visual Basic `RightStr` function.

Errors: None.

See also: `AnsiLeftStr` (1045), `AnsiMidStr` (1045), `LeftStr` (1056), `RightStr` (1062), `MidStr` (1057), `LeftBStr` (1056), `RightBStr` (1061), `MidBStr` (1057)

28.3.19 AnsiStartsStr

Synopsis: Check whether a string starts with a given substring, observing case

Declaration: `function AnsiStartsStr(const ASubText: String;const AText: String)
: Boolean`

Visibility: default

Description: `AnsiStartsStr` checks `AText` to see whether it starts with `ASubText` , and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals 1.

Errors:

See also: `AnsiEndsStr` ([1043](#)), `AnsiStartsStr` ([1047](#)), `AnsiIndexStr` ([1044](#)), `AnsiContainsStr` ([1043](#))

28.3.20 `AnsiStartsText`

Synopsis: Check whether a string starts with a given substring, ignoring case

Declaration: `function AnsiStartsText(const ASubText: String;const AText: String) : Boolean`

Visibility: default

Description: `AnsiStartsText` checks `AText` to see whether it starts with `ASubText` , and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals 1.

Errors: None.

See also: `AnsiEndsText` ([1044](#)), `AnsiStartsStr` ([1047](#)), `AnsiIndexText` ([1044](#)), `AnsiContainsText` ([1043](#))

28.3.21 `BinToHex`

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex(BinValue: PChar;HexValue: PChar;BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size `2*BufSize`.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` ([1054](#))

28.3.22 `Copy2Space`

Synopsis: Returns all characters in a string till the first space character (not included).

Declaration: `function Copy2Space(const S: String) : String`

Visibility: default

Description: `Copy2Space` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. The string `S` is left untouched. If there is no space in `S`, then the whole string `S` is returned.

This function simply calls `Copy2Symb` ([1049](#)) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2Symb` ([1049](#)), `Copy2SpaceDel` ([1049](#))

28.3.23 Copy2SpaceDel

Synopsis: Deletes and returns all characters in a string till the first space character (not included).

Declaration: `function Copy2SpaceDel (var S: String) : String`

Visibility: default

Description: `Copy2SpaceDel` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. All returned characters, including the space, are deleted from the string `S`, after which it is right-trimmed. If there is no space in `S`, then the whole string `S` is returned, and `S` itself is emptied.

This function simply calls `Copy2SymbDel` (1049) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2SymbDel` (1049), `Copy2Space` (1048)

28.3.24 Copy2Symb

Synopsis: Returns all characters in a string till a given character (not included).

Declaration: `function Copy2Symb (const S: String; Symb: Char) : String`

Visibility: default

Description: `Copy2SymbDel` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. The string `S` is left untouched. If `Symb` does not appear in `S`, then the whole of `S` is returned.

Errors: None.

See also: `Copy2Space` (1048), `Copy2SymbDel` (1049)

28.3.25 Copy2SymbDel

Synopsis: Deletes and returns all characters in a string till a given character (not included).

Declaration: `function Copy2SymbDel (var S: String; Symb: Char) : String`

Visibility: default

Description: `Copy2SymbDel` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. All returned characters, *not* including the `Symb` character, are deleted from the string `S`, after which it is right-trimmed. If `Symb` does not appear in `S`, then the whole of `S` is returned, and `S` itself is emptied.

Errors: None.

See also: `Copy2SpaceDel` (1049), `Copy2Symb` (1049)

28.3.26 Dec2Numb

Synopsis: Convert a decimal number to a string representation, using given a base.

Declaration: `function Dec2Numb(N: LongInt; Len: Byte; Base: Byte) : String`

Visibility: default

Description: `Dec2Numb` converts `N` to its representation using base `Base`. The resulting string is left-padded with zeroes till it has length `Len`. `Base` must be in the range 2-36 to be meaningful, but no checking on this is performed.

Errors: If `Base` is out of range, the resulting string will contain unreadable (non-alphanumeric) characters.

See also: `Hex2Dec` ([1054](#)), `IntToBin` ([1055](#)), `intToRoman` ([1055](#)), `RomanToInt` ([1062](#))

28.3.27 DecodeSoundexInt

Synopsis: Decodes the integer representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexInt(AValue: Integer) : String`

Visibility: default

Description: `DecodeSoundexInt` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexInt` ([1064](#)) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: `SoundexInt` ([1064](#)), `DecodeSoundexWord` ([1050](#)), `Soundex` ([1063](#))

28.3.28 DecodeSoundexWord

Synopsis: Decodes the word-sized representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexWord(AValue: Word) : String`

Visibility: default

Description: `DecodeSoundexWord` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexWord` ([1065](#)) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: `SoundexInt` ([1064](#)), `DecodeSoundexInt` ([1050](#)), `Soundex` ([1063](#))

28.3.29 DelChars

Synopsis: Delete all occurrences of a given character from a string.

Declaration: `function DelChars(const S: String; Chr: Char) : String`

Visibility: default

Description: `DelChars` returns a copy of `S` with all `Chr` characters removed from it.

Errors: None.

See also: `DelSpace` ([1051](#)), `DelSpace1` ([1051](#))

28.3.30 DelSpace

Synopsis: Delete all occurrences of a space from a string.

Declaration: `function DelSpace(const S: String) : String`

Visibility: default

Description: `DelSpace` returns a copy of `S` with all spaces (ASCII code 32) removed from it.

Errors: None.

See also: `DelChars` ([1050](#)), `DelSpace1` ([1051](#))

28.3.31 DelSpace1

Synopsis: Reduces sequences of space characters to 1 space character.

Declaration: `function DelSpace1(const S: String) : String`

Visibility: default

Description: `DelSpace1` returns a copy of `S` with all sequences of spaces reduced to 1 space.

Errors: None.

See also: `DelChars` ([1050](#)), `DelSpace` ([1051](#))

28.3.32 DupeString

Synopsis: Creates and concatenates `N` copies of a string

Declaration: `function DupeString(const AText: String; ACount: Integer) : String`

Visibility: default

Description: `DupeString` returns a string consisting of `ACount` concatenations of `AText`. Thus

```
DupeString('1234567890', 3);
```

will produce a string

```
'123456789012345678901234567890'
```

Errors: None.

28.3.33 ExtractDelimited

Synopsis: Extract the `N`-th delimited part from a string.

Declaration: `function ExtractDelimited(N: Integer; const S: String;
const Delims: TSysCharSet) : String`

Visibility: default

Description: `ExtractDelimited` extracts the N-th part from the string `S`. The set of characters in `Delims` are used to mark part boundaries. When a delimiter is encountered, a new part is started and the old part is ended. Another way of stating this is that any (possibly empty) series of characters not in `Delims`, situated between 2 characters in `Delims`, it is considered as piece of a part. This means that if 2 delimiter characters appear next to each other, there is an empty part between it. If an N-th part cannot be found, an empty string is returned. However, unlike `ExtractWord` (1052), an empty string is a valid return value, i.e. a part can be empty.

The pre-defined constant `StdWordDelims` (1041) can be used for the `Delims` argument. The pre-defined constant `Brackets` (1041) would be better suited the `Delims` argument e.g. in case factors in a mathematical expression are searched.

Errors: None.

See also: `ExtractSubStr` (1052), `ExtractWord` (1052), `ExtractWordPos` (1053)

28.3.34 ExtractSubstr

Synopsis: Extract a word from a string, starting at a given position in the string.

Declaration:

```
function ExtractSubstr(const S: String; var Pos: Integer;
                      const Delims: TSysCharSet) : String
```

Visibility: default

Description: `ExtractSubStr` returns all characters from `S` starting at position `Pos` till the first character in `Delims`, or till the end of `S` is reached. The delimiter character is not included in the result. `Pos` is then updated to point to the next first non-delimiter character in `S`. If `Pos` is larger than the `Length` of `S`, an empty string is returned.

The pre-defined constant `StdWordDelims` (1041) can be used for the `Delims` argument.

Errors: None.

See also: `ExtractDelimited` (1051), `ExtractWord` (1052), `ExtractWordPos` (1053)

28.3.35 ExtractWord

Synopsis: Extract the N-th word out of a string.

Declaration:

```
function ExtractWord(N: Integer; const S: String;
                    const WordDelims: TSysCharSet) : String
```

Visibility: default

Description: `ExtractWord` extracts the N-th word from the string `S`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned.

Unlike `ExtractDelimited` (1051), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The pre-defined constant `StdWordDelims` (1041) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWordPos` (1053), `ExtractSubStr` (1052), `ExtractDelimited` (1051), `IsWordPresent` (1056), `WordCount` (1067), `WordPosition` (1067)

28.3.36 ExtractWordPos

Synopsis: Extract a word from a string, and return the position where it was located in the string.

Declaration:

```
function ExtractWordPos(N: Integer; const S: String;
                        const WordDelims: TSysCharSet; var Pos: Integer)
                        : String
```

Visibility: default

Description: `ExtractWordPos` extracts the `N`-th word from the string `S` and returns the position of this word in `Pos`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an `N`-th word cannot be found, an empty string is returned and `Pos` is zero.

Unlike `ExtractDelimited` (1051), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The pre-defined constant `StdWordDelims` (1041) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWord` (1052), `ExtractSubStr` (1052), `IsWordPresent` (1056), `WordCount` (1067), `WordPosition` (1067)

28.3.37 FindPart

Synopsis: Search for a substring in a string, using wildcards.

Declaration:

```
function FindPart(const HelpWilds: String; const InputStr: String)
                  : Integer
```

Visibility: default

Description: `FindPart` searches the string `InputStr` and returns the first string that matches the wildcards specification in `HelpWilds`. If no match is found, an empty string is returned. Currently, the only valid wildcards is the "?" character.

Errors: None.

See also: `SearchBuf` (1063)

28.3.38 GetCmdLineArg

Synopsis: Returns the command-line argument following the given switch.

Declaration:

```
function GetCmdLineArg(const Switch: String; SwitchChars: TSysCharSet)
                      : String
```

Visibility: default

Description: `GetCmdLineArg` returns the value for the `Switch` option on the command-line, if any is given. Command-line arguments are considered switches if they start with one of the characters in the `SwitchChars` set. The value is the command-line argument following the switch command-line argument.

Gnu-style (long) Options of the form `switch=value` are not supported.

The `StdSwitchChars` (1041) constant can be used as value for the `SwitchChars` parameter.

Errors: The `GetCmdLineArg` does not check whether the value of the option does not start with a switch character. i.e.

```
myprogram -option1 -option2
```

will result in "-option2" as the result of the `GetCmdLineArg` call for option1.

See also: `StdSwitchChars` ([1041](#))

28.3.39 Hex2Dec

Synopsis: Converts a hexadecimal string to a decimal value

Declaration: `function Hex2Dec(const S: String) : LongInt`

Visibility: default

Description: `Hex2Dec` converts the hexadecimal value in the string `S` to its decimal value. Unlike the standard `Val` or `StrToInt` functions, there need not be a \$ sign in front of the hexadecimal value to indicate that it is indeed a hexadecimal value.

Errors: If `S` does not contain a valid hexadecimal value, an `EConvertError` exception will be raised.

See also: `Dec2Numb` ([1050](#)), `IntToBin` ([1055](#)), `intToRoman` ([1055](#)), `RomanToInt` ([1062](#))

28.3.40 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer) : Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` ([1048](#))

28.3.41 IfThen

Synopsis: Returns one of two strings, depending on a boolean expression

Declaration: `function IfThen(AValue: Boolean; const ATrue: String; AFalse: String) : String`
`function IfThen(AValue: Boolean; const ATrue: String) : String`

Visibility: default

Description: `IfThen` returns `ATrue` if `AValue` is `True`, and returns `AFalse` if `AValue` is `false`.

Errors: None.

See also: `AnsiMatchStr` ([1045](#)), `AnsiMatchText` ([1045](#))

28.3.42 IntToBin

Synopsis: Converts an integer to a binary string representation, inserting spaces at fixed locations.

Declaration: `function IntToBin(Value: LongInt; Digits: Integer; Spaces: Integer)
: String`

Visibility: default

Description: `IntToBin` converts `Value` to a string with its binary (base 2) representation. The resulting string contains at least `Digits` digits, with spaces inserted every `Spaces` digits. `Spaces` should be a nonzero value. If `Digits` is larger than 32, it is truncated to 32.

Errors: If `Spaces` is zero, a division by zero error will occur.

See also: `Hex2Dec` ([1054](#)), `IntToRoman` ([1055](#))

28.3.43 IntToRoman

Synopsis: Represent an integer with roman numerals

Declaration: `function IntToRoman(Value: LongInt) : String`

Visibility: default

Description: `IntToRoman` converts `Value` to a string with the Roman representation of `Value`. Number up to 1 million can be represented this way.

Errors: None.

See also: `RomanToInt` ([1062](#)), `Hex2Dec` ([1054](#)), `IntToBin` ([1055](#))

28.3.44 IsEmptyStr

Synopsis: Check whether a string is empty, disregarding whitespace characters

Declaration: `function IsEmptyStr(const S: String; const EmptyChars: TSysCharSet)
: Boolean`

Visibility: default

Description: `IsEmptyStr` returns `True` if the string `S` only contains characters whitespace characters, all characters in `EmptyChars` are considered whitespace characters. If a character not present in `EmptyChars` is found in `S`, `False` is returned.

Errors: None.

See also: `IsWild` ([1055](#)), `FindPart` ([1053](#)), `IsWordPresent` ([1056](#))

28.3.45 IsWild

Synopsis: Check whether a string matches a wildcard search expression.

Declaration: `function IsWild(InputStr: String; Wilds: String; IgnoreCase: Boolean)
: Boolean`

Visibility: default

Description: `IsWild` checks `InputStr` for the presence of the `Wilds` string. `Wilds` may contain "?" and "*" wildcard characters, which have their usual meaning: "*" matches any series of characters, possibly empty. "?" matches any single character. The function returns `True` if a string is found that matches `Wilds`, `False` otherwise.

If `IgnoreCase` is `True`, the non-wildcard characters are matched case insensitively. If it is `False`, case is observed when searching.

Errors: None.

See also: `SearchBuf` (1063), `FindPart` (1053)

28.3.46 IsWordPresent

Synopsis: Check for the presence of a word in a string.

Declaration: `function IsWordPresent(const W: String; const S: String;
const WordDelims: TSysCharSet) : Boolean`

Visibility: default

Description: `IsWordPresent` checks for the presence of the word `W` in the string `S`. Words are delimited by the characters found in `WordDelims`. The function returns `True` if a match is found, `False` otherwise. The search is performed case sensitive.

This function is equivalent to the `SearchBuf` (1063) function with the `soWholeWords` option specified.

Errors: None.

See also: `SearchBuf` (1063)

28.3.47 LeftBStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration: `function LeftBStr(const AText: AnsiString; const AByteCount: Integer)
: AnsiString`

Visibility: default

Description: `LeftBStr` returns a string containing the leftmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftStr` (1056), `AnsiLeftStr` (1045), `RightBStr` (1061), `MidBStr` (1057)

28.3.48 LeftStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration: `function LeftStr(const AText: AnsiString; const ACount: Integer)
: AnsiString
function LeftStr(const AText: WideString; const ACount: Integer)
: WideString`

Visibility: default

Description: `LeftStr` returns a string containing the leftmost `ACount` characters from the string `AText` . If `ACount` is larger than the length (in characters) of `AText` , only as many characters as available are returned.

Errors: None.

See also: `LeftBStr` (1056), `AnsiLeftStr` (1045), `RightStr` (1062), `MidStr` (1057)

28.3.49 MidBStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration: `function MidBStr(const AText: AnsiString; const AByteStart: Integer;
const AByteCount: Integer) : AnsiString`

Visibility: default

Description: `MidBStr` returns a string containing the first `AByteCount` bytes from the string `AText` starting at position `AByteStart`. If `AByteStart+AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned. If `AByteStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

Errors: None.

See also: `LeftBStr` (1056), `AnsiMidStr` (1045), `RightBStr` (1061), `MidStr` (1057)

28.3.50 MidStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration: `function MidStr(const AText: AnsiString; const AStart: Integer;
const ACount: Integer) : AnsiString
function MidStr(const AText: WideString; const AStart: Integer;
const ACount: Integer) : WideString`

Visibility: default

Description: `MidStr` returns a string containing the first `ACount` bytes from the string `AText` starting at position `AStart`. If `AStart+ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned. If `AStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

This function is equivalent to the standard `Copy` function, and is provided for completeness only.

Errors: None.

See also: `LeftStr` (1056), `AnsiMidStr` (1045), `RightStr` (1062), `MidBStr` (1057)

28.3.51 NPos

Synopsis: Returns the position of the N-th occurrence of a substring in a string.

Declaration: `function NPos(const C: String; S: String; N: Integer) : Integer`

Visibility: default

Description: `NPos` checks `S` for the position of the N-th occurrence of `C`. If `C` occurs less than `N` times in `S`, or does not occur in `S` at all, 0 is returned. If `N` is less than 1, zero is returned.

Errors: None.

See also: [WordPosition \(1067\)](#), [FindPart \(1053\)](#)

28.3.52 Numb2Dec

Synopsis: Converts a string representation of a number to its numerical value, given a certain base.

Declaration: `function Numb2Dec(S: String;Base: Byte) : LongInt`

Visibility: default

Description: `Numb2Dec` converts the number in string `S` to a decimal value. It assumes the number is represented using `Base` as the base. No checking is performed to see whether `S` contains a valid number using base `Base`.

Errors: None.

See also: [Hex2Dec \(1054\)](#), [Numb2USA \(1058\)](#)

28.3.53 Numb2USA

Synopsis: Insert thousand separators.

Declaration: `function Numb2USA(const S: String) : String`

Visibility: default

Description: `Numb2USA` inserts thousand separators in the string `S` at the places where they are supposed to be, i.e. every 3 digits. The string `S` should contain a valid integer number, i.e. no digital number. No checking on this is done.

Errors: None.

28.3.54 PadCenter

Synopsis: Pad the string to a certain length, so the string is centered.

Declaration: `function PadCenter(const S: String;Len: Integer) : String`

Visibility: default

Description: `PadCenter` add spaces to the left and right of the string `S` till the result reaches length `Len`. If the number of spaces to add is odd, then the extra space will be added at the end. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is.

Errors: None.

See also: [PadLeft \(1059\)](#), [PadRight \(1059\)](#), [AddChar \(1042\)](#), [AddCharR \(1043\)](#)

28.3.55 PadLeft

Synopsis: Add spaces to the left of a string till a certain length is reached.

Declaration: `function PadLeft(const S: String;N: Integer) : String`

Visibility: default

Description: `PadLeft` add spaces to the left of the string `S` till the result reaches length `Len` . If the string `S` has length equal to or largert than `Len` , no spaces are added, and the string `S` is returned as-is. The resulting string is `S` , right-justified on length `Len` .

Errors: None.

See also: `PadLeft` ([1059](#)), `PadCenter` ([1058](#)), `AddChar` ([1042](#)), `AddCharR` ([1043](#))

28.3.56 PadRight

Synopsis: Add spaces to the right of a string till a certain length is reached.

Declaration: `function PadRight(const S: String;N: Integer) : String`

Visibility: default

Description: `PadRight` add spaces to the left of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, left-justified on length `Len` .

Errors: None.

See also: `PadLeft` ([1059](#)), `PadCenter` ([1058](#)), `AddChar` ([1042](#)), `AddCharR` ([1043](#))

28.3.57 PosEx

Synopsis: Search for the occurance of a character in a string, starting at a certain position.

Declaration: `function PosEx(const SubStr: String;const S: String;Offset: Cardinal)
: Integer
function PosEx(const SubStr: String;const S: String) : Integer
function PosEx(c: Char;const S: String;Offset: Cardinal) : Integer`

Visibility: default

Description: `PosEx` returns the position of the first occurrence of the character `C` or the substring `SubStr` in the string `S`, starting the search at position `Offset` (default 1). If `C` or `SubStr` does not occur in `S` after the given `Offset`, zero is returned. The position `Offset` is also searched.

Errors: None.

See also: `NPos` ([1057](#)), `AnsiContainsText` ([1043](#)), `AnsiContainsStr` ([1043](#))

28.3.58 PosSet

Synopsis: Return the position in a string of any character out of a set of characters

Declaration: `function PosSet(const c: TSysCharSet;const s: ansistring) : Integer
function PosSet(const c: String;const s: ansistring) : Integer`

Visibility: default

Description: `PosSet` returns the position in `s` of the first found character which is in the set `c`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1059](#)), `PosSetEx` ([1060](#)), `#rtl.system.pos` ([1228](#)), `RPosEx` ([1063](#))

28.3.59 PosSetEx

Synopsis: Return the position in a string of any character out of a set of characters, starting at a certain position

Declaration:

```
function PosSetEx(const c: TSysCharSet; const s: ansistring;
                  count: Integer) : Integer
function PosSetEx(const c: String; const s: ansistring; count: Integer)
                  : Integer
```

Visibility: default

Description: `PosSetEx` returns the position in `s` of the first found character which is in the set `c`, and starts searching at character position `Count`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1059](#)), `PosSet` ([1059](#)), `#rtl.system.pos` ([1228](#)), `RPosEx` ([1063](#))

28.3.60 RandomFrom

Synopsis: Choose a random string from an array of strings.

Declaration:

```
function RandomFrom(const AValues: Array[] of String) : String
; Overload
```

Visibility: default

Description: `RandomFrom` picks at random a valid index in the array `AValues` and returns the string at that position in the array.

Errors: None.

See also: `AnsiMatchStr` ([1045](#)), `AnsiMatchText` ([1045](#))

28.3.61 Removeleadingchars

Synopsis: Remove any leading characters in a set from a string

Declaration:

```
procedure Removeleadingchars(var S: AnsiString; const CSet: TSysCharSet)
```

Visibility: default

Description: `Removeleadingchars` removes any starting characters from `S` that appear in the set `CSet`. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimLeft` ([1405](#)) which used whitespace as the set.

Errors: None.

See also: `rtl.sysutils.TrimLeft` ([1041](#)), `RemoveTrailingChars` ([1061](#)), `RemovePadChars` ([1061](#)), `TrimLeftSet` ([1066](#))

28.3.62 RemovePadChars

Synopsis: Remove any trailing or leading characters in a set from a string

Declaration: `procedure RemovePadChars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `RemovePadChars` removes any leading trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string, and it stops removing characters as soon as a character not in `CSet` is encountered. Then the same procedure is repeated starting from the beginning of the string. This is similar in behaviour to `Trim` (1404) which used whitespace as the set.

Errors: None.

See also: `rtl.sysutils.Trim` (1041), `RemoveLeadingChars` (1060), `RemoveTrailingChars` (1061), `TrimSet` (1066), `TrimLeftSet` (1066), `TrimRightSet` (1066)

28.3.63 RemoveTrailingChars

Synopsis: Remove any trailing characters in a set from a string

Declaration: `procedure RemoveTrailingChars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `RemoveTrailingChars` removes any trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimRight` (1405) which used whitespace as the set.

Errors:

See also: `rtl.sysutils.TrimLeft` (1041), `RemoveLeadingChars` (1060), `TrimRightSet` (1066)

28.3.64 ReverseString

Synopsis: Reverse characters in a string

Declaration: `function ReverseString(const AText: String) : String`

Visibility: default

Description: `ReverseString` returns a string, made up of the characters in string `AText`, in reverse order.

Errors: None.

See also: `RandomFrom` (1060)

28.3.65 RightBStr

Synopsis: Copy a given number of characters (bytes), counting from the right of a string.

Declaration: `function RightBStr(const AText: AnsiString; const AByteCount: Integer) : AnsiString`

Visibility: default

Description: `RightBStr` returns a string containing the rightmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftBStr` ([1056](#)), `AnsiRightStr` ([1047](#)), `RightStr` ([1062](#)), `MidBStr` ([1057](#))

28.3.66 RightStr

Synopsis: Copy a given number of characters, counting from the right of a string.

Declaration:

```
function RightStr(const AText: AnsiString; const ACount: Integer)
    : AnsiString
function RightStr(const AText: WideString; const ACount: Integer)
    : WideString
```

Visibility: default

Description: `RightStr` returns a string containing the rightmost `ACount` characters from the string `AText`. If `ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned.

Errors: None.

See also: `LeftStr` ([1056](#)), `AnsiRightStr` ([1047](#)), `RightBStr` ([1061](#)), `MidStr` ([1057](#))

28.3.67 RomanToInt

Synopsis: Convert a string with a Roman number to its decimal value.

Declaration:

```
function RomanToInt(const S: String) : LongInt
```

Visibility: default

Description: `RomanToInt` returns the decimal equivalent of the Roman numerals in the string `S`. Invalid characters are dropped from `S`. A negative numeral is supported as well.

Errors: None.

See also: `IntToRoman` ([1055](#)), `Hex2Dec` ([1054](#)), `Numb2Dec` ([1058](#))

28.3.68 RPos

Synopsis: Find last occurrence of substring or character in a string

Declaration:

```
function RPos(c: Char; const S: AnsiString) : Integer; Overload
function RPos(const Substr: AnsiString; const Source: AnsiString)
    : Integer; Overload
```

Visibility: default

Description: `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at the end of the string, and searches towards the beginning of the string. If a match is found, it returns the position of the match.

See also: `RPosEx` ([1063](#))

28.3.69 RPosex

Synopsis: Find last occurrence substring or character in a string, starting at a certain position

Declaration: `function RPosEX(C: Char;const S: AnsiString;offs: cardinal) : Integer`
`; Overload`
`function RPosex(const Substr: AnsiString;const Source: AnsiString;`
`offs: cardinal) : Integer; Overload`

Visibility: default

Description: `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at position `Offs`, and searches towards the beginning of the string. If a match is found, it returns the position of the match.

See also: `RPos` ([1062](#))

28.3.70 SearchBuf

Synopsis: Search a buffer for a certain string.

Declaration: `function SearchBuf(Buf: PChar;BufLen: Integer;SelStart: Integer;`
`SelLength: Integer;SearchString: String;`
`Options: TStringSearchOptions) : PChar`
`function SearchBuf(Buf: PChar;BufLen: Integer;SelStart: Integer;`
`SelLength: Integer;SearchString: String) : PChar`

Visibility: default

Description: `SearchBuf` searches the buffer `Buf` for the occurrence of `SearchString`. At most `Buflen` characters are searched, and the search is started at `SelStart+SelLength`. If a match is found, a pointer to the position of the match is returned. The parameter `Options` ([1042](#)) specifies how the search is conducted. It is a set of the following options:

Table 28.3:

Option	Effect
<code>soDown</code>	Searches forward, starting at the end of the selection. Default is searching up
<code>soMatchCase</code>	Observe case when searching. Default is to ignore case.
<code>soWholeWord</code>	Match only whole words. Default also returns parts of words

The standard constant `WordDelimiters` ([1042](#)) is used to mark the boundaries of words.

The `SelStart` parameter is zero based.

Errors: `Buflen` must be the real length of the string, no checking on this is performed.

See also: `FindPart` ([1053](#)), `ExtractWord` ([1052](#)), `ExtractWordPos` ([1053](#)), `ExtractSubStr` ([1052](#)), `IsWordPresent` ([1056](#))

28.3.71 Soundex

Synopsis: Compute the soundex of a string

Declaration: `function Soundex(const AText: String;ALength: TSoundexLength) : String`
`function Soundex(const AText: String) : String`

Visibility: default

Description: Soundex computes a soundex code for AText. The resulting code will at most have ALength characters. The soundex code is computed according to the US system of soundex computing, which may result in inaccurate results in other languages.

Errors: None.

See also: SoundexCompare (1064), SoundexInt (1064), SoundexProc (1064), SoundexWord (1065), SoundexSimilar (1065)

28.3.72 SoundexCompare

Synopsis: Compare soundex values of 2 strings.

Declaration:

```
function SoundexCompare(const AText: String;const AOther: String;
                        ALength: TSoundexLength) : Integer
function SoundexCompare(const AText: String;const AOther: String)
                        : Integer
```

Visibility: default

Description: SoundexCompare computes the soundex codes of AText and AOther and feeds these to CompareText. It will return -1 if the soundex code of AText is less than the soundex code of AOther, 0 if they are equal, and 1 if the code of AOther is larger than the code of AText.

Errors: None.

See also: Soundex (1063), SoundexInt (1064), SoundexProc (1064), SoundexWord (1065), SoundexSimilar (1065)

28.3.73 SoundexInt

Synopsis: Soundex value as an integer.

Declaration:

```
function SoundexInt(const AText: String;ALength: TSoundexIntLength)
                    : Integer
function SoundexInt(const AText: String) : Integer
```

Visibility: default

Description: SoundexInt computes the Soundex (1063) code (with length ALength, default 4) of AText, and converts the code to an integer value.

Errors: None.

See also: Soundex (1063), SoundexCompare (1064), SoundexProc (1064), SoundexWord (1065), SoundexSimilar (1065)

28.3.74 SoundexProc

Synopsis: Default AnsiResemblesText implementation.

Declaration: function SoundexProc(const AText: String;const AOther: String) : Boolean

Visibility: default

Description: SoundexProc is the standard implementation for the AnsiResemblesText (1047) procedure: By default, AnsiResemblesProc is set to this function. It compares the soundex codes of AOther and AText and returns True if they are equal, or False if they are not.

Errors: None.

See also: [Soundex \(1063\)](#), [SoundexCompare \(1064\)](#), [SoundexInt \(1064\)](#), [SoundexWord \(1065\)](#), [SoundexSimilar \(1065\)](#)

28.3.75 SoundexSimilar

Synopsis: Check whether 2 strings have equal soundex values

Declaration:

```
function SoundexSimilar(const AText: String;const AOther: String;
                        ALength: TSoundexLength) : Boolean
function SoundexSimilar(const AText: String;const AOther: String)
                        : Boolean
```

Visibility: default

Description: `SoundexSimilar` returns `True` if the soundex codes (with length `ALength`) of `AText` and `AOther` are equal, and `False` if they are not.

Errors: None.

See also: [Soundex \(1063\)](#), [SoundexCompare \(1064\)](#), [SoundexInt \(1064\)](#), [SoundexProc \(1064\)](#), [SoundexWord \(1065\)](#), [Soundex \(1063\)](#)

28.3.76 SoundexWord

Synopsis: Calculate a word-sized soundex value

Declaration:

```
function SoundexWord(const AText: String) : Word
```

Visibility: default

Description: `SoundexInt` computes the [Soundex \(1063\)](#) code (with length 4) of `AText`, and converts the code to a word-sized value.

Errors: None.

See also: [Soundex \(1063\)](#), [SoundexCompare \(1064\)](#), [SoundexInt \(1064\)](#), [SoundexProc \(1064\)](#), [SoundexSimilar \(1065\)](#)

28.3.77 StuffString

Synopsis: Replace part of a string with another string.

Declaration:

```
function StuffString(const AText: String;AStart: Cardinal;
                    ALength: Cardinal;const ASubText: String) : String
```

Visibility: default

Description: `StuffString` returns a copy of `AText` with the segment starting at `AStart` with length `ALength`, replaced with the string `ASubText`. Basically it deletes the segment of `Atext` and inserts the new text in it's place.

Errors: No checking on the validity of the `AStart` and `ALength` parameters is done. Providing invalid values may result in access violation errors.

See also: [FindPart \(1053\)](#), [DelChars \(1050\)](#), [DelSpace \(1051\)](#), [ExtractSubStr \(1052\)](#), [DupeString \(1051\)](#)

28.3.78 Tab2Space

Synopsis: Convert tab characters to a number of spaces

Declaration: `function Tab2Space(const S: String;Numb: Byte) : String`

Visibility: default

Description: `Tab2Space` returns a copy of `S` with all tab characters (ASCII character 9) converted to `Numb` spaces.

Errors: None.

See also: `StuffString` (1065), `FindPart` (1053), `ExtractWord` (1052), `DelChars` (1050), `DelSpace` (1051), `DelSpace1` (1051), `DupeString` (1051)

28.3.79 TrimLeftSet

Synopsis: Remove any leading characters in a set from a string and returns the result

Declaration: `function TrimLeftSet(const S: String;const CSet: TSysCharSet) : String`

Visibility: default

Description: `TrimLeftSet` performs the same action as `RemoveLeadingChars` (1060), but returns the resulting string.

Errors: None.

See also: `rtl.sysutils.TrimLeft` (1041), `RemoveLeadingChars` (1060), `RemoveTrailingChars` (1061), `RemovePadChars` (1061), `TrimSet` (1066), `TrimRightSet` (1066)

28.3.80 TrimRightSet

Synopsis: Remove any trailing characters in a set from a string and returns the result

Declaration: `function TrimRightSet(const S: String;const CSet: TSysCharSet) : String`

Visibility: default

Description: `TrimRightSet` performs the same action as `RemoveTrailingChars` (1061), but returns the resulting string.

Errors: None.

See also: `rtl.sysutils.TrimRight` (1041), `RemoveLeadingChars` (1060), `RemoveTrailingChars` (1061), `RemovePadChars` (1061), `TrimSet` (1066), `TrimLeftSet` (1066)

28.3.81 TrimSet

Synopsis: Remove any leading or trailing characters in a set from a string and returns the result

Declaration: `function TrimSet(const S: String;const CSet: TSysCharSet) : String`

Visibility: default

Description: `TrimSet` performs the same action as `RemovePadChars` (1061), but returns the resulting string.

Errors: None.

See also: `rtl.sysutils.Trim` (1041), `RemoveLeadingChars` (1060), `RemoveTrailingChars` (1061), `RemovePadChars` (1061), `TrimRightSet` (1066), `TrimLeftSet` (1066)

28.3.82 WordCount

Synopsis: Count the number of words in a string.

Declaration: `function WordCount(const S: String; const WordDelims: TSysCharSet)
: Integer`

Visibility: default

Description: `WordCount` returns the number of words in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`.

The pre-defined `StdWordDelims` (1041) constant can be used for the `WordDelims` argument.

Errors: None.

See also: `WordPosition` (1067), `StdWordDelims` (1041), `ExtractWord` (1052), `ExtractWordPos` (1053)

28.3.83 WordPosition

Synopsis: Search position of Nth word in a string.

Declaration: `function WordPosition(const N: Integer; const S: String;
const WordDelims: TSysCharSet) : Integer`

Visibility: default

Description: `WordPosition` returns the position (in characters) of the N-th word in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`. If `N` is out of range, zero is returned.

The pre-defined `StdWordDelims` (1041) constant can be used for the `WordDelims` argument.

Errors: None

See also: `WordCount` (1067), `StdWordDelims` (1041), `ExtractWord` (1052), `ExtractWordPos` (1053)

28.3.84 XorDecode

Synopsis: Decode a string encoded with `XorEncode` (1068)

Declaration: `function XorDecode(const Key: String; const Source: String) : String`

Visibility: default

Description: `XorDecode` decodes `Source` and returns the original string that was encrypted using `XorEncode` (1068) with key `Key`. If a different key is used than the key used to encode the string, the result will be unreadable.

Errors: If the string `Source` is not a valid `XorEncode` result (e.g. contains non-numerical characters), then a `EConversionError` exception will be raised.

See also: `XorEncode` (1068), `XorString` (1068)

28.3.85 XorEncode

Synopsis: Encode a string by XOR-ing its characters using characters of a given key, representing the result as hex values.

Declaration: `function XorEncode(const Key: String;const Source: String) : String`

Visibility: default

Description: `XorEncode` encodes the string `Source` by XOR-ing each character in `Source` with the corresponding character in `Key` (repeating `Key` as often as necessary) and representing the resulting ASCII code as a hexadecimal number (of length 2). The result is therefore twice as long as the original string, and every 2 bytes represent an ASCII code.

Feeding the resulting string with the same key `Key` to the `XorDecode` (1067) function will result in the original `Source` string.

This function can be used e.g. to trivially encode a password in a configuration file.

Errors: None.

See also: `XorDecode` (1067), `XorString` (1068), `Hex2Dec` (1054)

28.3.86 XorString

Synopsis: Encode a string by XOR-ing its characters using characters of a given key.

Declaration: `function XorString(const Key: ShortString;const Src: ShortString)
: ShortString`

Visibility: default

Description: `XorString` encodes the string `Src` by XOR-ing each character in `Source` with the corresponding character in `Key`, repeating `Key` as often as necessary. The resulting string may contain unreadable characters and may even contain null characters. For this reason it may be a better idea to use the `XorEncode` (1068) function instead, which will representing each resulting ASCII code as a hexadecimal number (of length 2).

Feeding the result again to `XorString` with the same `Key`, will result in the original string `Src`.

Errors: None.

See also: `XorEncode` (1068), `XorDecode` (1067)

Chapter 29

Reference for unit 'System'

29.1 Miscellaneous functions

Functions that do not belong in one of the other categories.

Table 29.1:

Name	Description
Assert (1116)	Conditionally abort program with error
Break (1121)	Abort current loop
Continue (1129)	Next cycle in current loop
Exclude (1139)	Exclude an element from a set
Exit (1140)	Exit current function or procedure
Include (1187)	Include an element into a set
LongJump (1197)	Jump to execution point
Ord (1226)	Return ordinal value of enumerated type
Pred (1229)	Return previous value of ordinal type
SetJump (1242)	Mark execution point for jump
SizeOf (1247)	Return size of variable or type
Succ (1252)	Return next value of ordinal type

29.2 Operating System functions

Functions that are connected to the operating system.

29.3 String handling

All things connected to string handling.

29.4 Mathematical routines

Functions connected to calculating and converting numbers.

Table 29.2:

Name	Description
Chdir (1122)	Change working directory
Getdir (1179)	Return current working directory
Halt (1183)	Halt program execution
Paramcount (1226)	Number of parameters with which program was called
Paramstr (1227)	Retrieve parameters with which program was called
Mkdir (1199)	Make a directory
Rmdir (1236)	Remove a directory
Runerror (1239)	Abort program execution with error condition

Table 29.3:

Name	Description
BinStr (1119)	Construct binary representation of integer
Chr (1123)	Convert ASCII code to character
Concat (1129)	Concatenate two strings
Copy (1069)	Copy part of a string
Delete (1133)	Delete part of a string
HexStr (1184)	Construct hexadecimal representation of integer
Insert (1191)	Insert one string in another
Length (1069)	Return length of string
Lowercase (1198)	Convert string to all-lowercase
OctStr (1201)	Construct octal representation of integer
Pos (1228)	Calculate position of one string in another
SetLength (1069)	Set length of a string
SetString (1244)	Set contents and length of a string
Str (1250)	Convert number to string representation
StringOfChar (1251)	Create string consisting of a number of characters
Uppcase (1260)	Convert string to all-uppercase
Val (1261)	Convert string to number

29.5 Memory management functions

Functions concerning memory issues.

29.6 File handling functions

Functions concerning input and output from and to file.

29.7 Overview

The system unit contains the standard supported functions of Free Pascal. It is the same for all platforms. Basically it is the same as the system unit provided with Borland or Turbo Pascal.

Functions are listed in alphabetical order. Arguments of functions or procedures that are optional are put between square brackets.

Table 29.4:

Name	Description
Abs (1112)	Calculate absolute value
Arctan (1115)	Calculate inverse tangent
Cos (1130)	Calculate cosine of angle
Dec (1131)	Decrease value of variable
Exp (1141)	Exponentiate
Frac (1178)	Return fractional part of floating point value
Hi (1184)	Return high byte/word of value
Inc (1186)	Increase value of variable
Int (1192)	Calculate integer part of floating point value
Ln (1195)	Calculate logarithm
Lo (1196)	Return low byte/word of value
Odd (1201)	Is a value odd or even ?
Pi (1227)	Return the value of pi
Power (1069)	Raise float to integer power
Random (1230)	Generate random number
Randomize (1231)	Initialize random number generator
Round (1237)	Round floating point value to nearest integer number
Sin (1247)	Calculate sine of angle
Sqr (1249)	Calculate the square of a value
Sqrt (1249)	Calculate the square root of a value
Swap (1253)	Swap high and low bytes/words of a variable
Trunc (1257)	Truncate a floating point value

The pre-defined constants and variables are listed in the first section. The second section contains an overview of all functions, grouped by functionality, and the last section contains the supported functions and procedures.

29.8 Constants, types and variables

29.8.1 Constants

```
AbstractErrorProc : TAbstractErrorProc = nil
```

If set, the `AbstractErrorProc` constant is used when an abstract error occurs. If it is not set, then the standard error handling is done: A stack dump is performed, and the program exits with error code 211.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
AssertErrorProc : TAssertErrorProc = @SysAssert
```

If set, the `AssertErrorProc` constant is used when an assert error occurs. If it is not set, then the standard error handling is done: The assertion error message is printed, together with the location of the assertion, and A stack dump is performed, and the program exits with error code 227.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
BackTraceStrFunc : TBackTraceStrFunc = @SysBackTraceStr
```

Table 29.5:

Name	Description
Addr (1113)	Return address of variable
Assigned (1117)	Check if a pointer is valid
CompareByte (1124)	Compare 2 memory buffers byte per byte
CompareChar (1125)	Compare 2 memory buffers byte per byte
CompareDWord (1127)	Compare 2 memory buffers byte per byte
CompareWord (1128)	Compare 2 memory buffers byte per byte
CSeg (1131)	Return code segment
Dispose (1133)	Free dynamically allocated memory
DSeg (1134)	Return data segment
FillByte (1143)	Fill memory region with 8-bit pattern
Fillchar (1144)	Fill memory region with certain character
FillDWord (1144)	Fill memory region with 32-bit pattern
Fillword (1145)	Fill memory region with 16-bit pattern
Freemem (1178)	Release allocated memory
Getmem (1180)	Allocate new memory
GetMemoryManager (1181)	Return current memory manager
High (1185)	Return highest index of open array or enumerated
IsMemoryManagerSet (1194)	Is the memory manager set
Low (1197)	Return lowest index of open array or enumerated
Move (1199)	Move data from one location in memory to another
MoveChar0 (1199)	Move data till first zero character
New (1200)	Dynamically allocate memory for variable
Ofs (1202)	Return offset of variable
Ptr (1229)	Combine segment and offset to pointer
ReAllocMem (1233)	Resize a memory block on the heap
Seg (1242)	Return segment
SetMemoryManager (1243)	Set a memory manager
Sptr (1248)	Return current stack pointer
SSeg (1250)	Return stack segment register value

This handler is called to get a standard format for the backtrace routine.

```
CmdLine : PChar = nil
```

Current command-line.

```
CtrlZMarksEOF : Boolean = false
```

CtrlZMarksEOF indicates whether on this system, an CTRL-Z character (ordinal 26) in a file marks the end of the file. This is False on most systems except on DOS.

To get DOS-compatible behaviour, this constant can be set to True

```
DefaultStackSize = 32768
```

Default size for a new thread's stack (32k by default).

```
DefaultTextLineBreakStyle : TTextLineBreakStyle = tlbsLF
```

Table 29.6:

Name	Description
Append (1114)	Open a file in append mode
Assign (1116)	Assign a name to a file
Blockread (1120)	Read data from a file into memory
Blockwrite (1121)	Write data from memory to a file
Close (1123)	Close a file
Eof (1136)	Check for end of file
Eoln (1137)	Check for end of line
Erase (1138)	Delete file from disk
Filepos (1141)	Position in file
Filesize (1142)	Size of file
Flush (1146)	Write file buffers to disk
IOresult (1193)	Return result of last file IO operation
Read (1231)	Read from file into variable
Readln (1232)	Read from file into variable and goto next line
Rename (1234)	Rename file on disk
Reset (1234)	Open file for reading
Rewrite (1236)	Open file for writing
Seek (1240)	Set file position
SeekEof (1241)	Set file position to end of file
SeekEoln (1241)	Set file position to end of line
SetTextBuf (1244)	Set size of file buffer
Truncate (1258)	Truncate the file at position
Write (1264)	Write variable to file
WriteLn (1264)	Write variable to file and append newline

`DefaultTextLineBreakStyle` contains the default OS setting for the `TTextLineBreakStyle` (1103) type. It is initialized by the system unit, and is used to determine the default line ending when writing to text files.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`DirectorySeparator = '/'`

`DirectorySeparator` is the character used by the current operating system to separate directory parts in a pathname. This constant is system dependent, and should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`DriveSeparator = ':'`

On systems that support driveletters, the `DriveSeparator` constant denotes the character that separates the drive indicator from the directory part in a filename path.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`Erroraddr : pointer = nil`

Address where the last error occurred.

Errorcode : Word = 0

Last error code.

ErrorProc : TErrorProc = nil

If set, the ErrorProc constant is used when a run-time error occurs. If it is not set, then the standard error handling is done: a stack dump is performed, and the program exits with the indicated error code.

The SysUtils unit sets this procedure and raises an exception in its handler.

ExceptProc : TExceptProc = nil

This constant points to the current exception handling procedure. This routine is called when an unhandled exception occurs, i.e. an exception that is not stopped by a except block.

If the handler is not set, the RTL will emit a run-time error 217 when an unhandler exception occurs.

It is set by the sysutils (1278) unit.

ExitProc : pointer = nil

Exit procedure pointer.

E_NOINTERFACE = HRESULT (\$80004002)

Interface call result: Error: not an interface

E_NOTIMPL = HRESULT (\$80004001)

Interface call result: Interface not implemented

E_UNEXPECTED = HRESULT (\$8000FFFF)

Interface call result: Unexpected error

Filemode : Byte = 2

Default file mode for untyped files.

FileNameCaseSensitive : Boolean = true

FileNameCaseSensitive is True if case is important when using filenames on the current OS. In this case, the OS will treat files with different cased names as different files. Note that this may depend on the filesystem: Unix operating systems that access a DOS or Windows partition will have this constant set to true, but when writing to the DOS partition, the casing is ignored.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

fmAppend = \$D7B4

File mode: File is open for writing, appending to the end.

fmClosed = \$D7B0

File mode: File is closed.

fmInOut = \$D7B3

File mode: File is open for reading and writing.

fmInput = \$D7B1

File mode: File is open for reading.

fmOutput = \$D7B2

File mode: File is open for writing.

fpc_in_abs_real = 127

FPC compiler internal procedure index: abs (real)

fpc_in_addr_x = 42

FPC compiler internal procedure index: addr

fpc_in_arctan_real = 130

FPC compiler internal procedure index: arctan (real)

fpc_in_assert_x_y = 41

FPC compiler internal procedure index: assert

fpc_in_assigned_x = 19

FPC compiler internal procedure index: assigned

fpc_in_break = 39

FPC compiler internal procedure index: break

fpc_in_chr_byte = 7

FPC compiler internal procedure index: chr

fpc_in_concat_x = 18

FPC compiler internal procedure index: concat

fpc_in_const_abs = 101

FPC compiler internal procedure index: abs

fpc_in_const_odd = 102

FPC compiler internal procedure index: sqr

fpc_in_const_ptr = 103

FPC compiler internal procedure index: sqr

fpc_in_const_sqr = 100

FPC compiler internal procedure index: sqr

fpc_in_const_swap_long = 105

FPC compiler internal procedure index: swap (long)

fpc_in_const_swap_qword = 108

FPC compiler internal procedure index: swap (qword)

fpc_in_const_swap_word = 104

FPC compiler internal procedure index: swap (word)

fpc_in_continue = 40

FPC compiler internal procedure index: continue

fpc_in_copy_x = 49

FPC compiler internal procedure index: copy

fpc_in_cos_real = 125

FPC compiler internal procedure index: cos (real)

fpc_in_cycle = 52

FPC compiler internal procedure index: cycle

fpc_in_dec_x = 36

FPC compiler internal procedure index: dec

fpc_in_dispose_x = 47

FPC compiler internal procedure index: dispose

fpc_in_exclude_x_y = 38

FPC compiler internal procedure index: exclude

fpc_in_exit = 48

FPC compiler internal procedure index: exit

fpc_in_exp_real = 124

FPC internal compiler routine: in_exp_real

fpc_in_finalize_x = 45

FPC compiler internal procedure index: finalize

fpc_in_frac_real = 122

FPC internal compiler routine: in_frac_real

fpc_in_high_x = 28

FPC compiler internal procedure index: high

fpc_in_hi_long = 4

FPC compiler internal procedure index: hi (long)

fpc_in_hi_qword = 107

FPC compiler internal procedure index: hi (qword)

fpc_in_hi_word = 2

FPC compiler internal procedure index: hi (word)

fpc_in_include_x_y = 37

FPC compiler internal procedure index: include

fpc_in_inc_x = 35

FPC compiler internal procedure index: inc

fpc_in_initialize_x = 50

FPC compiler internal procedure index: initialize

fpc_in_int_real = 123

FPC internal compiler routine: in_int_real

fpc_in_leave = 51

FPC compiler internal procedure index: leave

`fpc_in_length_string = 6`

FPC compiler internal procedure index: length

`fpc_in_ln_real = 131`

FPC compiler internal procedure index: ln (real)

`fpc_in_low_x = 27`

FPC compiler internal procedure index: low

`fpc_in_lo_long = 3`

FPC compiler internal procedure index: lo (long)

`fpc_in_lo_qword = 106`

FPC compiler internal procedure index: lo (qword)

`fpc_in_lo_word = 1`

FPC compiler internal procedure index: lo (word)

`fpc_in_mmx_pcmpeqb = 200`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpeqd = 202`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpeqw = 201`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtb = 203`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtd = 205`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtw = 204`

FPC compiler internal procedure index: MMX

`fpc_in_new_x = 46`

FPC compiler internal procedure index: new

fpc_in_ofs_x = 21

FPC compiler internal procedure index: ofs

fpc_in_ord_x = 5

FPC compiler internal procedure index: ord

fpc_in_pi_real = 126

FPC internal compiler routine: in_pi_real

fpc_in_pred_x = 30

FPC compiler internal procedure index: pred

fpc_in_prefetch_var = 109

FPC compiler internal procedure index: prefetch

fpc_in_readln_x = 17

FPC compiler internal procedure index: readln

fpc_in_read_x = 16

FPC compiler internal procedure index: read

fpc_in_reset_typedfile = 32

FPC compiler internal procedure index: reset

fpc_in_reset_x = 25

FPC compiler internal procedure index: reset

fpc_in_rewrite_typedfile = 33

FPC compiler internal procedure index: rewrite

fpc_in_rewrite_x = 26

FPC compiler internal procedure index: rewrite

fpc_in_round_real = 121

FPC internal compiler routine: in_round_real

fpc_in_seg_x = 29

FPC compiler internal procedure index: seg

fpc_in_setlength_x = 44

FPC compiler internal procedure index: setlength

fpc_in_settextbuf_file_x = 34

FPC compiler internal procedure index: settextbuf

fpc_in_sin_real = 132

FPC compiler internal procedure index: sin (real)

fpc_in_sizeof_x = 22

FPC compiler internal procedure index: sizeof

fpc_in_slice = 53

FPC internal compiler routine: in_slice

fpc_in_sqrt_real = 129

FPC compiler internal procedure index: sqrt (real)

fpc_in_sqr_real = 128

FPC compiler internal procedure index: sqr (real)

fpc_in_str_x_string = 20

FPC compiler internal procedure index: str

fpc_in_succ_x = 31

FPC compiler internal procedure index: succ

fpc_in_trunc_real = 120

FPC internal compiler routine: in_trunc_real

fpc_in_typeinfo_x = 43

FPC compiler internal procedure index: typeinfo

fpc_in_typeof_x = 23

FPC compiler internal procedure index: typeof

fpc_in_val_x = 24

FPC compiler internal procedure index: val

`fpc_in_writeln_x = 15`

FPC compiler internal procedure index: `writeln`

`fpc_in_write_x = 14`

FPC compiler internal procedure index: `write`

`growheapsize1 : PtrInt = 256 * 1024`

Grow rate for block less than 256 Kb.

`growheapsize2 : PtrInt = 1024 * 1024`

Grow rate for block larger than 256 Kb.

`growheapsize_small : PtrInt = 32 * 1024`

Fixed size small blocks grow rate

`InitProc : Pointer = nil`

`InitProc` is a routine that can be called after all units were initialized. It can be set by units to execute code that can be initialized after all units were initialized.

Remark: When setting the value of `InitProc`, the previous value should always be saved, and called when the installed initialization routine has finished executing.

`IsMultiThread : Boolean = false`

Indicates whether more than one thread is running in the application.

`LFNSupport = true`

`LFNSupport` determines whether the current OS supports long file names, i.e. filenames that are not of the form 8.3 as on ancient DOS systems. If the value of this constant is `True` then long filenames are supported. If it is false, then not.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`LineEnding = #10`

`LineEnding` is a constant which contains the current line-ending character. This character is system dependent, and is initialized by the system. It should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`maxExitCode = 255`

`maxExitCode` is the maximum value for the `Halt` (1183) call.

`maxint = maxsmallint`

Maximum integer value.

`MaxKeptOSChunks : DWord = 3`

`MaxKeptOSChunks` tells the heap manager how many free chunks of OS-allocated memory it should keep in memory. When freeing memory, it can happen that a memory block obtained from the OS is completely free. If more than `MaxKeptOSChunks` such blocks are free, then the heap manager will return them to the OS, to reduce memory requirements.

`maxLongint = $7fffffff`

Maximum longint value.

`MaxPathLen = 256`

This constant is system dependent.

`MaxSIntValue = High (ValSInt)`

Maximum String-size value.

`maxSmallint = 32767`

Maximum smallint value.

`MaxUIntValue = High (ValUInt)`

Maximum unsigned integer value.

`Max_Frame_Dump : Word = 8`

Maximum number of frames to show in error frame dump.

`PathSeparator = ':'`

`PathSeparator` is the character used commonly on the current operating system to separate paths in a list of paths, such as the `PATH` environment variable.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`RaiseMaxFrameCount : LongInt = 16`

Maximum number of frames to include in `TExceptObject` ([1100](#))

`RaiseProc : TExceptProc = nil`

Procedure to raise an exception.

`RT_ACCELERATOR = MAKEINTRESOURCE (9)`

Constant identifying an accelerator resource

RT_BITMAP = MAKEINTRESOURCE (2)

Constant identifying a bitmap resource

RT_CURSOR = MAKEINTRESOURCE (1)

Constant identifying a cursor resource

RT_DIALOG = MAKEINTRESOURCE (5)

Constant identifying a dialog resource

RT_FONT = MAKEINTRESOURCE (8)

Constant identifying a font resource

RT_FONTDIR = MAKEINTRESOURCE (7)

Constant identifying a font directory resource

RT_GROUP_CURSOR = MAKEINTRESOURCE (12)

Constant identifying a group cursor resource

RT_GROUP_ICON = MAKEINTRESOURCE (13)

Constant identifying a group icon resource

RT_ICON = MAKEINTRESOURCE (3)

Constant identifying an icon resource

RT_MENU = MAKEINTRESOURCE (4)

Constant identifying a menu resource

RT_MESSAGE_TABLE = MAKEINTRESOURCE (11)

Constant identifying a message data resource

RT_RCDATA = MAKEINTRESOURCE (10)

Constant identifying a binary data resource

RT_STRING = MAKEINTRESOURCE (6)

Constant identifying a string table resource

RT_VERSION = MAKEINTRESOURCE (16)

Constant identifying a version info resource

```
RuntimeErrorExitCodes : Array[TRuntimeError] of Byte = (0,203,204,200,201,215,207,20
```

This array is used by the Error ([1138](#)) routine to to convert a TRuntimeError ([1103](#)) enumeration type to a process exit code.

```
SIGSTKSZ = 40960
```

```
sLineBreak = LineEnding
```

sLineBreak is an alias for LineEnding ([1081](#)) and is supplied for Delphi compatibility.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
StackError : Boolean = false
```

Indicate whether there was a stack error.

```
StdErrorHandle = 2
```

Value of the OS handle for the standard error-output file.

```
StdInputHandle = 0
```

Value of the OS handle for the standard input file.

```
StdOutputHandle = 1
```

Value of the OS handle for the standard output file.

```
S_FALSE = 1
```

Interface call result: Not OK

```
S_OK = 0
```

Interface call result: OK

```
ThreadingAlreadyUsed : Boolean = false
```

Internal constant for the threading system. Don't use.

```
UnusedHandle = -1
```

Value indicating an unused file handle (as reported by the OS).

```
VarAddRefProc : procedure(var v: tvardata) = nil
```

Callback to increase reference count of a variant.

`varany = $101`

Variant type: Any

`vararray = $2000`

Variant type: variant Array

`varboolean = 11`

Variant type: Boolean type

`varbyref = $4000`

Variant type: By reference

`varbyte = 17`

Variant type: Byte (8 bit)

`VarClearProc : procedure(var v: tvardata) = nil`

Callback to clear a variant.

`VarCopyProc : procedure(var d: tvardata;const s: tvardata) = nil`

Callback to copy a variant

`varcurrency = 6`

Variant type: Currency

`vardate = 7`

Variant type: Date

`vardecimal = 14`

Variant type: Decimal (BCD)

`vardispatch = 9`

Variant type: dispatch interface

`vardouble = 5`

Variant type: Double float

`vareempty = 0`

Variant type: Empty variant

`varerror = 10`

Variant type: Error type

`varint64 = 20`

Variant type: Integer (64-Bit)

`varinteger = 3`

Variant type: Integer (32-bit)

`varlongword = 19`

Variant type: Word (32 bit)

`varnull = 1`

Variant type: Null (1110) variant

`varolestr = 8`

Variant type: OLE string (widerstring)

`varqword = 21`

Variant type: Word (64-bit)

`varshortint = 16`

Variant type: Shortint (16 bit)

`varsingle = 4`

Variant type: Single float

`varsmallint = 2`

Variant type: smallint (8 bit)

`varstrarg = $48`

Variant type: String

`varstring = $100`

Variant type: String

`VarToLStrProc : procedure (var d: AnsiString; const s: tvardata) = nil`

Callback to convert a variant to a ansistring.

`VarToWStrProc : procedure (var d: WideString; const s: tvardata) = nil`

Callback to convert a variant to a widestring.

`vartypemask = $fff`

Variant type: Mask to extract type

`varunknown = 13`

Variant type: Unknown

`varvariant = 12`

Variant type: Variant (arrays only)

`varword = 18`

Variant type: Word (16 bit)

`varword64 = varqword`

Variant type: Word (64-bit)

`vmtAfterConstruction = vmtMethodStart + sizeof (pointer) * 5`

VMt Layout: ?

`vmtAutoTable = vmtParent + sizeof (pointer) * 7`

VMt layout: ?

`vmtBeforeDestruction = vmtMethodStart + sizeof (pointer) * 6`

VMt Layout: ?

`vmtClassName = vmtParent + sizeof (pointer)`

VMt Layout: location of class name.

`vmtDefaultHandler = vmtMethodStart + sizeof (pointer) * 4`

VMt Layout: ?

`vmtDefaultHandlerStr = vmtMethodStart + sizeof (pointer) * 7`

VMt Layout: ?

`vmtDestroy = vmtMethodStart`

VMt Layout: Location of destructor pointer.

`vmtDynamicTable = vmtParent + sizeof (pointer) * 2`

VMТ Layout: location of dynamic methods table.

`vmtFieldTable = vmtParent + sizeof (pointer) * 4`

VMТ Layout: Location of fields table.

`vmtFreeInstance = vmtMethodStart + sizeof (pointer) * 2`

VMТ Layout: location of FreeInstance method.

`vmtInitTable = vmtParent + sizeof (pointer) * 6`

VMТ Layout: ?

`vmtInstanceSize = 0`

VMТ Layout: Location of class instance size in VMТ

`vmtIntfTable = vmtParent + sizeof (pointer) * 8`

VMТ layout: Interface table

`vmtMethodStart = vmtParent + sizeof (pointer) * 10`

VMТ layout: start of method table.

`vmtMethodTable = vmtParent + sizeof (pointer) * 3`

VMТ Layout: Method table start.

`vmtMsgStrPtr = vmtParent + sizeof (pointer) * 9`

VMТ layout: message strings table.

`vmtNewInstance = vmtMethodStart + sizeof (pointer)`

VMТ Layout: location of NewInstance method.

`vmtParent = sizeof (ptrint) * 2`

VMТ Layout: location of pointer to parent VMТ.

`vmtSafeCallException = vmtMethodStart + sizeof (pointer) * 3`

VMТ Layout: ?

`vmtTypeInfo = vmtParent + sizeof (pointer) * 5`

VMТ Layout: Location of class type information.

vtAnsiString = 11

TVarRec type: Ansistring

vtBoolean = 1

TVarRec type: Boolean

vtChar = 2

TVarRec type: Char

vtClass = 8

TVarRec type: Class type

vtCurrency = 12

TVarRec type: Currency

vtExtended = 3

TVarRec type: Extended

vtInt64 = 16

TVarRec type: Int64 (signed 64-bit integer)

vtInteger = 0

TVarRec type: Integer

vtInterface = 14

TVarRec type: Interface

vtObject = 7

TVarRec type: Object instance

vtPChar = 6

TVarRec type: PChar

vtPointer = 5

TVarRec type: pointer

vtPWideChar = 10

TVarRec type: PWideChar

`vtQWord = 17`

TVarRec type: QWord (unsigned 64-bit integer)

`vtString = 4`

TVarRec type: String

`vtVariant = 13`

TVarRec type: Variant

`vtWideChar = 9`

TVarRec type: Widechar

`vtWideString = 15`

TVarRec type: WideString

29.8.2 Types

`AnsiChar = Char`

Alias for 1-byte sized char.

`Cardinal = LongWord`

An unsigned 32-bits integer.

`DWord = LongWord`

An unsigned 32-bits integer

`fpc_big_chararray = Array[0..1023] of Char`

Array of char.

`fpc_big_widechararray = Array[0..1023] of widechar`

Internal type used by widestring routines. Do not use

`fpc_normal_set = Array[0..7] of LongInt`

Type with the size of a normal set

`fpc_small_set = LongInt`

Type with the size of a small set

HGLOBAL = Cardinal

This is an opaque type.

HMODULE = Cardinal

This is an opaque type.

HRESULT = LongInt

32-Bit signed integer.

IInterface = IUnknown

IInterface is the basic interface from which all COM style interfaces descend.

Integer = SmallInt

The system unit defines `Integer` as a signed 16-bit integer. But when DELPHI or OBJFPC mode are active, then the `objpas` unit redefines `Integer` as a 16-bit integer.

IntegerArray = Array[0..\$effffff] of Integer

Generic array of integer.

```
jmp_buf = packed record
  ebx : LongInt;
  esi : LongInt;
  edi : LongInt;
  bp  : Pointer;
  sp  : Pointer;
  pc  : Pointer;
end
```

Record type to store processor information.

MAKEINTRESOURCE = PChar

Alias for the PChar ([1092](#)) type.

PAnsiChar = PChar

Alias for PChar ([1092](#)) type.

PAnsiString = ^AnsiString

Pointer to an ansistring type.

PBoolean = ^Boolean

Pointer to a Boolean type.

```
PByte = ^Byte
```

Pointer to byte (1069) type

```
pcallldesc = ^tcallldesc
```

Pointer to TCallDesc (1098) record.

```
PCardinal = ^Cardinal
```

Pointer to Cardinal (1090) type

```
PChar = ^Char
```

Or the same as a pointer to an array of char. See the reference manual for more information about this type.

```
PClass = ^TClass
```

Pointer to TClass (1098)

```
PCurrency = ^Currency
```

Pointer to currency type.

```
PDate = ^TDateTime
```

Pointer to a TDateTime (1099) type.

```
PDispatch = ^IDispatch
```

Pointer to IDispatch (1265) interface type

```
pdispdesc = ^tdispdesc
```

Pointer to tdispdesc (1099) record

```
PDouble = ^Double
```

Pointer to double-sized float value.

```
PDWord = ^DWord
```

Pointer to DWord (1090) type

```
pdynarrayindex = ^tdynarrayindex
```

Pointer to tdynarrayindex (1099) type.

`pdynarraytypeinfo = ^tdynarraytypeinfo`

Pointer to TDynArrayTypeInfo (1099) type.

`PError = ^TError`

Pointer to an Error (1138) type.

`PEventState = pointer`

Pointer to EventState, which is an opaque type.

`PExceptObject = ^TExceptObject`

Pointer to Exception handler procedural type TExceptProc (1100)

`PExtended = ^Extended`

Pointer to extended-sized float value.

`PGuid = ^TGuid`

Pointer to TGUID (1100) type.

`PInt64 = ^Int64`

Pointer to Int64 type

`PInteger = ^Integer`

Pointer to integer (1091) type

`PIntegerArray = ^IntegerArray`

Pointer to IntegerArray (1091) type

`pinterfaceentry = ^tinterfaceentry`

Pointer to tinterfaceentry (1101) record.

`pinterfacetable = ^tinterfacetable`

Pointer to tinterfacetable (1101) record.

`PJump_buf = ^jmp_buf`

Pointer to jmp_buf (1091) record

`PLongBool = ^LongBool`

Pointer to a LongBool type.

PLongint = ^LongInt

Pointer to Longint (1069) type

PLongWord = ^LongWord

Pointer to LongWord type

PMemoryManager = ^TMemoryManager

Pointer to TMemoryManager (1101) record

PMsgStrTable = ^TMsgStrTable

Pointer to array of TMsgStrTable (1102) records.

PointerArray = Array[0..512*1024*1024-2] of Pointer

Generic pointer array.

PoleVariant = ^OleVariant

Pointer to OleVariant type.

PPAnsiChar = PPChar

Alias for PPChar (1094) type.

PPChar = ^PChar

Pointer to an array of pointers to null-terminated strings.

PPCharArray = ^TPCharArray

Pointer to TPCharArray (1102) type.

PPDispatch = ^PDispatch

Pointer to PDispatch (1092) pointer type

PPointer = ^Pointer

Pointer to a pointer type.

PPointerArray = ^PointerArray

Pointer to PointerArray (1094) type

PPPointer = ^PPointer

Pointer to a PPointer (1094) type.

`PPtrInt = ^PtrInt`

Pointer to `PtrInt` (1096) type.

`PPUnknown = ^PUnknown`

Pointer to untyped pointer

`PPWideChar = ^PWideChar`

Pointer to link id="PWideChar"> type.

`PQWord = ^QWord`

Pointer to `QWord` type

`PRTLCriticalSection = ^RTLCriticalSection`

Pointer to `#rtl.system.RTLCriticalSection` (1102) type.

`PRTLEvent = pointer`

Pointer to `RTLEvent`, which is an opaque type.

`PShortInt = ^ShortInt`

Pointer to `shortint` (1069) type

`PShortString = ^ShortString`

Pointer to a `shortstring` type.

`PSingle = ^Single`

Pointer to single-sized float value.

`PSizeInt = ^SizeInt`

Pointer to a `SizeInt` (1097) type

`PSmallInt = ^SmallInt`

Pointer to `smallint` (1069) type

`pstringmessagetable = ^TStringMessageTable`

Pointer to `TStringMessageTable` (1103) record.

`PText = ^Text`

Pointer to text file.

`PtrInt = LongInt`

`PtrInt` is an integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular integer type.

`PtrUInt = DWord`

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular Cardinal type.

`PUCS2Char = PWideChar`

Pointer to UCS2Char (1109) character.

`PUCS4Char = ^UCS4Char`

Pointer to UCS4Char (1109)

`PUCS4CharArray = ^TUCS4CharArray`

Pointer to array of UCS4Char (1109) characters.

`PUnknown = ^IUnknown`

Untyped pointer

`PUTF8String = ^UTF8String`

Pointer to UTF8String (1109)

`pvararray = ^tvararray`

Pointer to TVarArray (1106) type.

`pvararraybound = ^tvararraybound`

Pointer to tvararraybound (1106) type.

`pvararrayboundarray = ^tvararrayboundarray`

Pointer to tvararrayboundarray (1106) type.

`pvararraycoorarray = ^tvararraycoorarray`

Pointer to tvararraycoorarray (1106) type.

`pvardata = ^tvardata`

Pointer to TVarData (1106) record.

`PVariant = ^Variant`

Pointer to Variant type.

```
pvariantmanager = ^tvariantmanager
```

Pointer to TVariantManager (1107) record.

```
PVarRec = ^TVarRec
```

Pointer to TVarRec (1107) type.

```
PWideChar = ^WideChar
```

Pointer to WChar (1109).

```
PWideString = ^WideString
```

Pointer to widestring type

```
PWord = ^Word
```

Pointer to word (1069) type

```
PWordBool = ^WordBool
```

Pointer to a WordBool type.

```
real48 = Array[0..5] of Byte
```

TP compatible real type (6 bytes) definition

```
SizeInt = LongInt
```

Signed integer type which fits for sizes

```
SizeUInt = DWord
```

Unsigned Integer type which fits for sizes

```
TAbstractErrorProc = procedure
```

Abstract error handler procedural type.

```
TAllocateThreadVarsHandler = procedure
```

Threadvar allocation callback type for TThreadManager (1105).

```
TAnsiChar = Char
```

Alias for 1-byte sized char.

```
TAssertErrorProc = procedure(const msg: ShortString;
                             const fname: ShortString;lineno: LongInt;
                             erroraddr: pointer)
```

Assert error handler procedural type.

```
TBackTraceStrFunc = function(Addr: Pointer) : ShortString
```

Type for formatting of backtrace dump.

```
TBasicEventCreateHandler = function(EventAttributes: Pointer;
                                    AManualReset: Boolean;
                                    InitialState: Boolean;
                                    const Name: ansistring)
                             : PEventState
```

callback type for creating eventstate in TThreadManager (1105).

```
TBasicEventHandler = procedure(state: PEventState)
```

Generic callback type for handling eventstate in TThreadManager (1105).

```
TBasicEventWaitForHandler = function(timeout: Cardinal;
                                     state: PEventState) : LongInt
```

Wait for basic event callback type for TThreadManager (1105).

```
TBeginThreadHandler = function(sa: Pointer;stacksize: PtrUInt;
                               ThreadFunction: TThreadFunc;p: pointer;
                               creationFlags: DWord;
                               var ThreadId: TThreadID) : TThreadID
```

Callback for thread start in TThreadManager (1105).

```
TBoundArray = Array[] of SizeInt
```

Dynamic array of integer.

```
tcalldesc = packed record
  calltype : Byte;
  argcount : Byte;
  namedargcount : Byte;
  argtypes : Array[0..255] of Byte;
end
```

tcalldesc is used to encode the arguments to a dispatch call to an OLE dual interface. It is used on windows only. It describes the arguments to a call.

```
TClass = Class of TObject
```

Class of TObject (1268).

```
TCriticalSectionHandler = procedure(var cs)
```

Generic callback type for critical section handling in TThreadManager ([1105](#)).

```
TDateTime = Double
```

Encoded Date-Time type.

```
tdispdesc = packed record
  dispid : LongInt;
  restype : Byte;
  calldesc : tcalldesc;
end
```

tcalldesc is used to encode a dispatch call to an OLE dispatch interface. It is used on windows only. It describes the dispatch call call.

```
tdynarrayindex = SizeInt
```

A variable of type tdynarrayindex will always have the correct size, suitable for serving as an index in a dynamic array.

```
tdynarraytypeinfo = packed record
  kind : Byte;
  namelen : Byte;
  elesize : SizeInt;
  eletype : pdynarraytypeinfo;
  vartype : LongInt;
end
```

tdynarraytypeinfo describes the structure of a multi-dimensional dynamical array. It is used in the DynArraySetLength ([1135](#)) call.

```
TEndThreadHandler = procedure(ExitCode: DWord)
```

Callback for thread end in TThreadManager ([1105](#)).

```
TError = LongInt
```

Error type, used in variants.

```
TErrorProc = procedure(ErrNo: LongInt;Address: Pointer;Frame: Pointer)
```

Standard error handler procedural type.

```
TExceptObject = record
  FObject : TObject;
  Addr : pointer;
  Next : PExceptObject;
  refcount : LongInt;
  Framecount : LongInt;
  Frames : PPointer;
end
```


TExceptObject is the exception description record which is found on the exception stack.

```
TExceptProc = procedure (Obj: TObject; Addr: Pointer; FrameCount: LongInt;
                        Frame: PPointer)
```

Exception handler procedural type

```
TextFile = Text
```

Alias for Text file type.

```
TFPCHeapStatus = record
    MaxHeapSize : PtrInt;
    MaxHeapUsed : PtrInt;
    CurrHeapSize : PtrInt;
    CurrHeapUsed : PtrInt;
    CurrHeapFree : PtrInt;
end
```

TFPCHeapStatus describes the state of the FPC heap manager. This is not equivalent to the THeapStatus (1101) record defined by Delphi, which contains information not meaningful for the FPC heap manager. The heap status can be retrieved by the GetFPCHeapStatus (1180) call.

```
TGetCurrentThreadIdHandler = function : TThreadId
```

Callback type for retrieving thread ID in TThreadManager (1105).

```
TGuid = packed record
end
```

Standard GUID representation type.

```
THandle = LongInt
```

This type should be considered opaque. It is used to describe file and other handles.

```
THeapStatus = record
    TotalAddrSpace : Cardinal;
    TotalUncommitted : Cardinal;
    TotalCommitted : Cardinal;
    TotalAllocated : Cardinal;
    TotalFree : Cardinal;
    FreeSmall : Cardinal;
    FreeBig : Cardinal;
    Unused : Cardinal;
    Overhead : Cardinal;
    HeapErrorCode : Cardinal;
end
```

THeapStatus is the record describing the current heap status. It is returned by the GetHeapStatus (1180) call.

```
TInitThreadVarHandler = procedure (var offset: DWord; size: DWord)
```

Threadvar initialization callback type for TThreadManager (1105).

```
TInterfacedClass = Class of TInterfacedObject
```

TInterfacedClass is a descendent of

```
tinterfaceentry = packed record
  IID : PGuid;
  VTable : Pointer;
  IOffset : DWord;
  IIDStr : PShortString;
end
```

tinterfaceentry is used to store the list of Interfaces of a class. This list is stored as an array of tinterfaceentry records.

```
tinterfacetable = packed record
  EntryCount : Word;
  Entries : Array[0..0] of tinterfaceentry;
end
```

Record to store list of interfaces of a class.

```
TMemoryManager = record
  NeedLock : Boolean;
  Getmem : function(Size: PtrInt) : Pointer;
  Freemem : function(p: pointer) : PtrInt;
  FreememSize : function(p: pointer; Size: PtrInt) : PtrInt;
  AllocMem : function(Size: PtrInt) : Pointer;
  ReAllocMem : function(var p: pointer; Size: PtrInt) : Pointer;
  MemSize : function(p: pointer) : PtrInt;
  GetHeapStatus : function : THeapStatus;
  GetFPCHeapStatus : function : TFPCHeapStatus;
end
```

TMemoryManager describes the memory manager. For more information about the memory manager, see the programmer's reference.

```
TMemoryMutexManager = record
  MutexInit : procedure;
  MutexDone : procedure;
  MutexLock : procedure;
  MutexUnlock : procedure;
end
```

When the heapmanager needs a lock, then the mutex manager is used to handle the lock.

```
TMethod = record
    Code : Pointer;
    Data : Pointer;
end
```

TMethod describes a general method pointer, and is used in Run-Time Type Information handling.

```
TMsgStrTable = record
    name : PShortString;
    method : pointer;
end
```

Record used in string message handler table.

```
TPCharArray = packed Array[0..(MaxLongintdivSizeOf(PChar))-1] of PChar
```

Array of PChar

```
TProcedure = procedure
```

Simple procedural type.

```
TReleaseThreadVarsHandler = procedure
```

Threadvar release callback type for TThreadManager (1105).

```
TRelocateThreadVarHandler = function(offset: DWord) : pointer
```

Threadvar relocation callback type for TThreadManager (1105).

```
TResourceHandle = Cardinal
```

This is an opaque type.

```
TRTLCreateEventHandler = function : PRTLEvent
```

Callback type for creating a TRTLEvent type in TThreadManager (1105).

```
TRTLCriticalSection = Opaque type
```

TRTLCriticalSection represents a critical section (a mutex). This is an opaque type, it can differ from operating system to operating system. No assumptions should be made about it's structure or contents.

```
TRTLEventHandler = procedure(AEvent: PRTLEvent)
```

Generic TRTLEvent handling type for TThreadManager (1105).

TRTLEventHandlerTimeout = procedure(AEvent: PRTLEvent; timeout: LongInt)

TRTLEvent timeout handling type for TThreadManager (1105).

TRTLEventSyncHandler = procedure(m: trtlmethod; p: TProcedure)

Callback type for event synchronization in TThreadManager (1105).

trtlmethod = procedure of object

Callback type for synchronization event.

```
TRuntimeError = (reNone, reOutOfMemory, reInvalidPtr, reDivByZero,
  reRangeError, reIntOverflow, reInvalidOp, reZeroDivide,
  reOverflow, reUnderflow, reInvalidCast, reAccessViolation,
  rePrivInstruction, reControlBreak, reStackOverflow,
  reVarTypeCast, reVarInvalidOp, reVarDispatch,
  reVarArrayCreate, reVarNotArray, reVarArrayBounds,
  reAssertionFailed, reExternalException, reIntfCastError,
  reSafeCallError, reQuit, reCodesetConversion)
```

TRuntimeError is used in the Error (1138) procedure to indicate what kind of error should be reported.

```
TStringMessageTable = record
  count : DWord;
  msgstrtable : Array[0..0] of TMsgStrTable;
end
```

Record used to describe the string messages handled by a class. It consists of a count, followed by an array of TMsgStrTable (1102) records.

TTextLineBreakStyle = (tlbsLF, tlbsCRLF, tlbsCR)

Text line break style. (end of line character)

TThreadFunc = function(parameter: pointer) : PtrInt

Thread function prototype

TThreadGetPriorityHandler = function(threadHandle: TThreadID) : LongInt

Callback type for thread priority getting in TThreadManager (1105).

TThreadHandler = function(threadHandle: TThreadID) : DWord

Generic thread handler callback for TThreadManager (1105).

TThreadID = THandle

Table 29.7: Enumeration values for type TRuntimeError

Value	Explanation
reAccessViolation	Access Violation
reAssertionFailed	Assertion failed error
reCodesetConversion	Code set conversion error
reControlBreak	User pressed CTRL-C
reDivByZero	Division by zero error
reExternalException	An external exception occurred
reIntfCastError	Interface typecast error
reIntOverflow	Integer overflow error
reInvalidCast	Invalid (class) typecast error
reInvalidOp	Invalid operation error
reInvalidPtr	Invalid pointer error
reNone	No error
reOutOfMemory	Out of memory error
reOverflow	Overflow error
rePrivInstruction	Privileged instruction error
reQuit	Quit signal error
reRangeError	Range check error
reSafeCallError	Safecall (IDispInterface) error
reStackOverflow	Stack overflow error
reUnderflow	Underflow error
reVarArrayBounds	Variant array bounds error
reVarArrayCreate	Variant array creation error
reVarDispatch	Variant Dispatch error.
reVarInvalidOp	Invalid variant operation error
reVarNotArray	Variant is not an array error.
reVarTypeCast	Invalid typecase from variant
reZeroDivide	Division by zero error

This is an opaque type, it can differ from operating system to operating system.

```

TThreadManager = record
  InitManager : function : Boolean;
  DoneManager : function : Boolean;
  BeginThread : TBeginThreadHandler;
  EndThread : TEndThreadHandler;
  SuspendThread : TThreadHandler;
  ResumeThread : TThreadHandler;
  KillThread : TThreadHandler;
  ThreadSwitch : TThreadSwitchHandler;
  WaitForThreadTerminate : TWaitForThreadTerminateHandler;
  ThreadSetPriority : TThreadSetPriorityHandler;
  ThreadGetPriority : TThreadGetPriorityHandler;
  GetCurrentThreadId : TGetCurrentThreadIdHandler;
  InitCriticalSection : TCriticalSectionHandler;
  DoneCriticalSection : TCriticalSectionHandler;
  EnterCriticalSection : TCriticalSectionHandler;
  LeaveCriticalSection : TCriticalSectionHandler;
  InitThreadVar : TInitThreadVarHandler;
  RelocateThreadVar : TRelocateThreadVarHandler;

```

Table 29.8: Enumeration values for type `TTextLineBreakStyle`

Value	Explanation
<code>tlbsCR</code>	Carriage-return (#13, Mac-OS style)
<code>tlbsCRLF</code>	Carriage-return, line-feed (#13#30, Windows style)
<code>tlbsLF</code>	Line-feed only (#10, unix style)

```

AllocateThreadVars : TAllocateThreadVarsHandler;
ReleaseThreadVars : TReleaseThreadVarsHandler;
BasicEventCreate : TBasicEventCreateHandler;
BasicEventDestroy : TBasicEventHandler;
BasicEventResetEvent : TBasicEventHandler;
BasicEventSetEvent : TBasicEventHandler;
BasicEventWaitFor : TBasicEventWaitForHandler;
RTLEventCreate : TRTLEventCreateHandler;
RTLEventDestroy : TRTLEventHandler;
RTLEventSetEvent : TRTLEventHandler;
RTLEventResetEvent : TRTLEventHandler;
RTLEventStartWait : TRTLEventHandler;
RTLEventWaitFor : TRTLEventHandler;
RTLEventSync : TRTLEventSyncHandler;
RTLEventWaitForTimeout : TRTLEventHandlerTimeout;
end

```

`TThreadManager` is a record that contains all callbacks needed for the thread handling routines of the Free Pascal Run-Time Library. The thread manager can be set by the `SetThreadManager` (1246) procedure, and the current thread manager can be retrieved with the `GetThreadManager` (1182) procedure.

The Windows RTL will set the thread manager automatically to a system thread manager, based on the Windows threading routines. Unix operating systems provide a unit `cthreads` which implements threads based on the C library POSIX thread routines. It is not included by default, because it would make the system unit dependent on the C library.

For more information about thread programming, see the programmer's guide.

```

TThreadSetPriorityHandler = function(threadHandle: TThreadID;
                                   Prio: LongInt) : Boolean

```

Callback type for thread priority setting in `TThreadManager` (1105).

```

TThreadSwitchHandler = procedure

```

Callback type for thread switch in `TThreadManager` (1105).

```

TUCS4CharArray = Array[0..$efffffff] of UCS4Char

```

Array of `UCS4Char` (1109) characters.

```

tvararray = packed record
  dimcount : Word;

```

```

    flags : Word;
    elementsize : PtrInt;
    lockcount : LongInt;
    data : pointer;
    bounds : tvararrayboundarray;
end

```

tvararray is a record describing a variant array. It contains some general data, followed by a number of TVarArrayBound (1106) records equal to the number of dimensions in the array (dimcount).

```

tvararraybound = packed record
    elementcount : SizeInt;
    lowbound : SizeInt;
end

```

tvararraybound is used to describe one dimension in a variant array.

```

tvararrayboundarray = Array[0..0] of tvararraybound

```

array of tvararraybound (1106) records.

```

tvararraycoorarray = Array[0..0] of SizeInt

```

Array of variant array coordinates

```

tvardata = packed record
    vtype : tvartype;
end

```

TVarData is a record representation of a variant. It contains the internal structure of a variant and is handled by the various variant handling routines.

```

tvariantmanager = record
    vartoint : function(const v: variant) : LongInt;
    vartoint64 : function(const v: variant) : Int64;
    vartoword64 : function(const v: variant) : qword;
    vartobool : function(const v: variant) : Boolean;
    vartoreal : function(const v: variant) : extended;
    vartotdatetime : function(const v: variant) : TDateTime;
    vartocurr : function(const v: variant) : currency;
    vartopstr : procedure(var s; const v: variant);
    vartolstr : procedure(var s: ansistring; const v: variant);
    vartowstr : procedure(var s: widestring; const v: variant);
    vartointf : procedure(var intf: IInterface; const v: variant);
    vartodisp : procedure(var disp: IDispatch; const v: variant);
    vartodynarray : procedure(var dynarr: pointer; const v: variant; typeinfo: pointer);
    varfrombool : procedure(var dest: variant; const source: Boolean);
    varfromint : procedure(var dest: variant; const source: LongInt; const Range: LongInt);
    varfromint64 : procedure(var dest: variant; const source: Int64);

```

```

varfromword64 : procedure(var dest: variant;const source: qword);
varfromreal : procedure(var dest: variant;const source: extended);
varfromdatetime : procedure(var dest: Variant;const source: TDateTime);
varfromcurr : procedure(var dest: Variant;const source: Currency);
varfrompstr : procedure(var dest: variant;const source: ShortString);
varfromlstr : procedure(var dest: variant;const source: ansistring);
varfromwstr : procedure(var dest: variant;const source: WideString);
varfromintf : procedure(var dest: variant;const source: IInterface);
varfromdisp : procedure(var dest: variant;const source: IDispatch);
varfromdynarray : procedure(var dest: variant;const source: pointer;typeinfo: poin
olevarfrompstr : procedure(var dest: olevariant;const source: shortstring);
olevarfromlstr : procedure(var dest: olevariant;const source: ansistring);
olevarfromvar : procedure(var dest: olevariant;const source: variant);
olevarfromint : procedure(var dest: olevariant;const source: LongInt;
    const range: ShortInt);
varop : procedure(var left: variant;const right: variant;opcode: tvarop);
cmpop : function(const left: variant;const right: variant;const opcode: tvarop)
    : Boolean;
varneg : procedure(var v: variant);
varnot : procedure(var v: variant);
varinit : procedure(var v: variant);
varclear : procedure(var v: variant);
varaddref : procedure(var v: variant);
varcopy : procedure(var dest: variant;const source: variant);
varcast : procedure(var dest: variant;const source: variant;vartype: LongInt);
varcastole : procedure(var dest: variant;const source: variant;vartype: LongInt);
dispinvoke : procedure(dest: pvardata;const source: tvardata;calldesc: pcalldesc;
    params: pointer);
vararrayredim : procedure(var a: variant;highbound: SizeInt);
vararrayget : function(const a: variant;indexcount: SizeInt;indices: PSizeInt)
    : variant;
vararrayput : procedure(var a: variant;const value: variant;indexcount: SizeInt;
    indices: PSizeInt);
writevariant : function(var t: text;const v: variant;width: LongInt) : Pointer;
write0Variant : function(var t: text;const v: Variant) : Pointer;
end

```

TVariantManager describes the variant manager as expected by the SetVariantManager (1246) call.

```

tvarop = (opadd,opsubtract,opmultiply,opdivide,opintdivide,opmodulus,
    opshiftleft,opshiftright,opand,opor,opxor,opcompare,opnegate,
    opnot,opcmpeq,opcmpne,opcmplt,opcmple,opcmpgt,opcmpge,oppower)

```

tvarop describes a variant operation. It is mainly used for the variant manager to implement the various conversions and mathematical operations on a variant.

```

TVarRec = record
end

```

TVarRec is a record generated by the compiler for each element in a array of const call. The procedure that receives the constant array receives an array of TVarRec elements, with lower

Table 29.9: Enumeration values for type tvarop

Value	Explanation
opadd	Variant operation: Addition.
opand	Variant operation: Binary AND operation
opcmpeq	Variant operation: Compare equal.
opcmpge	Variant operation: Compare larger than or equal
opcmpgt	Variant operation: Compare larger than
opcmple	Variant operation: Compare less than or equal to
opcmplt	Variant operation: Compare less than.
opcmpne	Variant operation: Compare not equal
opcompare	Variant operation: Compare
opdivide	Variant operation: division
opintdivide	Variant operation: integer divide
opmodulus	Variant operation: Modulus
opmultiply	Variant operation: multiplication
opnegate	Variant operation: negation.
opnot	Variant operation: Binary NOT operation.
opor	Variant operation: Binary OR operation
oppower	Variant operation: Power
opshiftright	Variant operation: Shift left
opshiftright	Variant operation: Shift right
opsubtract	Variant operation: Substraction
opxor	Variant operation: binary XOR operation.

bound zero and high bound equal to the number of elements in the array minus one (as returned by High (Args))

tvartype = Word

Type with size of variant type.

```
TWaitForThreadTerminateHandler = function(threadHandle: TThreadID;
                                           TimeoutMs: LongInt) : DWord
```

Callback type for thread termination in TThreadManager (1105).

```
TWideStringManager = record
  Wide2AnsiMoveProc : procedure(source: PWideChar;var dest: ansistring;len: SizeInt)
  Ansi2WideMoveProc : procedure(source: PChar;var dest: widestring;len: SizeInt);
  UpperWideStringProc : function(const S: WideString) : WideString;
  LowerWideStringProc : function(const S: WideString) : WideString;
  CompareWideStringProc : function(const s1: WideString;const s2: WideString) : PtrInt;
  CompareTextWideStringProc : function(const s1: WideString;const s2: WideString) : PtrInt;
  CharLengthPCharProc : function(const Str: PChar) : PtrInt;
  UpperAnsiStringProc : function(const s: ansistring) : ansistring;
  LowerAnsiStringProc : function(const s: ansistring) : ansistring;
  CompareStrAnsiStringProc : function(const S1: ansistring;const S2: ansistring) : PtrInt;
  CompareTextAnsiStringProc : function(const S1: ansistring;const S2: ansistring) : PtrInt;
  StrCompAnsiStringProc : function(S1: PChar;S2: PChar) : PtrInt;
  StrICompAnsiStringProc : function(S1: PChar;S2: PChar) : PtrInt;
```

```

    StrLCompAnsiStringProc : function(S1: PChar;S2: PChar;MaxLen: PtrUInt) : PtrInt;
    StrLICompAnsiStringProc : function(S1: PChar;S2: PChar;MaxLen: PtrUInt) : PtrInt;
    StrLowerAnsiStringProc : function(Str: PChar) : PChar;
    StrUpperAnsiStringProc : function(Str: PChar) : PChar;
end

```

TWideStringManager contains the definition of the widestring manager.

UCS2Char = WideChar

UCS2 unicode character.

UCS4Char = LongWord

UCS unicode character (unsigned 32 bit word)

UCS4String = Array[] of UCS4Char

String of UCS4Char ([1109](#)) characters.

UTF8String = ansistring

UTF-8 unicode (ansi) string.

ValSInt = LongInt

Integer with teh same size as the return code of the Val ([1261](#)) function.

ValUInt = Cardinal

Integer with teh same size as the return code of the Val ([1261](#)) function.

WChar = Widechar

Wide char (16-bit sized char)

29.8.3 Variables

argc : LongInt;external name operatingsystem_parameter_argc

argc contains the number of command-line arguments passed to the program by the OS. It is not available on all systems.

argv : PPChar;external name operatingsystem_parameter_argv

argv contains a pointer to a nil-terminated array of null-terminated strings, containing the command-line arguments passed to the program by the OS. It is not available on all systems.

DispCallByIDProc : pointer

VarDispProc is called by the compiler if it needs to perform an interface call from a variant which contains a dispatch interface. For instance, the following call:

```
Var
  V : OleVariant;
begin
  (V as IWord).OpenDocument('c:\temp\mydoc.doc');
end;
```

where IWord is a dispatch interface is encoded by the compiler and passed to DispCallByIDProc. This pointer must be set by a routine that calls the OS COM handling routines.

envp : PPChar;external name operatingsystem_parameter_envp

envp contains a pointer to a nil-terminated array of null-terminated strings, containing the environment variables passed to the program by the OS. It is not available on all systems.

ErrOutput : Text

ErrOutput is provided for Delphi compatibility.

ExitCode : Word;public name operatingsystem_result

Exit code for the program, will be communicated to the OS on exit.

fpc_threadvar_relocate_proc : pointer;public name FPC_THREADVAR_RELOCATE

InOutRes : Word

Result of last I/O operation. Read-Only.

Input : Text

Standard input text file.

IsConsole : Boolean

True for console applications, False for GUI applications.

IsLibrary : Boolean

True if the current module is a library. Otherwise module is an executable

Null : Variant

Null variant

Output : Text

Standard output text file.

`RandSeed : Cardinal`

Seed for Random (1230) function.

`ReturnNilIfGrowHeapFails : Boolean`

`ReturnNilIfGrowHeapFails` describes what happens if there is no more memory available from the operating system. if set to `True` the memory manager will return `Nil`. If set to `False` then a run-time error will occur.

`StackBottom : Pointer`

Current stack bottom.

`StackLength : SizeUInt`

Maximum stack length.

`StdErr : Text`

Standard diagnostic output text file.

`StdOut : Text`

Alias for Output (1110).

`ThreadID : TThreadID`

Current Thread ID.

`Unassigned : Variant`

Unassigned variant.

`VarDispProc : pointer`

`VarDispProc` is called by the compiler if it needs to perform an interface call from a variant. For instance, the following call:

```
Var
  V : OleVariant;
begin
  V.OpenDocument('c:\temp\mydoc.doc');
end;
```

is encoded by the compiler and passed to `VarDispProc`.

This pointer must be set by a routine that calls the OS COM handling routines.

`widestringmanager : TWideStringManager`

Contains the current widestring manager. Do not use directly.

29.9 Procedures and functions

29.9.1 abs

Synopsis: Calculate absolute value

Declaration: `function abs(l: LongInt) : LongInt`
`function abs(l: Int64) : Int64`
`function abs(d: ValReal) : ValReal`

Visibility: default

Description: `Abs` returns the absolute value of a variable. The result of the function has the same type as its argument, which can be any numerical type.

Errors: None.

See also: `Round` ([1237](#))

Listing: `./refex/ex1.pp`

```

Program Example1;

{ Program to demonstrate the Abs function. }

Var
  r : real;
  i : integer;

begin
  r:=abs(-1.0);    { r:=1.0 }
  i:=abs(-21);     { i:=21 }
end.

```

29.9.2 AbstractError

Synopsis: Generate an abstract error.

Declaration: `procedure AbstractError`

Visibility: default

Description: `AbstractError` generates an abstract error (run-time error 211). If the `AbstractErrorProc` ([1071](#)) constant is set, it will be called instead.

Errors: This routine causes a run-time error 211.

See also: `AbstractErrorProc` ([1071](#))

29.9.3 AcquireExceptionObject

Synopsis: Obtain a reference to the current exception object

Declaration: `function AcquireExceptionObject : Pointer`

Visibility: default

Description: `AcquireExceptionObject` returns the current exception object. It raises the reference count of the exception object, so it will not be freed. Calling this method is only valid within an `except` block.

The effect of this function is countered by re-raising an exception via `raise`;

To make sure that the exception object is released when it is no longer needed, `ReleaseExceptionObject` (1234) must be called when the reference is no longer needed.

Errors: If there is no current exception, a run-time error 231 will occur.

See also: `ReleaseExceptionObject` (1234)

29.9.4 AddExitProc

Synopsis: Add an exit procedure to the exit procedure chain.

Declaration: `procedure AddExitProc(Proc: TProcedure)`

Visibility: `default`

Description: `AddExitProc` adds `Proc` to the exit procedure chain. At program exit, all procedures added in this way will be called in reverse order.

Errors: None.

See also: `ExitProc` (1074)

29.9.5 Addr

Synopsis: Return address of a variable

Declaration: `function Addr(X: TAnytype) : Pointer`

Visibility: `default`

Description: `Addr` returns a pointer to its argument, which can be any type, or a function or procedure name. The returned pointer isn't typed. The same result can be obtained by the `@` operator, which can return a typed pointer (`\progref`).

Errors: None

See also: `SizeOf` (1247)

Listing: `./refex/ex2.pp`

Program `Example2`;

{ Program to demonstrate the Addr function. }

Const `Zero : integer = 0;`

Var `p : pointer;`
 `i : Integer;`

begin
 `p:=Addr(p);` *{ P points to itself }*
 `p:=Addr(1);` *{ P points to 1 }*
 `p:=Addr(Zero);` *{ P points to 'Zero' }*
end.

29.9.6 Align

Synopsis: Return aligned version of an address

Declaration: `function Align (Addr: PtrInt; Alignment: PtrInt) : PtrInt`
`function Align (Addr: Pointer; Alignment: PtrInt) : Pointer`

Visibility: default

Description: `Align` returns `Address`, aligned to `Alignment` bytes.

Errors: None.

29.9.7 AllocMem

Synopsis: Alias for `GetMem` ([1180](#))

Declaration: `function AllocMem (Size: PtrInt) : pointer`

Visibility: default

Description: `AllocMem` is an alias for `GetMem` ([1180](#)).

See also: `GetMem` ([1180](#))

29.9.8 AnsiToUtf8

Synopsis: Convert ansi string to UTF-8 string

Declaration: `function AnsiToUtf8 (const s: ansistring) : UTF8String`

Visibility: default

Description: `AnsiToUtf8` converts the `ansistring` `S` to a `WideString` in UTF-8 format.

Errors: None.

See also: `Utf8toAnsi` ([1261](#))

29.9.9 Append

Synopsis: Open a file in append mode

Declaration: `procedure Append (var t: Text)`

Visibility: default

Description: `Append` opens an existing file in append mode. Any data written to `F` will be appended to the file. Only text files can be opened in append mode. After a call to `Append`, the file `F` becomes write-only. File sharing is not taken into account when calling `Append`.

Errors: If the file doesn't exist when appending, a run-time error will be generated. This behaviour has changed on Windows and Linux platforms, where in versions prior to 1.0.6, the file would be created in append mode.

See also: `Rewrite` ([1236](#)), `Close` ([1123](#)), `Reset` ([1234](#))

Listing: `./refex/ex3.pp`

Program Example3;

{ Program to demonstrate the Append function. }

Var f : text;

begin

Assign (f, 'test.txt');

Rewrite (f); *{ file is opened for write , and emptied }*

WriteLn (F, 'This is the first line of text.txt');

close (f);

Append(f); *{ file is opened for write , but NOT emptied.
any text written to it is appended. }*

WriteLn (f, 'This is the second line of text.txt');

close (f);

end.

29.9.10 arctan

Synopsis: Calculate inverse tangent

Declaration: `function arctan(d: ValReal) : ValReal`

Visibility: default

Description: `Arctan` returns the Arctangent of X, which can be any Real type. The resulting angle is in radial units.

Errors: None

See also: [Sin \(1247\)](#), [Cos \(1130\)](#)

Listing: ./refex/ex4.pp

Program Example4;

{ Program to demonstrate the ArcTan function. }

Var R : Real;

begin

R:=**ArcTan**(0); *{ R:=0 }*

R:=**ArcTan**(1)/**pi**; *{ R:=0.25 }*

end.

29.9.11 ArrayStringToPPchar

Synopsis: Concert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array[] of AnsiString;
reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1251](#))

29.9.12 Assert

Synopsis: Check validity of a given condition.

Declaration: `procedure Assert (Expr: Boolean)`
`procedure Assert (Expr: Boolean; const Msg: String)`

Visibility: default

Description: With assertions on, `Assert` tests if `expr` is false, and if so, aborts the application with a Runtime error 227 and an optional error message in `msg`. If `expr` is true, program execution continues normally. If assertions are not enabled at compile time, this routine does nothing, and no code is generated for the `Assert` call. Enabling and disabling assertions at compile time is done via the `\$C` or `\$ASSERTIONS` compiler switches. These are global switches. The default behavior of the assert call can be changed by setting a new handler in the `AssertErrorProc` variable. `Sysutils` overrides the default handler to raise a `EAssertionFailed` exception.

Errors: None.

See also: `Halt` ([1183](#)), `Runerror` ([1239](#))

29.9.13 Assign

Synopsis: Assign a name to a file

Declaration: `procedure Assign (var f: File; const Name: String)`
`procedure Assign (var f: File; p: PChar)`
`procedure Assign (var f: File; c: Char)`
`procedure Assign (var f: TypedFile; const Name: String)`
`procedure Assign (var f: TypedFile; p: PChar)`
`procedure Assign (var f: TypedFile; c: Char)`
`procedure Assign (var t: Text; const s: String)`
`procedure Assign (var t: Text; p: PChar)`
`procedure Assign (var t: Text; c: Char)`

Visibility: default

Description: `Assign` assigns a name to `F`, which can be any file type. This call doesn't open the file, it just assigns a name to a file variable, and marks the file as closed.

Errors: None.

See also: `Reset` ([1234](#)), `Rewrite` ([1236](#)), `Append` ([1114](#))

Listing: `./refex/ex5.pp`

```

Program Example5;

{ Program to demonstrate the Assign function. }

Var F : text;

begin
  Assign (F, '');
  Rewrite (f);
  { The following can be put in any file by redirecting it
    from the command line.}
  Writeln (f, 'This goes to standard output !');
  Close (f);
  Assign (F, 'Test.txt');
  rewrite (f);
  writeln (f, 'This doesn''t go to standard output !');
  close (f);
end.

```

29.9.14 Assigned

Synopsis: Check if a pointer is valid

Declaration: `function Assigned(P: Pointer) : Boolean`

Visibility: default

Description: `Assigned` returns `True` if `P` is non-nil and returns `False` if `P` is nil. The main use of `Assigned` is that Procedural variables, method variables and class-type variables also can be passed to `Assigned`.

Errors: None

See also: `New` ([1200](#))

Listing: `./refex/ex96.pp`

```

Program Example96;

{ Program to demonstrate the Assigned function. }

Var P : Pointer;

begin
  If Not Assigned(P) then
    Writeln ('Pointer is initially NIL');
  P:=@P;
  If Not Assigned(P) then
    Writeln ('Internal inconsistency')
  else
    Writeln ('All is well in FPC')
end.

```

29.9.15 BasicEventCreate

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventCreate(EventAttributes: Pointer;
 AManualReset: Boolean;InitialState: Boolean;
 const Name: ansistring) : PEventState`

Visibility: default

Description: `BasicEventCreate` is obsolete, use `RTLEventCreate` ([1238](#)) instead.

See also: `RTLEventCreate` ([1238](#))

29.9.16 basiceventdestroy

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventdestroy(state: PEventState)`

Visibility: default

Description: `basiceventdestroy` is obsolete. Use `RTLEventDestroy` ([1238](#)) instead.

See also: `RTLEventDestroy` ([1238](#))

29.9.17 basiceventResetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventResetEvent(state: PEventState)`

Visibility: default

Description: `basiceventResetEvent` is obsolete. Use `RTLEventResetEvent` ([1238](#)) instead.

See also: `RTLEventResetEvent` ([1238](#))

29.9.18 basiceventSetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventSetEvent(state: PEventState)`

Visibility: default

Description: `basiceventSetEvent` is obsolete. Use `RTLEventSetEvent` ([1238](#)) instead.

See also: `RTLEventSetEvent` ([1238](#))

29.9.19 basiceventWaitFor

Synopsis: Obsolete. Don't use

Declaration: `function basiceventWaitFor(Timeout: Cardinal;state: PEventState)
 : LongInt`

Visibility: default

Description: `basiceventwaitfor` is obsolete. Use `RTLEventWaitFor` ([1239](#)) instead.

See also: `RTLEventWaitFor` ([1239](#))

29.9.20 BeginThread

Synopsis: Start a new thread.

Declaration:

```
function BeginThread(sa: Pointer;stacksize: SizeUInt;
                    ThreadFunction: TThreadFunc;p: pointer;
                    creationFlags: DWord;var ThreadId: TThreadID)
                    : TThreadID
function BeginThread(ThreadFunction: TThreadFunc) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc;p: pointer) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc;p: pointer;
                    var ThreadId: TThreadID) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc;p: pointer;
                    var ThreadId: TThreadID;const stacksize: SizeUInt)
                    : TThreadID
```

Visibility: default

Description: `BeginThread` starts a new thread and executes `ThreadFunction` in the new thread. If `P` is specified, then it is passed to `ThreadFunction`. If `ThreadId` is specified, it is filled with the thread ID of the newly started thread.

The function returns zero on success.

Errors: On error, a nonzero value is returned.

See also: `EndThread` ([1136](#))

29.9.21 BEtoN

Synopsis: Convert Big Endian-ordered integer to Native-ordered integer

Declaration:

```
function BEtoN(const AValue: SmallInt) : SmallInt
function BEtoN(const AValue: Word) : Word
function BEtoN(const AValue: LongInt) : LongInt
function BEtoN(const AValue: DWord) : DWord
function BEtoN(const AValue: Int64) : Int64
function BEtoN(const AValue: QWord) : QWord
```

Visibility: default

Description: `BEtoN` will rearrange the bytes in a Big-Endian number to the native order for the current processor. That is, for a big-endian processor, it will do nothing, and for a little-endian processor, it will invert the order of the bytes.

See also: `LEtoN` ([1195](#)), `NtoBE` ([1200](#)), `NtoLE` ([1201](#))

29.9.22 binStr

Synopsis: Convert integer to string with binary representation.

Declaration:

```
function binStr(Val: LongInt;cnt: Byte) : shortstring
function binStr(Val: Int64;cnt: Byte) : shortstring
```

Visibility: default

Description: `BinStr` returns a string with the binary representation of `Value`. The string has at most `cnt` characters. (i.e. only the `cnt` rightmost bits are taken into account) To have a complete representation of any longint-type value, 32 bits are needed, i.e. `cnt=32`

Errors: None.

See also: Str ([1250](#)), Val ([1261](#)), HexStr ([1184](#)), OctStr ([1201](#))

Listing: ./refex/ex82.pp

```

Program example82;

  { Program to demonstrate the BinStr function }

  Const Value = 45678;

  Var I : longint;

  begin
    For I:=8 to 20 do
      Writeln ( BinStr(Value,I):20);
  end.
```

29.9.23 BlockRead

Synopsis: Read data from an untyped file into memory

Declaration:

```

procedure BlockRead(var f: File;var Buf;count: Int64;var Result: Int64)
procedure BlockRead(var f: File;var Buf;count: LongInt;
                    var Result: LongInt)
procedure BlockRead(var f: File;var Buf;count: Cardinal;
                    var Result: Cardinal)
procedure BlockRead(var f: File;var Buf;count: Word;var Result: Word)
procedure BlockRead(var f: File;var Buf;count: Word;var Result: Integer)
procedure BlockRead(var f: File;var Buf;count: Int64)
```

Visibility: default

Description: Blockread reads `count` or less records from file `F`. A record is a block of bytes with size specified by the Rewrite ([1236](#)) or Reset ([1234](#)) statement. The result is placed in `Buffer`, which must contain enough room for `Count` records. The function cannot read partial records. If `Result` is specified, it contains the number of records actually read. If `Result` isn't specified, and less than `Count` records were read, a run-time error is generated. This behavior can be controlled by the `\var{\{$i\}}` switch.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: Blockwrite ([1121](#)), Close ([1123](#)), Reset ([1234](#)), Assign ([1116](#))

Listing: ./refex/ex6.pp

```

Program Example6;

  { Program to demonstrate the BlockRead and BlockWrite functions. }

  Var Fin, fout : File;
      NumRead, NumWritten : Word;
      Buf : Array[1..2048] of byte;
      Total : Longint;
```

```

begin
  Assign (Fin, Paramstr(1));
  Assign (Fout, Paramstr(2));
  Reset (Fin, 1);
  Rewrite (Fout, 1);
  Total:=0;
  Repeat
    BlockRead (Fin, buf, Sizeof(buf), NumRead);
    BlockWrite (Fout, Buf, NumRead, NumWritten);
    inc (Total, NumWritten);
  Until (NumRead=0) or (NumWritten<>NumRead);
  Write ('Copied ', Total, ' bytes from file ', paramstr(1));
  Writeln (' to file ', paramstr(2));
  close(fin);
  close(fout);
end.

```

29.9.24 BlockWrite

Synopsis: Write data from memory to an untyped file

Declaration: `procedure BlockWrite(var f: File; const Buf; Count: Int64; var Result: Int64)`
`procedure BlockWrite(var f: File; const Buf; Count: LongInt; var Result: LongInt)`
`procedure BlockWrite(var f: File; const Buf; Count: Cardinal; var Result: Cardinal)`
`procedure BlockWrite(var f: File; const Buf; Count: Word; var Result: Word)`
`procedure BlockWrite(var f: File; const Buf; Count: Word; var Result: Integer)`
`procedure BlockWrite(var f: File; const Buf; Count: LongInt)`

Visibility: default

Description: `BlockWrite` writes count records from buffer to the file F. A record is a block of bytes with size specified by the `Rewrite` (1236) or `Reset` (1234) statement. If the records couldn't be written to disk, a run-time error is generated. This behavior can be controlled by the `\var{\{$i\}}` switch.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Blockread` (1120), `Close` (1123), `Rewrite` (1236), `Assign` (1116)

29.9.25 Break

Synopsis: Exit current loop construct.

Declaration: `procedure Break`

Visibility: default

Description: `Break` jumps to the statement following the end of the current repetitive statement. The code between the `Break` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is NOT evaluated.

This can be used with `For`, `var{repeat}` and `While` statements.

Note that while this is a procedure, `Break` is a reserved word and hence cannot be redefined.

Errors: None.

See also: Continue ([1129](#)), Exit ([1140](#))

Listing: ./refex/ex87.pp

Program Example87;

{ Program to demonstrate the Break function. }

```

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I>5 Then
        Break;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I>5 Then
      Break;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I>5 Then
        Break;
      Writeln (i);
    end;
end.
```

29.9.26 chdir

Synopsis: Change current working directory.

Declaration: `procedure chdir(const s:String)`

Visibility: default

Description: Chdir changes the working directory of the process to S.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: Mkdir ([1199](#)), Rmdir ([1236](#))

Listing: ./refex/ex7.pp

Program Example7;

{ Program to demonstrate the ChDir function. }

```

begin
```

```

    {$I-}
    ChDir (ParamStr(1));
    if IOResult <> 0 then
        Writeln ('Cannot change to directory : ', paramstr (1));
    end.

```

29.9.27 chr

Synopsis: Convert byte value to character value

Declaration: `function chr(b: Byte) : Char`

Visibility: default

Description: Chr returns the character which has ASCII value X.

Historical note:

Originally, Pascal did not have typecasts and chr was a necessary function in order to do certain operations on ASCII values of characters. With the arrival of typecasting a generic approach became possible, making chr mostly obsolete. However, chr is not considered deprecated and remains in wide use today.

Errors: None.

See also: Ord ([1226](#)), Str ([1250](#))

Listing: ./refex/ex8.pp

Program Example8;

{ Program to demonstrate the Chr function. }

begin

 Write (chr(10),chr(13)); *{ The same effect as Writeln; }*

end.

29.9.28 Close

Synopsis: Close a file

Declaration: `procedure Close(var f: File)`
 `procedure Close(var t: Text)`

Visibility: default

Description: Close flushes the buffer of the file F and closes F. After a call to Close, data can no longer be read from or written to F. To reopen a file closed with Close, it isn't necessary to assign the file again. A call to Reset ([1234](#)) or Rewrite ([1236](#)) is sufficient.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use IOResult to check for errors.

See also: Assign ([1116](#)), Reset ([1234](#)), Rewrite ([1236](#)), Flush ([1146](#))

Listing: ./refex/ex9.pp

```

Program Example9;

{ Program to demonstrate the Close function. }

Var F : text;

begin
  Assign (f, 'Test.txt ');
  ReWrite (F);
  WriteLn (F, 'Some text written to Test.txt ');
  close (f); { Flushes contents of buffer to disk,
               closes the file. Omitting this may
               cause data NOT to be written to disk. }
end.

```

29.9.29 CompareByte

Synopsis: Compare 2 memory buffers byte per byte

Declaration: `function CompareByte(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: CompareByte compares two memory regions buf1,buf2 on a byte-per-byte basis for a total of len bytes.

The function returns one of the following values:

less than 0 if buf1 and buf2 contain different bytes in the first len bytes, and the first such byte is smaller in buf1 than the byte at the same position in buf2.

0 if the first len bytes in buf1 and buf2 are equal. \item [greater than 0] if buf1 and buf2 contain different bytes in the first len bytes, and the first such byte is larger in buf1 than the byte at the same position in buf2.

Errors: None.

See also: CompareChar ([1125](#)), CompareWord ([1128](#)), CompareDWord ([1127](#))

Listing: ./refex/ex99.pp

```

Program Example99;

{ Program to demonstrate the CompareByte function. }

Const
  ArraySize      = 100;
  HalfArraySize = ArraySize Div 2;

Var
  Buf1, Buf2 : Array[1..ArraySize] of byte;
  I : longint;

Procedure CheckPos(Len : Longint);

Begin
  Write ('First ', Len, ' positions are ');
  if CompareByte(Buf1, Buf2, Len) <> 0 then

```

```

        Write( 'NOT ');
        Writeln( 'equal');
    end;

begin
    For I:=1 to ArraySize do
        begin
            Buf1[I]:= I;
            If I<=HalfArraySize Then
                Buf2[I]:= I
            else
                Buf2[I]:= HalfArraySize-I;
            end;
        CheckPos(HalfArraySize div 2);
        CheckPos(HalfArraySize);
        CheckPos(HalfArraySize+1);
        CheckPos(HalfArraySize + HalfArraySize Div 2);
    end.

```

29.9.30 CompareChar

Synopsis: ompare 2 memory buffers character per character

Declaration: `function CompareChar(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar` compares two memory regions `buf1`,`buf2` on a character-per-character basis for a total of `len` characters.

The `CompareChar0` variant compares `len` bytes, or until a zero character is found.

The function returns one of the following values:

-1if `buf1` and `buf2` contain different characters in the first `len` positions, and the first such character is smaller in `buf1` than the character at the same position in `buf2`.

0if the first `len` characters in `buf1` and `buf2` are equal.

1if `buf1` and `buf2` contain different characters in the first `len` positions, and the first such character is larger in `buf1` than the character at the same position in `buf2`.

Errors: None.

See also: [CompareByte \(1124\)](#), [CompareWord \(1128\)](#), [CompareDWord \(1127\)](#)

Listing: `./refex/ex100.pp`

Program `Example100;`

{ Program to demonstrate the CompareChar function. }

Const

```

    ArraySize      = 100;
    HalfArraySize = ArraySize Div 2;

```

Var

```

    Buf1, Buf2 : Array[1..ArraySize] of char;
    I : longint;

```

```

Procedure CheckPos(Len : Longint);

Begin
  Write('First ',Len,' characters are ');
  if CompareChar(Buf1,Buf2,Len)<>0 then
    Write('NOT ');
    Writeln('equal');
end;

Procedure CheckNullPos(Len : Longint);

Begin
  Write('First ',Len,' non-null characters are ');
  if CompareChar0(Buf1,Buf2,Len)<>0 then
    Write('NOT ');
    Writeln('equal');
end;

begin
  For I:=1 to ArraySize do
    begin
      Buf1[I]:=chr(I);
      If I<=HalfArraySize Then
        Buf2[I]:=chr(I)
      else
        Buf2[I]:=chr(HalfArraySize-I);
      end;
  CheckPos(HalfArraySize div 2);
  CheckPos(HalfArraySize);
  CheckPos(HalfArraySize+1);
  CheckPos(HalfArraySize + HalfArraySize Div 2);
  For I:=1 to 4 do
    begin
      buf1[Random(ArraySize)+1]:=Chr(0);
      buf2[Random(ArraySize)+1]:=Chr(0);
    end;
  Randomize;
  CheckNullPos(HalfArraySize div 2);
  CheckNullPos(HalfArraySize);
  CheckNullPos(HalfArraySize+1);
  CheckNullPos(HalfArraySize + HalfArraySize Div 2);
end.

```

29.9.31 CompareChar0

Synopsis: Compare two buffers character by character till a null-character is reached.

Declaration: `function CompareChar0(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: CompareChar0 compares 2 buffers buf1 and buf2 for a maximum length of len or till a null character is reached in either buffer. The result depends on the contents of the buffers:

< 0 If buf1 contains a character less than the corresponding character in buf2.

0 If both buffers are equal

> 0 If buf1 contains a character greater than the corresponding character in buf2.

Errors: None.

See also: CompareByte (1124), CompareChar (1125), CompareDWord (1127), CompareWord (1128)

29.9.32 CompareDWord

Synopsis: Compare 2 memory buffers DWord per DWord

Declaration: `function CompareDWord(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: CompareDWord compares two memory regions buf1,buf2 on a DWord-per-DWord basis for a total of len DWords. (A DWord is 4 bytes).

The function returns one of the following values:

-1 if buf1 and buf2 contain different DWords in the first len DWords, and the first such DWord is smaller in buf1 than the DWord at the same position in buf2.

0 if the first len DWords in buf1 and buf2 are equal.

1 if buf1 and buf2 contain different DWords in the first len DWords, and the first such DWord is larger in buf1 than the DWord at the same position in buf2.

Errors: None.

See also: CompareChar (1125), CompareByte (1124), CompareWord (1128)

Listing: ./refex/ex101.pp

Program Example101;

{ Program to demonstrate the CompareDWord function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize Div 2;

Var

 Buf1, Buf2 : **Array**[1..ArraySize] **of** Dword;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write('First ', Len, ' DWords are ');
 if CompareDWord(Buf1, Buf2, Len) <> 0 **then**
 Write('NOT ');
 Writeln('equal ');
end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I]:= I;
 If I<=HalfArraySize **Then**

```

    Buf2[1]:=1
  else
    Buf2[i]:= HalfArraySize-1;
  end;
  CheckPos( HalfArraySize div 2);
  CheckPos( HalfArraySize );
  CheckPos( HalfArraySize+1);
  CheckPos( HalfArraySize + HalfArraySize Div 2);
end.

```

29.9.33 CompareWord

Synopsis: Compare 2 memory buffers word per word

Declaration: `function CompareWord(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareWord` compares two memory regions `buf1, buf2` on a Word-per-Word basis for a total of `len` Words. (A Word is 2 bytes).

The function returns one of the following values:

-1 if `buf1` and `buf2` contain different Words in the first `len` Words, and the first such Word is smaller in `buf1` than the Word at the same position in `buf2`.

0 if the first `len` Words in `buf1` and `buf2` are equal.

1 if `buf1` and `buf2` contain different Words in the first `len` Words, and the first such Word is larger in `buf1` than the Word at the same position in `buf2`.

Errors: None.

See also: `CompareChar` ([1125](#)), `CompareByte` ([1124](#)), `CompareDWord` ([1127](#))

Listing: `./refex/ex102.pp`

Program `Example102;`

{ Program to demonstrate the CompareWord function. }

Const

```

  ArraySize      = 100;
  HalfArraySize = ArraySize Div 2;

```

Var

```

  Buf1, Buf2 : Array[1.. ArraySize] of Word;
  I : longint;

```

Procedure `CheckPos(Len : Longint);`

Begin

```

  Write( 'First ', Len, ' words are ');
  if CompareWord( Buf1, Buf2, Len) <> 0 then
    Write( 'NOT ');
    Writeln( 'equal ');
  end;

```

```

begin
  For I:=1 to ArraySize do
    begin
      Buf1[I]:=I;
      If I<=HalfArraySize Then
        Buf2[I]:=I
      else
        Buf2[I]:=HalfArraySize-I;
      end;
      CheckPos(HalfArraySize div 2);
      CheckPos(HalfArraySize);
      CheckPos(HalfArraySize+1);
      CheckPos(HalfArraySize + HalfArraySize Div 2);
    end.

```

29.9.34 Concat

Synopsis: Append one string to another.

Declaration: `function Concat(const S1: String;const S2: String;const S3: String;
const Sn: String) : String`

Visibility: default

Description: `Concat` concatenates the strings `S1,S2` etc. to one long string. The resulting string is truncated at a length of 255 bytes. The same operation can be performed with the `+` operation.

Errors: None.

See also: `Copy` ([1069](#)), `Delete` ([1133](#)), `Insert` ([1191](#)), `Pos` ([1228](#)), `Length` ([1069](#))

Listing: `./refex/ex10.pp`

Program `Example10;`

```

{ Program to demonstrate the Concat function. }
Var
  S : String;

begin
  S:=Concat('This can be done',' Easier ','with the + operator !');
end.

```

29.9.35 Continue

Synopsis: Continue with next loop cycle.

Declaration: `procedure Continue`

Visibility: default

Description: `Continue` jumps to the end of the current repetitive statement. The code between the `Continue` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is then checked again.

This can be used with `For`, `var{repeat}` and `While` statements.

Note that while this is a procedure, `Continue` is a reserved word and hence cannot be redefined.

Errors: None.

See also: Break ([1121](#)), Exit ([1140](#))

Listing: ./refex/ex86.pp

Program Example86;

{ Program to demonstrate the Continue function. }

Var I : longint;

begin

 I:=0;

While I<10 **Do**

begin

Inc(I);

If I<5 **Then**

Continue;

Writeln (i);

end;

 I:=0;

Repeat

Inc(I);

If I<5 **Then**

Continue;

Writeln (i);

Until I>=10;

For I:=1 **to** 10 **do**

begin

If I<5 **Then**

Continue;

Writeln (i);

end;

end.

29.9.36 cos

Synopsis: Calculate cosine of angle

Declaration: `function cos(d: ValReal) : ValReal`

Visibility: default

Description: `Cos` returns the cosine of X, where X is an angle, in radians. If the absolute value of the argument is larger than 263, then the result is undefined.

Errors: None.

See also: Arctan ([1115](#)), Sin ([1247](#))

Listing: ./refex/ex12.pp

Program Example12;

{ Program to demonstrate the Cos function. }

Var R : Real;

```

begin
  R:=Cos(Pi);      { R:=-1 }
  R:=Cos(Pi/2);    { R:=0  }
  R:=Cos(0);       { R:=1  }
end.

```

29.9.37 Cseg

Synopsis: Return code segment

Declaration: `function Cseg : Word`

Visibility: default

Description: `Cseg` returns the Code segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32 bit compiler.

Errors: None.

See also: `Dseg` ([1134](#)), `Seg` ([1242](#)), `Ofs` ([1202](#)), `Ptr` ([1229](#))

Listing: `./refex/ex13.pp`

Program `Example13;`

```

{ Program to demonstrate the CSeg function. }

var W : word;

begin
  W:=CSeg; {W:=0, provided for compatibility,
           FPC is 32 bit.}
end.

```

29.9.38 Dec

Synopsis: Decrease value of variable

Declaration: `procedure Dec(var X: TOrdinal)`
`procedure Dec(var X: TOrdinal;Decrement: TOrdinal)`

Visibility: default

Description: `Dec` decreases the value of `X` with `Decrement`. If `Decrement` isn't specified, then 1 is taken as a default.

Errors: A range check can occur, or an underflow error, if an attempt it made to decrease `X` below its minimum value.

See also: `Inc` ([1186](#))

Listing: `./refex/ex14.pp`

Program Example14;

{ Program to demonstrate the Dec function. }

Var

I : Integer;
L : Longint;
W : Word;
B : Byte;
Si : ShortInt;

begin

I:=1;
L:=2;
W:=3;
B:=4;
Si:=5;
Dec (i); { i:=0 }
Dec (L,2); { L:=0 }
Dec (W,2); { W:=1 }
Dec (B,-2); { B:=6 }
Dec (Si,0); { Si:=5 }
end.

29.9.39 DefaultAnsi2WideMove

Synopsis: Standard implementation of Ansi to Widestring conversion routine

Declaration: `procedure DefaultAnsi2WideMove(source: PChar; var dest: widestring;
len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2WideMove` simply copies each character of the null-terminated ansi-string `Source` to the corresponding `WideChar` in `Dest`. At most `Len` characters will be copied.

Errors: None.

See also: `DefaultWide2AnsiMove` ([1132](#))

29.9.40 DefaultWide2AnsiMove

Synopsis: Standard implementation of Widestring to Ansi conversion routine

Declaration: `procedure DefaultWide2AnsiMove(source: PWideChar; var dest: ansistring;
len: SizeInt)`

Visibility: default

Description: `DefaultWide2AnsiMove` simply copies each character from `Source` having an ordinal value of less than 255 to the corresponding character in `Dest`. Characters having an ordinal value larger than 255 will be replaced by question marks. At most `Len` characters will be copied.

Errors: None.

See also: `DefaultAnsi2WideMove` ([1132](#))

29.9.41 Delete

Synopsis: Delete part of a string.

Declaration: `procedure Delete(var s: shortstring; index: SizeInt; count: SizeInt)`
`procedure Delete(var S: AnsiString; Index: SizeInt; Size: SizeInt)`
`procedure Delete(var S: WideString; Index: SizeInt; Size: SizeInt)`

Visibility: default

Description: `Delete` removes `Count` characters from string `S`, starting at position `Index`. All characters after the deleted characters are shifted `Count` positions to the left, and the length of the string is adjusted.

Errors: None.

See also: [Copy \(1069\)](#), [Pos \(1228\)](#), [Insert \(1191\)](#)

Listing: `./refex/ex15.pp`

Program `Example15;`

{ Program to demonstrate the Delete function. }

Var

`S : String;`

begin

`S := 'This is not easy !';`

`Delete (S, 9, 4); { S := 'This is easy !' }`

end.

29.9.42 Dispose

Synopsis: Free dynamically allocated memory

Declaration: `procedure Dispose(P: Pointer)`
`procedure Dispose(P: TypedPointer; Des: TProcedure)`

Visibility: default

Description: The first form `Dispose` releases the memory allocated with a call to [New \(1200\)](#). The pointer `P` must be typed. The released memory is returned to the heap.

The second form of `Dispose` accepts as a first parameter a pointer to an object type, and as a second parameter the name of a destructor of this object. The destructor will be called, and the memory allocated for the object will be freed.

Errors: An runtime error will occur if the pointer doesn't point to a location in the heap.

See also: [New \(1200\)](#), [Getmem \(1180\)](#), [Freemem \(1178\)](#)

Listing: `./refex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the Dispose and New functions. }

Type `SS = String[20];`

```

    AnObj = Object
      I : integer;
      Constructor Init;
      Destructor Done;
    end;

Var
  P : ^SS;
  T : ^AnObj;

Constructor Anobj.Init;

begin
  WriteLn ('Initializing an instance of AnObj !');
end;

Destructor AnObj.Done;

begin
  WriteLn ('Destroying an instance of AnObj !');
end;

begin
  New (P);
  P^:= 'Hello , World !';
  Dispose (P);
  { P is undefined from here on !}
  New(T, Init);
  T^.i:=0;
  Dispose (T, Done);
end.

```

29.9.43 DoneCriticalsection

Synopsis: Clean up a critical section.

Declaration: `procedure DoneCriticalsection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `DoneCriticalsection` cleans up the critical section CS. After a call to `DoneCriticalsection`, the critical section can no longer be used with `EnterCriticalsection` (1136) or `LeaveCriticalsection` (1195), unless it is again initialized with `InitCriticalSection` (1191)

See also: `InitCriticalsection` (1191), `EnterCriticalsection` (1136), `LeaveCriticalsection` (1195)

29.9.44 Dseg

Synopsis: Return data segment

Declaration: `function Dseg : Word`

Visibility: default

Description: `Dseg` returns the data segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32 bit compiler.

Errors: None.

See also: CSeg ([1131](#)), Seg ([1242](#)), Ofs ([1202](#)), Ptr ([1229](#))

Listing: ./refex/ex17.pp

Program Example17;

{ Program to demonstrate the DSeg function. }

Var

W : Word;

begin

W:=DSeg; *{W:=0, This function is provided for compatibility,
FPC is a 32 bit compiler.}*

end.

29.9.45 Dump_Stack

Synopsis: Dump stack to the given text file.

Declaration: procedure Dump_Stack(var f: text;bp: pointer)

Visibility: default

Description: Dump_Stack prints a stack dump to the file f, with base frame pointer bp

Errors: The file f must be opened for writing or an error will occur.

See also: get_caller_addr ([1182](#)), get_caller_frame ([1183](#)), get_frame ([1183](#))

29.9.46 DynArraySetLength

Synopsis: Set the length of a dynamic array

Declaration: procedure DynArraySetLength(var a: Pointer;typeInfo: Pointer;
dimCnt: SizeInt;lengthVec: PSizeInt)

Visibility: default

Description: DynArraySetLength sets the length of the dynamical array a to the first dimCnt lengths specified in the array lengthVec. The dynamical array type is described in typeInfo which points to a record of type TDynArrayTypeInfo ([1099](#))

It should never be necessary to call this function directly, the standard SetLength ([1069](#)) function should be used instead.

Errors: If an invalid pointer is specified, an error may occur.

See also: SetLength ([1069](#)), tdynarraytypeinfo ([1099](#))

29.9.47 EndThread

Synopsis: End the current thread.

Declaration: `procedure EndThread(ExitCode: DWord)`
`procedure EndThread`

Visibility: default

Description: `EndThread` ends the current thread. If `ExitCode` is supplied, it is returned as the exit code for the thread to a function waiting for the thread to terminate (`WaitForThreadTerminate` (1262)). If it is omitted, zero is used.

This function does not return.

See also: `WaitForThreadTerminate` (1262), `BeginThread` (1119)

29.9.48 EnterCriticalSection

Synopsis: Enter a critical section

Declaration: `procedure EnterCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `EnterCriticalSection` will suspend the current thread if another thread has currently entered the critical section. When the other thread has left the critical section (through `LeaveCriticalSection` (1195)), the current thread resumes execution. The result is that only 1 thread is executing code which is protected by a `EnterCriticalSection` and `LeaveCriticalSection` pair.

The critical section must have been initialized with `InitCriticalSection` (1191) prior to a call to `EnterCriticalSection`.

A call to `EnterCriticalSection` must always be matched by a call to `LeaveCriticalSection` (1195). To avoid problems, it is best to include the code to be execute in a `try...finally` block, as follows:

```
EnterCriticalSection(Section);
try
  // Code to be protected goes here.
finally
  LeaveCriticalSection(Section);
end;
```

For performance reasons it is best to limit the code between the entering and leaving of a critical section as short as possible.

See also: `InitCriticalSection` (1191), `DoneCriticalSection` (1134), `LeaveCriticalSection` (1195)

29.9.49 EOF

Synopsis: Check for end of file

Declaration: `function EOF(var f: File) : Boolean`
`function EOF(var t: Text) : Boolean`
`function EOF : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file-pointer has reached the end of the file, or if the file is empty. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed.

Note that calling this function may cause your program to wait: to determine whether you are at EOF, it is necessary to read data. If the file descriptor is not a real file (for instance for standard input or sockets), then this call may seem to hang the program while it is waiting for data to appear or for the file descriptor to be closed.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Eoln` ([1137](#)), `Assign` ([1116](#)), `Reset` ([1234](#)), `Rewrite` ([1236](#))

Listing: `./refex/ex18.pp`

Program `Example18`;

```
{ Program to demonstrate the Eof function. }

Var T1,T2 : text;
      C : Char;

begin
  { Set file to read from. Empty means from standard input. }
  assign (t1,paramstr(1));
  reset (t1);
  { Set file to write to. Empty means to standard output. }
  assign (t2,paramstr(2));
  rewrite (t2);
  While not eof(t1) do
    begin
      read (t1,C);
      write (t2,C);
    end;
    Close (t1);
    Close (t2);
end.
```

29.9.50 EOLn

Synopsis: Check for end of line

Declaration: `function EOLn(var t: Text) : Boolean`
`function EOLn : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file pointer has reached the end of a line, which is demarcated by a line-feed character (ASCII value 10), or if the end of the file is reached. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed. It can only be used on files of type `Text`.

Errors: None.

See also: `Eof` ([1136](#)), `Assign` ([1116](#)), `Reset` ([1234](#)), `Rewrite` ([1236](#))

Listing: `./refex/ex19.pp`

Program Example19;

```
{ Program to demonstrate the Eoln function. }

begin
  { This program waits for keyboard input. }
  { It will print True when an empty line is put in ,
    and false when you type a non-empty line.
    It will only stop when you press enter. }
  While not Eoln do
    Writeln (eoln);
end.
```

29.9.51 Erase

Synopsis: Delete a file from disk

Declaration: `procedure Erase(var f: File)`
`procedure Erase(var t: Text)`

Visibility: default

Description: `Erase` removes an unopened file from disk. The file should be assigned with `Assign`, but not opened with `Reset` or `Rewrite`

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Assign` ([1116](#))

Listing: `./refex/ex20.pp`

Program Example20;

```
{ Program to demonstrate the Erase function. }

Var F : Text;

begin
  { Create a file with a line of text in it }
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'Try and find this when I 'm finished !');
  close (f);
  { Now remove the file }
  Erase (f);
end.
```

29.9.52 Error

Synopsis: 32-bit signed integer.

Declaration: `procedure Error(RuntimeError: TRuntimeError)`

Visibility: default

29.9.53 Exclude

Synopsis: Exclude element from a set if it is present.

Declaration: `procedure Exclude(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Exclude` removes `E` from the set `S` if it is included in the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S := S - [E];
Exclude(S, E);
```

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: Include ([1187](#))

Listing: `./refex/ex111.pp`

```
program Example111;

{ Program to demonstrate the Include/Exclude functions }

Type
  TEnumA = (aOne, aTwo, aThree);
  TEnumAs = Set of TEnumA;

Var
  SA : TEnumAs;

Procedure PrintSet(S : TEnumAs);

var
  B : Boolean;

procedure DoEl(A : TEnumA; Desc : String);

begin
  if A in S then
    begin
      if B then
        Write(' ');
      B := True;
      Write(Desc);
    end;
  end;

begin
  Write(' ');
  B := False;
  DoEl(aOne, 'aOne');
  DoEl(aTwo, 'aTwo');
  DoEl(aThree, 'aThree');
  Writeln(' ');
end;
```



```

begin
  SA:=[];
  Include(SA,aOne);
  PrintSet(SA);
  Include(SA,aThree);
  PrintSet(SA);
  Exclude(SA,aOne);
  PrintSet(SA);
  Exclude(SA,aTwo);
  PrintSet(SA);
  Exclude(SA,aThree);
  PrintSet(SA);
end.

```

29.9.54 Exit

Synopsis: Exit current subroutine.

Declaration: `procedure Exit(const X: TAnyType)`
`procedure Exit`

Visibility: default

Description: `Exit` exits the current subroutine, and returns control to the calling routine. If invoked in the main program routine, exit stops the program. The optional argument `X` allows to specify a return value, in the case `Exit` is invoked in a function. The function result will then be equal to `X`.

Errors: None.

See also: `Halt` ([1183](#))

Listing: `./refex/ex21.pp`

Program `Example21`;

{ Program to demonstrate the Exit function. }

Procedure `DoAnExit (Yes : Boolean);`

{ This procedure demonstrates the normal Exit }

```

begin
  Writeln ( 'Hello from DoAnExit !' );
  If Yes then
    begin
      Writeln ( 'Bailing out early.' );
      exit;
    end;
  Writeln ( 'Continuing to the end.' );
end;

```

Function `Positive (Which : Integer) : Boolean;`

*{ This function demonstrates the extra FPC feature of Exit :
 You can specify a return value for the function }*

```

begin

```

```

    if Which>0 then
        exit (True)
    else
        exit (False);
end;

begin
    { This call will go to the end }
    DoAnExit (False);
    { This call will bail out early }
    DoAnExit (True);
    if Positive (-1) then
        Writeln ('The compiler is nuts, -1 is not positive.')
    else
        Writeln ('The compiler is not so bad, -1 seems to be negative.');
```

29.9.55 exp

Synopsis: Exponentiate

Declaration: `function exp(d: ValReal) : ValReal`

Visibility: default

Description: `Exp` returns the exponent of `X`, i.e. the number `e` to the power `X`.

Errors: None.

See also: `Ln` ([1195](#)), `Power` ([1069](#))

Listing: `./refex/ex22.pp`

Program `Example22`;

{ Program to demonstrate the Exp function. }

```

begin
    Writeln (Exp(1):8:2); { Should print 2.72 }
end.
```

29.9.56 FilePos

Synopsis: Get position in file

Declaration: `function FilePos(var f: File) : Int64`

Visibility: default

Description: `Filepos` returns the current record position of the file-pointer in file `F`. It cannot be invoked with a file of type `Text`. A compiler error will be generated if this is attempted.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Filesize` ([1142](#))

Listing: ./refex/ex23.pp

Program Example23;

```

{ Program to demonstrate the FilePos function. }

Var F : File of Longint;
    L,FP : longint;

begin
  { Fill a file with data :
    Each position contains the position ! }
  Assign (F, 'test.tmp');
  Rewrite (F);
  For L:=0 to 100 do
    begin
      FP:=FilePos(F);
      Write (F,FP);
    end;
  Close (F);
  Reset (F);
  { If all goes well, nothing is displayed here. }
  While not (Eof(F)) do
    begin
      FP:=FilePos (F);
      Read (F,L);
      if L<>FP then
        WriteLn ( 'Something wrong: Got ',L, ' on pos ',FP);
    end;
  Close (F);
  Erase (f);
end.

```

29.9.57 FileSize

Synopsis: Size of file

Declaration: function FileSize(var f: File) : Int64

Visibility: default

Description: Filesize returns the total number of records in file F. It cannot be invoked with a file of type Text. (under linux and unix, this also means that it cannot be invoked on pipes). If F is empty, 0 is returned.

Errors: Depending on the state of the \var{\{\$I\}} switch, a runtime error can be generated if there is an error. In the \var{\{\$I-\}} state, use IOResult to check for errors.

See also: Filepos ([1141](#))

Listing: ./refex/ex24.pp

Program Example24;

```

{ Program to demonstrate the FileSize function. }

Var F : File Of byte;
    L : File Of Longint;

```

```

begin
  Assign (F,paramstr(1));
  Reset (F);
  Writeln ('File size in bytes : ',FileSize(F));
  Close (F);
  Assign (L,paramstr (1));
  Reset (L);
  Writeln ('File size in Longints : ',FileSize(L));
  Close (f);
end.

```

29.9.58 FillByte

Synopsis: Fill memory region with 8-bit pattern

Declaration: `procedure FillByte(var x;count: SizeInt;value: Byte)`

Visibility: default

Description: `FillByte` fills the memory starting at `X` with `Count` bytes with value equal to `Value`. This is useful for quickly zeroing out a memory location. When the size of the memory location to be filled out is a multiple of 2 bytes, it is better to use `FillWord` (1145), and if it is a multiple of 4 bytes it is better to use `FillDWord` (1144), these routines are optimized for their respective sizes.

Errors: No checking on the size of `X` is done.

See also: `Fillchar` (1144), `FillDWord` (1144), `Fillword` (1145), `Move` (1199)

Listing: `./refex/ex102.pp`

Program Example102;

{ Program to demonstrate the CompareWord function. }

Const

```

  ArraySize      = 100;
  HalfArraySize = ArraySize Div 2;

```

Var

```

  Buf1,Buf2 : Array[1..ArraySize] of Word;
  I : longint;

```

Procedure CheckPos(Len : Longint);

Begin

```

  Write('First ',Len,' words are ');
  if CompareWord(Buf1,Buf2,Len)<>0 then
    Write('NOT ');
  Writeln('equal');
end;

```

begin

```

  For I:=1 to ArraySize do
    begin
      Buf1[I]:=I;
      If I<=HalfArraySize Then

```

```

    Buf2[i] := 1
  else
    Buf2[i] := HalfArraySize - 1;
  end;
  CheckPos(HalfArraySize div 2);
  CheckPos(HalfArraySize);
  CheckPos(HalfArraySize + 1);
  CheckPos(HalfArraySize + HalfArraySize Div 2);
end.

```

29.9.59 FillChar

Synopsis: Fill memory region with certain character

Declaration: `procedure FillChar(var x; count: SizeInt; Value: Boolean)`
`procedure FillChar(var x; count: SizeInt; Value: Char)`
`procedure FillChar(var x; count: SizeInt; Value: Byte)`

Visibility: default

Description: `Fillchar` fills the memory starting at `X` with `Count` bytes or characters with value equal to `Value`.

Errors: No checking on the size of `X` is done.

See also: `Fillword` ([1145](#)), `Move` ([1199](#)), `FillByte` ([1143](#)), `FillDWord` ([1144](#))

Listing: `./refex/ex25.pp`

Program `Example25;`

{ Program to demonstrate the FillChar function. }

```

Var S : String[10];
    I : Byte;
begin
  For i:=10 downto 0 do
    begin
      { Fill S with i spaces }
      FillChar (S, SizeOf(S), ' ');
      { Set Length }
      SetLength(S, I);
      Writeln (s, '*');
    end;
  end.

```

29.9.60 FillDWord

Synopsis: Fill memory region with 32-bit pattern

Declaration: `procedure FillDWord(var x; count: SizeInt; value: DWord)`

Visibility: default

Description: `Fillword` fills the memory starting at `X` with `Count` `DWords` with value equal to `Value`. A `DWord` is 4 bytes in size.

Errors: No checking on the size of X is done.

See also: FillByte ([1143](#)), Fillchar ([1144](#)), Fillword ([1145](#)), Move ([1199](#))

Listing: ./refex/ex103.pp

Program Example103;

{ Program to demonstrate the FillByte function. }

```

Var S : String[10];
      I : Byte;

begin
  For i:=10 downto 0 do
    begin
      { Fill S with i bytes }
      FillChar (S, SizeOf(S), 32);
      { Set Length }
      SetLength(S, I);
      Writeln (s, '*');
    end;
  end.

```

29.9.61 FillWord

Synopsis: Fill memory region with 16-bit pattern

Declaration: `procedure FillWord(var x; count: SizeInt; Value: Word)`

Visibility: default

Description: Fillword fills the memory starting at X with Count words with value equal to Value. A word is 2 bytes in size.

Errors: No checking on the size of X is done.

See also: Fillchar ([1144](#)), Move ([1199](#))

Listing: ./refex/ex76.pp

Program Example76;

{ Program to demonstrate the FillWord function. }

```

Var W : Array[1..100] of Word;

begin
  { Quick initialization of array W }
  FillWord(W, 100, 0);
end.

```

29.9.62 FindResource

Synopsis: Locate a resource and return a handle to it.

Declaration: `function FindResource (ModuleHandle: HMODULE; ResourceName: PChar;
ResourceType: PChar) : TResourceHandle
function FindResource (ModuleHandle: HMODULE; ResourceName: AnsiString;
ResourceType: AnsiString) : TResourceHandle`

Visibility: default

Description: `FindResource` searches for a resource with name `ResourceName` and of type `ResourceType` in the executable or library identified by `ModuleHandle`. It returns a `TResourceHandle` which can be used to load the resource with `LoadResource` (1196).

Errors: None. In case the resource was not found, 0 is returned.

See also: `FreeResource` (1179), `LoadResource` (1196), `SizeofResource` (1248), `LockResource` (1197), `UnlockResource` (1259), `FreeResource` (1179)

29.9.63 Flush

Synopsis: Write file buffers to disk

Declaration: `procedure Flush (var t: Text)`

Visibility: default

Description: `Flush` empties the internal buffer of an opened file `F` and writes the contents to disk. The file is `\textit{not}` closed as a result of this call.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Close` (1123)

Listing: `./refex/ex26.pp`

Program `Example26`;

{ Program to demonstrate the Flush function. }

Var `F : Text`;

begin

{ Assign F to standard output }

`Assign (F, '');`

`Rewrite (F);`

`Writeln (F, 'This line is written first , but appears later !');`

*{ At this point the text is in the internal pascal buffer ,
and not yet written to standard output }*

`Writeln ('This line appears first , but is written later !');`

*{ A writeln to 'output' always causes a flush – so this text is
written to screen }*

`Flush (f);`

{ At this point , the text written to F is written to screen. }

`Write (F, 'Finishing ');`

`Close (f); { Closing a file always causes a flush first }`

`Writeln ('off.');`

end.

29.9.64 fpc_AbstractErrorIntern

Synopsis: FPC internal compiler routine: AbstractErrorIntern

Declaration: `procedure fpc_AbstractErrorIntern`

Visibility: default

29.9.65 fpc_abs_real

Synopsis: FPC internal compiler routine: abs_real

Declaration: `function fpc_abs_real(d: ValReal) : ValReal`

Visibility: default

29.9.66 fpc_Addref

Synopsis: FPC internal compiler routine: Addref

Declaration: `procedure fpc_Addref(Data: Pointer;TypeInfo: Pointer)`

Visibility: default

29.9.67 fpc_ansistr_append_ansistring

Synopsis: FPC internal compiler routine: ansistr_append_ansistring

Declaration: `procedure fpc_ansistr_append_ansistring(var S: AnsiString;
const Str: AnsiString)`

Visibility: default

29.9.68 fpc_ansistr_append_char

Synopsis: FPC internal compiler routine: ansistr_append_char

Declaration: `procedure fpc_ansistr_append_char(var S: AnsiString;c: Char)`

Visibility: default

29.9.69 fpc_ansistr_append_shortstring

Synopsis: FPC internal compiler routine: ansistr_append_shortstring

Declaration: `procedure fpc_ansistr_append_shortstring(var S: AnsiString;
const Str: ShortString)`

Visibility: default

29.9.70 fpc_AnsiStr_Assign

Synopsis: FPC internal compiler routine: AnsiStr_Assign

Declaration: `procedure fpc_AnsiStr_Assign(var S1: Pointer;S2: Pointer)`

Visibility: default

29.9.71 fpc_AnsiStr_CheckRange

Synopsis: FPC internal compiler routine: AnsiStr_CheckRange

Declaration: `procedure fpc_AnsiStr_CheckRange(len: SizeInt; index: SizeInt)`

Visibility: default

29.9.72 fpc_AnsiStr_CheckZero

Synopsis: FPC internal compiler routine: AnsiStr_CheckZero

Declaration: `procedure fpc_AnsiStr_CheckZero(p: pointer)`

Visibility: default

29.9.73 fpc_AnsiStr_Compare

Synopsis: FPC internal compiler routine: AnsiStr_Compare

Declaration: `function fpc_AnsiStr_Compare(const S1: AnsiString; const S2: AnsiString)
: SizeInt`

Visibility: default

29.9.74 fpc_AnsiStr_Concat

Synopsis: FPC internal compiler routine: AnsiStr_Concat

Declaration: `function fpc_AnsiStr_Concat(const S1: AnsiString; const S2: AnsiString)
: AnsiString`

Visibility: default

29.9.75 fpc_ansistr_Copy

Synopsis: FPC internal compiler routine: ansistr_Copy

Declaration: `function fpc_ansistr_Copy(const S: AnsiString; Index: SizeInt;
Size: SizeInt) : AnsiString`

Visibility: default

29.9.76 fpc_ansistr_decr_ref

Synopsis: FPC internal compiler routine: ansistr_decr_ref

Declaration: `procedure fpc_ansistr_decr_ref(var S: Pointer)`

Visibility: default

29.9.77 fpc_AnsiStr_Float

Synopsis: FPC internal compiler routine: AnsiStr_Float

Declaration: `procedure fpc_AnsiStr_Float(d: ValReal; len: SizeInt; fr: SizeInt;
rt: SizeInt; out s: ansistring)`

Visibility: default

29.9.78 fpc_ansistr_incr_ref

Synopsis: FPC internal compiler routine: ansistr_incr_ref

Declaration: `procedure fpc_ansistr_incr_ref(S: Pointer)`

Visibility: default

29.9.79 fpc_ansistr_int64

Synopsis: FPC internal compiler routine: ansistr_int64

Declaration: `procedure fpc_ansistr_int64(v: Int64; len: SizeInt; out s: ansistring)`

Visibility: default

29.9.80 fpc_ansistr_qword

Synopsis: FPC internal compiler routine: ansistr_qword

Declaration: `procedure fpc_ansistr_qword(v: qword; len: SizeInt; out s: ansistring)`

Visibility: default

29.9.81 fpc_AnsiStr_SetLength

Synopsis: FPC internal compiler routine: AnsiStr_SetLength

Declaration: `procedure fpc_AnsiStr_SetLength(var S: AnsiString; l: SizeInt)`

Visibility: default

29.9.82 fpc_AnsiStr_sint

Synopsis: FPC internal compiler routine: AnsiStr_sint

Declaration: `procedure fpc_AnsiStr_sint(v: ValSInt; Len: SizeInt; out S: AnsiString)`

Visibility: default

29.9.83 fpc_ansistr_to_chararray

Synopsis: FPC internal compiler routine: ansistr_to_chararray

Declaration: `function fpc_ansistr_to_chararray(arraysize: SizeInt;
const src: ansistring)
: fpc_big_chararray`

Visibility: default

29.9.84 fpc_AnsiStr_To_ShortStr

Synopsis: FPC internal compiler routine: AnsiStr_To_ShortStr

Declaration: `function fpc_AnsiStr_To_ShortStr(high_of_res: SizeInt;
const S2: AnsiString) : shortstring`

Visibility: default

29.9.85 fpc_ansistr_to_widechararray

Synopsis: FPC internal compiler routine: ansistr_to_widechararray

Declaration: `function fpc_ansistr_to_widechararray(arraysize: SizeInt;
const src: AnsiString)
: fpc_big_widechararray`

Visibility: default

29.9.86 fpc_AnsiStr_To_WideStr

Synopsis: FPC internal compiler routine: AnsiStr_To_WideStr

Declaration: `function fpc_AnsiStr_To_WideStr(const S2: AnsiString) : WideString`

Visibility: default

29.9.87 fpc_AnsiStr_uint

Synopsis: FPC internal compiler routine: AnsiStr_uint

Declaration: `procedure fpc_AnsiStr_uint(v: ValUInt; Len: SizeInt; out S: AnsiString)`

Visibility: default

29.9.88 fpc_ansistr_Unique

Synopsis: FPC internal compiler routine: ansistr_Unique

Declaration: `function fpc_ansistr_Unique(var S: Pointer) : Pointer`

Visibility: default

29.9.89 fpc_arctan_real

Synopsis: FPC internal compiler routine: arctan_real

Declaration: `function fpc_arctan_real(d: ValReal) : ValReal`

Visibility: default

29.9.90 fpc_assert

Synopsis: FPC internal compiler routine: assert

Declaration: `procedure fpc_assert(const Msg: Shortstring; const FName: Shortstring;
LineNo: LongInt; ErrorAddr: Pointer)`

Visibility: default

29.9.91 fpc_Catches

Synopsis: FPC internal compiler routine: Catches

Declaration: `function fpc_Catches(Objtype: TClass) : TObject`

Visibility: default

29.9.92 fpc_chararray_Float

Synopsis: FPC internal compiler routine: chararray_Float

Declaration: `procedure fpc_chararray_Float(d: ValReal; len: SizeInt; fr: SizeInt;
rt: SizeInt; out a: Array[] of Char)`

Visibility: default

29.9.93 fpc_chararray_int64

Synopsis: FPC internal compiler routine: chararray_int64

Declaration: `procedure fpc_chararray_int64(v: Int64; len: SizeInt;
out a: Array[] of Char)`

Visibility: default

29.9.94 fpc_chararray_qword

Synopsis: FPC internal compiler routine: chararray_qword

Declaration: `procedure fpc_chararray_qword(v: qword; len: SizeInt;
out a: Array[] of Char)`

Visibility: default

29.9.95 fpc_chararray_sint

Synopsis: FPC internal compiler routine: chararray_sint

Declaration: `procedure fpc_chararray_sint(v: ValSInt; len: SizeInt;
out a: Array[] of Char)`

Visibility: default

29.9.102 fpc_Char_To_WideStr

Synopsis: FPC internal compiler routine: Char_To_WideStr

Declaration: `function fpc_Char_To_WideStr(const c: WideChar) : WideString`

Visibility: default

29.9.103 fpc_class_as_intf

Synopsis: FPC internal compiler routine: class_as_intf

Declaration: `function fpc_class_as_intf(const S: pointer;const iid: TGuid)
: IInterface`

Visibility: default

29.9.104 fpc_cos_real

Synopsis: FPC internal compiler routine: cos_real

Declaration: `function fpc_cos_real(d: ValReal) : ValReal`

Visibility: default

29.9.105 fpc_DecRef

Synopsis: FPC internal compiler routine: DecRef

Declaration: `procedure fpc_DecRef(Data: Pointer;TypeInfo: Pointer)`

Visibility: default

29.9.106 fpc_divbyzero

Synopsis: FPC internal compiler routine: divbyzero

Declaration: `procedure fpc_divbyzero`

Visibility: default

29.9.107 fpc_div_int64

Synopsis: FPC internal compiler routine: div_int64

Declaration: `function fpc_div_int64(n: Int64;z: Int64) : Int64`

Visibility: default

29.9.108 fpc_div_qword

Synopsis: FPC internal compiler routine: div_qword

Declaration: `function fpc_div_qword(n: qword;z: qword) : qword`

Visibility: default

29.9.109 fpc_do_as

Synopsis: FPC internal compiler routine: do_as

Declaration: `function fpc_do_as(aclass: TClass;aobject: TObject) : TObject`

Visibility: default

29.9.110 fpc_do_is

Synopsis: FPC internal compiler routine: do_is

Declaration: `function fpc_do_is(aclass: TClass;aobject: TObject) : Boolean`

Visibility: default

29.9.111 fpc_dynarray_clear

Synopsis: FPC internal compiler routine: dynarray_clear

Declaration: `procedure fpc_dynarray_clear(var p: pointer;ti: pointer)`

Visibility: default

29.9.112 fpc_dynarray_copy

Synopsis: FPC internal compiler routine: dynarray_copy

Declaration: `function fpc_dynarray_copy(psrc: pointer;ti: pointer;
 lowidx: tdynarrayindex;count: tdynarrayindex)
 : pointer`

Visibility: default

29.9.113 fpc_dynarray_decr_ref

Synopsis: FPC internal compiler routine: dynarray_decr_ref

Declaration: `procedure fpc_dynarray_decr_ref(var p: pointer;ti: pointer)`

Visibility: default

29.9.114 fpc_dynarray_high

Synopsis: FPC internal compiler routine: dynarray_high

Declaration: `function fpc_dynarray_high(p: pointer) : tdynarrayindex`

Visibility: default

29.9.115 fpc_dynarray_incr_ref

Synopsis: FPC internal compiler routine: dynarray_incr_ref

Declaration: `procedure fpc_dynarray_incr_ref(p: pointer)`

Visibility: default

29.9.116 fpc_dynarray_length

Synopsis: FPC internal compiler routine: dynarray_length

Declaration: `function fpc_dynarray_length(p: pointer) : tdynarrayindex`

Visibility: default

29.9.117 fpc_dynarray_setlength

Synopsis: FPC internal compiler routine: dynarray_setlength

Declaration: `procedure fpc_dynarray_setlength(var p: pointer;pti: pointer;
dimcount: DWord;dims: pdynarrayindex)`

Visibility: default

29.9.118 fpc_dynarray_to_variant

Synopsis: FPC internal compiler routine: dynarray_to_variant

Declaration: `function fpc_dynarray_to_variant(dynarr: pointer;typeinfo: pointer)
: variant`

Visibility: default

29.9.119 fpc_exp_real

Synopsis: FPC internal compiler routine: exp_real

Declaration: `function fpc_exp_real(d: ValReal) : ValReal`

Visibility: default

29.9.120 fpc_finalize

Synopsis: FPC internal compiler routine: finalize

Declaration: `procedure fpc_finalize(Data: Pointer;TypeInfo: Pointer)`

Visibility: default

29.9.121 fpc_finalize_array

Synopsis: FPC internal compiler routine: finalize_array

Declaration: `procedure fpc_finalize_array(data: pointer;typeinfo: pointer;
count: LongInt;size: LongInt)`

Visibility: default

29.9.122 fpc_frac_real

Synopsis: FPC internal compiler routine: frac_real

Declaration: `function fpc_frac_real(d: ValReal) : ValReal`

Visibility: default

29.9.123 fpc_freemem

Synopsis: FPC internal compiler routine: freemem

Declaration: `procedure fpc_freemem(p: pointer)`

Visibility: default

29.9.124 fpc_getmem

Synopsis: FPC internal compiler routine: getmem

Declaration: `function fpc_getmem(size: PtrInt) : pointer`

Visibility: default

29.9.125 fpc_get_input

Synopsis: FPC internal compiler routine: get_input

Declaration: `function fpc_get_input : PText`

Visibility: default

29.9.126 fpc_get_output

Synopsis: FPC internal compiler routine: get_output

Declaration: `function fpc_get_output : PText`

Visibility: default

29.9.127 fpc_help_constructor

Synopsis: FPC internal compiler routine: help_constructor

Declaration: `function fpc_help_constructor(_self: pointer; var _vmt: pointer;
_vmt_pos: Cardinal) : pointer`

Visibility: default

29.9.128 fpc_help_destructor

Synopsis: FPC internal compiler routine: help_destructor

Declaration: `procedure fpc_help_destructor(_self: pointer; _vmt: pointer;
vmt_pos: Cardinal)`

Visibility: default

29.9.129 fpc_help_fail

Synopsis: FPC internal compiler routine: help_fail

Declaration: `procedure fpc_help_fail(_self: pointer; var _vmt: pointer;
vmt_pos: Cardinal)`

Visibility: default

29.9.130 fpc_Initialize

Synopsis: FPC internal compiler routine: Initialize

Declaration: `procedure fpc_Initialize(Data: pointer;TypeInfo: pointer)`

Visibility: default

29.9.131 fpc_InitializeUnits

Synopsis: FPC internal compiler routine: InitializeUnits

Declaration: `procedure fpc_InitializeUnits`

Visibility: default

29.9.132 fpc_interface_to_variant

Synopsis: FPC internal compiler routine: interface_to_variant

Declaration: `function fpc_interface_to_variant(const i: IInterface) : variant`

Visibility: default

29.9.133 fpc_intf_as

Synopsis: FPC internal compiler routine: intf_as

Declaration: `function fpc_intf_as(const S: pointer;const iid: TGuid) : IInterface`

Visibility: default

29.9.134 fpc_intf_assign

Synopsis: FPC internal compiler routine: intf_assign

Declaration: `procedure fpc_intf_assign(var D: pointer;const S: pointer)`

Visibility: default

29.9.135 fpc_intf_decr_ref

Synopsis: FPC internal compiler routine: intf_decr_ref

Declaration: `procedure fpc_intf_decr_ref(var i: pointer)`

Visibility: default

29.9.136 fpc_intf_incr_ref

Synopsis: FPC internal compiler routine: intf_incr_ref

Declaration: `procedure fpc_intf_incr_ref(i: pointer)`

Visibility: default

29.9.137 fpc_int_real

Synopsis: FPC internal compiler routine: `int_real`

Declaration: `function fpc_int_real(d: ValReal) : ValReal`

Visibility: `default`

29.9.138 fpc_iocheck

Synopsis: FPC internal compiler routine: `iocheck`

Declaration: `procedure fpc_iocheck`

Visibility: `default`

29.9.139 fpc_ln_real

Synopsis: FPC internal compiler routine: `ln_real`

Declaration: `function fpc_ln_real(d: ValReal) : ValReal`

Visibility: `default`

29.9.140 fpc_mod_int64

Synopsis: FPC internal compiler routine: `mod_int64`

Declaration: `function fpc_mod_int64(n: Int64; z: Int64) : Int64`

Visibility: `default`

29.9.141 fpc_mod_qword

Synopsis: FPC internal compiler routine: `mod_qword`

Declaration: `function fpc_mod_qword(n: qword; z: qword) : qword`

Visibility: `default`

29.9.142 fpc_mul_int64

Synopsis: FPC internal compiler routine: `mul_int64`

Declaration: `function fpc_mul_int64(f1: Int64; f2: Int64; checkoverflow: longbool)
: Int64`

Visibility: `default`

29.9.143 fpc_mul_qword

Synopsis: FPC internal compiler routine: `mul_qword`

Declaration: `function fpc_mul_qword(f1: qword; f2: qword; checkoverflow: longbool)
: qword`

Visibility: `default`

29.9.144 fpc_overflow

Synopsis: FPC internal compiler routine: overflow

Declaration: `procedure fpc_overflow`

Visibility: default

29.9.145 fpc_pchar_length

Synopsis: FPC internal compiler routine: pchar_length

Declaration: `function fpc_pchar_length(p: PChar) : LongInt`

Visibility: default

29.9.146 fpc_PChar_To_AnsiStr

Synopsis: FPC internal compiler routine: PChar_To_AnsiStr

Declaration: `function fpc_PChar_To_AnsiStr(const p: PChar) : ansistring`

Visibility: default

29.9.147 fpc_pchar_to_shortstr

Synopsis: FPC internal compiler routine: pchar_to_shortstr

Declaration: `function fpc_pchar_to_shortstr(p: PChar) : shortstring`

Visibility: default

29.9.148 fpc_PChar_To_WideStr

Synopsis: FPC internal compiler routine: PChar_To_WideStr

Declaration: `function fpc_PChar_To_WideStr(const p: PChar) : WideString`

Visibility: default

29.9.149 fpc_pi_real

Synopsis: FPC internal compiler routine: pi_real

Declaration: `function fpc_pi_real : ValReal`

Visibility: default

29.9.150 fpc_PopAddrStack

Synopsis: FPC internal compiler routine: PopAddrStack

Declaration: `procedure fpc_PopAddrStack`

Visibility: default

29.9.151 fpc_PopObjectStack

Synopsis: FPC internal compiler routine: PopObjectStack

Declaration: `function fpc_PopObjectStack : TObject`

Visibility: default

29.9.152 fpc_PopSecondObjectStack

Synopsis: FPC internal compiler routine: PopSecondObjectStack

Declaration: `function fpc_PopSecondObjectStack : TObject`

Visibility: default

29.9.153 fpc_PushExceptAddr

Synopsis: FPC internal compiler routine: PushExceptAddr

Declaration: `function fpc_PushExceptAddr (Ft: LongInt; _buf: pointer; _newaddr: pointer)
: PJump_buf`

Visibility: default

29.9.154 fpc_PushExceptObj

Synopsis: FPC internal compiler routine: PushExceptObj

Declaration: `procedure fpc_PushExceptObj (Obj: TObject; AnAddr: Pointer;
AFrame: Pointer)`

Visibility: default

29.9.155 fpc_pwchar_length

Synopsis: FPC internal compiler routine: pwchar_length

Declaration: `function fpc_pwchar_length(p: PWideChar) : LongInt`

Visibility: default

29.9.156 fpc_PWideChar_To_AnsiStr

Synopsis: FPC internal compiler routine: PWideChar_To_AnsiStr

Declaration: `function fpc_PWideChar_To_AnsiStr(const p: PWideChar) : ansistring`

Visibility: default

29.9.157 fpc_PWideChar_To_ShortStr

Synopsis: FPC internal compiler routine: PWideChar_To_ShortStr

Declaration: `function fpc_PWideChar_To_ShortStr(const p: PWideChar) : shortstring`

Visibility: default

29.9.158 fpc_PWideChar_To_WideStr

Synopsis: FPC internal compiler routine: PWideChar_To_WideStr

Declaration: `function fpc_PWideChar_To_WideStr(const p: PWideChar) : widestring`

Visibility: default

29.9.159 fpc_Raiseexception

Synopsis: FPC internal compiler routine: Raiseexception

Declaration: `function fpc_Raiseexception(Obj: TObject; AnAddr: Pointer;
AFrame: Pointer) : TObject`

Visibility: default

29.9.160 fpc_rangeerror

Synopsis: FPC internal compiler routine: rangeerror

Declaration: `procedure fpc_rangeerror`

Visibility: default

29.9.161 fpc_ReadLn_End

Synopsis: FPC internal compiler routine: ReadLn_End

Declaration: `procedure fpc_ReadLn_End(var f: Text)`

Visibility: default

29.9.162 fpc_Read_End

Synopsis: FPC internal compiler routine: Read_End

Declaration: `procedure fpc_Read_End(var f: Text)`

Visibility: default

29.9.163 fpc_Read_Text_AnsiStr

Synopsis: FPC internal compiler routine: Read_Text_AnsiStr

Declaration: `procedure fpc_Read_Text_AnsiStr(var f: Text; out s: AnsiString)`

Visibility: default

29.9.164 fpc_Read_Text_Char

Synopsis: FPC internal compiler routine: Read_Text_Char

Declaration: `procedure fpc_Read_Text_Char(var f: Text; out c: Char)`

Visibility: default

29.9.165 fpc_Read_Text_Float

Synopsis: FPC internal compiler routine: Read_Text_Float

Declaration: `procedure fpc_Read_Text_Float(var f: Text; out v: ValReal)`

Visibility: default

29.9.166 fpc_Read_Text_Int64

Synopsis: FPC internal compiler routine: Read_Text_Int64

Declaration: `procedure fpc_Read_Text_Int64(var f: text; out i: Int64)`

Visibility: default

29.9.167 fpc_Read_Text_PChar_As_Array

Synopsis: FPC internal compiler routine: Read_Text_PChar_As_Array

Declaration: `procedure fpc_Read_Text_PChar_As_Array(var f: Text;
out s: Array[] of Char)`

Visibility: default

29.9.168 fpc_Read_Text_PChar_As_Pointer

Synopsis: FPC internal compiler routine: Read_Text_PChar_As_Pointer

Declaration: `procedure fpc_Read_Text_PChar_As_Pointer(var f: Text; const s: PChar)`

Visibility: default

29.9.169 fpc_Read_Text_QWord

Synopsis: FPC internal compiler routine: Read_Text_QWord

Declaration: `procedure fpc_Read_Text_QWord(var f: text; out q: qword)`

Visibility: default

29.9.170 fpc_Read_Text_ShortStr

Synopsis: FPC internal compiler routine: Read_Text_ShortStr

Declaration: `procedure fpc_Read_Text_ShortStr(var f: Text; out s: String)`

Visibility: default

29.9.171 fpc_Read_Text_SInt

Synopsis: FPC internal compiler routine: Read_Text_SInt

Declaration: `procedure fpc_Read_Text_SInt(var f: Text; out l: ValSInt)`

Visibility: default

29.9.172 fpc_Read_Text_UInt

Synopsis: FPC internal compiler routine: Read_Text_UInt

Declaration: `procedure fpc_Read_Text_UInt (var f: Text; out u: ValUInt)`

Visibility: default

29.9.173 fpc_ReRaise

Synopsis: FPC internal compiler routine: ReRaise

Declaration: `procedure fpc_ReRaise`

Visibility: default

29.9.174 fpc_reset_typed

Synopsis: FPC internal compiler routine: reset_typed

Declaration: `procedure fpc_reset_typed (var f: TypedFile; Size: LongInt)`

Visibility: default

29.9.175 fpc_rewrite_typed

Synopsis: FPC internal compiler routine: rewrite_typed

Declaration: `procedure fpc_rewrite_typed (var f: TypedFile; Size: LongInt)`

Visibility: default

29.9.176 fpc_round_real

Synopsis: FPC internal compiler routine: round_real

Declaration: `function fpc_round_real (d: ValReal) : Int64`

Visibility: default

29.9.177 fpc_set_add_sets

Synopsis: FPC internal compiler routine: set_add_sets

Declaration: `function fpc_set_add_sets (const set1: fpc_normal_set;
const set2: fpc_normal_set) : fpc_normal_set`

Visibility: default

29.9.178 fpc_set_comp_sets

Synopsis: FPC internal compiler routine: set_comp_sets

Declaration: `function fpc_set_comp_sets (const set1: fpc_normal_set;
const set2: fpc_normal_set) : Boolean`

Visibility: default

29.9.179 fpc_set_contains_sets

Synopsis: FPC internal compiler routine: set_contains_sets

Declaration: `function fpc_set_contains_sets(const set1: fpc_normal_set;
const set2: fpc_normal_set) : Boolean`

Visibility: default

29.9.180 fpc_set_create_element

Synopsis: FPC internal compiler routine: set_create_element

Declaration: `function fpc_set_create_element(b: Byte) : fpc_normal_set`

Visibility: default

29.9.181 fpc_set_in_byte

Synopsis: FPC internal compiler routine: set_in_byte

Declaration: `function fpc_set_in_byte(const p: fpc_normal_set; b: Byte) : Boolean`

Visibility: default

29.9.182 fpc_set_load_small

Synopsis: FPC internal compiler routine: set_load_small

Declaration: `function fpc_set_load_small(l: fpc_small_set) : fpc_normal_set`

Visibility: default

29.9.183 fpc_set_mul_sets

Synopsis: FPC internal compiler routine: set_mul_sets

Declaration: `function fpc_set_mul_sets(const set1: fpc_normal_set;
const set2: fpc_normal_set) : fpc_normal_set`

Visibility: default

29.9.184 fpc_set_set_byte

Synopsis: FPC internal compiler routine: set_set_byte

Declaration: `function fpc_set_set_byte(const source: fpc_normal_set; b: Byte)
: fpc_normal_set`

Visibility: default

29.9.185 fpc_set_set_range

Synopsis: FPC internal compiler routine: set_set_range

Declaration: `function fpc_set_set_range(const orgset: fpc_normal_set; l: Byte; h: Byte)
: fpc_normal_set`

Visibility: default

29.9.186 fpc_set_sub_sets

Synopsis: FPC internal compiler routine: set_sub_sets

Declaration: `function fpc_set_sub_sets(const set1: fpc_normal_set;
const set2: fpc_normal_set) : fpc_normal_set`

Visibility: default

29.9.187 fpc_set_symdif_sets

Synopsis: FPC internal compiler routine: set_symdif_sets

Declaration: `function fpc_set_symdif_sets(const set1: fpc_normal_set;
const set2: fpc_normal_set) : fpc_normal_set`

Visibility: default

29.9.188 fpc_set_unset_byte

Synopsis: FPC internal compiler routine: set_unset_byte

Declaration: `function fpc_set_unset_byte(const source: fpc_normal_set; b: Byte)
: fpc_normal_set`

Visibility: default

29.9.189 fpc_shortstr_append_shortstr

Synopsis: FPC internal compiler routine: shortstr_append_shortstr

Declaration: `procedure fpc_shortstr_append_shortstr(var s1: shortstring;
const s2: shortstring)`

Visibility: default

29.9.190 fpc_shortstr_compare

Synopsis: FPC internal compiler routine: shortstr_compare

Declaration: `function fpc_shortstr_compare(const left: shortstring;
const right: shortstring) : LongInt`

Visibility: default

29.9.191 fpc_shortstr_concat

Synopsis: FPC internal compiler routine: shortstr_concat

Declaration: `function fpc_shortstr_concat(const s1: shortstring;
const s2: shortstring) : shortstring`

Visibility: default

29.9.192 fpc_shortstr_Copy

Synopsis: FPC internal compiler routine: shortstr_Copy

Declaration: `function fpc_shortstr_Copy(const s: shortstring; index: SizeInt;
count: SizeInt) : shortstring`

Visibility: default

29.9.193 fpc_ShortStr_Float

Synopsis: FPC internal compiler routine: ShortStr_Float

Declaration: `procedure fpc_ShortStr_Float(d: ValReal; len: SizeInt; fr: SizeInt;
rt: SizeInt; out s: shortstring)`

Visibility: default

29.9.194 fpc_shortstr_int64

Synopsis: FPC internal compiler routine: shortstr_int64

Declaration: `procedure fpc_shortstr_int64(v: Int64; len: SizeInt; out s: shortstring)`

Visibility: default

29.9.195 fpc_shortstr_qword

Synopsis: FPC internal compiler routine: shortstr_qword

Declaration: `procedure fpc_shortstr_qword(v: qword; len: SizeInt; out s: shortstring)`

Visibility: default

29.9.196 fpc_Shortstr_SetLength

Synopsis: FPC internal compiler routine: Shortstr_SetLength

Declaration: `procedure fpc_Shortstr_SetLength(var s: shortstring; len: SizeInt)`

Visibility: default

29.9.197 fpc_ShortStr_sint

Synopsis: FPC internal compiler routine: ShortStr_sint

Declaration: `procedure fpc_ShortStr_sint(v: ValSInt; len: SizeInt; out s: shortstring)`

Visibility: default

29.9.198 fpc_ShortStr_To_AnsiStr

Synopsis: FPC internal compiler routine: ShortStr_To_AnsiStr

Declaration: `function fpc_ShortStr_To_AnsiStr(const S2: ShortString) : ansistring`

Visibility: default

29.9.199 fpc_shortstr_to_chararray

Synopsis: FPC internal compiler routine: shortstr_to_chararray

Declaration: `function fpc_shortstr_to_chararray(arraysize: LongInt;
const src: ShortString)
: fpc_big_chararray`

Visibility: default

29.9.200 fpc_shortstr_to_shortstr

Synopsis: FPC internal compiler routine: shortstr_to_shortstr

Declaration: `function fpc_shortstr_to_shortstr(len: LongInt;const sstr: shortstring)
: shortstring`

Visibility: default

29.9.201 fpc_shortstr_to_widechararray

Synopsis: FPC internal compiler routine: shortstr_to_widechararray

Declaration: `function fpc_shortstr_to_widechararray(arraysize: SizeInt;
const src: ShortString)
: fpc_big_widechararray`

Visibility: default

29.9.202 fpc_ShortStr_To_WideStr

Synopsis: FPC internal compiler routine: ShortStr_To_WideStr

Declaration: `function fpc_ShortStr_To_WideStr(const S2: ShortString) : WideString`

Visibility: default

29.9.203 fpc_shortstr_uint

Synopsis: FPC internal compiler routine: shortstr_uint

Declaration: `procedure fpc_shortstr_uint(v: ValUInt;len: SizeInt;out s: shortstring)`

Visibility: default

29.9.204 fpc_sin_real

Synopsis: FPC internal compiler routine: sin_real

Declaration: `function fpc_sin_real(d: ValReal) : ValReal`

Visibility: default

29.9.205 fpc_sqrt_real

Synopsis: FPC internal compiler routine: sqrt_real

Declaration: `function fpc_sqrt_real(d: ValReal) : ValReal`

Visibility: default

29.9.206 fpc_sqr_real

Synopsis: FPC internal compiler routine: sqr_real

Declaration: `function fpc_sqr_real(d: ValReal) : ValReal`

Visibility: default

29.9.207 fpc_trunc_real

Synopsis: FPC internal compiler routine: trunc_real

Declaration: `function fpc_trunc_real(d: ValReal) : Int64`

Visibility: default

29.9.208 fpc_typed_read

Synopsis: FPC internal compiler routine: typed_read

Declaration: `procedure fpc_typed_read(BufferSize: LongInt; var f: TypedFile; out Buf)`

Visibility: default

29.9.209 fpc_typed_write

Synopsis: FPC internal compiler routine: typed_write

Declaration: `procedure fpc_typed_write(BufferSize: LongInt; var f: TypedFile; const Buf)`

Visibility: default

29.9.210 fpc_Val_int64_AnsiStr

Synopsis: FPC internal compiler routine: Val_int64_AnsiStr

Declaration: `function fpc_Val_int64_AnsiStr(const S: AnsiString; out Code: ValSInt)
: Int64`

Visibility: default

29.9.211 **fpc_val_int64_shortstr**

Synopsis: FPC internal compiler routine: val_int64_shortstr

Declaration: `function fpc_val_int64_shortstr(const S: ShortString;out Code: ValSInt)
: Int64`

Visibility: default

29.9.212 **fpc_Val_int64_WideStr**

Synopsis: FPC internal compiler routine: Val_int64_WideStr

Declaration: `function fpc_Val_int64_WideStr(const S: WideString;out Code: ValSInt)
: Int64`

Visibility: default

29.9.213 **fpc_Val_qword_AnsiStr**

Synopsis: FPC internal compiler routine: Val_qword_AnsiStr

Declaration: `function fpc_Val_qword_AnsiStr(const S: AnsiString;out Code: ValSInt)
: qword`

Visibility: default

29.9.214 **fpc_val_qword_shortstr**

Synopsis: FPC internal compiler routine: val_qword_shortstr

Declaration: `function fpc_val_qword_shortstr(const S: ShortString;out Code: ValSInt)
: QWord`

Visibility: default

29.9.215 **fpc_Val_qword_WideStr**

Synopsis: FPC internal compiler routine: Val_qword_WideStr

Declaration: `function fpc_Val_qword_WideStr(const S: WideString;out Code: ValSInt)
: qword`

Visibility: default

29.9.216 **fpc_Val_Real_AnsiStr**

Synopsis: FPC internal compiler routine: Val_Real_AnsiStr

Declaration: `function fpc_Val_Real_AnsiStr(const S: AnsiString;out Code: ValSInt)
: ValReal`

Visibility: default

29.9.217 fpc_Val_Real_ShortStr

Synopsis: FPC internal compiler routine: Val_Real_ShortStr

Declaration: `function fpc_Val_Real_ShortStr(const s: shortstring; out code: ValSInt)
: ValReal`

Visibility: default

29.9.218 fpc_Val_Real_WideStr

Synopsis: FPC internal compiler routine: Val_Real_WideStr

Declaration: `function fpc_Val_Real_WideStr(const S: WideString; out Code: ValSInt)
: ValReal`

Visibility: default

29.9.219 fpc_Val_SInt_AnsiStr

Synopsis: FPC internal compiler routine: Val_SInt_AnsiStr

Declaration: `function fpc_Val_SInt_AnsiStr(DestSize: SizeInt; const S: AnsiString;
out Code: ValSInt) : ValSInt`

Visibility: default

29.9.220 fpc_Val_SInt_ShortStr

Synopsis: FPC internal compiler routine: Val_SInt_ShortStr

Declaration: `function fpc_Val_SInt_ShortStr(DestSize: SizeInt; const S: ShortString;
out Code: ValSInt) : ValSInt`

Visibility: default

29.9.221 fpc_Val_SInt_WideStr

Synopsis: FPC internal compiler routine: Val_SInt_WideStr

Declaration: `function fpc_Val_SInt_WideStr(DestSize: SizeInt; const S: WideString;
out Code: ValSInt) : ValSInt`

Visibility: default

29.9.222 fpc_Val_UInt_AnsiStr

Synopsis: FPC internal compiler routine: Val_UInt_AnsiStr

Declaration: `function fpc_Val_UInt_AnsiStr(const S: AnsiString; out Code: ValSInt)
: ValUInt`

Visibility: default

29.9.223 fpc_Val_UInt_Shortstr

Synopsis: FPC internal compiler routine: Val_UInt_Shortstr

Declaration: `function fpc_Val_UInt_Shortstr(const S: ShortString; out Code: ValSInt)
: ValUInt`

Visibility: default

29.9.224 fpc_Val_UInt_WideStr

Synopsis: FPC internal compiler routine: Val_UInt_WideStr

Declaration: `function fpc_Val_UInt_WideStr(const S: WideString; out Code: ValSInt)
: ValUInt`

Visibility: default

29.9.225 fpc_vararray_get

Synopsis: FPC internal compiler routine: vararray_get

Declaration: `procedure fpc_vararray_get(var d: variant; const s: variant;
indices: PSizeInt; len: SizeInt)`

Visibility: default

29.9.226 fpc_vararray_put

Synopsis: FPC internal compiler routine: vararray_put

Declaration: `procedure fpc_vararray_put(var d: variant; const s: variant;
indices: PSizeInt; len: SizeInt)`

Visibility: default

29.9.227 fpc_variant_copy

Synopsis: FPC internal compiler routine: variant_copy

Declaration: `procedure fpc_variant_copy(d: pointer; s: pointer)`

Visibility: default

29.9.228 fpc_variant_to_dynarray

Synopsis: FPC internal compiler routine: variant_to_dynarray

Declaration: `function fpc_variant_to_dynarray(const v: variant; typeinfo: pointer)
: pointer`

Visibility: default

29.9.229 fpc_variant_to_interface

Synopsis: FPC internal compiler routine: variant_to_interface

Declaration: `function fpc_variant_to_interface(const v: variant) : IInterface`

Visibility: default

29.9.230 fpc_WideCharArray_To_AnsiStr

Synopsis: FPC internal compiler routine: WideCharArray_To_AnsiStr

Declaration: `function fpc_WideCharArray_To_AnsiStr(const arr: Array[] of widechar;
zerobased: Boolean) : AnsiString`

Visibility: default

29.9.231 fpc_WideCharArray_To_ShortStr

Synopsis: FPC internal compiler routine: WideCharArray_To_ShortStr

Declaration: `function fpc_WideCharArray_To_ShortStr(const arr: Array[] of widechar;
zerobased: Boolean) : shortstring`

Visibility: default

29.9.232 fpc_WideCharArray_To_WideStr

Synopsis: FPC internal compiler routine: WideCharArray_To_WideStr

Declaration: `function fpc_WideCharArray_To_WideStr(const arr: Array[] of widechar;
zerobased: Boolean) : WideString`

Visibility: default

29.9.233 fpc_WideStr_Assign

Synopsis: FPC internal compiler routine: WideStr_Assign

Declaration: `procedure fpc_WideStr_Assign(var S1: Pointer; S2: Pointer)`

Visibility: default

29.9.234 fpc_WideStr_CheckRange

Synopsis: FPC internal compiler routine: WideStr_CheckRange

Declaration: `procedure fpc_WideStr_CheckRange(len: SizeInt; index: SizeInt)`

Visibility: default

29.9.235 fpc_WideStr_CheckZero

Synopsis: FPC internal compiler routine: WideStr_CheckZero

Declaration: `procedure fpc_WideStr_CheckZero(p: pointer)`

Visibility: default

29.9.236 fpc_WideStr_Compare

Synopsis: FPC internal compiler routine: WideStr_Compare

Declaration: `function fpc_WideStr_Compare(const S1: WideString;const S2: WideString)
: SizeInt`

Visibility: default

29.9.237 fpc_WideStr_Concat

Synopsis: FPC internal compiler routine: WideStr_Concat

Declaration: `function fpc_WideStr_Concat(const S1: WideString;const S2: WideString)
: WideString`

Visibility: default

29.9.238 fpc_widestr_Copy

Synopsis: FPC internal compiler routine: widestr_Copy

Declaration: `function fpc_widestr_Copy(const S: WideString;Index: SizeInt;
Size: SizeInt) : WideString`

Visibility: default

29.9.239 fpc_WideStr_Decr_Ref

Synopsis: FPC internal compiler routine: WideStr_Decr_Ref

Declaration: `procedure fpc_WideStr_Decr_Ref(var S: Pointer)`

Visibility: default

29.9.240 fpc_WideStr_Float

Synopsis: FPC internal compiler routine: WideStr_Float

Declaration: `procedure fpc_WideStr_Float(d: ValReal;len: SizeInt;fr: SizeInt;
rt: SizeInt;out s: WideString)`

Visibility: default

29.9.241 fpc_WideStr_Incr_Ref

Synopsis: FPC internal compiler routine: WideStr_Incr_Ref

Declaration: `procedure fpc_WideStr_Incr_Ref(S: Pointer)`

Visibility: default

29.9.242 fpc_widestr_int64

Synopsis: FPC internal compiler routine: `widestr_int64`

Declaration: `procedure fpc_widestr_int64(v: Int64; len: SizeInt; out s: widestring)`

Visibility: default

29.9.243 fpc_widestr_qword

Synopsis: FPC internal compiler routine: `widestr_qword`

Declaration: `procedure fpc_widestr_qword(v: qword; len: SizeInt; out s: widestring)`

Visibility: default

29.9.244 fpc_WideStr_SetLength

Synopsis: FPC internal compiler routine: `WideStr_SetLength`

Declaration: `procedure fpc_WideStr_SetLength(var S: WideString; l: SizeInt)`

Visibility: default

29.9.245 fpc_WideStr_sint

Synopsis: FPC internal compiler routine: `WideStr_sint`

Declaration: `procedure fpc_WideStr_sint(v: ValSInt; Len: SizeInt; out S: WideString)`

Visibility: default

29.9.246 fpc_WideStr_To_AnsiStr

Synopsis: FPC internal compiler routine: `WideStr_To_AnsiStr`

Declaration: `function fpc_WideStr_To_AnsiStr(const S2: WideString) : AnsiString`

Visibility: default

29.9.247 fpc_widestr_to_chararray

Synopsis: FPC internal compiler routine: `widestr_to_chararray`

Declaration: `function fpc_widestr_to_chararray(arraysize: SizeInt;
const src: WideString)
: fpc_big_chararray`

Visibility: default

29.9.248 fpc_WideStr_To_ShortStr

Synopsis: FPC internal compiler routine: `WideStr_To_ShortStr`

Declaration: `function fpc_WideStr_To_ShortStr(high_of_res: SizeInt;
const S2: WideString) : shortstring`

Visibility: default

29.9.249 fpc_widestr_to_widechararray

Synopsis: FPC internal compiler routine: widestr_to_widechararray

Declaration: `function fpc_widestr_to_widechararray(arraysize: SizeInt;
const src: WideString)
: fpc_big_widechararray`

Visibility: default

29.9.250 fpc_WideStr_uint

Synopsis: FPC internal compiler routine: WideStr_uint

Declaration: `procedure fpc_WideStr_uint(v: ValUInt; Len: SizeInt; out S: WideString)`

Visibility: default

29.9.251 fpc_widestr_Unique

Synopsis: FPC internal compiler routine: widestr_Unique

Declaration: `function fpc_widestr_Unique(var S: Pointer) : Pointer`

Visibility: default

29.9.252 fpc_Writeln_End

Synopsis: FPC internal compiler routine: Writeln_End

Declaration: `procedure fpc_Writeln_End(var f: Text)`

Visibility: default

29.9.253 fpc_Write_End

Synopsis: FPC internal compiler routine: Write_End

Declaration: `procedure fpc_Write_End(var f: Text)`

Visibility: default

29.9.254 fpc_Write_Text_AnsiStr

Synopsis: FPC internal compiler routine: Write_Text_AnsiStr

Declaration: `procedure fpc_Write_Text_AnsiStr(Len: LongInt; var f: Text;
const S: AnsiString)`

Visibility: default

29.9.255 fpc_Write_Text_Boolean

Synopsis: FPC internal compiler routine: Write_Text_Boolean

Declaration: `procedure fpc_Write_Text_Boolean(Len: LongInt; var t: Text; b: Boolean)`

Visibility: default

29.9.256 fpc_Write_Text_Char

Synopsis: FPC internal compiler routine: Write_Text_Char

Declaration: `procedure fpc_Write_Text_Char(Len: LongInt; var t: Text; c: Char)`

Visibility: default

29.9.257 fpc_Write_Text_Float

Synopsis: FPC internal compiler routine: Write_Text_Float

Declaration: `procedure fpc_Write_Text_Float(rt: LongInt; fixkomma: LongInt;
Len: LongInt; var t: Text; r: ValReal)`

Visibility: default

29.9.258 fpc_write_text_int64

Synopsis: FPC internal compiler routine: write_text_int64

Declaration: `procedure fpc_write_text_int64(len: LongInt; var t: text; i: Int64)`

Visibility: default

29.9.259 fpc_Write_Text_Pchar_as_Array

Synopsis: FPC internal compiler routine: Write_Text_Pchar_as_Array

Declaration: `procedure fpc_Write_Text_Pchar_as_Array(Len: LongInt; var f: Text;
const s: Array[] of Char;
zerobased: Boolean)`

Visibility: default

29.9.260 fpc_Write_Text_PChar_As_Pointer

Synopsis: FPC internal compiler routine: Write_Text_PChar_As_Pointer

Declaration: `procedure fpc_Write_Text_PChar_As_Pointer(Len: LongInt; var f: Text;
p: PChar)`

Visibility: default

29.9.261 fpc_write_text_qword

Synopsis: FPC internal compiler routine: write_text_qword

Declaration: `procedure fpc_write_text_qword(len: LongInt; var t: text; q: qword)`

Visibility: default

29.9.262 fpc_Write_Text_ShortStr

Synopsis: FPC internal compiler routine: Write_Text_ShortStr

Declaration: `procedure fpc_Write_Text_ShortStr(Len: LongInt; var f: Text;
const s: String)`

Visibility: default

29.9.263 fpc_Write_Text_SInt

Synopsis: FPC internal compiler routine: Write_Text_SInt

Declaration: `procedure fpc_Write_Text_SInt(Len: LongInt; var t: Text; l: ValSInt)`

Visibility: default

29.9.264 fpc_Write_Text_UInt

Synopsis: FPC internal compiler routine: Write_Text_UInt

Declaration: `procedure fpc_Write_Text_UInt(Len: LongInt; var t: Text; l: ValUInt)`

Visibility: default

29.9.265 fpc_write_text_variant

Synopsis: FPC internal compiler routine: write_text_variant

Declaration: `procedure fpc_write_text_variant(Len: LongInt; var f: Text;
const v: variant)`

Visibility: default

29.9.266 fpc_Write_Text_WideChar

Synopsis: FPC internal compiler routine: Write_Text_WideChar

Declaration: `procedure fpc_Write_Text_WideChar(Len: LongInt; var t: Text; c: WideChar)`

Visibility: default

29.9.267 fpc_Write_Text_WideStr

Synopsis: FPC internal compiler routine: Write_Text_WideStr

Declaration: `procedure fpc_Write_Text_WideStr(Len: LongInt; var f: Text;
const S: WideString)`

Visibility: default

29.9.268 frac

Synopsis: Return fractional part of floating point value.

Declaration: `function frac(d: ValReal) : ValReal`

Visibility: default

Description: `Frac` returns the non-integer part of `X`.

Errors: None.

See also: `Round` ([1237](#)), `Int` ([1192](#))

Listing: `./refex/ex27.pp`

Program `Example27;`

{ Program to demonstrate the Frac function. }

Var `R : Real;`

begin

`WriteLn (Frac (123.456):0:3); { Prints 0.456 }`

`WriteLn (Frac (-123.456):0:3); { Prints -0.456 }`

end.

29.9.269 Freemem

Synopsis: Release allocated memory

Declaration: `procedure Freemem(p: pointer;Size: PtrInt)`
`function Freemem(p: pointer) : PtrInt`

Visibility: default

Description: `Freemem` releases the memory occupied by the pointer `P`, of size `Count` (in bytes), and returns it to the heap. `P` should point to the memory allocated to a dynamic variable.

Errors: An error will occur when `P` doesn't point to the heap.

See also: `Getmem` ([1180](#)), `New` ([1200](#)), `Dispose` ([1133](#))

Listing: `./refex/ex28.pp`

Program `Example28;`

{ Program to demonstrate the FreeMem and GetMem functions. }

Var `P : Pointer;`

`MM : Longint;`

begin

{ Get memory for P }

`GetMem (P,80);`

`FillChar (P^,80,' ');`

`FreeMem (P,80);`

end.

29.9.270 Freememory

Synopsis: Alias for FreeMem ([1178](#))

Declaration: `procedure Freememory(p: pointer; Size: PtrInt)`
`function Freememory(p: pointer) : PtrInt`

Visibility: default

Description: FreeMemory is an alias for FreeMem ([1178](#)).

See also: FreeMem ([1178](#))

29.9.271 FreeResource

Synopsis: Free a loaded resource

Declaration: `function FreeResource(ResData: HGLOBAL) : LongBool`

Visibility: default

Description: FreeResource unloads the resource identified by ResData from memory. The resource must have been loaded by LoadResource ([1196](#)). It returns True if the operation was succesful, False otherwise.

Errors: On error, False is returned.

See also: FindResource ([1145](#)), LoadResource ([1196](#)), SizeofResource ([1248](#)), LockResource ([1197](#)), UnlockResource ([1259](#)), FreeResource ([1179](#))

29.9.272 GetCurrentThreadId

Synopsis: Return the id of the currently running thread.

Declaration: `function GetCurrentThreadId : TThreadId`

Visibility: default

Description: GetCurrentThreadId returns the ID of the currently running thread. It can be used in calls such as KillThread ([1194](#)) or ThreadSetPriority ([1257](#))

Errors: None.

See also: KillThread ([1194](#)), ThreadSetPriority ([1257](#))

29.9.273 getdir

Synopsis: Return the current directory

Declaration: `procedure getdir(drivenr: Byte; var dir: shortstring)`
`procedure getdir(drivenr: Byte; var dir: ansistring)`

Visibility: default

Description: Getdir returns in dir the current directory on the drive drivenr, where {drivenr} is 1 for the first floppy drive, 3 for the first hard disk etc. A value of 0 returns the directory on the current disk. On linux and unix systems, drivenr is ignored, as there is only one directory tree.

Errors: An error is returned under dos, if the drive requested isn't ready.

See also: [Chdir \(1122\)](#)

Listing: ./refex/ex29.pp

```

Program Example29;

{ Program to demonstrate the GetDir function. }

Var S : String;

begin
  GetDir (0,S);
  Writeln ( 'Current directory is : ',S);
end.

```

29.9.274 GetFPCHeapStatus

Synopsis: Return FPC heap manager status information

Declaration: `function GetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: Return FPC heap manager status information

Errors:

29.9.275 GetHeapStatus

Synopsis: Return the memory manager heap status.

Declaration: `function GetHeapStatus : THeapStatus`

Visibility: default

29.9.276 GetMem

Synopsis: Allocate new memory on the heap

Declaration: `procedure Getmem(var p: pointer;Size: PtrInt)`
`function GetMem(size: PtrInt) : pointer`

Visibility: default

Description: `Getmem` reserves `Size` bytes memory on the heap, and returns a pointer to this memory in `p`. If no more memory is available, `nil` is returned.

For an example, see [Freemem \(1178\)](#).

Errors: None.

See also: [Freemem \(1178\)](#), [Dispose \(1133\)](#), [New \(1200\)](#)

29.9.277 GetMemory

Synopsis: Alias for GetMem ([1180](#))

Declaration: `procedure Getmemory(var p: pointer; Size: PtrInt)`
`function GetMemory(size: PtrInt) : pointer`

Visibility: default

Description: `Getmemory` is an alias for `GetMem` ([1180](#)).

See also: `GetMem` ([1180](#))

29.9.278 GetMemoryManager

Synopsis: Return current memory manager

Declaration: `procedure GetMemoryManager(var MemMgr: TMemoryManager)`

Visibility: default

Description: `GetMemoryManager` stores the current Memory Manager record in `MemMgr`.
For an example, see `\progrefer`.

Errors: None.

See also: `SetMemoryManager` ([1243](#)), `IsMemoryManagerSet` ([1194](#))

29.9.279 GetProcessID

Synopsis: Get the current process ID

Declaration: `function GetProcessID : SizeUInt`

Visibility: default

Description: `GetProcessID` returns the current process ID. The meaning of the return value of this call is system dependent.

Errors: None.

See also: `GetThreadID` ([1181](#))

29.9.280 GetThreadID

Synopsis: Get the current Thread ID.

Declaration: `function GetThreadID : TThreadID`

Visibility: default

Description: `GetThreadID` returns the current process ID. The meaning of the return value of this call is system dependent.

See also: `GetProcessID` ([1181](#))

29.9.281 **GetThreadManager**

Synopsis: Return the current thread manager

Declaration: `function GetThreadManager(var TM: TThreadManager) : Boolean`

Visibility: default

Description: `GetThreadManager` returns the currently used thread manager in `TM`.

For more information about thread programming, see the programmer's guide.

See also: `SetThreadManager` ([1246](#)), `TThreadManager` ([1105](#))

29.9.282 **GetVariantManager**

Synopsis: Return the current variant manager.

Declaration: `procedure GetVariantManager(var VarMgr: tvariantmanager)`

Visibility: default

Description: `GetVariantManager` returns the current variant manager in `varmgr`.

See also: `IsVariantManagerSet` ([1194](#)), `SetVariantManager` ([1246](#))

29.9.283 **GetWideStringManager**

Synopsis: Return a copy of the currently active widestring manager.

Declaration: `procedure GetWideStringManager(var Manager: TWideStringManager)`

Visibility: default

Description: `GetWideStringManager` returns a copy of the currently active heap manager in `Old`

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `WideString` manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstrings`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetWideStringManager` ([1246](#)), `TWideStringManager` ([1109](#))

29.9.284 **get_caller_addr**

Synopsis: Return the address of the caller.

Declaration: `function get_caller_addr(framebp: pointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to address (the return address) of the caller of the routine which has as frame `framebp`.

See also: `get_frame` ([1183](#)), `get_caller_frame` ([1183](#)), `Dump_Stack` ([1135](#))

29.9.285 **get_caller_frame**

Synopsis: Return the frame pointer of the caller

Declaration: `function get_caller_frame(framebp: pointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to the frame of the caller of the routine which has as frame `framebp`.

See also: `get_caller_addr` ([1182](#)), `get_frame` ([1183](#)), `Dump_Stack` ([1135](#))

29.9.286 **get_frame**

Synopsis: Return the current frame

Declaration: `function get_frame : pointer`

Visibility: default

Description: `get_frame` returns a pointer to the current stack frame.

See also: `get_caller_addr` ([1182](#)), `get_caller_frame` ([1183](#))

29.9.287 **halt**

Synopsis: Stop program execution.

Declaration: `procedure halt(errnum: Byte)`
`procedure halt`

Visibility: default

Description: `Halt` stops program execution and returns control to the calling program. The optional argument `Errnum` specifies an exit value. If omitted, zero is returned.

Errors: None.

See also: `Exit` ([1140](#))

Listing: `./refex/ex30.pp`

Program `Example30`;

{ Program to demonstrate the Halt function. }

```
begin
  Writeln ('Before Halt. ');
  Halt (1); { Stop with exit code 1 }
  Writeln ('After Halt doesn't get executed. ');
end.
```

29.9.288 hexStr

Synopsis: Convert integer value to string with hexadecimal representation.

Declaration: `function hexStr(Val: LongInt;cnt: Byte) : shortstring`
`function hexStr(Val: Int64;cnt: Byte) : shortstring`
`function hexStr(Val: Pointer) : shortstring`

Visibility: default

Description: `HexStr` returns a string with the hexadecimal representation of `Value`. The string has exactly `cnt` characters. (i.e. only the `cnt` rightmost nibbles are taken into account) To have a complete representation of a Longint-type value, 8 nibbles are needed, i.e. `cnt=8`.

Errors: None.

See also: `Str` ([1250](#)), `Val` ([1261](#)), `BinStr` ([1119](#))

Listing: `./refex/ex81.pp`

```
Program example81;

{ Program to demonstrate the HexStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=1 to 10 do
    Writeln ( HexStr(Value, I));
end.
```

29.9.289 hi

Synopsis: Return high byte/word of value.

Declaration: `function hi(b: Byte) : Byte`
`function hi(i: Integer) : Byte`
`function hi(w: Word) : Byte`
`function hi(l: LongInt) : Word`
`function hi(l: DWord) : Word`
`function hi(i: Int64) : DWord`
`function hi(q: QWord) : DWord`

Visibility: default

Description: `Hi` returns the high byte or word from `X`, depending on the size of `X`. If the size of `X` is 4, then the high word is returned. If the size is 2 then the high byte is returned. `Hi` cannot be invoked on types of size 1, such as `byte` or `char`.

Errors: None

See also: `Lo` ([1196](#))

Listing: `./refex/ex31.pp`

```

Program Example31;

{ Program to demonstrate the Hi function. }

var
  L : Longint;
  W : Word;

begin
  L:=1 Shl 16;      { = $10000 }
  W:=1 Shl 8;       { = $100 }
  WriteIn (Hi(L)); { Prints 1 }
  WriteIn (Hi(W)); { Prints 1 }
end.

```

29.9.290 High

Synopsis: Return highest index of open array or enumerated

Declaration: `function High(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `High` depends on it's argument:

- 1.If the argument is an ordinal type, `High` returns the highest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `High` returns the highest possible value of it's index.
- 3.If the argument is an open array identifier in a function or procedure, then `High` returns the highest index of the array, as if the array has a zero-based index.

The return type is always the same type as the type of the argument (This can lead to some nasty surprises !).

Errors: None.

See also: `Low` ([1197](#)), `Ord` ([1226](#)), `Pred` ([1229](#)), `Succ` ([1252](#))

Listing: `./refex/ex80.pp`

```

Program example80;

{ Example to demonstrate the High and Low functions. }

Type TEnum = ( North , East , South , West );
          TRange = 14..55;
          TArray = Array [2..10] of Longint;

Function Average (Row : Array of Longint) : Real;

Var I : longint;
      Temp : Real;

begin

```

```

Temp := Row[0];
For I := 1 to High(Row) do
    Temp := Temp + Row[I];
Average := Temp / (High(Row)+1);
end;

Var A : TEnum;
    B : TRange;
    C : TArray;
    I : longint;

begin
    Writeln ('TEnum goes from : ',Ord(Low(TEnum)), ' to ', Ord(high(TEnum)), '.');
    Writeln ('A goes from : ',Ord(Low(A)), ' to ', Ord(high(A)), '.');
    Writeln ('TRange goes from : ',Ord(Low(TRange)), ' to ', Ord(high(TRange)), '.');
    Writeln ('B goes from : ',Ord(Low(B)), ' to ', Ord(high(B)), '.');
    Writeln ('TArray index goes from : ',Ord(Low(TArray)), ' to ', Ord(high(TArray)), '.');
    Writeln ('C index goes from : ',Low(C), ' to ', high(C), '.');
    For I:=Low(C) to High(C) do
        C[I]:=I;
    Writeln ('Average : ',Average(c));
    Write ('Type of return value is always same as type of argument:');
    Writeln (high(high(word)));
end.

```

29.9.291 HINSTANCE

Synopsis: Windows compatibility type for use in resources

Declaration: `function HINSTANCE : HMODULE`

Visibility: default

Description: This is an opaque type.

29.9.292 Inc

Synopsis: Increase value of integer variable

Declaration: `procedure Inc(var X: TOrdinal)`
`procedure Inc(var X: TOrdinal; Increment: TOrdinal)`

Visibility: default

Description: `Inc` increases the value of `X` with `Increment`. If `Increment` isn't specified, then 1 is taken as a default.

Errors: If range checking is on, then a range check can occur, or an overflow error, when an attempt is made to increase `X` over its maximum value.

See also: `Dec` ([1131](#))

Listing: `./refex/ex32.pp`

Program `Example32;`

```
{ Program to demonstrate the Inc function. }
```

Const

```

C : Cardinal   = 1;
L : Longint    = 1;
I : Integer    = 1;
W : Word       = 1;
B : Byte       = 1;
SI : ShortInt  = 1;
CH : Char      = 'A';

```

begin

```

Inc (C);      { C:=2    }
Inc (L,5);    { L:=6    }
Inc (I,-3);   { I:=-2   }
Inc (W,3);    { W:=4    }
Inc (B,100);  { B:=101  }
Inc (SI,-3);  { SI:=-2  }
Inc (CH,1);   { ch:='B' }

```

end.**29.9.293 Include**

Synopsis: Include element in set if it was not yet present.

Declaration: `procedure Include (var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Include` includes `E` in the set `S` if it is not yet part of the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```

S:=S+[E];
Include(S,E);

```

For an example, see `Exclude` ([1139](#))

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Exclude` ([1139](#))

29.9.294 IndexByte

Synopsis: Search for a byte in a memory range.

Declaration: `function IndexByte (const buf; len: SizeInt; b: Byte) : SizeInt`

Visibility: default

Description: `IndexByte` searches the memory at `buf` for maximally `len` positions for the byte `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexChar` ([1188](#)), `IndexDWord` ([1189](#)), `IndexWord` ([1190](#)), `CompareByte` ([1124](#))

Listing: ./refex/ex105.pp

Program Example105;

{ Program to demonstrate the IndexByte function. }

Const

 ArraySize = 256;
 MaxValue = 256;

Var

 Buffer : **Array**[1..ArraySize] **of** Byte;
 I,J : longint;
 K : Byte;

begin

Randomize;
 For I:=1 **To** ArraySize **do**
 Buffer[I]:=Random(MaxValue);
 For I:=1 **to** 10 **do**
 begin
 K:=Random(MaxValue);
 J:=IndexByte(Buffer ,ArraySize ,K);
 if J=-1 **then**
 WriteLn('Value ',K, ' was not found in buffer. ')
 else
 WriteLn('Found ',K, ' at position ',J, ' in buffer ');
 end;
 end;

end.

29.9.295 IndexChar

Synopsis: Search for a character in a memory range.

Declaration: function IndexChar(const buf;len: SizeInt;b: Char) : SizeInt

Visibility: default

Description: IndexChar searches the memory at buf for maximally len positions for the character b and returns it's position if it found one. If b is not found then -1 is returned. The position is zero-based. The IndexChar0 variant stops looking if a null character is found, and returns -1 in that case.

Errors: Buf and Len are not checked to see if they are valid values.

See also: IndexByte ([1187](#)), IndexDWord ([1189](#)), IndexWord ([1190](#)), CompareChar ([1125](#))

Listing: ./refex/ex108.pp

Program Example108;

{ Program to demonstrate the IndexChar function. }

Const

 ArraySize = 1000;
 MaxValue = 26;

Var

 Buffer : **Array**[1..ArraySize] **of** Char;

```

I,J : longint;
K : Char;

begin
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=chr(Ord('A')+Random(MaxValue));
  For I:=1 to 10 do
    begin
      K:=chr(Ord('A')+Random(MaxValue));
      J:=IndexChar(Buffer,ArraySize,K);
      if J=-1 then
        Writeln('Value ',K,' was not found in buffer.')
      else
        Writeln('Found ',K,' at position ',J,' in buffer');
      end;
    end;
end.

```

29.9.296 IndexChar0

Synopsis: Return index of a character in null-terminated array of char.

Declaration: `function IndexChar0(const buf;len: SizeInt;b: Char) : SizeInt`

Visibility: default

Description: `IndexChar0` returns the index of the character `b` in the null-terminated array `Buf`. At most `len` characters will be searched, or the null character if it is encountered first. If the character is not found, 0 is returned.

Errors: On error, 0 is returned.

See also: [IndexByte \(1187\)](#), [IndexChar \(1188\)](#), [IndexWord \(1190\)](#), [IndexDWord \(1189\)](#), [CompareChar0 \(1126\)](#)

29.9.297 IndexDWord

Synopsis: Search for a DWord value in a memory range.

Declaration: `function IndexDWord(const buf;len: SizeInt;b: DWord) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the DWord `DW` and returns it's position if it found one. If `DW` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: [IndexByte \(1187\)](#), [IndexChar \(1188\)](#), [IndexWord \(1190\)](#), [CompareDWord \(1127\)](#)

Listing: `./refex/ex106.pp`

Program `Example106;`

{ Program to demonstrate the IndexDWord function. }

Const

```

  ArraySize = 1000;
  MaxValue = 1000;

```

```

Var
  Buffer : Array[1..ArraySize] of DWord;
  I,J : longint;
  K : DWord;

begin
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);
      J:=IndexDWord( Buffer , ArraySize ,K);
      if J=-1 then
        WriteLn('Value ',K,' was not found in buffer.')
      else
        WriteLn('Found ',K,' at position ',J,' in buffer');
      end;
    end.

```

29.9.298 Indexword

Synopsis: Search for a WORD value in a memory range.

Declaration: `function Indexword(const buf;len: SizeInt;b: Word) : SizeInt`

Visibility: default

Description: IndexChar searches the memory at buf for maximally len positions for the Word W and returns it's position if it found one. If W is not found then -1 is returned.

Errors: Buf and Len are not checked to see if they are valid values.

See also: IndexByte ([1187](#)), IndexDWord ([1189](#)), IndexChar ([1188](#)), CompareWord ([1128](#))

Listing: ./refex/ex107.pp

Program Example107;

{ Program to demonstrate the IndexWord function. }

Const

```

  ArraySize = 1000;
  MaxValue = 1000;

```

Var

```

  Buffer : Array[1..ArraySize] of Word;
  I,J : longint;
  K : Word;

```

begin

```

  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);

```

```

J:=IndexWord( Buffer , ArraySize ,K);
if J=-1 then
  WriteLn( 'Value ',K,' was not found in buffer. ')
else
  WriteLn( 'Found ',K,' at position ',J,' in buffer ');
end;
end.

```

29.9.299 InitCriticalSection

Synopsis: Initialize a critical section

Declaration: `procedure InitCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `InitCriticalSection` initializes a critical section CS for use. Before using a critical section with `EnterCriticalSection` (1136) or `LeaveCriticalSection` (1195) the critical section should be initialized with `InitCriticalSection`.

When a critical section is no longer used, it should be disposed of with `DoneCriticalSection` (1134)

See also: `DoneCriticalSection` (1134), `EnterCriticalSection` (1136), `LeaveCriticalSection` (1195)

29.9.300 InitThread

Synopsis: Initialize a thread

Declaration: `procedure InitThread(stklen: SizeUInt)`

Visibility: default

Description: Do not use, this is used internally by the thread manager.

29.9.301 InitThreadVars

Synopsis: Initialize threadvars

Declaration: `procedure InitThreadVars(RelocProc: Pointer)`

Visibility: default

Description: This routine should be called when threading is started. It is called by the compiler and should never be called manually, only from a thread manager.

Errors: None.

See also: `TThreadManager` (1105), `TThreadManager.InitThreadVar` (1105)

29.9.302 Insert

Synopsis: Insert one string in another.

Declaration: `procedure Insert(const source: shortstring; var s: shortstring;
 index: SizeInt)
 procedure Insert(source: Char; var s: shortstring; index: SizeInt)
 procedure Insert(const Source: AnsiString; var S: AnsiString;
 Index: SizeInt)
 procedure Insert(const Source: WideString; var S: WideString;
 Index: SizeInt)`

Visibility: default

Description: `Insert` inserts string `Source` in string `S`, at position `Index`, shifting all characters after `Index` to the right. The resulting string is truncated at 255 characters, if needed. (i.e. for shortstrings)

Errors: None.

See also: `Delete` ([1133](#)), `Copy` ([1069](#)), `Pos` ([1228](#))

Listing: `./refex/ex33.pp`

Program `Example33;`

{ Program to demonstrate the Insert function. }

Var `S : String;`

begin

`S := 'Free Pascal is difficult to use !';`

`Insert ('NOT ', S, pos('difficult', S));`

`writeln (s);`

end.

29.9.303 int

Synopsis: Calculate integer part of floating point value.

Declaration: `function int(d: ValReal) : ValReal`

Visibility: default

Description: `Int` returns the integer part of any Real `X`, as a Real.

Errors: None.

See also: `Frac` ([1178](#)), `Round` ([1237](#))

Listing: `./refex/ex34.pp`

Program `Example34;`

{ Program to demonstrate the Int function. }

begin

`Writeln (Int(123.456):0:1); { Prints 123.0 }`

`Writeln (Int(-123.456):0:1); { Prints -123.0 }`

end.

29.9.304 IOResult

Synopsis: Return result of last file IO operation

Declaration: `function IOResult : Word`

Visibility: default

Description: IOResult contains the result of any input/output call, when the `{\Si-}` compiler directive is active, disabling IO checking. When the flag is read, it is reset to zero. If IOResult is zero, the operation completed successfully. If non-zero, an error occurred. The following errors can occur:

dos errors :

- 2**File not found.
- 3**Path not found.
- 4**Too many open files.
- 5**Access denied.
- 6**Invalid file handle.
- 12**Invalid file-access mode.
- 15**Invalid disk number.
- 16**Cannot remove current directory.
- 17**Cannot rename across volumes.

I/O errors :

- 100**Error when reading from disk.
- 101**Error when writing to disk.
- 102**File not assigned.
- 103**File not open.
- 104**File not opened for input.
- 105**File not opened for output.
- 106**Invalid number.

Fatal errors :

- 150**Disk is write protected.
- 151**Unknown device.
- 152**Drive not ready.
- 153**Unknown command.
- 154**CRC check failed.
- 155**Invalid drive specified..
- 156**Seek error on disk.
- 157**Invalid media type.
- 158**Sector not found.
- 159**Printer out of paper.
- 160**Error when writing to device.
- 161**Error when reading from device.
- 162**Hardware failure.

Errors: None.

Listing: ./refex/ex35.pp

Program Example35;

```
{ Program to demonstrate the IOResult function. }

Var F : text;

begin
  Assign (f,paramstr(1));
  {$i-}
  Reset (f);
  {$i+}
  If IOresult <> 0 then
    writeln ('File ',paramstr(1), ' doesn't exist')
  else
    writeln ('File ',paramstr(1), ' exists');
end.
```

29.9.305 IsMemoryManagerSet

Synopsis: Is the memory manager set

Declaration: `function IsMemoryManagerSet : Boolean`

Visibility: default

Description: `IsMemoryManagerSet` will return `True` if the memory manager has been set to another value than the system heap manager, it will return `False` otherwise.

Errors: None.

See also: `SetMemoryManager` ([1243](#)), `GetMemoryManager` ([1181](#))

29.9.306 IsVariantManagerSet

Synopsis: Determine if variant manager is currently set.

Declaration: `function IsVariantManagerSet : Boolean`

Visibility: default

Description: `IsVariantManagerSet` determines whether the variant manager was set to a correct variant manager. It returns `True` if it is, or `False` if it is not.

The routine checks all variant operation handlers, they should all be set correctly.

See also: `SetVariantManager` ([1246](#)), `GetVariantManager` ([1182](#))

29.9.307 KillThread

Synopsis: Kill a running thread

Declaration: `function KillThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `KillThread` causes a running thread to be aborted. The thread is identified by its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `WaitForThreadTerminate` (1262), `EndThread` (1136), `SuspendThread` (1253)

29.9.308 LeaveCriticalSection

Synopsis: Leave a critical section

Declaration: `procedure LeaveCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `LeaveCriticalSection` signals that the current thread is exiting the critical section CS it has entered with `EnterCriticalSection` (1136).

The critical section must have been initialized with `InitCriticalSection` (1191) prior to a call to `EnterCriticalSection` and `LeaveCriticalSection`.

See also: `InitCriticalSection` (1191), `DoneCriticalSection` (1134), `EnterCriticalSection` (1136)

29.9.309 LEtoN

Synopsis: Convert Little Endian-ordered integer to Native-ordered integer

Declaration: `function LEtoN(const AValue: SmallInt) : SmallInt`
`function LEtoN(const AValue: Word) : Word`
`function LEtoN(const AValue: LongInt) : LongInt`
`function LEtoN(const AValue: DWord) : DWord`
`function LEtoN(const AValue: Int64) : Int64`
`function LEtoN(const AValue: QWord) : QWord`

Visibility: default

Description: `LEtoN` will rearrange the bytes in a Little-Endian number to the native order for the current processor. That is, for a little-endian processor, it will do nothing, and for a big-endian processor, it will invert the order of the bytes.

See also: `BEtoN` (1119), `NtoBE` (1200), `NtoLE` (1201)

29.9.310 ln

Synopsis: Calculate logarithm

Declaration: `function ln(d: ValReal) : ValReal`

Visibility: default

Description: `Ln` returns the natural logarithm of the Real parameter X. X must be positive.

Errors: An run-time error will occur when X is negative.

See also: `Exp` (1141), `Power` (1069)

Listing: `./refex/ex37.pp`

Program Example37;

{ Program to demonstrate the Ln function. }

```
begin
  WriteLn (Ln(1));      { Prints 0 }
  WriteLn (Ln(Exp(1))); { Prints 1 }
end.
```

29.9.311 lo

Synopsis: Return low byte/word of value.

Declaration:

```
function lo(B: Byte) : Byte
function lo(i: Integer) : Byte
function lo(w: Word) : Byte
function lo(l: LongInt) : Word
function lo(l: DWord) : Word
function lo(i: Int64) : DWord
function lo(q: QWord) : DWord
```

Visibility: default

Description: Lo returns the low byte of its argument if this is of type Integer or Word. It returns the low word of its argument if this is of type Longint or Cardinal.

Errors: None.

See also: Ord ([1226](#)), Chr ([1123](#)), Hi ([1184](#))

Listing: ./refex/ex38.pp

Program Example38;

{ Program to demonstrate the Lo function. }

```
Var L : Longint;
    W : Word;

begin
  L:=(1 Shl 16) + (1 Shl 4); { $10010 }
  WriteLn (Lo(L));          { Prints 16 }
  W:=(1 Shl 8) + (1 Shl 4);  { $110 }
  WriteLn (Lo(W));          { Prints 16 }
end.
```

29.9.312 LoadResource

Synopsis: Load a resource for use

Declaration:

```
function LoadResource(ModuleHandle: HMODULE; ResHandle: TResourceHandle)
                        : HGLOBAL
```

Visibility: default

Description: `LoadResource` loads a resource identified by `ResHandle` from a module identified by `ModuleHandle` into memory. It returns a handle to the resource.

Loaded resources must be unloaded again using the `FreeResource` (1179) function.

Errors: On error, 0 is returned.

See also: `FindResource` (1145), `FreeResource` (1179), `SizeofResource` (1248), `LockResource` (1197), `UnlockResource` (1259), `FreeResource` (1179)

29.9.313 LockResource

Synopsis: Lock a resource

Declaration: `function LockResource(ResData: HGLOBAL) : Pointer`

Visibility: default

Description: `LockResource` locks a resource previously loaded by `LoadResource` into memory. This means that any attempt to modify the resource will fail while it is locked. The function returns a pointer to the resource location in memory.

The resource can be freed again using the `UnlockResource` (1259) function.

Errors: if the function fails, `Nil` is returned.

See also: `FindResource` (1145), `FreeResource` (1179), `SizeofResource` (1248), `LoadResource` (1196), `UnlockResource` (1259), `FreeResource` (1179)

29.9.314 longjmp

Synopsis: Jump to address.

Declaration: `procedure longjmp(var S: jmp_buf; value: LongInt)`

Visibility: default

Description: `LongJump` jumps to the adress in the `envjmp_buf`, and restores the registers that were stored in it at the corresponding `SetJump` (1242) call. In effect, program flow will continue at the `SetJump` call, which will return `value` instead of 0. If a value equal to zero is passed, it will be converted to 1 before passing it on. The call will not return, so it must be used with extreme care. This can be used for error recovery, for instance when a segmentation fault occurred.

For an example, see `SetJump` (1242)

Errors: None.

See also: `SetJump` (1242)

29.9.315 Low

Synopsis: Return lowest index of open array or enumerated

Declaration: `function Low(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `Low` depends on it's argument:

- 1.If the argument is an ordinal type, `Low` returns the lowest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `Low` returns the lowest possible value of it's index.

The return type is always the same type as the type of the argument.
for an example, see `High` ([1185](#)).

Errors: None.

See also: `High` ([1185](#)), `Ord` ([1226](#)), `Pred` ([1229](#)), `Succ` ([1252](#))

29.9.316 `lowerCase`

Synopsis: Return lowercase version of a string.

Declaration: `function lowerCase(const s: shortstring) : shortstring; Overload`
`function lowerCase(c: Char) : Char; Overload`
`function lowercase(const s: ansistring) : ansistring`

Visibility: default

Description: `Lowercase` returns the lowercase version of its argument `C`. If its argument is a string, then the complete string is converted to lowercase. The type of the returned value is the same as the type of the argument.

Errors: None.

See also: `Upcase` ([1260](#))

Listing: `./refex/ex73.pp`

```

program Example73;

{ Program to demonstrate the Lowercase function. }

var c:char;

begin
  for c:= 'A' to 'Z' do
    write(lowercase(c));
    Writeln;
    Writeln(Lowercase( 'ABCDEFGHIJKLMNOPQRSTUVWXYZ' ));
end.
```

29.9.317 `MemSize`

Synopsis: Return the size of a memory block.

Declaration: `function MemSize(p: pointer) : PtrInt`

Visibility: default

Description: `MemSize` returns the size of a memory block on the heap.

Errors: Passing an invalid pointer may lead to run-time errors (access violations).

See also: `GetMem` ([1180](#)), `FreeMem` ([1178](#))

29.9.318 mkdir

Synopsis: Create a new directory.

Declaration: `procedure mkdir(const s: String)`

Visibility: default

Description: `Mkdir` creates a new directory `S`.

For an example, see `Rmdir` ([1236](#)).

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Chdir` ([1122](#)), `Rmdir` ([1236](#))

29.9.319 Move

Synopsis: Move data from one location in memory to another

Declaration: `procedure Move(const source;var dest;count: SizeInt)`

Visibility: default

Description: `Move` moves `Count` bytes from `Source` to `Dest`.

Errors: If either `Dest` or `Source` is outside the accessible memory for the process, then a run-time error will be generated.

See also: `Fillword` ([1145](#)), `Fillchar` ([1144](#))

Listing: `./refex/ex42.pp`

Program `Example42`;

{ Program to demonstrate the Move function. }

Var `S1,S2 : String [30];`

begin

`S1:= 'Hello World !';`

`S2:= 'Bye, bye !';`

`Move (S1,S2,Sizeof(S1));`

`Writeln (S2);`

end.

29.9.320 MoveChar0

Synopsis: Move data till first zero character

Declaration: `procedure MoveChar0(const buf1;var buf2;len: SizeInt)`

Visibility: default

Description: `MoveChar0` moves `Count` bytes from `Src` to `Dest`, and stops moving if a zero character is found.

Errors: No checking is done to see if `Count` stays within the memory allocated to the process.

See also: `Move` ([1199](#))

Listing: ./refex/ex109.pp

Program Example109;

{ Program to demonstrate the MoveChar0 function. }

Var

Buf1, Buf2 : **Array**[1..80] **of** char;
I : longint;

begin

Randomize;

For I:=**low**(buf1) **to high**(buf1) **do**

Buf1[I]:=chr(**Random**(16)+**Ord**('A'));

Writeln('Original buffer');

writeln(Buf1);

Buf1[**Random**(80)+1]:=#0;

MoveChar0(Buf1, Buf2, 80);

Writeln('Randomly zero-terminated Buffer');

Writeln(Buf2);

end.

29.9.321 New

Synopsis: Dynamically allocate memory for variable

Declaration: procedure New(var P: Pointer)
procedure New(var P: Pointer; Cons: TProcedure)

Visibility: default

Description: New allocates a new instance of the type pointed to by P, and puts the address in P. If P is an object, then it is possible to specify the name of the constructor with which the instance will be created.

For an example, see Dispose ([1133](#)).

Errors: If not enough memory is available, Nil will be returned.

See also: Dispose ([1133](#)), Freemem ([1178](#)), Getmem ([1180](#))

29.9.322 NtoBE

Synopsis: Convert Native-ordered integer to a Big Endian-ordered integer

Declaration: function NtoBE(const AValue: SmallInt) : SmallInt
function NtoBE(const AValue: Word) : Word
function NtoBE(const AValue: LongInt) : LongInt
function NtoBE(const AValue: DWord) : DWord
function NtoBE(const AValue: Int64) : Int64
function NtoBE(const AValue: QWord) : QWord

Visibility: default

Description: NtoBE will rearrange the bytes in a natively-ordered number to the Big-Endian order. That is, for a Little-Endian processor, it will invert the order of the bytes and for a big-endian processor, it will do nothing.

See also: BEtoN ([1119](#)), LEtoN ([1195](#)), NtoLE ([1201](#))

29.9.323 NtoLE

Synopsis: Convert Native-ordered integer to a Little Endian-ordered integer

Declaration: `function NtoLE(const AValue: SmallInt) : SmallInt`
`function NtoLE(const AValue: Word) : Word`
`function NtoLE(const AValue: LongInt) : LongInt`
`function NtoLE(const AValue: DWord) : DWord`
`function NtoLE(const AValue: Int64) : Int64`
`function NtoLE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoLE` will rearrange the bytes in a natively-ordered number to the little-Endian order. That is, for a Big-Endian processor, it will invert the order of the bytes and for a Little-Endian processor, it will do nothing.

See also: `BEtoN` ([1119](#)), `LEtoN` ([1195](#)), `NtoBE` ([1200](#))

29.9.324 OctStr

Synopsis: Convert integer to a string with octal representation.

Declaration: `function OctStr(Val: LongInt;cnt: Byte) : shortstring`
`function OctStr(Val: Int64;cnt: Byte) : shortstring`

Visibility: default

Description: `OctStr` returns a string with the octal representation of `Value`. The string has exactly `cnt` characters.

Errors: None.

See also: `Str` ([1250](#)), `Val` ([1261](#)), `BinStr` ([1119](#)), `HexStr` ([1184](#))

Listing: `./refex/ex112.pp`

```

Program example112;

{ Program to demonstrate the OctStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=1 to 10 do
    Writeln ( OctStr(Value,I) );
  For I:=1 to 16 do
    Writeln ( OctStr(I,3) );
end.

```

29.9.325 odd

Synopsis: Is a value odd or even ?

Declaration: `function odd(l: LongInt) : Boolean`
`function odd(l: LongWord) : Boolean`
`function odd(l: Int64) : Boolean`
`function odd(l: QWord) : Boolean`

Visibility: default

Description: Odd returns True if X is odd, or False otherwise.

Errors: None.

See also: Abs ([1112](#)), Ord ([1226](#))

Listing: ./refex/ex43.pp

Program Example43;

{ Program to demonstrate the Odd function. }

```
begin
  If Odd(1) Then
    Writeln ( 'Everything OK with 1 !' );
  If Not Odd(2) Then
    Writeln ( 'Everything OK with 2 !' );
end.
```

29.9.326 Ofs

Synopsis: Return offset of a variable.

Declaration: `function Ofs(var X) : LongInt`

Visibility: default

Description: Ofs returns the offset of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always the complete address of the variable, since Free Pascal is a 32 bit compiler.

Errors: None.

See also: DSeg ([1134](#)), CSeg ([1131](#)), Seg ([1242](#)), Ptr ([1229](#))

Listing: ./refex/ex44.pp

Program Example44;

{ Program to demonstrate the Ofs function. }

Var W : Pointer;

```
begin
  W:=Pointer( Ofs(W)); { W contains its own offset. }
end.
```

29.9.327 operator *(variant, variant): variant

Synopsis:

Declaration: `function operator *(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.328 operator **(variant, variant): variant

Synopsis:

Declaration: `function operator **(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.329 operator +(variant, variant): variant

Synopsis:

Declaration: `function operator +(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.330 operator -(variant): variant

Synopsis:

Declaration: `function operator -(variant): variant(const op: variant) : variant`

Visibility: default

Description:

Errors:

29.9.331 operator -(variant, variant): variant

Synopsis:

Declaration: `function operator -(variant, variant): variant (const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.332 operator /(variant, variant): variant

Synopsis:

Declaration: `function operator /(variant, variant): variant (const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.333 operator :=(ansistring): olevariant

Synopsis:

Declaration: `function operator :=(ansistring): olevariant (const source: ansistring)
: olevariant`

Visibility: default

Description:

Errors:

29.9.334 operator :=(ansistring): variant

Synopsis:

Declaration: `function operator :=(ansistring): variant (const source: ansistring)
: variant`

Visibility: default

Description:

Errors:

29.9.335 operator :=(Boolean): olevariant

Synopsis:

Declaration: `function operator :=(Boolean): olevariant(const source: Boolean)
: olevariant`

Visibility: default

Description:

Errors:

29.9.336 operator :=(Boolean): variant

Synopsis:

Declaration: `function operator :=(Boolean): variant(const source: Boolean) : variant`

Visibility: default

Description:

Errors:

29.9.337 operator :=(Byte): olevariant

Synopsis:

Declaration: `function operator :=(Byte): olevariant(const source: Byte) : olevariant`

Visibility: default

Description:

Errors:

29.9.338 operator :=(Byte): variant

Synopsis:

Declaration: `function operator :=(Byte): variant(const source: Byte) : variant`

Visibility: default

Description:

Errors:

29.9.339 operator :=(Char): olevariant

Synopsis:

Declaration: `function operator :=(Char): olevariant(const source: Char) : olevariant`

Visibility: default

Description:

Errors:

29.9.340 operator :=(Char): variant

Synopsis:

Declaration: `function operator :=(Char): variant(const source: Char) : variant`

Visibility: default

Description:

Errors:

29.9.341 operator :=(currency): olevariant

Synopsis:

Declaration: `function operator :=(currency): olevariant(const source: currency)
: olevariant`

Visibility: default

Description:

Errors:

29.9.342 operator :=(currency): variant

Synopsis:

Declaration: `function operator :=(currency): variant(const source: currency)
: variant`

Visibility: default

Description:

Errors:

29.9.343 operator :=(double): olevariant

Synopsis:

Declaration: `function operator :=(double): olevariant(const source: double)
: olevariant`

Visibility: default

Description:

Errors:

29.9.344 operator :=(double): variant

Synopsis:

Declaration: `function operator :=(double): variant(const source: double) : variant`

Visibility: default

Description:

Errors:

29.9.345 operator :=(DWord): olevariant

Synopsis:

Declaration: `function operator :=(DWord): olevariant(const source: DWord)
: olevariant`

Visibility: default

Description:

Errors:

29.9.346 operator :=(DWord): variant

Synopsis:

Declaration: `function operator :=(DWord): variant(const source: DWord) : variant`

Visibility: default

Description:

Errors:

29.9.347 operator :=(Int64): olevariant

Synopsis:

Declaration: `function operator :=(Int64): olevariant(const source: Int64)
: olevariant`

Visibility: default

Description:

Errors:

29.9.348 operator :=(Int64): variant

Synopsis:

Declaration: `function operator :=(Int64): variant(const source: Int64) : variant`

Visibility: default

Description:

Errors:

29.9.349 operator :=(longbool): olevariant

Synopsis:

Declaration: `function operator :=(longbool): olevariant(const source: longbool)
: olevariant`

Visibility: default

Description:

Errors:

29.9.350 operator :=(longbool): variant

Synopsis:

Declaration: `function operator :=(longbool): variant(const source: longbool)
: variant`

Visibility: default

Description:

Errors:

29.9.351 operator :=(LongInt): olevariant

Synopsis:

Declaration: `function operator :=(LongInt): olevariant(const source: LongInt)
: olevariant`

Visibility: default

Description:

Errors:

29.9.352 operator :=(LongInt): variant

Synopsis:

Declaration: `function operator :=(LongInt): variant(const source: LongInt) : variant`

Visibility: default

Description:

Errors:

29.9.353 operator :=(olevariant): ansistring

Synopsis:

Declaration: `function operator :=(olevariant): ansistring(const source: olevariant)
: ansistring`

Visibility: default

Description:

Errors:

29.9.354 operator :=(olevariant): Boolean

Synopsis:

Declaration: `function operator :=(olevariant): Boolean(const source: olevariant)
: Boolean`

Visibility: default

Description:

Errors:

29.9.355 operator :=(olevariant): Byte

Synopsis:

Declaration: `function operator :=(olevariant): Byte(const source: olevariant) : Byte`

Visibility: default

Description:

Errors:

29.9.356 operator :=(olevariant): Char

Synopsis:

Declaration: `function operator :=(olevariant): Char(const source: olevariant) : Char`

Visibility: default

Description:

Errors:

29.9.357 operator :=(olevariant): currency

Synopsis:

Declaration: `function operator :=(olevariant): currency(const source: olevariant)
: currency`

Visibility: default

Description:

Errors:

29.9.358 operator :=(olevariant): double

Synopsis:

Declaration: `function operator :=(olevariant): double(const source: olevariant)
: double`

Visibility: default

Description:

Errors:

29.9.359 operator :=(olevariant): DWord

Synopsis:

Declaration: `function operator :=(olevariant): DWord(const source: olevariant)
: DWord`

Visibility: default

Description:

Errors:

29.9.360 operator :=(olevariant): Int64

Synopsis:

Declaration: `function operator :=(olevariant): Int64(const source: olevariant)
: Int64`

Visibility: default

Description:

Errors:

29.9.361 operator :=(olevariant): longbool

Synopsis:

Declaration: `function operator :=(olevariant): longbool(const source: olevariant)
: longbool`

Visibility: default

Description:

Errors:

29.9.362 operator :=(olevariant): LongInt

Synopsis:

Declaration: `function operator :=(olevariant): LongInt(const source: olevariant)
: LongInt`

Visibility: default

Description:

Errors:

29.9.363 operator :=(olevariant): qword

Synopsis:

Declaration: `function operator :=(olevariant): qword(const source: olevariant)
: qword`

Visibility: default

Description:

Errors:

29.9.364 operator :=(olevariant): ShortInt

Synopsis:

Declaration: `function operator :=(olevariant): ShortInt(const source: olevariant)
: ShortInt`

Visibility: default

Description:

Errors:

29.9.365 operator :=(olevariant): shortstring

Synopsis:

Declaration: `function operator :=(olevariant): shortstring(const source: olevariant)
: shortstring`

Visibility: default

Description:

Errors:

29.9.366 operator :=(olevariant): SmallInt

Synopsis:

Declaration: `function operator :=(olevariant): SmallInt(const source: olevariant)
: SmallInt`

Visibility: default

Description:

Errors:

29.9.367 operator :=(olevariant): TDateTime

Synopsis:

Declaration: `function operator :=(olevariant): TDateTime(const source: olevariant)
: TDateTime`

Visibility: default

Description:

Errors:

29.9.368 operator :=(olevariant): TError

Synopsis:

Declaration: `function operator :=(olevariant): TError(const source: olevariant)
: TError`

Visibility: default

Description:

Errors:

29.9.369 operator :=(olevariant): variant

Synopsis:

Declaration: `function operator :=(olevariant): variant(const source: olevariant)
: variant`

Visibility: default

Description:

Errors:

29.9.370 operator :=(olevariant): widechar

Synopsis:

Declaration: `function operator :=(olevariant): widechar(const source: olevariant)
: widechar`

Visibility: default

Description:

Errors:

29.9.371 operator :=(olevariant): widestring

Synopsis:

Declaration: `function operator :=(olevariant): widestring(const source: olevariant)
: widestring`

Visibility: default

Description:

Errors:

29.9.372 operator :=(olevariant): Word

Synopsis:

Declaration: `function operator :=(olevariant): Word(const source: olevariant) : Word`

Visibility: default

Description:

Errors:

29.9.373 operator :=(olevariant): wordbool

Synopsis:

Declaration: `function operator :=(olevariant): wordbool(const source: olevariant)
: wordbool`

Visibility: default

Description:

Errors:

29.9.374 operator :=(qword): olevariant

Synopsis:

Declaration: `function operator :=(qword): olevariant(const source: qword)
: olevariant`

Visibility: default

Description:

Errors:

29.9.375 operator :=(qword): variant

Synopsis:

Declaration: `function operator :=(qword): variant(const source: qword) : variant`

Visibility: default

Description:

Errors:

29.9.376 operator :=(real48): double

Synopsis:

Declaration: `function operator :=(real48): double(b: real48) : double`

Visibility: default

Description:

Errors:

29.9.377 operator :=(ShortInt): olevariant

Synopsis:

Declaration: `function operator :=(ShortInt): olevariant(const source: ShortInt)
: olevariant`

Visibility: default

Description:

Errors:

29.9.378 operator :=(ShortInt): variant

Synopsis:

Declaration: `function operator :=(ShortInt): variant(const source: ShortInt)
: variant`

Visibility: default

Description:

Errors:

29.9.379 operator :=(shortstring): olevariant

Synopsis:

Declaration: `function operator :=(shortstring): olevariant(const source: shortstring)
: olevariant`

Visibility: default

Description:

Errors:

29.9.380 operator :=(shortstring): variant

Synopsis:

Declaration: `function operator :=(shortstring): variant(const source: shortstring)
: variant`

Visibility: default

Description:

Errors:

29.9.381 operator :=(SmallInt): olevariant

Synopsis:

Declaration: `function operator :=(SmallInt): olevariant(const source: SmallInt)
: olevariant`

Visibility: default

Description:

Errors:

29.9.382 operator :=(SmallInt): variant

Synopsis:

Declaration: `function operator :=(SmallInt): variant(const source: SmallInt)
: variant`

Visibility: default

Description:

Errors:

29.9.383 operator :=(TDateTime): olevariant

Synopsis:

Declaration: `function operator :=(TDateTime): olevariant(const source: TDateTime)
: olevariant`

Visibility: default

Description:

Errors:

29.9.384 operator :=(TDateTime): variant

Synopsis:

Declaration: `function operator :=(TDateTime): variant(const source: TDateTime)
: variant`

Visibility: default

Description:

Errors:

29.9.385 operator :=(TError): olevariant

Synopsis:

Declaration: `function operator :=(TError): olevariant(const source: TError)
: olevariant`

Visibility: default

Description:

Errors:

29.9.386 operator :=(TError): variant

Synopsis:

Declaration: `function operator :=(TError): variant(const source: TError) : variant`

Visibility: default

Description:

Errors:

29.9.387 operator :=(variant): ansistring

Synopsis:

Declaration: `function operator :=(variant): ansistring(const source: variant)
: ansistring`

Visibility: default

Description:

Errors:

29.9.388 operator :=(variant): Boolean

Synopsis:

Declaration: `function operator :=(variant): Boolean(const source: variant) : Boolean`

Visibility: default

Description:

Errors:

29.9.389 operator :=(variant): Byte

Synopsis:

Declaration: `function operator :=(variant): Byte(const source: variant) : Byte`

Visibility: default

Description:

Errors:

29.9.390 operator :=(variant): Char

Synopsis:

Declaration: `function operator :=(variant): Char(const source: variant) : Char`

Visibility: default

Description:

Errors:

29.9.391 operator :=(variant): currency

Synopsis:

Declaration: `function operator :=(variant): currency(const source: variant)
: currency`

Visibility: default

Description:

Errors:

29.9.392 operator :=(variant): double

Synopsis:

Declaration: `function operator :=(variant): double(const source: variant) : double`

Visibility: default

Description:

Errors:

29.9.393 operator :=(variant): DWord

Synopsis:

Declaration: `function operator :=(variant): DWord(const source: variant) : DWord`

Visibility: default

Description:

Errors:

29.9.394 operator :=(variant): Int64

Synopsis:

Declaration: `function operator :=(variant): Int64(const source: variant) : Int64`

Visibility: default

Description:

Errors:

29.9.395 operator :=(variant): longbool

Synopsis:

Declaration: `function operator :=(variant): longbool(const source: variant)
: longbool`

Visibility: default

Description:

Errors:

29.9.396 operator :=(variant): LongInt

Synopsis:

Declaration: `function operator :=(variant): LongInt(const source: variant) : LongInt`

Visibility: default

Description:

Errors:

29.9.397 operator :=(variant): olevariant

Synopsis:

Declaration: `function operator :=(variant): olevariant(const source: variant)
: olevariant`

Visibility: default

Description:

Errors:

29.9.398 operator :=(variant): qword

Synopsis:

Declaration: `function operator :=(variant): qword(const source: variant) : qword`

Visibility: default

Description:

Errors:

29.9.399 operator :=(variant): ShortInt

Synopsis:

Declaration: `function operator :=(variant): ShortInt(const source: variant)
: ShortInt`

Visibility: default

Description:

Errors:

29.9.400 operator :=(variant): shortstring

Synopsis:

Declaration: `function operator :=(variant): shortstring(const source: variant)
: shortstring`

Visibility: default

Description:

Errors:

29.9.401 operator :=(variant): SmallInt

Synopsis:

Declaration: `function operator :=(variant): SmallInt(const source: variant)
: SmallInt`

Visibility: default

Description:

Errors:

29.9.402 operator :=(variant): TDateTime

Synopsis:

Declaration: `function operator :=(variant): TDateTime(const source: variant)
: TDateTime`

Visibility: default

Description:

Errors:

29.9.403 operator :=(variant): TError

Synopsis:

Declaration: `function operator :=(variant): TError(const source: variant) : TError`

Visibility: default

Description:

Errors:

29.9.404 operator :=(variant): widechar

Synopsis:

Declaration: `function operator :=(variant): widechar(const source: variant)
: widechar`

Visibility: default

Description:

Errors:

29.9.405 operator :=(variant): widestring

Synopsis:

Declaration: `function operator :=(variant): widestring(const source: variant)
: widestring`

Visibility: default

Description:

Errors:

29.9.406 operator :=(variant): Word

Synopsis:

Declaration: `function operator :=(variant): Word(const source: variant) : Word`

Visibility: default

Description:

Errors:

29.9.407 operator :=(variant): wordbool

Synopsis:

Declaration: `function operator :=(variant): wordbool(const source: variant)
: wordbool`

Visibility: default

Description:

Errors:

29.9.408 operator :=(widechar): olevariant

Synopsis:

Declaration: `function operator :=(widechar): olevariant(const source: widechar)
: olevariant`

Visibility: default

Description:

Errors:

29.9.409 operator :=(widechar): variant

Synopsis:

Declaration: `function operator :=(widechar): variant(const source: widechar)
: variant`

Visibility: default

Description:

Errors:

29.9.410 operator :=(widestring): olevariant

Synopsis:

Declaration: `function operator :=(widestring): olevariant(const source: widestring)
: olevariant`

Visibility: default

Description:

Errors:

29.9.411 operator :=(widestring): variant

Synopsis:

Declaration: `function operator :=(widestring): variant(const source: widestring)
: variant`

Visibility: default

Description:

Errors:

29.9.412 operator :=(Word): olevariant

Synopsis:

Declaration: `function operator :=(Word): olevariant(const source: Word) : olevariant`

Visibility: default

Description:

Errors:

29.9.413 operator :=(Word): variant

Synopsis:

Declaration: `function operator :=(Word): variant(const source: Word) : variant`

Visibility: default

Description:

Errors:

29.9.414 operator :=(wordbool): olevariant

Synopsis:

Declaration: `function operator :=(wordbool): olevariant(const source: wordbool)
: olevariant`

Visibility: default

Description:

Errors:

29.9.415 operator :=(wordbool): variant

Synopsis:

Declaration: `function operator :=(wordbool): variant(const source: wordbool)
: variant`

Visibility: default

Description:

Errors:

29.9.416 operator <(variant, variant): Boolean

Synopsis:

Declaration: `function operator <(variant, variant): Boolean(const op1: variant;
const op2: variant)
: Boolean`

Visibility: default

Description:

Errors:

29.9.417 operator <=(variant, variant): Boolean

Synopsis:

Declaration: `function operator <=(variant, variant): Boolean(const op1: variant;
const op2: variant)
: Boolean`

Visibility: default

Description:

Errors:

29.9.418 operator =(variant, variant): Boolean

Synopsis:

Declaration: `function operator =(variant, variant): Boolean(const op1: variant;
const op2: variant)
: Boolean`

Visibility: default

Description:

Errors:

29.9.419 operator >(variant, variant): Boolean

Synopsis:

Declaration: `function operator >(variant, variant): Boolean(const op1: variant;
const op2: variant)
: Boolean`

Visibility: default

Description:

Errors:

29.9.420 operator >=(variant, variant): Boolean

Synopsis:

Declaration: `function operator >=(variant, variant): Boolean(const op1: variant;
const op2: variant)
: Boolean`

Visibility: default

Description:

Errors:

29.9.421 operator and(variant, variant): variant

Synopsis:

Declaration: `function operator and(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.422 operator div(variant, variant): variant

Synopsis:

Declaration: `function operator div(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.423 operator mod(variant, variant): variant

Synopsis:

Declaration: `function operator mod(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.424 operator not(variant): variant

Synopsis:

Declaration: `function operator not(variant): variant(const op: variant) : variant`

Visibility: default

Description:

Errors:

29.9.425 operator or(variant, variant): variant

Synopsis:

Declaration: `function operator or(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.426 operator shl(variant, variant): variant

Synopsis:

Declaration: `function operator shl(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.427 operator shr(variant, variant): variant

Synopsis:

Declaration: `function operator shr(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.428 operator xor(variant, variant): variant

Synopsis:

Declaration: `function operator xor(variant, variant): variant(const op1: variant;
const op2: variant)
: variant`

Visibility: default

Description:

Errors:

29.9.429 Ord

Synopsis: Return ordinal value of an ordinal type.

Declaration: `function Ord(X: TOrdinal) : LongInt`

Visibility: default

Description: `Ord` returns the Ordinal value of a ordinal-type variable X.

Historical note:

Originally, Pascal did not have typecasts and `ord` was a necessary function in order to do certain operations on non-integer ordinal types. With the arrival of typecasting a generic approach became possible, making `ord` mostly obsolete. However `ord` is not considered deprecated and remains in wide use today.

Errors: None.

See also: `Chr` ([1123](#)), `Succ` ([1252](#)), `Pred` ([1229](#)), `High` ([1185](#)), `Low` ([1197](#))

Listing: `./refex/ex45.pp`

Program `Example45;`

{ Program to demonstrate the Ord, Pred, Succ functions. }

Type

`TEnum = (Zero, One, Two, Three, Four);`

Var

`X : Longint;`

`Y : TEnum;`

begin

`X:=125;`

`WriteLn (Ord(X)); { Prints 125 }`

`X:=Pred(X);`

`WriteLn (Ord(X)); { prints 124 }`

`Y:= One;`

`WriteLn (Ord(y)); { Prints 1 }`

`Y:=Succ(Y);`

`WriteLn (Ord(Y)); { Prints 2 }`

end.

29.9.430 Paramcount

Synopsis: Return number of command-line parameters passed to the program.

Declaration: `function Paramcount : LongInt`

Visibility: default

Description: `Paramcount` returns the number of command-line arguments. If no arguments were given to the running program, 0 is returned.

Errors: None.

See also: `Paramstr` ([1227](#))

Listing: ./refex/ex46.pp

Program Example46;

```
{ Program to demonstrate the ParamCount and ParamStr functions. }
Var
  I : LongInt;

begin
  Writeln (paramstr(0), ' : Got ', ParamCount, ' command-line parameters: ');
  For i:=1 to ParamCount do
    Writeln ( ParamStr ( i ));
end.
```

29.9.431 ParamStr

Synopsis: Return value of a command-line argument.

Declaration: function ParamStr(l: LongInt) : String

Visibility: default

Description: Paramstr returns the L-th command-line argument. L must be between 0 and Paramcount, these values included. The zeroth argument is the path and file name with which the program was started.

The command-line parameters will be truncated to a length of 255, even though the operating system may support bigger command-lines. The Objpas unit (used in objfpc or delphi mode) define versions of Paramstr which return the full-length command-line arguments.

In the interest of portability, the paramstr function behaves the same on all operating systems: like the original paramstr function in Turbo Pascal. This means even on Unix, paramstr(0) returns the full path to the program executable. When the complete Unix command-line must be accessed, the argv pointer should be used to retrieve the real values of the command-line parameters.

For an example, see Paramcount ([1226](#)).

Errors: None.

See also: Paramcount ([1226](#))

29.9.432 pi

Synopsis: Return the value of PI.

Declaration: function pi : ValReal

Visibility: default

Description: Pi returns the value of Pi (3.1415926535897932385).

Errors: None.

See also: Cos ([1130](#)), Sin ([1247](#))

Listing: ./refex/ex47.pp

Program Example47;

{ Program to demonstrate the Pi function. }

```
begin
  Writeln (Pi);           {3.1415926}
  Writeln (Sin(Pi));
end.
```

29.9.433 Pos

Synopsis: Search for substring in a string.

Declaration:

```
function Pos(const substr: shortstring;const s: shortstring) : SizeInt
function Pos(C: Char;const s: shortstring) : SizeInt
function Pos(const Substr: ShortString;const Source: AnsiString)
      : SizeInt
function pos(const substr: shortstring;c: Char) : SizeInt
function Pos(const Substr: AnsiString;const Source: AnsiString)
      : SizeInt
function Pos(c: Char;const s: AnsiString) : SizeInt
function Pos(const Substr: WideString;const Source: WideString)
      : SizeInt
function Pos(c: Char;const s: WideString) : SizeInt
function Pos(c: WideChar;const s: WideString) : SizeInt
function Pos(c: WideChar;const s: AnsiString) : SizeInt
function Pos(c: AnsiString;const s: WideString) : SizeInt
function Pos(c: WideString;const s: AnsiString) : SizeInt
function Pos(c: ShortString;const s: WideString) : SizeInt
```

Visibility: default

Description: Pos returns the index of Substr in S, if S contains Substr. In case Substr isn't found, 0 is returned. The search is case-sensitive.

Errors: None

See also: Length ([1069](#)), Copy ([1069](#)), Delete ([1133](#)), Insert ([1191](#))

Listing: ./refex/ex48.pp

Program Example48;

{ Program to demonstrate the Pos function. }

```
Var
  S : String;

begin
  S:= 'The first space in this sentence is at position : ';
  Writeln (S,pos(' ',S));
  S:= 'The last letter of the alphabet doesn't appear in this sentence ';
  If (Pos ('Z',S)=0) and (Pos('z',S)=0) then
    Writeln (S);
end.
```

29.9.434 Pred

Synopsis: Return previous element for an ordinal type.

Declaration: `function Pred(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Pred` returns the element that precedes the element that was passed to it. If it is applied to the first value of the ordinal type, and the program was compiled with range checking on (`\var{\{$R+\}}`), then a run-time error will be generated.

for an example, see `Ord` ([1226](#))

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1226](#)), `Pred` ([1229](#)), `High` ([1185](#)), `Low` ([1197](#))

29.9.435 prefetch

Synopsis: Prefetch a memory location

Declaration: `procedure prefetch(const mem)`

Visibility: default

Description: `Prefetch` can be used to optimize the CPU behaviour by already loading a memory location. It is mainly used as a hint for those processors that support it.

Errors: None.

29.9.436 ptr

Synopsis: Combine segment and offset to pointer

Declaration: `function ptr(sel: LongInt; off: LongInt) : farpointer`

Visibility: default

Description: `Ptr` returns a pointer, pointing to the address specified by segment `Sel` and offset `Off`.

Remark:

1. In the 32-bit flat-memory model supported by Free Pascal, this function is obsolete.
2. The returned address is simply the offset.

Errors: None.

See also: `Addr` ([1113](#))

Listing: `./refex/ex59.pp`

Program `Example59;`

```
{ Program to demonstrate the Ptr (compability) function.
}
```

```
type pString = ^String;
```

```
Var P : pString;
    S : String;
```

```

begin
  S:= 'Hello , World !';
  P:= pString ( Ptr(Seg(S), Longint(Ofs(S))));
  {P now points to S !}
  WriteLn (P^);
end.

```

29.9.437 RaiseList

Synopsis: List of currently raised exceptions.

Declaration: `function RaiseList : PExceptObject`

Visibility: default

Description: `RaiseList` returns a pointer to the list of currently raised exceptions (i.e. a pointer to the first exception block).

Errors:

29.9.438 Random

Synopsis: Generate random number

Declaration: `function Random(l: LongInt) : LongInt`
`function Random(l: Int64) : Int64`
`function Random : extended`

Visibility: default

Description: `Random` returns a random number larger or equal to 0 and strictly less than L. If the argument L is omitted, a Real number between 0 and 1 is returned. (0 included, 1 excluded)

Errors: None.

See also: `Randomize` ([1231](#))

Listing: `./refex/ex49.pp`

Program `Example49`;

{ Program to demonstrate the Random and Randomize functions. }

```

Var I, Count, guess : Longint;
      R : Real;

```

```

begin
  Randomize; { This way we generate a new sequence every time
               the program is run }
  Count:=0;
  For i:=1 to 1000 do
    If Random>0.5 then inc(Count);
  WriteLn ( 'Generated ', Count, ' numbers > 0.5 ');
  WriteLn ( 'out of 1000 generated numbers. ');
  count:=0;
  For i:=1 to 5 do

```

```

begin
write ( 'Guess a number between 1 and 5 : ');
readln(Guess);
If Guess=Random(5)+1 then inc(count);
end;
Writeln ( 'You guessed ',Count,' out of 5 correct. ');
end.

```

29.9.439 Randomize

Synopsis: Initialize random number generator

Declaration: `procedure Randomize`

Visibility: default

Description: `Randomize` initializes the random number generator of Free Pascal, by giving a value to `Randseed`, calculated with the system clock.

For an example, see `Random` ([1230](#)).

Errors: None.

See also: `Random` ([1230](#))

29.9.440 Read

Synopsis: Read from a text file into variable

Declaration: `procedure Read(var F: Text; Args: Arguments)`
`procedure Read(Args: Arguments)`

Visibility: default

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc.; If no file `F` is specified, then standard input is read. If `F` is of type `Text`, then the variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String` or `PChar`. If `F` is a typed file, then each of the variables must be of the type specified in the declaration of `F`. Untyped files are not allowed as an argument.

Errors: If no data is available, a run-time error is generated. This behavior can be controlled with the `\var{\{$i\}}` compiler switch.

See also: `Readln` ([1232](#)), `Blockread` ([1120](#)), `Write` ([1264](#)), `Blockwrite` ([1121](#))

Listing: `./refex/ex50.pp`

Program `Example50`;

{ Program to demonstrate the Read(Ln) function. }

```

Var S : String;
    C : Char;
    F : File of char;

```

```

begin
Assign (F, 'ex50.pp');
Reset (F);
C:= 'A';

```

```

WriteLn ( 'The characters before the first space in ex50.pp are : ');
While not Eof(f) and (C<>' ') do
  Begin
    Read (F,C);
    Write (C);
  end;
WriteLn;
Close (F);
WriteLn ( 'Type some words. An empty line ends the program. ');
repeat
  ReadLn (S);
until S='';
end.

```

29.9.441 ReadLn

Synopsis: Read from a text file into variable and goto next line

Declaration: `procedure ReadLn(var F: Text;Args: Arguments)`
`procedure ReadLn(Args: Arguments)`

Visibility: default

Description: Read reads one or more values from a file F, and stores the result in V1, V2, etc. After that it goes to the next line in the file. The end of the line is marked by the `LineEnding` character sequence (which is platform dependent). The end-of-line marker is not considered part of the line and is ignored.

If no file F is specified, then standard input is read. The variables V1, V2 etc. must be of type `Char`, `Integer`, `Real`, `String` or `PChar`.

For an example, see Read ([1231](#)).

Errors: If no data is available, a run-time error is generated. This behavior can be controlled with the `\var{\{$i\}}` compiler switch.

See also: Read ([1231](#)), Blockread ([1120](#)), Write ([1264](#)), Blockwrite ([1121](#))

29.9.442 Real2Double

Synopsis: Convert Turbo Pascal style real to double.

Declaration: `function Real2Double(r: real48) : double`

Visibility: default

Description: The `Real2Double` function converts a Turbo Pascal style real (6 bytes long) to a native Free Pascal double type. It can be used e.g. to read old binary TP files with FPC and convert them to Free Pascal binary files.

Note that the assignment operator has been overloaded so a `Real48` type can be assigned directly to a double or extended.

Errors: None.

Listing: `./refex/ex110.pp`

```

program Example110;

{ Program to demonstrate the Real2Double function. }

Var
  i : integer;
  R : Real48;
  D : Double;
  E : Extended;
  F : File of Real48;

begin
  Assign(F, 'reals.dat');
  Reset(f);
  For i:=1 to 10 do
    begin
      Read(F,R);
      D:=Real2Double(R);
      Writeln( 'Real ',i, ' : ',D);
      D:=R;
      Writeln( 'Real (direct to double) ',i, ' : ',D);
      E:=R;
      Writeln( 'Real (direct to Extended) ',i, ' : ',E);
    end;
  Close(f);
end.

```

29.9.443 ReAllocMem

Synopsis: Re-allocate memory on the heap

Declaration: `function ReAllocMem(var p: pointer;Size: PtrInt) : pointer`

Visibility: default

Description: `ReAllocMem` resizes the memory pointed to by `P` so it has size `Size`. The value of `P` may change during this operation. The contents of the memory pointed to by `P` (if any) will be copied to the new location, but may be truncated if the newly allocated memory block is smaller in size. If a larger block is allocated, only the used memory is initialized, extra memory will not be zeroed out.

Note that `P` may be `nil`, in that case the behaviour of `ReAllocMem` is equivalent to `Getmem`.

See also: `GetMem` ([1180](#)), `FreeMem` ([1178](#))

29.9.444 ReAllocMemory

Synopsis: Alias for `ReAllocMem` ([1233](#))

Declaration: `function ReAllocMemory(var p: pointer;Size: PtrInt) : pointer`

Visibility: default

Description: `ReAllocMemory` is an alias for `ReAllocMem` ([1233](#)).

See also: `ReAllocMem` ([1233](#))

29.9.445 ReleaseExceptionObject

Synopsis: Decrease the reference count of the current exception object.

Declaration: `procedure ReleaseExceptionObject`

Visibility: default

Description: `ReleaseExceptionObject` decreases the reference count of the current exception object. This should be called whenever a reference to the exception object was obtained via the `AcquireExceptionObject` (1112) call.

Calling this method is only valid within an `except` block.

Errors: If there is no current exception object, a run-time error 231 will occur.

See also: `AcquireExceptionObject` (1112)

29.9.446 Rename

Synopsis: Rename file on disk

Declaration: `procedure Rename (var f: File; const s: String)`
`procedure Rename (var f: File; p: PChar)`
`procedure Rename (var f: File; c: Char)`
`procedure Rename (var t: Text; const s: String)`
`procedure Rename (var t: Text; p: PChar)`
`procedure Rename (var t: Text; c: Char)`

Visibility: default

Description: `Rename` changes the name of the assigned file `F` to `S`. `F` must be assigned, but not opened.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Erase` (1138)

Listing: `./refex/ex77.pp`

Program `Example77`;

```
{ Program to demonstrate the Rename function. }
Var F : Text;

begin
  Assign (F, paramstr(1));
  Rename (F, paramstr(2));
end.
```

29.9.447 Reset

Synopsis: Open file for reading

Declaration: `procedure Reset (var f: File; l: LongInt)`
`procedure Reset (var f: File)`
`procedure Reset (var f: TypedFile)`
`procedure Reset (var t: Text)`

Visibility: default

Description: `Reset` opens a file `F` for reading. `F` can be any file type. If `F` is a text file, or refers to standard I/O (e.g. `:`) then it is opened read-only, otherwise it is opened using the mode specified in `filemode`. If `F` is an untyped file, the record size can be specified in the optional parameter `L`. A default value of 128 is used. File sharing is not taken into account when calling `Reset`.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Rewrite` (1236), `Assign` (1116), `Close` (1123), `Append` (1114)

Listing: `./refex/ex51.pp`

Program `Example51`;

{ Program to demonstrate the Reset function. }

Function `FileExists (Name : String) : boolean`;

Var `F : File`;

begin

{ \$i- }

`Assign (F,Name);`

`Reset (F);`

{ \$I+ }

`FileExists := (IOResult=0) and (Name<>'');`

`Close (f);`

end;

begin

`If FileExists (Paramstr(1)) then`

`Writeln ('File found')`

`else`

`Writeln ('File NOT found');`

end.

29.9.448 ResumeThread

Synopsis: Resume a suspended thread.

Declaration: `function ResumeThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `ResumeThread` causes a suspended thread (using `SuspendThread` (1253)) to resume its execution. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `SuspendThread` (1253), `KillThread` (1194)

29.9.449 Rewrite

Synopsis: Open file for writing

Declaration: `procedure Rewrite(var f: File; l: LongInt)`
`procedure Rewrite(var f: File)`
`procedure Rewrite(var f: TypedFile)`
`procedure Rewrite(var t: Text)`

Visibility: default

Description: `Rewrite` opens a file `F` for writing. `F` can be any file type. If `F` is an untyped or typed file, then it is opened for reading and writing. If `F` is an untyped file, the record size can be specified in the optional parameter `L`. Default a value of 128 is used. if `Rewrite` finds a file with the same name as `F`, this file is truncated to length 0. If it doesn't find such a file, a new file is created. Contrary to Turbo Pascal, Free Pascal opens the file with mode `fmoutput`. If it should be opened in `fminout` mode, an extra call to `Reset` (1234) is needed. File sharing is not taken into account when calling `Rewrite`.

Errors: Depending on the state of the `\var{\{\$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{\$I-\}}` state, use `IOResult` to check for errors.

See also: `Reset` (1234), `Assign` (1116), `Close` (1123), `Flush` (1146), `Append` (1114)

Listing: `./refex/ex52.pp`

Program `Example52`;

{ Program to demonstrate the Rewrite function. }

Var `F : File`;
`l : longint`;

begin

`Assign (F, 'Test.tmp');`
{ Create the file. Recordsize is 4 }
`Rewrite (F, Sizeof(l));`
`For l:=1 to 10 do`
`BlockWrite (F,l,1);`
`close (f);`
{ F contains now a binary representation of
10 longints going from 1 to 10 }

end.

29.9.450 rmdir

Synopsis: Remove directory when empty.

Declaration: `procedure rmdir(const s: String)`

Visibility: default

Description: `Rmdir` removes the directory `S`.

Errors: Depending on the state of the `\var{\{\$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{\$I-\}}` state, use `IOResult` to check for errors.

See also: `Chdir` (1122), `Mkdir` (1199)

Listing: ./refex/ex53.pp

Program Example53;

{ Program to demonstrate the Mkdir and Rmdir functions. }

Const D : **String**[8] = 'TEST.DIR';

Var S : **String**;

begin

Writeln ('Making directory ',D);

Mkdir (D);

Writeln ('Changing directory to ',D);

ChDir (D);

GetDir (0,S);

Writeln ('Current Directory is : ',S);

WRiteln ('Going back');

ChDir ('..');

Writeln ('Removing directory ',D);

Rmdir (D);

end.

29.9.451 round

Synopsis: Round floating point value to nearest integer number.

Declaration: `function round(d: ValReal) : Int64`

Visibility: default

Description: Round rounds X to the closest integer, which may be bigger or smaller than X.

In the case of .5, the algorithm uses "banker's rounding": .5 values are always rounded towards the even number.

Errors: None.

See also: [Frac \(1178\)](#), [Int \(1192\)](#), [Trunc \(1257\)](#)

Listing: ./refex/ex54.pp

Program Example54;

{ Program to demonstrate the Round function. }

begin

Writeln (**Round**(1234.56)); { Prints 1235 }

Writeln (**Round**(-1234.56)); { Prints -1235 }

Writeln (**Round**(12.3456)); { Prints 12 }

Writeln (**Round**(-12.3456)); { Prints -12 }

Writeln (**Round**(2.5)); { Prints 2 (down) }

Writeln (**Round**(3.5)); { Prints 4 (up) }

end.

29.9.452 RTLEventCreate

Synopsis: Create a new RTL event

Declaration: `function RTLEventCreate : PRTLEvent`

Visibility: default

Description: `RTLEventCreate` creates and initializes a new RTL event. RTL events are used to notify other threads that a certain condition is met, and to notify other threads of condition changes (conditional variables).

The function returns an initialized RTL event, which must be disposed of with `RTLEventdestroy` (1238)

`RTLEvent` is used mainly for the `synchronize` method.

See also: `RTLEventDestroy` (1238), `RTLEventSet` (1069), `RTLEventReSet` (1069), `RTLEventWaitFor` (1239)

29.9.453 RTLeventdestroy

Synopsis: Destroy a RTL Event

Declaration: `procedure RTLeventdestroy(state: PRTLEvent)`

Visibility: default

Description: `RTLeventdestroy` destroys the RTL event `State`. After a call to `RTLeventdestroy`, the `State` RTL event may no longer be used.

See also: `RTLEventCreate` (1238), `RTLEventReset` (1069), `RTLEventSet` (1069)

29.9.454 RTLeventResetEvent

Synopsis: Reset an event

Declaration: `procedure RTLeventResetEvent(state: PRTLEvent)`

Visibility: default

Description: `RTLeventSetEvent` notifies other threads which are listening, that the event has occurred.

See also: `RTLEventCreate` (1238), `RTLEventDestroy` (1238), `RTLEventSetEvent` (1238), `RTLEventWaitFor` (1239)

29.9.455 RTLeventSetEvent

Synopsis: Notify threads of the event.

Declaration: `procedure RTLeventSetEvent(state: PRTLEvent)`

Visibility: default

Description: `RTLeventSetEvent` notifies other threads which are listening, that the event has occurred.

See also: `RTLEventCreate` (1238), `RTLEventResetEvent` (1238), `RTLEventDestroy` (1238), `RTLEventWait-For` (1239)

29.9.456 RTLeventStartWait

Synopsis: Prepare the event for waiting.

Declaration: `procedure RTLeventStartWait (state: PRTLEvent)`

Visibility: default

Description: `RTLeventResetEvent` signals that a thread is ready to start waiting on an event `state`. No event can be posted until a thread explicitly starts waiting on the event using `RTLeventWaitFor` (1239).

See also: `RTLeventCreate` (1238), `RTLeventDestroy` (1238), `RTLeventSetEvent` (1238), `RTLeventWaitFor` (1239)

29.9.457 RTLeventsync

Synopsis: Obsolete. Don't use

Declaration: `procedure RTLeventsync (m: trtlmethod; p: TProcedure)`

Visibility: default

Description: `RTLeventsync` is obsolete, don't use it.

29.9.458 RTLeventWaitFor

Synopsis: Wait for an event.

Declaration: `procedure RTLeventWaitFor (state: PRTLEvent)`
`procedure RTLeventWaitFor (state: PRTLEvent; timeout: LongInt)`

Visibility: default

Description: `RTLeventWaitFor` suspends the thread till the event occurs. The event will occur when another thread calls `RTLeventSetEvent` (1238) on `State`.

By default, the thread will be suspended indefinitely. However, if `TimeOut` is specified, then the thread will resume after timeout milliseconds have elapsed.

See also: `RTLeventCreate` (1238), `RTLeventDestroy` (1238), `RTLeventSetEvent` (1238), `RTLeventWaitFor` (1239)

29.9.459 RunError

Synopsis: Generate a run-time error.

Declaration: `procedure RunError (w: Word)`
`procedure RunError`

Visibility: default

Description: `Runerror` stops the execution of the program, and generates a run-time error `ErrorCode`.

Errors: None.

See also: `Exit` (1140), `Halt` (1183)

Listing: `./refex/ex55.pp`

Program Example55;

```
{ Program to demonstrate the RunError function. }

begin
  { The program will stop and emit a run-error 106 }
  RunError (106);
end.
```

29.9.460 Seek

Synopsis: Set file position

Declaration: `procedure Seek(var f: File; Pos: Int64)`

Visibility: default

Description: `Seek` sets the file-pointer for file `F` to record `Nr. Count`. The first record in a file has `Count=0`. `F` can be any file type, except `Text`. If `F` is an untyped file, with no record size specified in `Reset` (1234) or `Rewrite` (1236), 128 is assumed.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: `Eof` (1136), `SeekEof` (1241), `SeekEoln` (1241)

Listing: ./refex/ex56.pp

Program Example56;

```
{ Program to demonstrate the Seek function. }

Var
  F : File;
  I, J : longint;

begin
  { Create a file and fill it with data }
  Assign (F, 'test.tmp');
  Rewrite(F); { Create file }
  Close(f);
  FileMode:=2;
  ReSet (F, Sizeof(i)); { Opened read/write }
  For I:=0 to 10 do
    BlockWrite (F, I, 1);
  { Go Back to the beginning of the file }
  Seek(F, 0);
  For I:=0 to 10 do
    begin
      BlockRead (F, J, 1);
      If J<>I then
        WriteLn ('Error: expected ', i, ', got ', j);
      end;
    Close (f);
  end.
```

29.9.461 SeekEOF

Synopsis: Set file position to end of file

Declaration: `function SeekEOF (var t: Text) : Boolean`
`function SeekEOF : Boolean`

Visibility: default

Description: `SeekEof` returns `True` if the file-pointer is at the end of the file. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-file marker is reached. If the end-of-file marker is reached, `True` is returned. Otherwise, `False` is returned. If the parameter `F` is omitted, standard `Input` is assumed.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1136](#)), `SeekEoln` ([1241](#)), `Seek` ([1240](#))

Listing: `./refex/ex57.pp`

Program `Example57`;

```
{ Program to demonstrate the SeekEof function. }
Var C : Char;

begin
  { this will print all characters from standard input except
    Whitespace characters. }
  While Not SeekEof do
    begin
      Read (C);
      Write (C);
    end;
end.
```

29.9.462 SeekEOLn

Synopsis: Set file position to end of line

Declaration: `function SeekEOLn (var t: Text) : Boolean`
`function SeekEOLn : Boolean`

Visibility: default

Description: `SeekEoln` returns `True` if the file-pointer is at the end of the current line. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-line marker is reached. If the end-of-line marker is reached, `True` is returned. Otherwise, `False` is returned. The end-of-line marker is defined as `#10`, the `LineFeed` character. If the parameter `F` is omitted, standard `Input` is assumed.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1136](#)), `SeekEof` ([1241](#)), `Seek` ([1240](#))

Listing: `./refex/ex58.pp`

Program Example58;

```
{ Program to demonstrate the SeekEoln function. }
Var
  C : Char;

begin
  { This will read the first line of standard output and print
    all characters except whitespace. }
  While not SeekEoln do
    Begin
      Read (c);
      Write (c);
    end;
end.
```

29.9.463 Seg

Synopsis: Return segment

Declaration: `function Seg(var X) : LongInt`

Visibility: default

Description: `Seg` returns the segment of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always 0, since Free Pascal uses a flat 32/64 bit memory model. In such a memory model segments have no meaning.

Errors: None.

See also: `DSeg` ([1134](#)), `CSeg` ([1131](#)), `Ofs` ([1202](#)), `Ptr` ([1229](#))

Listing: ./refex/ex60.pp

Program Example60;

```
{ Program to demonstrate the Seg function. }
Var
  W : Word;

begin
  W:=Seg(W); { W contains its own Segment}
end.
```

29.9.464 Setjmp

Synopsis: Save current execution point.

Declaration: `function Setjmp(var S: jmp_buf) : LongInt`

Visibility: default

Description: `SetJmp` fills `env` with the necessary data for a jump back to the point where it was called. It returns zero if called in this way. If the function returns nonzero, then it means that a call to `LongJmp` ([1197](#)) with `env` as an argument was made somewhere in the program.

Errors: None.

See also: LongJump ([1197](#))

Listing: ./refex/ex79.pp

```

program example79;

  { Program to demonstrate the setjmp, longjmp functions }

  procedure dojmp(var env : jmp_buf; value : longint);

  begin
    value:=2;
    Writeln ( 'Going to jump !');
    { This will return to the setjmp call,
      and return value instead of 0 }
    longjmp(env,value);
  end;

  var env : jmp_buf;

  begin
    if setjmp(env)=0 then
      begin
        writeln ( 'Passed first time. ');
        dojmp(env,2);
      end
    else
      writeln ( 'Passed second time. ');
    end.
  
```

29.9.465 SetMemoryManager

Synopsis: Set a memory manager

Declaration: `procedure SetMemoryManager(const MemMgr: TMemoryManager)`

Visibility: default

Description: SetMemoryManager sets the current memory manager record to MemMgr.

For an example, see \progref.

Errors: None.

See also: GetMemoryManager ([1181](#)), IsMemoryManagerSet ([1194](#))

29.9.466 SetMemoryMutexManager

Synopsis: Procedure to set the mutex manager.

Declaration: `procedure SetMemoryMutexManager(var MutexMgr: TMemoryMutexManager)`

Visibility: default

Description: SetMemoryMutexManager sets the mutex manager used by the memory manager to MutexMgr.
The current mutex manager is returned in MutexMgr

Errors: None.

See also: [TMemoryMutexManager \(1102\)](#), [SetMemoryManager \(1243\)](#)

29.9.467 SetNoThreadManager

Synopsis: Clear the threadmanager

Declaration: `procedure SetNoThreadManager`

Visibility: default

Description: `SetNoThreadManager` clears the thread manager by setting the thread manager to an empty thread manager record.

29.9.468 SetString

Synopsis: Set length of a string and copy buffer.

Declaration: `procedure SetString(out S: Shortstring; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: AnsiString; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PChar; Len: SizeInt)`

Visibility: default

Description: `SetString` sets the length of the string `S` to `Len` and if `Buf` is non-nil, copies `Len` characters from `Buf` into `S`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255.

Errors: None.

See also: [SetLength \(1069\)](#)

29.9.469 SetTextBuf

Synopsis: Set size of text file internal buffer

Declaration: `procedure SetTextBuf(var f: Text; var Buf)`
`procedure SetTextBuf(var f: Text; var Buf; Size: SizeInt)`

Visibility: default

Description: `SetTextBuf` assigns an I/O buffer to a text file. The new buffer is located at `Buf` and is `Size` bytes long. If `Size` is omitted, then `SizeOf (Buf)` is assumed. The standard buffer of any text file is 128 bytes long. For heavy I/O operations this may prove too slow. The `SetTextBuf` procedure allows to set a bigger buffer for the IO of the application, thus reducing the number of system calls, and thus reducing the load on the system resources. The maximum size of the newly assigned buffer is 65355 bytes.

Remark:

- Never assign a new buffer to an opened file. A new buffer can be assigned immediately after a call to [Rewrite \(1236\)](#) [Reset \(1234\)](#) or [Append](#), but not after the file was read from/written to. This may cause loss of data. If a new buffer must be assigned after read/write operations have been performed, the file should be flushed first. This will ensure that the current buffer is emptied.

- Take care that the assigned buffer is always valid. If a local variable is assigned as a buffer, then after the program exits the local program block, the buffer will no longer be valid, and stack problems may occur.

Errors: No checking on Size is done.

See also: Assign ([1116](#)), Reset ([1234](#)), Rewrite ([1236](#)), Append ([1114](#))

Listing: ./refex/ex61.pp

Program Example61 ;

{ Program to demonstrate the SetTextBuf function. }

Var

Fin , Fout : Text ;

Ch : Char ;

Bufin , Bufout : **Array**[1..10000] **of** byte ;

begin

Assign (Fin , **paramstr**(1));

Reset (Fin);

Assign (Fout , **paramstr**(2));

Rewrite (Fout);

{ This is harmless before IO has begun }

*{ Try this program again on a big file ,
after commenting out the following 2
lines and recompiling it. }*

SetTextBuf (Fin , Bufin);

SetTextBuf (Fout , Bufout);

While not eof(Fin) **do**

begin

Read (Fin , ch);

write (Fout , ch);

end;

Close (Fin);

Close (Fout);

end.

29.9.470 SetTextLineEnding

Synopsis: Set the end-of-line character for the given text file.

Declaration: procedure SetTextLineEnding(var f: Text;Ending: String)

Visibility: default

Description: SetTextLineEnding sets the end-of-line character for the text file F to Ending. By default, this is the string indicated by DefaultTextLineBreakStyle ([1073](#)).

Errors: None.

See also: DefaultTextLineBreakStyle ([1073](#)), TTextLineBreakStyle ([1103](#))

29.9.471 SetThreadManager

Synopsis: Set the thread manager, optionally return the current thread manager.

Declaration:

```
function SetThreadManager(const NewTM: TThreadManager;
                        var OldTM: TThreadManager) : Boolean
function SetThreadManager(const NewTM: TThreadManager) : Boolean
```

Visibility: default

Description: `SetThreadManager` sets the thread manager to `NewTM`. If `OldTM` is given, `SetThreadManager` uses it to return the previously used thread manager.

The function returns `True` if the threadmanager was set succesfully, `False` if an error occurred.

For more information about thread programming, see the programmer's guide.

Errors: If an error occurred cleaning up the previous manager, or an error occurred initializing the new manager, `False` is returned.

See also: `GetThreadManager` ([1182](#)), `TThreadManager` ([1105](#))

29.9.472 SetVariantManager

Synopsis: Set the current variant manager.

Declaration:

```
procedure SetVariantManager(const VarMgr: tvariantmanager)
```

Visibility: default

Description: `SetVariantManager` sets the variant manager to `varmgr`.

See also: `IsVariantManagerSet` ([1194](#)), `GetVariantManager` ([1182](#))

29.9.473 SetWideStringManager

Synopsis: Set the widestring manager

Declaration:

```
procedure SetWideStringManager(const New: TWideStringManager)
procedure SetWideStringManager(const New: TWideStringManager;
                        var Old: TWideStringManager)
```

Visibility: default

Description: `SetWideStringManager` sets the current widestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `WideString` manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstrings`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

Errors:

See also: `TWideStringManager` ([1109](#))

29.9.474 sin

Synopsis: Calculate sine of angle

Declaration: `function sin(d: ValReal) : ValReal`

Visibility: default

Description: `Sin` returns the sine of its argument `X`, where `X` is an angle in radians. If the absolute value of the argument is larger than 2^{63} , then the result is undefined.

Errors: None.

See also: `Cos` ([1130](#)), `Pi` ([1227](#)), `Exp` ([1141](#)), `Ln` ([1195](#))

Listing: `./refex/ex62.pp`

Program `Example62;`

```
{ Program to demonstrate the Sin function. }

begin
  WriteLn (Sin(Pi):0:1); { Prints 0.0 }
  WriteLn (Sin(Pi/2):0:1); { Prints 1.0 }
end.
```

29.9.475 SizeOf

Synopsis: Return size of a variable or type.

Declaration: `function SizeOf(X: TAnyType) : LongInt`

Visibility: default

Description: `SizeOf` returns the size, in bytes, of any variable or type-identifier.

Remark: This isn't really a RTL function. Its result is calculated at compile-time, and hard-coded in the executable.

Errors: None.

See also: `Addr` ([1113](#))

Listing: `./refex/ex63.pp`

Program `Example63;`

```
{ Program to demonstrate the SizeOf function. }
Var
  I : Longint;
  S : String [10];

begin
  WriteLn (SizeOf(I)); { Prints 4 }
  WriteLn (SizeOf(S)); { Prints 11 }
end.
```

29.9.476 SizeofResource

Synopsis: Return the size of a particular resource

Declaration: `function SizeofResource(ModuleHandle: HMODULE;
ResHandle: TResourceHandle) : Integer`

Visibility: default

Description: `SizeOfResource` returns the size of the resource identified by `ResHandle` in module identified by `ModuleHandle`. `ResHandle` should be obtained from a call to `LoadResource` ([1196](#))

Errors: In case of an error, 0 is returned.

See also: `FindResource` ([1145](#)), `FreeResource` ([1179](#)), `LoadResource` ([1196](#)), `LockResource` ([1197](#)), `UnlockResource` ([1259](#)), `FreeResource` ([1179](#))

29.9.477 Space

Synopsis: Return a string of spaces

Declaration: `function Space(b: Byte) : shortstring`

Visibility: default

Description: `Space` returns a shortstring with length B, consisting of spaces.

See also: `StringOfChar` ([1251](#))

29.9.478 Sptr

Synopsis: Return current stack pointer

Declaration: `function Sptr : Pointer`

Visibility: default

Description: `Sptr` returns the current stack pointer.

Errors: None.

See also: `SSeg` ([1250](#))

Listing: `./refex/ex64.pp`

```

program Example64;

  { Program to demonstrate the sptr function. }

  var p: pstdint;

  begin
    p := ofs(sptr); { P Contains now the current stack position. }
  end.
```

29.9.479 sqr

Synopsis: Calculate the square of a value.

Declaration: `function sqr(l: LongInt) : LongInt`
`function sqr(l: Int64) : Int64`
`function sqr(l: QWord) : QWord`
`function sqr(d: ValReal) : ValReal`

Visibility: default

Description: `Sqr` returns the square of its argument `X`.

Errors: None.

See also: `Sqrt` ([1249](#)), `Ln` ([1195](#)), `Exp` ([1141](#))

Listing: `./refex/ex65.pp`

Program `Example65;`

```
{ Program to demonstrate the Sqr function. }
Var i : Integer;

begin
  For i:=1 to 10 do
    writeln (Sqr(i):3);
end.
```

29.9.480 sqrt

Synopsis: Calculate the square root of a value

Declaration: `function sqrt(d: ValReal) : ValReal`

Visibility: default

Description: `Sqrt` returns the square root of its argument `X`, which must be positive.

Errors: If `X` is negative, then a run-time error is generated.

See also: `Sqr` ([1249](#)), `Ln` ([1195](#)), `Exp` ([1141](#))

Listing: `./refex/ex66.pp`

Program `Example66;`

```
{ Program to demonstrate the Sqrt function. }

begin
  Writeln (Sqrt(4):0:3); { Prints 2.000 }
  Writeln (Sqrt(2):0:3); { Prints 1.414 }
end.
```

29.9.481 Sseg

Synopsis: Return stack segment register value.

Declaration: `function Sseg : Word`

Visibility: default

Description: `SSeg` returns the Stack Segment. This function is only supported for compatibility reasons, as `Sptr` returns the correct contents of the stackpointer.

Errors: None.

See also: `Sptr` ([1248](#))

Listing: `./refex/ex67.pp`

Program Example67;

```
{ Program to demonstrate the SSeg function. }
Var W : Longint;

begin
  W:=SSeg;
end.
```

29.9.482 Str

Synopsis: Convert a numerical value to a string.

Declaration: `procedure Str(var X: TNumericType;var S: String)`

Visibility: default

Description: `Str` returns a string which represents the value of X. X can be any numerical type. The optional `NumPlaces` and `Decimals` specifiers control the formatting of the string.

Errors: None.

See also: `Val` ([1261](#))

Listing: `./refex/ex68.pp`

Program Example68;

```
{ Program to demonstrate the Str function. }
Var S : String;

Function IntToStr (I : Longint) : String;

Var S : String;

begin
  Str (I,S);
  IntToStr:=S;
end;

begin
  S:= '*'+IntToStr(-233)+'*';
  Writeln (S);
end.
```

29.9.483 StringOfChar

Synopsis: Return a string consisting of 1 character repeated N times.

Declaration: `function StringOfChar(c: Char;l: SizeInt) : AnsiString`

Visibility: default

Description: `StringOfChar` creates a new `String` of length `l` and fills it with the character `c`.

It is equivalent to the following calls:

```
SetLength (StringOfChar, 1);
```

```
FillChar(Pointer(StringOfChar)^,Length(StringOfChar),c);
```

Errors: None.

See also: [SetLength \(1069\)](#)

Listing: ./refex/ex97.pp

Program Example97;

 $\{SH_+\}$

```
{ Program to demonstrate the StringOfChar function. }
```

```
Var S : String;
```

begin

```
S:=StringOfChar(' ',40)+'Aligned at column 41.';
```

```
WriteIn (s);
```

end .

29.9.484 StringToPPChar

Synopsis: Split string in list of null-terminated strings

```
Declaration: function StringToPPChar(var S: AnsiString; ReserveEntries: Integer)
                                     : PPChar
```

```
function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar
```

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of `pchars` that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function is only available on certain platforms.

Errors: None.

See also: [ArrayStringToPPchar \(1115\)](#)

29.9.485 StringToWideChar

Synopsis: Convert a string to an array of widechars.

Declaration: `function StringToWideChar(const Src: AnsiString; Dest: PWideChar;
DestSize: SizeInt) : PWideChar`

Visibility: default

Description: `StringToWideChar` converts an ansistring `Src` to a null-terminated array of `WideChars`. The destination for this array is pointed to by `Dest`, and contains room for at least `DestSize` widechars.

Errors: No validity checking is performed on `Dest`.

See also: `WideCharToString` ([1263](#)), `WideCharToStrVar` ([1263](#)), `WideCharLenToStrVar` ([1263](#)), `WideCharLenToString` ([1262](#))

29.9.486 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : LongInt`

Visibility: default

Description: Returns the length of the null-terminated string `P`.

Errors: None.

29.9.487 strpas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in `P` to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

29.9.488 Succ

Synopsis: Return next element of ordinal type.

Declaration: `function Succ(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Succ` returns the element that succeeds the element that was passed to it. If it is applied to the last value of the ordinal type, and the program was compiled with range checking on (`\var{\{$R+\}}`), then a run-time error will be generated.

for an example, see `Ord` ([1226](#)).

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1226](#)), `Pred` ([1229](#)), `High` ([1185](#)), `Low` ([1197](#))

29.9.489 SuspendThread

Synopsis: Suspend a running thread.

Declaration: `function SuspendThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `SuspendThread` suspends a running thread. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is systemm dependent.

See also: `ResumeThread` ([1235](#)), `KillThread` ([1194](#))

29.9.490 Swap

Synopsis: Swap high and low bytes/words of a variable

Declaration: `function swap(X: Word) : Word`
`function Swap(X: Integer) : Integer`
`function swap(X: LongInt) : LongInt`
`function Swap(X: Cardinal) : Cardinal`
`function Swap(X: QWord) : QWord`
`function swap(X: Int64) : Int64`

Visibility: default

Description: `Swap` swaps the high and low order bytes of `X` if `X` is of type `Word` or `Integer`, or swaps the high and low order words of `X` if `X` is of type `Longint` or `Cardinal`. The return type is the type of `X`

Errors: None.

See also: `Lo` ([1196](#)), `Hi` ([1184](#))

Listing: `./refex/ex69.pp`

Program `Example69;`

```
{ Program to demonstrate the Swap function. }
Var W : Word;
    L : Longint;

begin
  W:=$1234;
  W:=Swap(W);
  if W<>$3412 then
    writeln ('Error when swapping word !');
  L:=$12345678;
  L:=Swap(L);
  if L<>$56781234 then
    writeln ('Error when swapping Longint !');
end.
```

29.9.491 SysAllocMem

Synopsis: System memory manager: Allocate memory

Declaration: `function SysAllocMem(size: PtrInt) : Pointer`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `AllocMem` ([1114](#))

See also: `AllocMem` ([1114](#))

29.9.492 SysAssert

Synopsis: Standard Assert failure implementation

Declaration: `procedure SysAssert(const Msg: ShortString; const FName: ShortString;
LineNo: LongInt; ErrorAddr: Pointer)`

Visibility: default

Description: `SysAssert` is the standard implementation of the assertion failed code. It is the default value of the `AssertErrorProc` constant. It will print the assert message `Msg` together with the filename `FName` and linenumber `LineNo` to standard error output (`StdErr`) and will halt the program with exit code 227. The error address `ErrorAddr` is ignored.

See also: `AssertErrorProc` ([1071](#))

29.9.493 SysBackTraceStr

Synopsis: Format an address suitable for inclusion in a backtrace

Declaration: `function SysBackTraceStr(Addr: Pointer) : ShortString`

Visibility: default

Description: `SysBackTraceStr` will create a string representation of the address `Addr`, suitable for inclusion in a stack backtrace.

Errors: None.

29.9.494 SysFreemem

Synopsis: System memory manager free routine.

Declaration: `function SysFreemem(p: pointer) : PtrInt`

Visibility: default

Description: `SysFreeem` is the system memory manager implementation for `FreeMem` ([1178](#))

See also: `FreeMem` ([1178](#))

29.9.495 SysFreememSize

Synopsis: System memory manager free routine.

Declaration: `function SysFreememSize(p: pointer; Size: PtrInt) : PtrInt`

Visibility: default

Description: `SysFreememSize` is the system memory manager implementation for `FreeMem` (1178)

See also: `MemSize` (1198)

29.9.496 SysGetFPCHeapStatus

Synopsis: Return the status of the FPC heapmanager

Declaration: `function SysGetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: `SysGetFPCHeapStatus` returns the status of the default FPC heapmanager. It is set as the default value of the corresponding `GetFPCHeapStatus` (1180) function.

Errors: None. The result of this function is bogus information if the current heapmanager is not the standard FPC heapmanager.

See also: `GetFPCHeapStatus` (1180)

29.9.497 SysGetHeapStatus

Synopsis: System implementation of `GetHeapStatus` (1180)

Declaration: `function SysGetHeapStatus : THeapStatus`

Visibility: default

Description: `SysGetHeapStatus` is the system implementation of the `GetHeapStatus` (1180) call.

See also: `GetHeapStatus` (1180)

29.9.498 SysGetmem

Synopsis: System memory manager memory allocator.

Declaration: `function SysGetmem(Size: PtrInt) : Pointer`

Visibility: default

Description: `SysGetmem` is the system memory manager implementation for `GetMem` (1180)

See also: `GetMem` (1180), `GetMemory` (1181)

29.9.499 SysInitExceptions

Synopsis: Initialize exceptions.

Declaration: `procedure SysInitExceptions`

Visibility: default

Description: `SysInitExceptions` initializes the exception system. This procedure should never be called directly, it is taken care of by the RTL.

29.9.500 SysInitStdIO

Synopsis: Initialize standard input and output.

Declaration: `procedure SysInitStdIO`

Visibility: default

Description: `SysInitStdIO` initializes the standard input and output files: Output (1110), Input (1110) and StdErr (1111). This routine is called by the initialization code of the system unit, there should be no need to call it directly.

29.9.501 SysMemSize

Synopsis: System memory manager: free size.

Declaration: `function SysMemSize(p: pointer) : PtrInt`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `MemSize` (1198)

See also: `MemSize` (1198)

29.9.502 SysReAllocMem

Synopsis: System memory manager: Reallocate memory

Declaration: `function SysReAllocMem(var p: pointer; size: PtrInt) : Pointer`

Visibility: default

Description: `SysReallocMem` is a help routine for the system memory manager implementation for `ReAllocMem` (1233).

See also: `ReAllocMem` (1233)

29.9.503 SysResetFPU

Synopsis: Reset the floating point unit.

Declaration: `procedure SysResetFPU`

Visibility: default

Description: `SysResetFPU` resets the floating point unit. There should normally be no need to call this unit; the compiler itself takes care of this.

29.9.504 SysTryResizeMem

Synopsis: System memory manager: attempt to resize memory.

Declaration: `function SysTryResizeMem(var p: pointer; size: PtrInt) : Boolean`

Visibility: default

Description: `SysTryResizeMem` is a help routine for the system memory manager implementation for `ReAllocMem` (1233), `SysReAllocMem` (1256)

See also: `SysReAllocMem` (1256), `ReAllocMem` (1233)

29.9.505 ThreadGetPriority

Synopsis: Return the priority of a thread.

Declaration: `function ThreadGetPriority(threadHandle: TThreadID) : LongInt`

Visibility: default

Description: `ThreadGetPriority` returns the priority of thread `TThreadID` to `Prio`. The returned priority is a value between -15 and 15.

Errors: None.

See also: `ThreadSetPriority` ([1257](#))

29.9.506 ThreadSetPriority

Synopsis: Set the priority of a thread.

Declaration: `function ThreadSetPriority(threadHandle: TThreadID; Prio: LongInt)
: Boolean`

Visibility: default

Description: `ThreadSetPriority` sets the priority of thread `TThreadID` to `Prio`. Priority is a value between -15 and 15.

Errors: None.

See also: `ThreadGetPriority` ([1257](#))

29.9.507 ThreadSwitch

Synopsis: Signal possibility of thread switch

Declaration: `procedure ThreadSwitch`

Visibility: default

Description: `ThreadSwitch` signals the operating system that the thread should be suspended and that another thread should be executed.

This call is a hint only, and may be ignored.

See also: `SuspendThread` ([1253](#)), `ResumeThread` ([1235](#)), `KillThread` ([1194](#))

29.9.508 trunc

Synopsis: Truncate a floating point value.

Declaration: `function trunc(d: ValReal) : Int64`

Visibility: default

Description: `Trunc` returns the integer part of `X`, which is always smaller than (or equal to) `X` in absolute value.

Errors: None.

See also: `Frac` ([1178](#)), `Int` ([1192](#)), `Round` ([1237](#))

Listing: ./refex/ex70.pp

Program Example70;

```
{ Program to demonstrate the Trunc function. }

begin
  Writeln (Trunc(123.456)); { Prints 123 }
  Writeln (Trunc(-123.456)); { Prints -123 }
  Writeln (Trunc(12.3456)); { Prints 12 }
  Writeln (Trunc(-12.3456)); { Prints -12 }
end.
```

29.9.509 Truncate

Synopsis: Truncate the file at position

Declaration: `procedure Truncate(var F: File)`

Visibility: default

Description: `Truncate` truncates the (opened) file `F` at the current file position.

Errors: Depending on the state of the `\var{\{$I\}}` switch, a runtime error can be generated if there is an error. In the `\var{\{$I-\}}` state, use `IOResult` to check for errors.

See also: Append ([1114](#)), Filepos ([1141](#)), Seek ([1240](#))

Listing: ./refex/ex71.pp

Program Example71;

```
{ Program to demonstrate the Truncate function. }

Var F : File of longint;
    I,L : Longint;

begin
  Assign (F, 'test.tmp');
  Rewrite (F);
  For I:=1 to 10 Do
    Write (F,I);
  Writeln ('Filesize before Truncate : ',FileSize(F));
  Close (f);
  Reset (F);
  Repeat
    Read (F,I);
  Until i=5;
  Truncate (F);
  Writeln ('Filesize after Truncate : ',FileSize(F));
  Close (f);
end.
```

29.9.510 UCS4StringToWideString

Synopsis:

Declaration: `function UCS4StringToWideString(const s: UCS4String) : WideString`

Visibility: default

Description:

Errors:

29.9.511 UnicodeToUtf8

Synopsis:

Declaration: `function UnicodeToUtf8(Dest: PChar;Source: PWideChar;MaxBytes: SizeInt)
: SizeInt
function UnicodeToUtf8(Dest: PChar;MaxDestBytes: SizeUInt;
Source: PWideChar;SourceChars: SizeUInt)
: SizeUInt`

Visibility: default

Description:

Errors:

29.9.512 UniqueString

Synopsis: Make sure reference count of string is 1

Declaration: `procedure UniqueString(var S: AnsiString)
procedure UniqueString(var S: WideString)`

Visibility: default

Description: `UniqueString` ensures that the ansistring `S` has reference count 1. It makes a copy of `S` if this is necessary, and returns the copy in `S`

Errors: None.

29.9.513 UnlockResource

Synopsis: Unlock a previously locked resource

Declaration: `function UnlockResource(ResData: HGLOBAL) : LongBool`

Visibility: default

Description: `UnlockResource` unlocks a previously locked resource. Note that this function does not exist on windows, it's only needed on other platforms.

Errors: The function returns `False` if it failed.

See also: `FindResource` ([1145](#)), `FreeResource` ([1179](#)), `SizeofResource` ([1248](#)), `LoadResource` ([1196](#)), `lockResource` ([1197](#)), `FreeResource` ([1179](#))

29.9.514 upCase

Synopsis: Convert a string to all uppercase.

Declaration: `function upCase(const s: shortstring) : shortstring`
`function upCase(c: Char) : Char`
`function upcase(const s: ansistring) : ansistring`
`function UpCase(const s: WideString) : WideString`

Visibility: default

Description: `UpCase` returns the uppercase version of its argument `C`. If its argument is a string, then the complete string is converted to uppercase. The type of the returned value is the same as the type of the argument.

Errors: None.

See also: Lowercase ([1198](#))

Listing: `./refex/ex72.pp`

```

program Example72;

  { Program to demonstrate the upcase function. }

  var c:char;

  begin
    for c:= 'a' to 'z' do
      write(upcase(c));
      Writeln;
      { This doesn't work in TP, but it does in Free Pascal }
      Writeln(upcase('abcdefghijklmnopqrstuvwxyz'));
  end.
```

29.9.515 UTF8Decode

Synopsis:

Declaration: `function UTF8Decode(const s: UTF8String) : WideString`

Visibility: default

Description:

Errors:

29.9.516 UTF8Encode

Synopsis:

Declaration: `function UTF8Encode(const s: WideString) : UTF8String`

Visibility: default

Description:

Errors:

29.9.517 Utf8ToAnsi

Synopsis:

Declaration: `function Utf8ToAnsi(const s: UTF8String) : ansistring`

Visibility: default

Description:

Errors:

29.9.518 Utf8ToUnicode

Synopsis:

Declaration: `function Utf8ToUnicode(Dest: PWideChar;Source: PChar;MaxChars: SizeInt)
: SizeInt
function Utf8ToUnicode(Dest: PWideChar;MaxDestChars: SizeUInt;
Source: PChar;SourceBytes: SizeUInt) : SizeUInt`

Visibility: default

Description:

Errors:

29.9.519 Val

Synopsis: Calculate numerical value of a string.

Declaration: `procedure Val(const S: String;var V;var Code: Word)`

Visibility: default

Description: `Val` converts the value represented in the string `S` to a numerical value, and stores this value in the variable `V`, which can be of type `Longint`, `Real` and `Byte`. If the conversion isn't successful, then the parameter `Code` contains the index of the character in `S` which prevented the conversion. The string `S` is allowed to contain spaces in the beginning. The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference.

Errors: If the conversion doesn't succeed, the value of `Code` indicates the position where the conversion went wrong.

See also: `Str` ([1250](#))

Listing: `./refex/ex74.pp`

Program `Example74;`

```
{ Program to demonstrate the Val function. }
Var I, Code : Integer;

begin
  Val (ParamStr (1), I, Code);
  If Code<>0 then
    Writeln ('Error at position ', code, ' : ', Paramstr(1)[Code])
  else
    Writeln ('Value : ', I);
end.
```

29.9.520 VarArrayRedim

Synopsis: Redimension a variant array

Declaration: `procedure VarArrayRedim(var A: Variant; HighBound: SizeInt)`

Visibility: default

Description: `VarArrayRedim` re-sizes the first dimension of the variant array `A`, giving it a new high bound `HighBound`. Obviously, `A` must be a variant array for this function to work.

Errors:

29.9.521 VarCast

Synopsis:

Declaration: `procedure VarCast(var dest: variant; const source: variant;
vartype: LongInt)`

Visibility: default

Description:

Errors:

29.9.522 WaitForThreadTerminate

Synopsis: Wait for a thread to terminate.

Declaration: `function WaitForThreadTerminate(threadHandle: TThreadID;
TimeoutMs: LongInt) : DWord`

Visibility: default

Description: `WaitForThreadTerminate` waits for a thread to finish its execution. The thread is identified by its handle or ID `threadHandle`. If the thread does not exit within `TimeoutMs` milliseconds, the function will return with an error value.

The function returns the exit code of the thread.

See also: `EndThread` ([1136](#)), `KillThread` ([1194](#))

29.9.523 WideCharLenToString

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `function WideCharLenToString(S: PWideChar; Len: SizeInt) : AnsiString`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `S`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1252](#)), `WideCharToString` ([1263](#)), `WideCharToStrVar` ([1263](#)), `WideCharLenToStrVar` ([1263](#))

29.9.524 WideCharLenToStrVar

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `Src` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` (1252), `WideCharToString` (1263), `WideCharToStrVar` (1263), `WideCharLenToString` (1262)

29.9.525 WideCharToString

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `function WideCharToString(S: PWideChar) : AnsiString`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` (1252), `WideCharToStrVar` (1263), `WideCharLenToStrVar` (1263), `WideCharLenToString` (1262)

29.9.526 WideCharToStrVar

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `procedure WideCharToStrVar(S: PWideChar; out Dest: AnsiString)`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `S`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` (1252), `WideCharToString` (1263), `WideCharToStrVar` (1263), `WideCharLenToString` (1262)

29.9.527 WideStringToUCS4String

Synopsis: Convert a widestring to a UCS-4 encoded string.

Declaration: `function WideStringToUCS4String(const s: WideString) : UCS4String`

Visibility: default

Description: Convert a widestring to a UCS-4 encoded string.

Errors:

29.9.528 Write

Synopsis: Write variable to a text file

Declaration: `procedure Write(Args: Arguments)`
`procedure Write(var F: Text; Args: Arguments)`

Visibility: default

Description: `Write` writes the contents of the variables `V1`, `V2` etc. to the file `F`. `F` can be a typed file, or a `Text` file. If `F` is a typed file, then the variables `V1`, `V2` etc. must be of the same type as the type in the declaration of `F`. Untyped files are not allowed. If the parameter `F` is omitted, standard output is assumed. If `F` is of type `Text`, then the necessary conversions are done such that the output of the variables is in human-readable format. This conversion is done for all numerical types. Strings are printed exactly as they are in memory, as well as `PChar` types. The format of the numerical conversions can be influenced through the following modifiers: `OutputVariable : NumChars [: Decimals]`. This will print the value of `OutputVariable` with a minimum of `NumChars` characters, from which `Decimals` are reserved for the decimals. If the number cannot be represented with `NumChars` characters, `NumChars` will be increased, until the representation fits. If the representation requires less than `NumChars` characters then the output is filled up with spaces, to the left of the generated string, thus resulting in a right-aligned representation. If no formatting is specified, then the number is written using its natural length, with nothing in front of it if it's positive, and a minus sign if it's negative. Real numbers are, by default, written in scientific notation.

Errors: If an error occurs, a run-time error is generated. This behavior can be controlled with the `\var{\{$i\}}` switch.

See also: `WriteLn` (1264), `Read` (1231), `ReadLn` (1232), `Blockwrite` (1121)

29.9.529 WriteLn

Synopsis: Write variable to a text file and append newline

Declaration: `procedure Writeln(Args: Arguments)`
`procedure WriteLn(var F: Text; Args: Arguments)`

Visibility: default

Description: `WriteLn` does the same as `Write` (1264) for text files, and emits a Carriage Return - LineFeed character pair after that. If the parameter `F` is omitted, standard output is assumed. If no variables are specified, a Carriage Return - LineFeed character pair is emitted, resulting in a new line in the file `F`.

Remark: Under linux and unix, the Carriage Return character is omitted, as customary in Unix environments.

Errors: If an error occurs, a run-time error is generated. This behavior can be controlled with the `\var{\{$i\}}` switch.

See also: `Write` (1264), `Read` (1231), `ReadLn` (1232), `Blockwrite` (1121)

Listing: `./refex/ex75.pp`

Program `Example75;`

{ Program to demonstrate the Write(Ln) function. }

Var

`F : File of Longint;`
`L : Longint;`

```

begin
  Write ( 'This is on the first line ! '); { No CR/LF pair ! }
  Writeln ( 'And this too... ');
  Writeln ( 'But this is already on the second line... ');
  Assign (f, 'test.tmp');
  Rewrite (f);
  For L:=1 to 10 do
    write (F,L); { No writeln allowed here ! }
  Close (f);
end.

```

29.10 IDispatch

29.10.1 Description

IDispatch is the pascal definition of the Windows Dispatch interface definition.

29.10.2 Method overview

Page	Property	Description
1265	GetIDsOfNames	Return IDs of named procedures
1265	GetTypeInfo	Return type information about properties
1265	GetTypeInfoCount	Return number of properties.
1266	Invoke	Invoke a dispatch method

29.10.3 IDispatch.GetTypeInfoCount

Synopsis: Return number of properties.

Declaration: `function GetTypeInfoCount(out count: LongInt) : LongInt`

Visibility: default

29.10.4 IDispatch.GetTypeInfo

Synopsis: Return type information about properties

Declaration: `function GetTypeInfo(Index: LongInt; LocaleID: LongInt; out TypeInfo) : LongInt`

Visibility: default

29.10.5 IDispatch.GetIDsOfNames

Synopsis: Return IDs of named procedures

Declaration: `function GetIDsOfNames(const iid: TGuid; names: Pointer; NameCount: LongInt; LocaleID: LongInt; DispIDs: Pointer) : LongInt`

Visibility: default

Description: Return the ID of a procedure.

29.10.6 IDispatch.Invoke

Synopsis: Invoke a dispatch method

Declaration: `function Invoke(DispID: LongInt; const iid: TGuid; LocaleID: LongInt;
Flags: Word; var params; VarResult: pointer;
ExcepInfo: pointer; ArgErr: pointer) : LongInt`

Visibility: default

29.11 IInvokable

29.11.1 Description

`IInvokable` is a descendent of `IInterface` ([1091](#)), compiled in the `{ $M+ }` state, so Run-Time Type Information (RTTI) is generated for it.

29.12 IUnknown

29.12.1 Description

`IUnknown` is defined by windows. It's the basic interface which all COM objects must implement. The definition does not contain any code.

29.12.2 Method overview

Page	Property	Description
1266	<code>_AddRef</code>	Increase reference count of the interface
1267	<code>_Release</code>	Decrease reference count of the interface
1266	<code>QueryInterface</code>	Return pointer to VMT table of interface

29.12.3 IUnknown.QueryInterface

Synopsis: Return pointer to VMT table of interface

Declaration: `function QueryInterface(const iid: TGuid; out obj) : LongInt`

Visibility: default

29.12.4 IUnknown._AddRef

Synopsis: Increase reference count of the interface

Declaration: `function _AddRef : LongInt`

Visibility: default

See also: `IUnknown._Release` ([1267](#))

29.12.5 IUnknown._Release

Synopsis: Decrease reference count of the interface

Declaration: `function _Release : LongInt`

Visibility: `default`

See also: `IUnknown._AddRef` ([1266](#))

29.13 TInterfacedObject

29.13.1 Description

`TInterfacedObject` is a descendent of `TObject` ([1268](#)) which implements the `IUnknown` ([1266](#)) interface. It can be used as a base class for all classes which need reference counting.

29.13.2 Method overview

Page	Property	Description
1267	<code>AfterConstruction</code>	Handle reference count properly.
1267	<code>BeforeDestruction</code>	Check reference count.
1268	<code>NewInstance</code>	Create a new instance

29.13.3 Property overview

Page	Property	Access	Description
1268	<code>RefCount</code>	<code>r</code>	Return the current reference count

29.13.4 TInterfacedObject.AfterConstruction

Synopsis: Handle reference count properly.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in `TObject` and adds some additional reference count handling.

Errors: None.

See also: `TInterfacedObject.BeforeDestruction` ([1267](#))

29.13.5 TInterfacedObject.BeforeDestruction

Synopsis: Check reference count.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in `TObject` and adds a reference count check: if the reference count is not zero, an error occurs.

Errors: A runtime-error 204 will be generated if the reference count is nonzero when the object is destroyed.

See also: `TInterfacedObject.AfterConstruction` ([1267](#))

29.13.6 TInterfacedObject.NewInstance

Synopsis: Create a new instance

Declaration: `function NewInstance : TObject; Override`

Visibility: `public`

Description: `NewInstance` initializes a new instance of `TInterfacedObject` ([1267](#))

Errors: None.

29.13.7 TInterfacedObject.RefCount

Synopsis: Return the current reference count

Declaration: `Property RefCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `RefCount` returns the current reference count. This reference count cannot be manipulated, except through the methods of `IUnknown` ([1266](#)). When it reaches zero, the class instance is destroyed.

See also: `IUnknown` ([1266](#))

29.14 TObject

29.14.1 Description

`TObject` is the parent root class for all classes in Object Pascal. If a class has no parent class explicitly declared, it is dependent on `TObject`. `TObject` introduces class methods that deal with the class' type information, and contains all necessary methods to create an instance at runtime, and to dispatch messages to the correct method (both string and integer messages).

29.14.2 Method overview

Page	Property	Description
1275	AfterConstruction	Method called after the constructor was called.
1275	BeforeDestruction	Method called before the destructor is called.
1272	ClassInfo	Return a pointer to the type information for this class.
1272	ClassName	Return the current class name.
1272	ClassNameIs	Check whether the class name equals the given name.
1273	ClassParent	Return the parent class.
1272	ClassType	Return a "class of" pointer for the current class
1271	CleanupInstance	Finalize the class instance.
1269	Create	TObject Constructor
1271	DefaultHandler	Default handler for integer message handlers.
1275	DefaultHandlerStr	Default handler for string messages.
1269	Destroy	TObject destructor.
1274	Dispatch	Dispatch an integer message
1274	DispatchStr	Dispatch a string message.
1275	FieldAddress	Return the address of a field.
1271	Free	Check for Nil and call destructor.
1270	FreeInstance	Clean up instance and free the memory reserved for the instance.
1276	GetInterface	Return a reference to an interface
1276	GetInterfaceByStr	
1276	GetInterfaceEntry	
1276	GetInterfaceEntryByStr	
1277	GetInterfaceTable	
1273	InheritsFrom	Check whether class is an ancestor.
1271	InitInstance	Initialize a new class instance.
1273	InstanceSize	Return the size of an instance.
1274	MethodAddress	Return the address of a method
1274	MethodName	Return the name of a method.
1270	newinstance	Allocate memory on the heap for a new instance
1270	SafeCallException	Handle exception object
1273	StringMessageTable	Return a pointer to the string message table.

29.14.3 TObject.Create

Synopsis: TObject Constructor

Declaration: constructor Create

Visibility: public

Description: Create creates a new instance of TObject. Currently it does nothing. It is also not virtual, so there is in principle no need to call it directly.

See also: TObject.Destroy ([1269](#))

29.14.4 TObject.Destroy

Synopsis: TObject destructor.

Declaration: destructor Destroy; Virtual

Visibility: public

Description: `Destroy` is the destructor of `TObject`. It will clean up the memory assigned to the instance. Descendent classes should override `destroy` if they want to do additional clean-up. No other destructor should be implemented.

It is bad programming practice to call `Destroy` directly. It is better to call the `Free` (1271) method, because that one will check first if `Self` is different from `Nil`.

To clean up an instance and reset the refence to the instance, it is best to use the `FreeAndNil` (1360) function.

See also: `TObject.Create` (1269), `TObject.Free` (1271)

29.14.5 TObject.newinstance

Synopsis: Allocate memory on the heap for a new instance

Declaration: `function newInstance : TObject; Virtual`

Visibility: public

Description: `NewInstance` allocates memory on the heap for a new instance of the current class. If the memory was allocated, the class will be initialized by a call to `InitInstance` (1271). The function returns the newly initialized instance.

Errors: If not enough memory is available, a `Nil` pointer may be returned, or an exception may be raised.

See also: `TObject.Create` (1269), `TObject.InitInstance` (1271), `TObject.InstanceSize` (1273), `TObject.FreeInstance` (1270)

29.14.6 TObject.FreeInstance

Synopsis: Clean up instance and free the memory reserved for the instance.

Declaration: `procedure FreeInstance; Virtual`

Visibility: public

Description: `FreeInstance` cleans up an instance of the current class, and releases the heap memory occupied by the class instance.

See also: `TObject.Destroy` (1269), `TObject.InitInstance` (1271), `TObject.NewInstance` (1270)

29.14.7 TObject.SafeCallException

Synopsis: Handle exception object

Declaration: `function SafeCallException(exceptobject: TObject;exceptaddr: pointer)
: LongInt; Virtual`

Visibility: public

Description: `SafeCallException` should be overridden to handle exceptions in a method marked with the `savecall` directive. The implementation in `TObject` simply returns zero.

29.14.8 TObject.DefaultHandler

Synopsis: Default handler for integer message handlers.

Declaration: `procedure DefaultHandler(var message); Virtual`

Visibility: `public`

Description: `DefaultHandler` is the default handler for messages. If a message has an unknown message ID (i.e. does not appear in the table with integer message handlers), then it will be passed to `DefaultHandler` by the `Dispatch` (1274) method.

Errors:

See also: `TObject.Dispatch` (1274), `TObject.DefaultHandlerStr` (1275)

29.14.9 TObject.Free

Synopsis: Check for `Nil` and call destructor.

Declaration: `procedure Free`

Visibility: `public`

Description: `Free` will check the `Self` pointer and calls `Destroy` (1269) if it is different from `Nil`. This is a safer method than calling `Destroy` directly. If a reference to the object must be reset as well (a recommended technique), then the function `FreeAndNil` (1360) should be called.

Errors: None.

See also: `TObject.Destroy` (1269), `#rtl.sysutils.freeandnil` (1360)

29.14.10 TObject.InitInstance

Synopsis: Initialize a new class instance.

Declaration: `function InitInstance(instance: pointer) : TObject`

Visibility: `public`

Description: `InitInstance` initializes the memory pointer to by `Instance`. This means that the VMT is initialized, and the interface pointers are set up correctly. The function returns the newly initialized instance.

See also: `TObject.NewInstance` (1270), `TObject.Create` (1269)

29.14.11 TObject.CleanupInstance

Synopsis: Finalize the class instance.

Declaration: `procedure CleanupInstance`

Visibility: `public`

Description: `CleanUpInstance` finalizes the instance, i.e. takes care of all reference counted objects, by decreasing their reference count by 1, and freeing them if their count reaches zero.

Normally, `CleanupInstance` should never be called, it is called automatically when the object is freed with it's constructor.

Errors: None.

See also: `TObject.Destroy` (1269), `TObject.Free` (1271), `TObject.InitInstance` (1271)

29.14.12 TObject.ClassType

Synopsis: Return a "class of" pointer for the current class

Declaration: `function ClassType : TClass`

Visibility: public

Description: `ClassType` returns a `TClass` (1098) class type reference for the current class.

See also: `TClass` (1098), `TObject.ClassInfo` (1272), `TObject.ClassName` (1272)

29.14.13 TObject.ClassInfo

Synopsis: Return a pointer to the type information for this class.

Declaration: `function ClassInfo : pointer`

Visibility: public

Description: `ClassInfo` returns a pointer to the type information for this class. This pointer can be used in the various type information routines.

29.14.14 TObject.ClassName

Synopsis: Return the current class name.

Declaration: `function ClassName : shortstring`

Visibility: public

Description: `ClassName` returns the class name for the current class, in all-uppercase letters. To check for the class name, use the `ClassNameIs` (1272) class method.

Errors: None.

See also: `TObject.ClassInfo` (1272), `TObject.ClassType` (1272), `TObject.ClassNameIs` (1272)

29.14.15 TObject.ClassNameIs

Synopsis: Check whether the class name equals the given name.

Declaration: `function ClassNameIs(const name: String) : Boolean`

Visibility: public

Description: `ClassNameIs` checks whether `Name` equals the class name. It takes of case sensitivity, i.e. it converts both names to uppercase before comparing.

See also: `TObject.ClassInfo` (1272), `TObject.ClassType` (1272), `TObject.ClassName` (1272)

29.14.16 TObject.ClassParent

Synopsis: Return the parent class.

Declaration: `function ClassParent : TClass`

Visibility: public

Description: `ClassParent` returns the class of the parent class of the current class. This is always different from `Nil`, except for `TObject`.

Errors: None.

See also: `TObject.ClassInfo` ([1272](#)), `TObject.ClassType` ([1272](#)), `TObject.ClassName` ([1272](#))

29.14.17 TObject.InstanceSize

Synopsis: Return the size of an instance.

Declaration: `function InstanceSize : SizeInt`

Visibility: public

Description: `InstanceSize` returns the number of bytes an instance takes in memory. This is Just the memory occupied by the class structure, and does not take into account any additional memory that might be allocated by the constructor of the class.

Errors: None.

See also: `TObject.InitInstance` ([1271](#)), `TObject.ClassName` ([1272](#)), `TObject.ClassInfo` ([1272](#)), `TObject.ClassType` ([1272](#))

29.14.18 TObject.InheritsFrom

Synopsis: Chck wether class is an ancestor.

Declaration: `function InheritsFrom(aclass: TClass) : Boolean`

Visibility: public

Description: `InheritsFrom` returns `True` if `AClass` is an ancestor class from the current class, and returns `false` if it is not.

Errors:

See also: `TObject.ClassName` ([1272](#)), `TObject.ClassInfo` ([1272](#)), `TObject.ClassType` ([1272](#)), `TClass` ([1098](#))

29.14.19 TObject.StringMessageTable

Synopsis: Return a pointer to the string message table.

Declaration: `function StringMessageTable : pstringmessagetable`

Visibility: public

Description: `StringMessageTable` returns a pointer to the string message table, which can be used to look up methods for dispatching a string message. It is used by the `DispatchStr` ([1274](#)) method.

Errors: If there are no string message handlers, `nil` is returned.

See also: `TObject.DispatchStr` ([1274](#)), `TObject.Dispatch` ([1274](#))

29.14.20 TObject.Dispatch

Synopsis: Dispatch an integer message

Declaration: `procedure Dispatch(var message)`

Visibility: public

Description: `Dispatch` looks in the message handler table for a handler that handles `message`. The message is identified by the first dword (cardinal) in the message structure.

If no matching message handler is found, the message is passed to the `DefaultHandler` ([1271](#)) method, which can be overridden by descendent classes to add custom handling of messages.

See also: `TObject.DispatchStr` ([1274](#)), `TObject.DefaultHandler` ([1271](#))

29.14.21 TObject.DispatchStr

Synopsis: Dispatch a string message.

Declaration: `procedure DispatchStr(var message)`

Visibility: public

Description: `DispatchStr` extracts the message identifier from `Message` and checks the message handler table to see if a handler for the message is found, and calls the handler, passing along the message.

If no handler is found, the default `DefaultHandlerStr` ([1275](#)) is called.

Errors: None.

See also: `TObject.DefaultHandlerStr` ([1275](#)), `TObject.Dispatch` ([1274](#)), `TObject.DefaultHandler` ([1271](#))

29.14.22 TObject.MethodAddress

Synopsis: Return the address of a method

Declaration: `function MethodAddress(const name: shortstring) : pointer`

Visibility: public

Description: `MethodAddress` returns the address of a method, searching the method by its name. The `Name` parameter specifies which method should be taken. The search is conducted in a case-insensitive manner.

Errors: If no matching method is found, `Nil` is returned.

See also: `TObject.MethodName` ([1274](#)), `TObject.FieldAddress` ([1275](#))

29.14.23 TObject.MethodName

Synopsis: Return the name of a method.

Declaration: `function MethodName(address: pointer) : shortstring`

Visibility: public

Description: `MethodName` searches the VMT for a method with the specified address and returns the name of the method.

Errors: If no method with the matching address is found, an empty string is returned.

See also: `TObject.MethodAddress` ([1274](#)), `TObject.FieldAddress` ([1275](#))

29.14.24 TObject.FieldAddress

Synopsis: Return the address of a field.

Declaration: `function FieldAddress(const name: shortstring) : pointer`

Visibility: public

Description: `FieldAddress` returns the address of the field with name `name`. The address is the address of the field in the current class instance.

Errors: If no field with the specified name is found, `Nil` is returned.

See also: `TObject.MethodAddress` ([1274](#)), `TObject.MethodName` ([1274](#))

29.14.25 TObject.AfterConstruction

Synopsis: Method called after the constructor was called.

Declaration: `procedure AfterConstruction; Virtual`

Visibility: public

Description: `AfterConstruction` is a method called after the constructor was called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed after the constructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `TObject.BeforeDestruction` ([1275](#)), `TObject.Create` ([1269](#))

29.14.26 TObject.BeforeDestruction

Synopsis: Method called before the destructor is called.

Declaration: `procedure BeforeDestruction; Virtual`

Visibility: public

Description: `BeforeDestruction` is a method called before the destructor is called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed before the destructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `TObject.AfterConstruction` ([1275](#)), `TObject.Destroy` ([1269](#)), `TObject.Free` ([1271](#))

29.14.27 TObject.DefaultHandlerStr

Synopsis: Default handler for string messages.

Declaration: `procedure DefaultHandlerStr(var message); Virtual`

Visibility: public

Description: `DefaultHandlerStr` is called for string messages which have no handler associated with them in the string message handler table. The implementation of `DefaultHandlerStr` in `TObject` does nothing and must be overridden by descendent classes to provide specific message handling behaviour.

See also: `TObject.DispatchStr` ([1274](#)), `TObject.Dispatch` ([1274](#)), `TObject.DefaultHandler` ([1271](#))

29.14.28 `TObject.GetInterface`

Synopsis: Return a reference to an interface

Declaration: `function GetInterface(const iid: TGuid;out obj) : Boolean`

Visibility: public

Description: `GetInterface` scans the interface tables and returns a reference to the interface `iid`. The reference is stored in `Obj` which should be an interface reference. It returns `True` if the interface was found, `False` if not.

The reference count of the interface is increased by this call.

Errors: If no interface was found, `False` is returned.

See also: `TObject.GetInterfaceByStr` ([1276](#))

29.14.29 `TObject.GetInterfaceByStr`

Synopsis:

Declaration: `function GetInterfaceByStr(const iidstr: String;out obj) : Boolean`

Visibility: public

Description:

Errors:

29.14.30 `TObject.GetInterfaceEntry`

Synopsis:

Declaration: `function GetInterfaceEntry(const iid: TGuid) : pinterfaceentry`

Visibility: public

Description:

Errors:

29.14.31 `TObject.GetInterfaceEntryByStr`

Synopsis:

Declaration: `function GetInterfaceEntryByStr(const iidstr: String) : pinterfaceentry`

Visibility: public

Description:

Errors:

29.14.32 TObject.GetInterfaceTable

Synopsis:

Declaration: `function GetInterfaceTable : pinterfacetable`

Visibility: `public`

Description:

Errors:

Chapter 30

Reference for unit 'sysutils'

30.1 Miscellaneous conversion routines

Functions for various conversions.

Table 30.1:

Name	Description
BCDToInt (1313)	Convert BCD number to integer
CompareMem (1315)	Compare two memory regions
FloatToStrF (1348)	Convert float to formatted string
FloatToStr (1347)	Convert float to string
FloatToText (1350)	Convert float to string
FormatFloat (1359)	Format a floating point value
GetDirs (1362)	Split string in list of directories
IntToHex (1368)	return hexadecimal representation of integer
IntToStr (1368)	return decumal representation of integer
StrToIntDef (1398)	Convert string to integer with default value
StrToInt (1396)	Convert string to integer
StrToFloat (1395)	Convert string to float
TextToFloat (1401)	Convert null-terminated string to float

30.2 Date/time routines

Functions for date and time handling.

30.3 FileName handling routines

Functions for file manipulation.

30.4 File input/output routines

Functions for reading/writing to file.

Table 30.2:

Name	Description
<code>DateTimeToFileDate</code> (1320)	Convert <code>DateTime</code> type to file date
<code>DateTimeToStr</code> (1321)	Construct string representation of <code>DateTime</code>
<code>DateTimeToString</code> (1321)	Construct string representation of <code>DateTime</code>
<code>DateTimeToSystemTime</code> (1322)	Convert <code>DateTime</code> to system time
<code>DateTimeToTimeStamp</code> (1323)	Convert <code>DateTime</code> to timestamp
<code>DateToStr</code> (1323)	Construct string representation of date
<code>Date</code> (1320)	Get current date
<code>DayOfWeek</code> (1324)	Get day of week
<code>DecodeDate</code> (1324)	Decode <code>DateTime</code> to year month and day
<code>DecodeTime</code> (1325)	Decode <code>DateTime</code> to hours, minutes and seconds
<code>EncodeDate</code> (1329)	Encode year, day and month to <code>DateTime</code>
<code>EncodeTime</code> (1329)	Encode hours, minutes and seconds to <code>DateTime</code>
<code>FormatDateTime</code> (1358)	Return string representation of <code>DateTime</code>
<code>IncMonth</code> (1366)	Add 1 to month
<code>IsLeapYear</code> (1370)	Determine if year is leap year
<code>MSecsToTimeStamp</code> (1373)	Convert nr of milliseconds to timestamp
<code>Now</code> (1374)	Get current date and time
<code>StrToDateTime</code> (1394)	Convert string to <code>DateTime</code>
<code>StrToDate</code> (1394)	Convert string to date
<code>StrToTime</code> (1399)	Convert string to time
<code>SystemTimeToDateTime</code> (1400)	Convert system time to datetime
<code>TimeStampToDateTime</code> (1402)	Convert time stamp to <code>DateTime</code>
<code>TimeStampToMSecs</code> (1403)	Convert Timestamp to number of millicseconds
<code>TimeToStr</code> (1403)	return string representation of Time
<code>Time</code> (1402)	Get current tyme

30.5 PChar related functions

Most PChar functions are the same as their counterparts in the STRINGS unit. The following functions are the same :

1. `StrCat` (1380) : Concatenates two PChar strings.
2. `StrComp` (1381) : Compares two PChar strings.
3. `StrCopy` (1382) : Copies a PChar string.
4. `StrECopy` (1383) : Copies a PChar string and returns a pointer to the terminating null byte.
5. `StrEnd` (1383) : Returns a pointer to the terminating null byte.
6. `StrIComp` (1384) : Case insensitive compare of 2 PChar strings.
7. `StrLCat` (1386) : Appends at most L characters from one PChar to another PChar.
8. `StrLComp` (1386) : Case sensitive compare of at most L characters of 2 PChar strings.
9. `StrLCopy` (1387) : Copies at most L characters from one PChar to another.
10. `StrLen` (1388) : Returns the length (exclusive terminating null byte) of a PChar string.
11. `StrLIComp` (1389) : Case insensitive compare of at most L characters of 2 PChar strings.

Table 30.3:

Name	Description
AddDisk (1298)	Add sisk to list of disk drives
ChangeFileExt (1315)	Change extension of file name
CreateDir (1318)	Create a directory
DeleteFile (1326)	Delete a file
DiskFree (1327)	Free space on disk
DiskSize (1327)	Total size of disk
ExpandFileName (1332)	Create full file name
ExpandUNCFileName (1333)	Create full UNC file name
ExtractFileDir (1333)	Extract drive and directory part of filename
ExtractFileDrive (1334)	Extract drive part of filename
ExtractFileExt (1334)	Extract extension part of filename
ExtractFileName (1334)	Extract name part of filename
ExtractFilePath (1335)	Extrct path part of filename
ExtractRelativePath (1335)	Construct relative path between two files
FileAge (1336)	Return file age
FileDateToDateTime (1338)	Convert file date to system date
FileExists (1338)	Determine whether a file exists on disk
FileGetAttr (1339)	Get attributes of file
FileGetDate (1340)	Get date of last file modification
FileSearch (1342)	Search for file in path
FileSetAttr (1343)	Get file attributes
FileSetDate (1343)	Get file dates
FindFirst (1345)	Start finding a file
FindNext (1346)	Find next file
GetCurrentDir (1361)	Return current working directory
RemoveDir (1375)	Remove a directory from disk
RenameFile (1376)	Rename a file on disk
SetCurrentDir (1377)	Set current working directory
SetDirSeparators (1378)	Set directory separator characters
FindClose (1344)	Stop searching a file
DoDirSeparators (1328)	Replace directory separator characters

12. StrLower (1389) : Converts a PChar to all lowercase letters.
13. StrMove (1390) : Moves one PChar to another.
14. StrNew (1390) : Makes a copy of a PChar on the heap, and returns a pointer to this copy.
15. StrPos (1392) : Returns the position of one PChar string in another?
16. StrRScan (1392) : returns a pointer to the last occurrence of on PChar string in another one.
17. StrScan (1392) : returns a pointer to the first occurrence of on PChar string in another one.
18. StrUpper (1399) : Converts a PChar to all uppercase letters.

The subsequent functions are different from their counterparts in **STRINGS**, although the same examples can be used.

Table 30.4:

Name	Description
FileCreate (1337)	Create a file and return handle
FileOpen (1341)	Open file end return handle
FileRead (1341)	Read from file
FileSeek (1342)	Set file position
FileTruncate (1344)	Truncate file length
FileWrite (1344)	Write to file
FileClose (1336)	Close file handle

30.6 Date and time formatting characters

Various date and time formatting routines accept a format string. to format the date and or time. The following characters can be used to control the date and time formatting:

c shortdateformat + ' ' + shorttimeformat

d day of month

dd day of month (leading zero)

ddd day of week (abbreviation)

dddd day of week (full)

dddddd shortdateformat

ddddddd longdateformat

m month

mm month (leading zero)

mmm month (abbreviation)

mmmm month (full)

y year (2 digits)

yy year (two digits)

yyyy year (with century)

h hour

hh hour (leading zero)

n minute

nn minute (leading zero)

s second

ss second (leading zero)

t shorttimeformat

tt longtimeformat

am/pm use 12 hour clock and display am and pm accordingly

a/p use 12 hour clock and display a and p accordingly

/ insert date separator

: insert time separator

"xx" literal text

'xx' literal text

30.7 Formatting strings

Functions for formatting strings.

Table 30.5:

Name	Description
AdjustLineBreaks (1298)	Convert line breaks to line breaks for system
FormatBuf (1357)	Format a buffer
Format (1352)	Format arguments in string
FmtStr (1351)	Format buffer
QuotedStr (1375)	Quote a string
StrFmt (1384)	Format arguments in a string
StrLFmt (1388)	Format maximum L characters in a string
TrimLeft (1405)	Remove whitespace at the left of a string
TrimRight (1405)	Remove whitespace at the right of a string
Trim (1404)	Remove whitespace at both ends of a string

30.8 String functions

Functions for handling strings.

30.9 Used units

30.10 Overview

This documentation describes the `sysutils` unit. The `sysutils` unit was started by Gertjan Schouten, and completed by Michael Van Canneyt. It aims to be compatible to the Delphi `sysutils` unit, but in contrast with the latter, it is designed to work on multiple platforms. It is implemented on all supported platforms.

30.11 Constants, types and variables

30.11.1 Constants

```
ConfigExtension : String = '.cfg'
```

Table 30.6:

Name	Description
AnsiCompareStr (1299)	Compare two strings
AnsiCompareText (1300)	Compare two strings, case insensitive
AnsiExtractQuotedStr (1301)	Removes quotes from string
AnsiLastChar (1302)	Get last character of string
AnsiLowerCase (1302)	Convert string to all-lowercase
AnsiQuotedStr (1304)	Quotes a string
AnsiStrComp (1304)	Compare strings case-sensitive
AnsiStrIComp (1305)	Compare strings case-insensitive
AnsiStrLComp (1307)	Compare L characters of strings case sensitive
AnsiStrLIComp (1307)	Compare L characters of strings case insensitive
AnsiStrLastChar (1306)	Get last character of string
AnsiStrLower (1308)	Convert string to all-lowercase
AnsiStrUpper (1310)	Convert string to all-uppercase
AnsiUpperCase (1310)	Convert string to all-uppercase
AppendStr (1311)	Append 2 strings
AssignStr (1312)	Assign value of strings on heap
CompareStr (1316)	Compare two strings case sensitive
CompareText (1317)	Compare two strings case insensitive
DisposeStr (1328)	Remove string from heap
IsValidIdent (1370)	Is string a valid pascal identifier
LastDelimiter (1371)	Last occurrence of character in a string
LeftStr (1372)	Get first N characters of a string
LoadStr (1372)	Load string from resources
LowerCase (1372)	Convert string to all-lowercase
NewStr (1373)	Allocate new string on heap
RightStr (1376)	Get last N characters of a string
StrAlloc (1379)	Allocate memory for string
StrBufSize (1380)	Reserve memory for a string
StrDispose (1382)	Remove string from heap
StrPas (1391)	Convert PChar to pascal string
StrPCopy (1391)	Copy pascal string
StrPLCopy (1391)	Copy N bytes of pascal string
UpperCase (1409)	Convert string to all-uppercase

`ConfigExtension` is the default extension used by the `GetAppConfigFile (1361)` call. It can be set to any valid extension for the current OS.

`CurrencyDecimals` : Byte = 2

`CurrencyDecimals` is the number of decimals to be used when formatting a currency. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`CurrencyFormat` : Byte = 1

`CurrencyFormat` is the default format string for positive currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

Table 30.7: Used units by unit 'sysutils'

Name	Page
errors	1278
sysconst	1278
Unix	1278
Unixtype	1278

`CurrencyString : String = '$'`

`CurrencyString` is the currency symbol for the current locale. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`DateDelta = 693594`

Days between 1/1/0001 and 12/31/1899

`DateSeparator : Char = '-'`

`DateSeparator` is the character used by various date/time conversion routines as the character that separates the day from the month and the month from the year in a date notation. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`DecimalSeparator : Char = '.'`

`DecimalSeparator` is used to display the decimal symbol in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`DirSeparators : Set of Char = ['/', '\']`

`DirSeparators` is a set of characters which are known directory separator characters on all supported platforms. This set is used by the `SetDirSeparators` ([1378](#)) call to correct pathnames for the current platform.

`DriveDelim = DriveSeparator`

`DriveDelim` refers to the system unit's `DriveSeparator` constant, it is for Delphi compatibility only.

`EmptyStr : String = ''`

Empty String Constant

`EmptyWideStr : WideString = ''`

Empty wide string.

`faAnyFile = $0000003f`

Use this attribute in the `FindFirst` (1345) call to find all matching files.

`faArchive = $00000020`

Attribute of a file, meaning the file has the archive bit set. Used in `TSearchRec` (1295) and `FindFirst` (1345)

`faDirectory = $00000010`

Attribute of a file, meaning the file is a directory. Used in `TSearchRec` (1295) and `FindFirst` (1345)

`faHidden = $00000002`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1295) and `FindFirst` (1345)

`faReadOnly = $00000001`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1295) and `FindFirst` (1345)

`faSymLink = $00000040`

`faSymLink` means the file (as returned e.g. by `FindFirst` (1345)/`FindNext` (1346)), is a symlink. It's ignored under Windows.

`faSysFile = $00000004`

Attribute of a file, meaning the file is a system file. Used in `TSearchRec` (1295) and `FindFirst` (1345)

`faVolumeId = $00000008`

Attribute of a file, meaning the file contains the volume ID. Used in `TSearchRec` (1295) and `FindFirst` (1345)

`feInvalidHandle : THandle = -1`

`feInvalidHandle` is the return value of `FileOpen` (1341) in case of an error.

`filerecnamelength = 255`

`filerecnamelength` describes the length of the `FileRec` (1291) filename field.

`fmOpenRead = $0000`

`fmOpenRead` is used in the `FileOpen` (1341) call to open a file in read-only mode.

`fmOpenReadWrite = $0002`

`fmOpenReadWrite` is used in the `FileOpen` (1341) call to open a file in read-write mode.

```
fmOpenWrite = $0001
```

fmOpenWrite is used in the FileOpen (1341) call to open a file in write-only mode.

```
fmShareCompat = $0000
```

fmOpenShareCompat is used in the FileOpen (1341) call OR-ed together with one of fmOpenReadWrite (1285), fmOpenRead (1285) or fmOpenWrite (1286), to open a file in a sharing modus that is equivalent to sharing implemented in MS-DOS.

```
fmShareDenyNone = $0040
```

fmOpenShareExclusive is used in the FileOpen (1341) call OR-ed together with one of fmOpenReadWrite (1285), fmOpenRead (1285) or fmOpenWrite (1286), to open a file so other processes can read/write the file as well.

```
fmShareDenyRead = $0030
```

fmOpenShareExclusive is used in the FileOpen (1341) call OR-ed together with one of fmOpenReadWrite (1285), fmOpenRead (1285) or fmOpenWrite (1286), to open a file so other processes cannot read from it.

```
fmShareDenyWrite = $0020
```

fmOpenShareExclusive is used in the FileOpen (1341) call OR-ed together with one of fmOpenReadWrite (1285), fmOpenRead (1285) or fmOpenWrite (1286), to open a file exclusively.

```
fmShareExclusive = $0010
```

fmOpenShareExclusive is used in the FileOpen (1341) call OR-ed together with one of fmOpenReadWrite (1285), fmOpenRead (1285) or fmOpenWrite (1286), to open a file exclusively.

```
fsFromBeginning = 0
```

fsFromBeginning is used to indicate in the FileSeek (1342) call that a seek operation should be started at the start of the file.

```
fsFromCurrent = 1
```

fsFromBeginning is used to indicate in the FileSeek (1342) call that a seek operation should be started at the current position in the file.

```
fsFromEnd = 2
```

fsFromBeginning is used to indicate in the FileSeek (1342) call that a seek operation should be started at the last position in the file.

```
HexDisplayPrefix : String = '$'
```

HexDisplayPrefix is used by the formatting routines to indicate that the number which follows the prefix is in Hexadecimal notation.

HoursPerDay = 24

Number of hours in a day.

LeadBytes : Set of Char = []

LeadBytes contains the set of bytes that serve as lead byte in a MBCS string.

ListSeparator : Char = ','

ListSeparator is the character used in lists of values. It is locale dependent.

LongDateFormat : String = 'dd" "mmmm" "yyyy'

LongDateFormat contains a template to format a date in a long format. It is used by the date formatting routines. The initialization routines of the **SysUtils** unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

LongDayNames : Array[1..7] of String = ('Sunday', 'Monday', 'Tuesday', 'Wednesday', 'Thu

LongDayNames is an array with the full names of days. It is used by the date formatting routines. The initialization routines of the **SysUtils** unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

LongMonthNames : Array[1..12] of String = ('January', 'February', 'March', 'April', 'May

LongMonthNames is an array with the full names of months. It is used by the date formatting routines. The initialization routines of the **SysUtils** unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

LongTimeFormat : String = 'hh:nn:ss'

LongTimeFormat contains a template to format a time in full notation. It is used by the time formatting routines. The initialization routines of the **SysUtils** unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

MaxCurrency : Currency = 922337203685477.0000

Maximum currency value

MaxDateTime : TDateTime = 2958465.99999

Maximum TDateTime value.

MAX_PATH = MaxPathLen

MAX_PATH is the maximum number of characters that a filename (including path) can contain on the current operating system.

MinCurrency : Currency = -922337203685477.0000

Minimum Currency value

`MinDateTime : TDateTime = -657434.0`

Minimum TDateTime value.

`MinsPerDay = HoursPerDay * MinsPerHour`

Number of minutes per day.

`MinsPerHour = 60`

Number of minutes per hour.

`MonthDays : Array[Boolean] of TDayTable = ((31,28,31,30,31,30,31,31,30,31,30,31)`

Array with number of days in the months for leap and non-leap years.

`MSecsPerDay = SecsPerDay * MSecsPerSec`

Number of milliseconds per day

`MSecsPerSec = 1000`

Number of milliseconds per second

`NegCurrFormat : Byte = 5`

`CurrencyFormat` is the default format string for negative currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`NullStr : PString = @EmptyStr`

Pointer to an empty string

`PathDelim = DirectorySeparator`

`PathDelim` refers to the system unit's `DirectorySeparator` constant, it is for Delphi compatibility only.

`PathSep = PathSeparator`

`PathSep` refers to the system unit's `PathSeparator` constant, it is for Delphi compatibility only.

`RTL_SIGBUS = 4`

Bus error signal number (Unix only)

`RTL_SIGDEFAULT = -1`

Default signal handler (Unix only)

`RTL_SIGFPE = 1`

Floating Point Error signal number (Unix only)

`RTL_SIGILL = 3`

Illegal instruction signal number (Unix only)

`RTL_SIGINT = 0`

INTERRUPT signal number (Unix only)

`RTL_SIGLAST = RTL_SIGQUIT`

Last signal number (Unix only)

`RTL_SIGQUIT = 5`

QUIT signal number (Unix only)

`RTL_SIGSEGV = 2`

Segmentation fault signal number (Unix only)

`SecsPerDay = MinsPerDay * SecsPerMin`

Number of seconds per day

`SecsPerMin = 60`

Number of seconds per minute

`ShortDateFormat : String = 'd/m/y'`

`ShortDateFormat` contains a template to format a date in a short format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`ShortDayNames : Array[1..7] of String = ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat')`

`ShortDayNames` is an array with the abbreviated names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`ShortMonthNames : Array[1..12] of String = ('Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun', 'Jul'`

`ShortMonthNames` is an array with the abbreviated names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
ShortTimeFormat : String = 'hh:nn'
```

`ShortTimeFormat` contains a template to format a time in a short notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
SwitchChars = ['-']
```

The characters in this set will be used by the `FindCmdLineSwitch` (1345) function to determine whether a command-line argument is a switch (an option) or a value. If the first character of an argument is in `SwitchChars`, it will be considered an option or switch.

```
SysConfigDir : String = ''
```

`SysConfigDir` is the default system configuration directory. It is set at application startup by the `sysutils` initialization routines.

This directory may be returned by the `GetAppConfigDir` (1360) call on some systems.

```
TextRecBufSize = 256
```

Buffer size of text file record.

```
TextRecNameLength = 256
```

Length of text file record filename field

```
ThousandSeparator : Char = ','
```

`ThousandSeparator` is used to separate groups of thousands in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
TimeAMString : String = 'AM'
```

`TimeAMString` is used to display the AM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
TimePMString : String = 'PM'
```

`TimePMString` is used to display the PM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
TimeSeparator : Char = ':'
```

`TimeSeparator` is used by the time formatting routines to separate the hours from the minutes and the minutes from the seconds. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
TwoDigitYearCenturyWindow : Word = 50
```

Window to determine what century 2 digit years are in.

```
UnixDateDelta = 25569
```

Number of days between 1.1.1900 and 1.1.1970

30.11.2 Types

```
EHeapException = EHeapMemoryError
```

EHeapMemoryError is raised when an error occurs in the heap management routines.

```
ExceptClass = Class of Exception
```

ExceptClass is a [Exception \(1418\)](#) class reference.

```
FileRec = packed record
  Handle : THandle;
  Mode : LongInt;
  RecSize : SizeInt;
  _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer)] of Byte;
  UserData : Array[1..32] of Byte;
  name : Array[0..filerecnamelength] of Char;
end
```

FileRec describes a untyped file. This record is made available so it can be used to implement drivers for other than the normal file system file records.

```
Int64Rec = packed record
end
```

Int64Rec can be used to extract the parts of a Int64: the high and low cardinal, or a zero-based array of 4 words, or a zero based array of 8 bytes. Note that the meaning of the High and Low parts are different on various CPUs.

```
LongRec = packed record
end
```

LongRec can be used to extract the parts of a long Integer: the high and low word, or the 4 separate bytes as a zero-based array of bytes. Note that the meaning of High and Low parts are different on various CPUs.

```
PByteArray = ^TByteArray
```

Generic pointer to TByteArray ([1292](#)). Use to access memory regions as a byte array.

```
PDayTable = ^TDayTable
```


Pointer to TDayTable type.

```
PString = ^String
```

Pointer to a ansistring

```
PSysCharSet = ^TSysCharSet
```

Pointer to TSysCharSet (1295) type.

```
PWordarray = ^TWordArray
```

Generic pointer to TWordArray (1296). Use to access memory regions as a word array.

```
TByteArray = Array[0..32767] of Byte
```

TByteArray is a generic array definition, mostly for use as a base type of the PByteArray (1291) type.

```
TCaseTranslationTable = Array[0..255] of Char
```

TCaseTranslationTable is the type for a lookup table that can convert 255 ascii characters.

```
TCreateGUIDFunc = function(out GUID: TGUID) : Integer
```

TCreateGUIDFunc is the prototype for a GUID creation handler. On return, the GUID argument should contain a new (unique) GUID. The return value of the function should be zero for success, nonzero for failure.

```
TDayTable = Array[1..12] of Word
```

Array of day names.

```
TextBuf = Array[0..TextRecBufSize-1] of Char
```

TextBuf is the type for the default buffer in TextRec (1293)

```
TextRec = packed record
```

```
  Handle : THandle;
```

```
  Mode : LongInt;
```

```
  bufsize : SizeInt;
```

```
  _private : SizeInt;
```

```
  bufpos : SizeInt;
```

```
  bufend : SizeInt;
```

```
  bufptr : ^TextBuf;
```

```
  openfunc : pointer;
```

```
  inoutfunc : pointer;
```

```
  flushfunc : pointer;
```

```
  closefunc : pointer;
```

```
  UserData : Array[1..32] of Byte;
```

```
  name : Array[0..textrecnamelength-1] of Char;
```

```
  LineEnd : TLineEndStr;
```

```
  buffer : TextBuf;
```

```
end
```

`TextRec` describes a text file. This record is made available so it can be used to implement drivers for other than the normal file system file records.

To implement a driver, an `Assign` procedure must be implemented, which fills in the various fields of the record. Most notably, the callback functions must be filled in appropriately. After this, the normal file operations will handle all necessary calls to the various callbacks.

```
TFilename = String
```

`TFileName` is used in the `TSearchRec` (1295) definition.

```
TFileRec = FileRec
```

Alias for `FileRec` (1291) for Delphi compatibility.

```
TFloatFormat = (ffGeneral, ffExponent, ffFixed, ffNumber, ffCurrency)
```

Table 30.8: Enumeration values for type `TFloatFormat`

Value	Explanation
<code>ffCurrency</code>	Monetary format.
<code>ffExponent</code>	Scientific format.
<code>ffFixed</code>	Fixed point format.
<code>ffGeneral</code>	General number format.
<code>ffNumber</code>	Fixed point format with thousand separator

`TFloatFormat` is used to determine how a float value should be formatted in the `FloatToText` (1350) function.

```
TFloatRec = record
  Exponent : Integer;
  Negative : Boolean;
  Digits : Array[0..18] of Char;
end
```

`TFloatRec` is used to describe a floating point value by the `FloatToDecimal` (1347) function.

```
TFloatValue = (fvExtended, fvCurrency, fvSingle, fvReal, fvDouble, fvComp)
```

`TFloatValue` determines which kind of value should be returned in the (untyped) buffer used by the `TextToFloat` (1401) function.

```
TGetAppNameEvent = function : String
```

This callback type is used by the `OnGetApplicationName` (1297) to return an alternative application name.

```
TGetTempDirEvent = function(Global: Boolean) : String
```

Function prototype for `OnGetTempDir` (1297) handler.

Table 30.9: Enumeration values for type TFloatValue

Value	Explanation
fvComp	Comp value
fvCurrency	Currency value
fvDouble	Double value
fvExtended	Extended value
fvReal	Real value
fvSingle	Single value

```
TGetTempFileEvent = function(const Dir: String;const Prefix: String)
                        : String
```

Function prototype for OnGetTempFile (1297) handler.

```
THandle = System.THandle
```

THandle refers to the definition of THandle in the system unit, and is provided for backward compatibility only.

```
TIntegerSet = Set of
```

TIntegerSet is a generic integer subrange set definition whose size fits in a single integer.

```
TLineEndStr =
```

TLineEndStr is used in the TextRec (1293) record to indicate the end-of-line sequence for a text file.

```
TMbcsByteType = (mbSingleByte,mbLeadByte,mbTrailByte)
```

Table 30.10: Enumeration values for type TMbcsByteType

Value	Explanation
mbLeadByte	Uses lead-byte
mbSingleByte	Single bytes
mbTrailByte	Uses trailing byte

Type of multi-byte character set.

```
TProcedure = procedure
```

TProcedure is a general definition of a procedural callback.

```
TReplaceFlags= Set of (rfReplaceAll,rfIgnoreCase)
```

TReplaceFlags determines the behaviour of the StringReplace (1385) function.

```

TSearchRec = record
  Time : LongInt;
  Size : Int64;
  Attr : LongInt;
  Name : TFilename;
  ExcludeAttr : LongInt;
  FindHandle : Pointer;
  Mode : TMode;
  PathOnly : AnsiString;
end

```

TSearchRec is a search handle description record. It is initialized by a call to FindFirst (1345) and can be used to do subsequent calls to FindNext (1346). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1344).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only.

```

TSignalState = (ssNotHooked, ssHooked, ssOverridden)

```

Table 30.11: Enumeration values for type TSignalState

Value	Explanation
ssHooked	A signal handler is set for the signal.
ssNotHooked	No signal handler is set for the signal.
ssOverridden	A signal handler was set for the signal

TSignalState indicates the state of a signal handler in a unix system for a particular signal.

```

TSysCharSet = Set of Char

```

Generic set of characters type.

```

TSysLocale = record
  DefaultLCID : Integer;
  PriLangID : Integer;
  SubLangID : Integer;
end

```

TSysLocale describes the current locale. If Fareast or MBCS is True, then the current locale uses a Multi-Byte Character Set. If MiddleEast or RightToLeft is True then words and sentences are read from right to left.

```

TSystemTime = record
  Year : Word;
  Month : Word;
  Day : Word;
  Hour : Word;
  Minute : Word;
  Second : Word;
  MilliSecond : Word;
end

```

The System time structure contains the date/time in a human-understandable format.

```
TTerminateProc = function : Boolean
```

`TTerminateProc` is the procedural type which should be used when adding exit procedures.

```
TTextRec = TextRec
```

Alias for `TextRec` ([1293](#)) for Delphi compatibility.

```
TTimeStamp = record
  Time : Integer;
  Date : Integer;
end
```

`TTimeStamp` contains a timestamp, with the date and time parts specified as separate `TDateTime` values.

```
TWordArray = Array[0..16383] of Word
```

`TWordArray` is a generic array definition, mostly for use as a base type of the `PWordArray` ([1292](#)) type.

```
WordRec = packed record
  Lo : Byte;
  Hi : Byte;
end
```

`LongRec` can be used to extract the parts of a word: the high and low byte. Note that the meaning of the High and Low parts are different on various CPUs.

30.11.3 Variables

```
LowerCaseTable : TCaseTranslationTable
```

`LowerCaseTable` is used by the `LowerCase` ([1372](#)) routine (and friends) to convert a string to all-lowercase characters. It is filled with the appropriate entries by the `SysUtils` unit initialization routines.

```
OnCreateGUID : TCreateGUIDFunc = nil
```

`OnCreateGUID` can be set to point to a custom routine that creates GUID values. If set, the `CreateGUID` ([1319](#)) function will use it to obtain a GUID value. If it is not set, a default implementation using random values will be used to create the unique value. The function should return a valid GUID in the GUID parameter, and should return zero in case of success.

```
OnGetApplicationName : TGetAppNameEvent
```

By default, the configuration file routines `GetAppConfigDir` (1360) and `GetAppConfigFile` (1361) use a default application name to construct a directory or filename. This callback can be used to provide an alternative application name.

Since the result of this callback will be used to construct a filename, care should be taken that the returned name does not contain directory separator characters or characters that cannot appear in a filename.

`OnGetTempDir` : `TGetTempDirEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempDir` (1364) function. Note that the returned name should have a trailing directory delimiter character.

`OnGetTempFile` : `TGetTempFileEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempFileName` (1365) function. Note that the values for `Prefix` and `Dir` should be observed.

`OnShowException` : `procedure(Msg: ShortString)`

`OnShowException` is the callback that `ShowException` (1378) uses to display a message in a GUI application. For GUI applications, this variable should always be set. Note that no memory may be available when this callback is called, so the callback should already have all resources it needs, when the callback is set.

`SysLocale` : `TSysLocale`

`SysLocale` is initialized by the initialization code of the `SysUtils` unit. For an explanation of the fields, see `TSysLocale` (1295)

`UpperCaseTable` : `TCaseTranslationTable`

`UpperCaseTable` is used by the `UpperCase` (1409) routine (and friends) to convert a string to all-uppercase characters. It is filled with the appropriate entries by the `SysUtils` unit initialization routines.

30.12 Procedures and functions

30.12.1 AbandonSignalHandler

Synopsis:

Declaration: `procedure AbandonSignalHandler(RtlSigNum: Integer)`

Visibility: default

Description: This function is declared for Kylix compatibility, but is not implemented.

30.12.2 Abort

Synopsis: Abort program execution.

Declaration: `procedure Abort`

Visibility: default

Description: `Abort` raises an `EAbort` (1413) exception.

See also: `Abort` (1297)

30.12.3 AddDisk

Synopsis: Add a disk to the list of known disks (Unix only)

Declaration: `function AddDisk(const path: String) : Byte`

Visibility: default

Description: On Linux both the `DiskFree` (1327) and `DiskSize` (1327) functions need a file on the specified drive, since is required for the `statfs` system call.

These filenames are set in `drivestr[0..26]`, and the first 4 have been preset to :

Disk 0' `.'` default drive - hence current directory is used.

Disk 1' `/fd0/.'` floppy drive 1.

Disk 2' `/fd1/.'` floppy drive 2.

Disk 3' `'C:` equivalent of DOS is the root partition.

Drives 4..26 can be set by your own applications with the `AddDisk` call.

The `AddDisk` call adds `Path` to the names of drive files, and returns the number of the disk that corresponds to this drive. If you add more than 21 drives, the count is wrapped to 4.

Errors: None.

See also: `DiskFree` (1327), `DiskSize` (1327)

30.12.4 AddTerminateProc

Synopsis: Add a procedure to the exit chain.

Declaration: `procedure AddTerminateProc(TermProc: TTerminateProc)`

Visibility: default

Description: `AddTerminateProc` adds `TermProc` to the list of exit procedures. When the program exits, the list of exit procedures is run over, and all procedures are called one by one, in the reverse order that they were added to the exit chain.

Errors: If no memory is available on the heap, an exception may be raised.

See also: `TTerminateProc` (1296), `CallTerminateProcs` (1314)

30.12.5 AdjustLineBreaks

Synopsis: Convert possible line-endings to the currently valid line ending.

Declaration: `function AdjustLineBreaks(const S: String) : String`
`function AdjustLineBreaks(const S: String; Style: TTextLineBreakStyle)`
`: String`

Visibility: default

Description: `AdjustLineBreaks` will change all `#13` characters with `#13#10` on Windows and `dos`. On linux, all `#13#10` character pairs are converted to `#10` and single `#13` characters also.

Errors: None.

See also: `AnsiCompareStr` ([1299](#)), `AnsiCompareText` ([1300](#))

Listing: `./sysutex/ex48.pp`

Program `Example48`;

{ This program demonstrates the AdjustLineBreaks function }

Uses `sysutils`;

Const

`S = 'This is a string'#13'with embedded'#10'linefeed and'+
#13'CR characters';`

Begin

`WriteLn (AdjustLineBreaks(S));`

End.

30.12.6 AnsiCompareFileName

Synopsis: Compare 2 filenames.

Declaration: `function AnsiCompareFileName(const S1: String;const S2: String)
: SizeInt`

Visibility: default

Description: `AnsiCompareFileName` compares 2 filenames `S1` and `S2`, and returns

`< 0` if `S1 < S2`.

`= 0` if `S1 = S2`.

`> 0` if `S1 > S2`.

The function actually checks `FileNameCaseSensitive` and returns the result of `AnsiCompareStr` ([1299](#)) or `AnsiCompareText` ([1300](#)) depending on whether `FileNameCaseSensitive` is `True` or `False`

Errors: None.

See also: `AnsiCompareStr` ([1299](#)), `AnsiCompareText` ([1300](#)), `AnsiLowerCaseFileName` ([1303](#))

30.12.7 AnsiCompareStr

Synopsis: Compare 2 ansistrings, case sensitive, ignoring accents characters.

Declaration: `function AnsiCompareStr(const S1: String;const S2: String) : Integer`

Visibility: default

Description: `AnsiCompareStr` compares two strings and returns the following result:

`< 0` if `S1 < S2`.

0if S1=S2.
 > 0if S1>S2.

The comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to AnsiCompareText (1300), the comparison is case sensitive.

Errors: None.

See also: AdjustLineBreaks (1298), AnsiCompareText (1300)

Listing: ./sysutex/ex49.pp

Program Example49;

```
{ This program demonstrates the AnsiCompareStr function }
{$H+}
```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

```
begin
  R:=AnsiCompareStr(S1,S2);
  Write ( ' ',S1, ' is ');
  If R<0 then
    write ( 'less than ');
  else If R=0 then
    Write ( 'equal to ');
  else
    Write ( 'larger than ');
  Writeln ( ' ',S2, ' ');
end;

Begin
  TestIt('One string','One smaller string');
  TestIt('One string','one string');
  TestIt('One string','One string');
  TestIt('One string','One tall string');
End.
```

30.12.8 AnsiCompareText

Synopsis: Compare 2 ansistrings, case insensitive, ignoring accents characters.

Declaration: function AnsiCompareText(const S1: String;const S2: String) : Integer

Visibility: default

Description: AnsiCompareText compares two strings and returns the following result:

<0if S1<S2.
 0if S1=S2.
 >0if S1>S2.

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareStr` (1299), the comparison is case insensitive.

Errors: None.

See also: `AdjustLineBreaks` (1298), `AnsiCompareText` (1300)

Listing: ./sysutex/ex50.pp

Program Example49;

{ This program demonstrates the AnsiCompareText function }
{ \$H+ }

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

begin

 R:=**AnsiCompareText**(S1,S2);

Write (' ',S1, ' is ');

If R<0 **then**

write ('less than ')

else If R=0 **then**

Write ('equal to ')

else

Write ('larger than ');

Writeln (' ',S2, ' ');

end;

Begin

 TestIt('One string ', 'One smaller string ');

 TestIt('One string ', 'one string ');

 TestIt('One string ', 'One string ');

 TestIt('One string ', 'One tall string ');

End.

30.12.9 AnsiExtractQuotedStr

Synopsis: Removes the first quoted string from a string.

Declaration: `function AnsiExtractQuotedStr(var Src: PChar;Quote: Char) : String`

Visibility: default

Description: `AnsiExtractQuotedStr` returns the first quoted string in `Src`, and deletes the result from `Src`.

The resulting string has with `Quote` characters removed from the beginning and end of the string (if they are present), and double `Quote` characters replaced by a single `Quote` characters. As such, it reverses the action of `AnsiQuotedStr` (1304).

Errors: None.

See also: `AnsiQuotedStr` (1304)

Listing: ./sysutex/ex51.pp

```

Program Example51;

{ This program demonstrates the AnsiQuotedStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'He said "Hello" and walked on';
  S:=AnsiQuotedStr(Pchar(S), '"');
  WriteLn (S);
  WriteLn (AnsiExtractQuotedStr(Pchar(S), '"'));
End.

```

30.12.10 AnsiLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: `function AnsiLastChar(const S: String) : PChar`

Visibility: default

Description: This function returns a pointer to the last character of S. Since multibyte characters are not yet supported, this is the same as `@S[Length(S)]`.

Errors: None.

See also: `AnsiStrLastChar` ([1306](#))

Listing: ./sysutex/ex52.pp

```

Program Example52;

{ This program demonstrates the AnsiLastChar function }

Uses sysutils;

Var S : AnsiString;
    L : Longint;

Begin
  S:= 'This is an ansistring.';
  WriteLn ('Last character of S is : ',AnsiLastChar(S));
  L:=Longint(AnsiLastChar(S))-Longint(@S[1])+1;
  WriteLn ('Length of S is : ',L);
End.

```

30.12.11 AnsiLowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function AnsiLowerCase(const s: String) : String`

Visibility: default

Description: `AnsiLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On linux, no language setting is taken in account yet.

Errors: None.

See also: `AnsiUpperCase` ([1310](#)), `AnsiStrLower` ([1308](#)), `AnsiStrUpper` ([1310](#))

Listing: `./sysutex/ex53.pp`

Program `Example53`;

{ This program demonstrates the `AnsiLowerCase` function }

Uses `sysutils`;

Procedure `Testit (S : String)`;

begin
 `WriteLn (S, ' -> ', AnsiLowerCase(S))`
end;

Begin
 `Testit('AN UPPERCASE STRING');`
 `Testit('Some mixed STring');`
 `Testit('a lowercase string');`
End.

30.12.12 `AnsiLowerCaseFileName`

Synopsis: Convert filename to lowercase.

Declaration: `function AnsiLowerCaseFileName(const s: String) : String`

Visibility: `default`

Description: `AnsiLowerCaseFileName` simply returns the result of

`AnsiLowerCase(S);`

See also: `AnsiLowerCase` ([1302](#)), `AnsiCompareFileName` ([1299](#)), `AnsiUpperCaseFileName` ([1311](#))

30.12.13 `AnsiPos`

Synopsis: Return Position of one anstring in another.

Declaration: `function AnsiPos(const substr: String; const s: String) : SizeInt`

Visibility: `default`

Description: `AnsiPos` does the same as the standard `Pos` function.

See also: `AnsiStrPos` ([1309](#)), `AnsiStrScan` ([1309](#)), `AnsiStrRScan` ([1309](#))

30.12.14 AnsiQuotedStr

Synopsis: Return a quoted version of a string.

Declaration: `function AnsiQuotedStr(const S: String; Quote: Char) : String`

Visibility: default

Description: `AnsiQuotedString` quotes the string `S` and returns the result. This means that it puts the `Quote` character at both the beginning and end of the string and replaces any occurrence of `Quote` in `S` with 2 `Quote` characters. The action of `AnsiQuotedString` can be reversed by `AnsiExtractQuotedStr` (1301).

For an example, see `AnsiExtractQuotedStr` (1301)

Errors: None.

See also: `AnsiExtractQuotedStr` (1301)

30.12.15 AnsiSameStr

Synopsis: Checks whether 2 strings are the same (case sensitive)

Declaration: `function AnsiSameStr(const s1: String; const s2: String) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareStr` (1299) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Errors: None.

See also: `AnsiCompareStr` (1299), `SameText` (1377), `AnsiSameText` (1304)

30.12.16 AnsiSameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function AnsiSameText(const s1: String; const s2: String) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareText` (1300) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Errors:

See also: `AnsiCompareText` (1300), `SameText` (1377), `AnsiSameStr` (1304)

30.12.17 AnsiStrComp

Synopsis: Compare two null-terminated strings. Case sensitive.

Declaration: `function AnsiStrComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrComp` compares 2 `PChar` strings, and returns the following result:

<0 if `S1 < S2`.

0if S1=S2.
 >0if S1>S2.

The comparison of the two strings is case-sensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(1300\)](#), [AnsiCompareStr \(1299\)](#)

Listing: ./sysutex/ex54.pp

Program Example54;

{ This program demonstrates the AnsiStrComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

 R:=AnsiStrComp(S1,S2);

Write (' ',S1,' is ');

If R<0 **then**

write ('less than ')

else If R=0 **then**

Write ('equal to ')

else

Write ('larger than ');

Writeln (' ',S2,' ');

end;

Begin

 TestIt('One string','One smaller string');

 TestIt('One string','one string');

 TestIt('One string','One string');

 TestIt('One string','One tall string');

End.

30.12.18 AnsiStrIComp

Synopsis: Compare two null-terminated strings. Case insensitive.

Declaration: function AnsiStrIComp(S1: PChar;S2: PChar) : Integer

Visibility: default

Description: AnsiStrIComp compares 2 PChar strings, and returns the following result:

<0if S1<S2.
 0if S1=S2.
 >0if S1>S2.

The comparison of the two strings is case-insensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(1300\)](#), [AnsiCompareStr \(1299\)](#)

Listing: ./sysutex/ex55.pp

Program Example55;

{ This program demonstrates the AnsiStrlComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

 R:= AnsiStrlComp (S1,S2);

Write ('',S1,' is ');

If R<0 **then**

write ('less than ');

else If R=0 **then**

Write ('equal to ');

else

Write ('larger than ');

WriteLn ('',S2,' ');

end;

Begin

 Testit('One string', 'One smaller string');

 Testit('One string', 'one string');

 Testit('One string', 'One string');

 Testit('One string', 'One tall string');

End.

30.12.19 AnsiStrLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: `function AnsiStrLastChar(Str: PChar) : PChar`

Visibility: default

Description: Return a pointer to the last character of the null-terminated string.

Errors: None.

See also: [AnsiCompareText \(1300\)](#), [AnsiCompareStr \(1299\)](#)

Listing: ./sysutex/ex56.pp

Program Example56;

{ This program demonstrates the AnsiStrLComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar; L : longint);

```

Var R : Longint;

begin
  R:=AnsiStrLComp(S1,S2,L);
  Write ( 'First ',L,' characters of "',S1,'" are ');
  If R<0 then
    write ( 'less than ' )
  else If R=0 then
    Write ( 'equal to ' )
  else
    Write ( 'larger than ' );
  Writeln ( 'those of "',S2,'" ');
end;

Begin
  Testit('One string ', 'One smaller string ',255);
  Testit('One string ', 'One String ',4);
  Testit('One string ', '1 string ',0);
  Testit('One string ', 'One string. ',9);
End.

```

30.12.20 AnsiStrLComp

Synopsis: Compare a limited number of characters of 2 strings

Declaration: `function AnsiStrLComp(S1: PChar;S2: PChar;MaxLen: cardinal) : Integer`

Visibility: default

Description: `AnsiStrLComp` functions the same as `AnsiStrComp` (1304), but compares at most `MaxLen` characters, if this is less than one of the lengths of the passed strings. If the first `MaxLen` characters in both strings are the same, then zero is returned.

Errors: None.

See also: `AnsiStrComp` (1304), `AnsiStrIComp` (1305), `AnsiStrLIComp` (1307)

30.12.21 AnsiStrLIComp

Synopsis: Compares a given number of characters of a string, case insensitive.

Declaration: `function AnsiStrLIComp(S1: PChar;S2: PChar;MaxLen: cardinal) : Integer`

Visibility: default

Description: `AnsiStrLIComp` compares the first `Maxlen` characters of 2 `PChar` strings, `S1` and `S2`, and returns the following result:

<0if `S1`<`S2`.

0if `S1`=`S2`.

>0if `S1`>`S2`.

The comparison of the two strings is case-insensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(1300\)](#), [AnsiCompareStr \(1299\)](#)

Listing: ./sysutex/ex57.pp

Program Example57;

{ This program demonstrates the AnsiStrLComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : PChar; L : longint);

Var R : Longint;

begin

R:=AnsiStrLComp(S1,S2,L);

Write ('First ',L,' characters of " ',S1,' " are ');

If R<0 **then**

write ('less than ');

else If R=0 **then**

Write ('equal to ');

else

Write ('larger than ');

Writeln ('those of " ',S2,' " ');

end;

Begin

TestIt('One string','One smaller string',255);

TestIt('ONE STRING','one String',4);

TestIt('One string','1 STRING',0);

TestIt('One STRING','one string.',9);

End.

30.12.22 AnsiStrLower

Synopsis: Convert a null-terminated string to all-lowercase characters.

Declaration: function AnsiStrLower(Str: PChar) : PChar

Visibility: default

Description: AnsiStrLower converts the PChar Str to lowercase characters and returns the resulting pchar.

Note that Str itself is modified, not a copy, as in the case of AnsiLowerCase ([1302](#)). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On unix, no language setting is taken in account yet.

Errors: None.

See also: [AnsiStrUpper \(1310\)](#), [AnsiLowerCase \(1302\)](#)

Listing: ./sysutex/ex59.pp

Program Example59;

{ This program demonstrates the AnsiStrLower function }

Uses sysutils;

Procedure Testit (S : PChar);

```
begin
  WriteLn (S, ' -> ', AnsiStrLower(S))
end;
```

```
Begin
  Testit('AN UPPERCASE STRING');
  Testit('Some mixed STring');
  Testit('a lowercase string');
End.
```

30.12.23 AnsiStrPos

Synopsis: Return position of one null-terminated substring in another

Declaration: function AnsiStrPos(str: PChar; substr: PChar) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the first occurrence of SubStr in Str. If SubStr does not occur in Str then Nil is returned.

Errors: An access violation may occur if either Str or SubStr point to invalid memory.

See also: AnsiPos ([1303](#)), AnsiStrScan ([1309](#)), AnsiStrRScan ([1309](#))

30.12.24 AnsiStrRScan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: function AnsiStrRScan(Str: PChar; Chr: Char) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the *last* occurrence of the character Chr in Str. If Chr does not occur in Str then Nil is returned.

Errors: An access violation may occur if Str points to invalid memory.

See also: AnsiPos ([1303](#)), AnsiStrScan ([1309](#)), AnsiStrPos ([1309](#))

30.12.25 AnsiStrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: function AnsiStrScan(Str: PChar; Chr: Char) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the *first* occurrence of the character Chr in Str. If Chr does not occur in Str then Nil is returned.

Errors: An access violation may occur if Str points to invalid memory.

See also: AnsiPos ([1303](#)), AnsiStrScan ([1309](#)), AnsiStrPos ([1309](#))

30.12.26 AnsiStrUpper

Synopsis: Convert a null-terminated string to all-uppercase characters.

Declaration: `function AnsiStrUpper(Str: PChar) : PChar`

Visibility: default

Description: `AnsiStrUpper` converts the `PCharStr` to uppercase characters and returns the resulting string.

Note that `Str` itself is modified, not a copy, as in the case of `AnsiUpperCase` (1310). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On linux, no language setting is taken in account yet.

Errors: None.

See also: `AnsiUpperCase` (1310), `AnsiStrLower` (1308), `AnsiLowerCase` (1302)

Listing: `./sysutex/ex60.pp`

Program Example60;

{ This program demonstrates the AnsiStrUpper function }

Uses sysutils;

Procedure Testit (S : Pchar);

begin

 WriteLn (S, ' -> ', AnsiStrUpper(S))

end;

Begin

 Testit('AN UPPERCASE STRING');

 Testit('Some mixed STring');

 Testit('a lowercase string');

End.

30.12.27 AnsiUpperCase

Synopsis: Return an uppercase version of a string, taking into account special characters.

Declaration: `function AnsiUpperCase(const s: String) : String`

Visibility: default

Description: `AnsiUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It

takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On linux, no language setting is taken in account yet.

Errors: None.

See also: `AnsiStrUpper` (1310), `AnsiStrLower` (1308), `AnsiLowerCase` (1302)

Listing: `./sysutex/ex61.pp`

```

Program Example60;

{ This program demonstrates the AnsiUpperCase function }

Uses sysutils;

Procedure Testit (S : String);

begin
  WriteLn (S, ' -> ',AnsiUpperCase(S))
end;

Begin
  Testit('AN UPPERCASE STRING');
  Testit('Some mixed STring');
  Testit('a lowercase string');
End.

```

30.12.28 AnsiUpperCaseFileName

Synopsis: Convert filename to uppercase.

Declaration: `function AnsiUpperCaseFileName(const s: String) : String`

Visibility: default

Description: `AnsiUpperCaseFileName` simply returns the result of

```
AnsiUpperCase(S);
```

See also: `AnsiUpperCase` ([1310](#)), `AnsiCompareFileName` ([1299](#)), `AnsiLowerCaseFileName` ([1303](#))

30.12.29 AppendStr

Synopsis: Append one ansistring to another.

Declaration: `procedure AppendStr(var Dest: String;const S: String)`

Visibility: default

Description: `AppendStr` appends `S` to `Dest`.

This function is provided for Delphi compatibility only, since it is completely equivalent to `Dest := Dest+S`.

Errors: None.

See also: `AssignStr` ([1312](#)), `NewStr` ([1373](#)), `DisposeStr` ([1328](#))

Listing: `./sysutex/ex62.pp`

```

Program Example62;

{ This program demonstrates the AppendStr function }

Uses sysutils;

Var S : AnsiString;

```

```

Begin
  S:= 'This is an ';
  AppendStr(S, 'AnsiString ');
  WriteLn ( 'S = " ', S, ' " ');
End.

```

30.12.30 ApplicationName

Synopsis: Return a default application name

Declaration: `function ApplicationName : String`

Visibility: default

Description: `ApplicationName` returns the name of the current application. Standard this is equal to the result of `ParamStr(0)`, but it can be customized by setting the `OnGetApplicationName` ([1297](#)) callback.

Errors: None.

See also: `GetAppConfigDir` ([1360](#)), `OnGetApplicationName` ([1297](#)), `GetAppConfigFile` ([1361](#)), `ConfigExtension` ([1283](#))

30.12.31 AssignStr

Synopsis: Assigns an ansistring to a null-terminated string.

Declaration: `procedure AssignStr(var P: PString; const S: String)`

Visibility: default

Description: `AssignStr` allocates `S` to `P`. The old value of `P` is disposed of.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: `NewStr` ([1373](#)), `AppendStr` ([1311](#)), `DisposeStr` ([1328](#))

Listing: `./sysutex/ex63.pp`

Program Example63;

```

{ This program demonstrates the AssignStr function }
{$H+}

```

Uses sysutils;

Var P : PString;

```

Begin
  P:=NewStr('A first AnsiString');
  WriteLn ( 'Before: P = " ', P^, ' " ');
  AssignStr(P, 'A Second ansistring');
  WriteLn ( 'After : P = " ', P^, ' " ');
  DisposeStr(P);
End.

```

30.12.32 BCDToInt

Synopsis: Convert a BCD coded integer to a normal integer.

Declaration: `function BCDToInt(Value: Integer) : Integer`

Visibility: default

Description: `BCDToInt` converts a BCD coded integer to a normal integer.

Errors: None.

See also: `StrToInt` ([1396](#)), `IntToStr` ([1368](#))

Listing: `./sysutex/ex64.pp`

Program `Example64;`

{ This program demonstrates the BCDToInt function }

Uses `sysutils;`

Procedure `Testit (L : longint);`
begin
 `WriteLn (L, ' -> ',BCDToInt(L));`
end;

Begin
 `Testit(10);`
 `Testit(100);`
 `Testit(1000);`
End.

30.12.33 Beep

Synopsis: Sound the system bell.

Declaration: `procedure Beep`

Visibility: default

Description: `Beep` sounds the system bell, if one is available.

Errors: This routine may not be implemented on all platforms.

30.12.34 BoolToStr

Synopsis: Convert a boolean value to a string.

Declaration: `function BoolToStr(B: Boolean) : String`

Visibility: default

Description: `BoolToStr` converts the boolean `B` to one of the strings `' TRUE'` or `' FALSE'`

Errors: None.

See also: `StrToBool` ([1393](#))

30.12.35 ByteToCharIndex

Synopsis: Convert a character index in Bytes to an Index in characters

Declaration: `function ByteToCharIndex(const S: String; Index: Integer) : Integer`

Visibility: default

Description: `ByteToCharIndex` returns the index (in characters) of the `Index`-th byte in `S`.

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1315](#)), `ByteToCharLen` ([1314](#))

30.12.36 ByteToCharLen

Synopsis: Convert a length in bytes to a length in characters.

Declaration: `function ByteToCharLen(const S: String; MaxLen: Integer) : Integer`

Visibility: default

Description: `ByteToCharLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1315](#)), `ByteToCharIndex` ([1314](#))

30.12.37 ByteType

Synopsis: Return the type of byte in an ansistring for a multi-byte character set

Declaration: `function ByteType(const S: String; Index: Integer) : TMBcsByteType`

Visibility: default

Description: `ByteType` returns the type of byte in the ansistring `S` at (1-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TMBcsByteType` ([1294](#)), `StrByteType` ([1380](#))

30.12.38 CallTerminateProcs

Synopsis: Call the exit chain procedures.

Declaration: `function CallTerminateProcs : Boolean`

Visibility: default

Description: `CallTerminateProcs` is run on program exit. It executes all terminate procedures that were added to the exit chain with `AddTerminateProc` ([1298](#)), and does this in reverse order.

Errors: If one of the exit procedure raises an exception, it is *not* caught, and the remaining exit procedures will not be executed.

See also: `TTerminateProc` ([1296](#)), `AddTerminateProc` ([1298](#))

30.12.39 ChangeFileExt

Synopsis: Change the extension of a filename.

Declaration: `function ChangeFileExt(const FileName: String;const Extension: String)
: String`

Visibility: default

Description: `ChangeFileExt` changes the file extension in `FileName` to `Extension`. The extension `Extension` includes the starting `.` (dot). The previous extension of `FileName` are all characters after the last `.`, the `.` character included.

If `FileName` doesn't have an extension, `Extension` is just appended.

Errors: None.

See also: `ExtractFileName` ([1334](#)), `ExtractFilePath` ([1335](#)), `ExpandFileName` ([1332](#))

30.12.40 CharToByteLen

Synopsis: Convert a length in characters to a length in bytes.

Declaration: `function CharToByteLen(const S: String;MaxLen: Integer) : Integer`

Visibility: default

Description: `CharToByteLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `ByteToCharLen` ([1314](#)), `ByteToCharIndex` ([1314](#))

30.12.41 CompareMem

Synopsis: Compare two memory areas.

Declaration: `function CompareMem(P1: Pointer;P2: Pointer;Length: cardinal) : Boolean`

Visibility: default

Description: `CompareMem` compares, byte by byte, 2 memory areas pointed to by `P1` and `P2`, for a length of `L` bytes.

It returns the following values:

<0 if at some position the byte at `P1` is less than the byte at the same position at `P2`.

0 if all `L` bytes are the same.

>0 if at some position the byte at `P1` is greater than the byte at the same position at `P2`.

Errors:

30.12.42 CompareMemRange

Synopsis: Compare 2 memory locations

Declaration: `function CompareMemRange (P1: Pointer; P2: Pointer; Length: cardinal)
: Integer`

Visibility: default

Description: `CompareMemRange` compares the 2 memory locations pointed to by `P1` and `P2` byte per byte. It stops comparing after `Length` bytes have been compared, or when it has encountered 2 different bytes. The result is then

>0 if a byte in range `P1` was found that is bigger than the corresponding byte in range `P2`.

0 if all bytes in range `P1` are the same as the corresponding bytes in range `P2`.

<0 if a byte in range `P1` was found that is less than the corresponding byte in range `P2`.

Errors: None.

See also: `SameText` ([1377](#))

30.12.43 CompareStr

Synopsis: Compare 2 ansistrings case-sensitively, ignoring special characters.

Declaration: `function CompareStr (const S1: String; const S2: String) : Integer`

Visibility: default

Description: `CompareStr` compares two strings, `S1` and `S2`, and returns the following result:

<0 if `S1` < `S2`.

0 if `S1` = `S2`.

>0 if `S1` > `S2`.

The comparison of the two strings is case-sensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `AnsiCompareText` ([1300](#)), `AnsiCompareStr` ([1299](#)), `CompareText` ([1317](#))

Listing: `./sysutex/ex65.pp`

Program `Example65`;

```
{ This program demonstrates the CompareStr function }  
{$H+}
```

Uses `sysutils`;

Procedure `TestIt` (`S1, S2 : String`);

Var `R : Longint`;

begin

`R := CompareStr (S1, S2);`

Write (' ', S1, ' is ');

```

If R<0 then
  write ( 'less than ' )
else If R=0 then
  Write ( 'equal to ' )
else
  Write ( 'larger than ' );
Writeln ( '""',S2, '""');
end;

Begin
  Testit( 'One string ', 'One smaller string ' );
  Testit( 'One string ', 'one string ' );
  Testit( 'One string ', 'One string ' );
  Testit( 'One string ', 'One tall string ' );
End.

```

30.12.44 CompareText

Synopsis: Compare 2 ansistrings case insensitive.

Declaration: `function CompareText(const S1: String;const S2: String) : Integer`

Visibility: default

Description: CompareText compares two strings, S1 and S2, and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `AnsiCompareText` ([1300](#)), `AnsiCompareStr` ([1299](#)), `CompareStr` ([1316](#))

Listing: ./sysutex/ex66.pp

Program Example66;

```

{ This program demonstrates the CompareText function }
{$H+}

```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

```

begin
  R:=CompareText(S1,S2);
  Write ( '""',S1, ' is ' );
  If R<0 then
    write ( 'less than ' )
  else If R=0 then
    Write ( 'equal to ' )

```

```

    else
      Write ( 'larger than ');
      Writeln ( '', S2, '' );
    end;

  Begin
    Testit( 'One string ', 'One smaller string ');
    Testit( 'One string ', 'one string ');
    Testit( 'One string ', 'One string ');
    Testit( 'One string ', 'One tall string ');
  End.

```

30.12.45 ComposeDateTime

Synopsis: Add a date and time

Declaration: `function ComposeDateTime(Date: TDateTime;Time: TDateTime) : TDateTime`

Visibility: default

Description: `ComposeDateTime` correctly adds `Date` and `Time`, also for dates before 1899-12-31. For dates after this date, it is just the mathematical addition.

Errors: None.

See also: `EncodeDateTime` ([1278](#))

30.12.46 CreateDir

Synopsis: Create a new directory

Declaration: `function CreateDir(const NewDir: String) : Boolean`

Visibility: default

Description: `CreateDir` creates a new directory with name `NewDir`. If the directory doesn't contain an absolute path, then the directory is created below the current working directory.

The function returns `True` if the directory was successfully created, `False` otherwise.

Errors: In case of an error, the function returns `False`.

See also: `RemoveDir` ([1375](#))

Listing: `./sysutex/ex26.pp`

Program `Example26;`

```

{ This program demonstrates the CreateDir and RemoveDir functions }
{ Run this program twice in the same directory }

```

Uses `sysutils;`

Begin

```

  If Not DirectoryExists( 'NewDir' ) then
    If Not CreateDir ( 'NewDir' ) Then
      Writeln ( 'Failed to create directory !' )
    else

```

```

        WriteLn ( 'Created "NewDir" directory ' )
    Else
        If Not RemoveDir ( 'NewDir' ) Then
            WriteLn ( 'Failed to remove directory ! ' )
        else
            WriteLn ( 'Removed "NewDir" directory ' );
End.

```

30.12.47 CreateGUID

Synopsis: Create a new GUID

Declaration: `function CreateGUID(out GUID: TGUID) : Integer`

Visibility: default

Description: `CreateGUID` can be called to create a new GUID (Globally Unique Identifier) value. The function returns the new GUID value in `GUID` and returns zero in case the GUID was created successfully. If no GUID was created, a nonzero error code is returned.

The default mechanism for creating a new GUID is system dependent. If operating system support is available, it is used. If none is available, a default implementation using random numbers is used.

The `OnCreateGUID` callback can be set to hook a custom mechanism behind the `CreateGUID` function. This can be used to let the GUID be created by an external GUID creation library.

Errors: On error, a nonzero return value is returned.

See also: `CreateGUID` ([1319](#))

30.12.48 CurrentYear

Synopsis: Return the current year

Declaration: `function CurrentYear : Word`

Visibility: default

Description: `CurrentYear` returns the current year as a 4-digit number.

Errors: None.

See also: `Date` ([1320](#)), `Time` ([1402](#)), `Now` ([1374](#))

30.12.49 CurrToStr

Synopsis: Convert a currency value to a string.

Declaration: `function CurrToStr(Value: Currency) : String`

Visibility: default

Description: `CurrToStr` will convert a currency value to a string with a maximum of 15 digits, and precision 2. Calling `CurrToStr` is equivalent to calling `FloatToStrF` ([1348](#)):

```
FloatToStrF(Value, ffNumber, 15, 2);
```

Errors: None.

See also: `FloatToStrF` ([1348](#)), `StrToCurr` ([1393](#))

30.12.50 CurrToStrF

Synopsis: Format a currency to a string

Declaration: `function CurrToStrF(Value: Currency;Format: TFloatFormat;
 Digits: Integer) : String`

Visibility: default

Description: `CurrToStrF` formats the currency `Value` according to the value in `Format`, using the number of digits specified in `Digits`, and a precision of 19. This function simply calls `FloatToStrF` (1348).

See also: `FloatToStrF` (1348)

30.12.51 Date

Synopsis: Return the current date.

Declaration: `function Date : TDateTime`

Visibility: default

Description: `Date` returns the current date in `TDateTime` format.

Errors: None.

See also: `Time` (1402), `Now` (1374)

Listing: `./sysutex/ex1.pp`

Program `Example1`;

{ This program demonstrates the Date function }

uses `sysutils`;

Var `YY,MM,DD` : `Word`;

Begin

`WriteLn ('Date : ',Date);`

`DeCodeDate (Date,YY,MM,DD);`

`WriteLn (format ('Date is (DD/MM/YY): %d/%d/%d ',[dd,mm,yy]));`

End.

30.12.52 DateTimeToFileDate

Synopsis: Convert a `TDateTime` value to a file age (integer)

Declaration: `function DateTimeToFileDate(DateTime: TDateTime) : LongInt`

Visibility: default

Description: `DateTimeToFileDate` function converts a date/time indication in `TDateTime` format to a file-date function, such as returned for instance by the `FileAge` (1336) function.

Errors: None.

See also: `Time` (1402), `Date` (1320), `FileDateToDateTime` (1338), `DateTimeToSystemTime` (1322), `DateTimeToTimeStamp` (1323)

Listing: ./sysutex/ex2.pp

Program Example2;

{ This program demonstrates the DateTimeToFileDate function }

Uses sysutils;

Begin

WriteLn ('FileTime of now would be: ', **DateTimeToFileDate** (**Now**));
End.

30.12.53 DateTimeToStr

Synopsis: Converts a TDateTime value to a string using a predefined format.

Declaration: function DateTimeToStr(DateTime: TDateTime) : String

Visibility: default

Description: DateTimeToStr returns a string representation of DateTime using the formatting specified in ShortDateTimeFormat. It corresponds to a call to FormatDateTime('c', DateTime) (see formatchars (1281)).

Errors: None.

See also: FormatDateTime (1358)

Listing: ./sysutex/ex3.pp

Program Example3;

{ This program demonstrates the DateTimeToStr function }

Uses sysutils;

Begin

WriteLn ('Today is : ', **DateTimeToStr** (**Now**));
 WriteLn ('Today is : ', **FormatDateTime** ('c', **Now**));
End.

30.12.54 DateTimeToString

Synopsis: Converts a TDateTime value to a string with a given format.

Declaration: procedure DateTimeToString(var Result: String; const FormatStr: String;
const DateTime: TDateTime)

Visibility: default

Description: DateTimeToString returns in Result a string representation of DateTime using the formatting specified in FormatStr. for a list of characters that can be used in the FormatStr formatting string, see formatchars (1281).

Errors: In case a wrong formatting character is found, an EConvertError is raised.

See also: FormatDateTime (1358), formatchars (1281)

Listing: ./sysutex/ex4.pp

Program Example4;

{ This program demonstrates the DateTimeToString function }

Uses sysutils;

Procedure today (Fmt : **string**);

Var S : AnsiString;

begin

DateTimeToString (S,Fmt,**Date**);

WriteLn (S);

end;

Procedure Now (Fmt : **string**);

Var S : AnsiString;

begin

DateTimeToString (S,Fmt,**Time**);

WriteLn (S);

end;

Begin

 Today ('"Today is "dddd dd mmm y' ');

 Today ('"Today is "d mmm yy' ');

 Today ('"Today is "d/mmm/yy' ');

Now ('''The time is 'am/pmh:n:s');

Now ('''The time is 'hh:nn:ssam/pm');

Now ('''The time is 'tt');

End.

30.12.55 DateTimeToSystemTime

Synopsis: Converts a TDateTime value to a systemtime structure.

Declaration: procedure DateTimeToSystemTime (DateTime: TDateTime;
 var SystemTime: TSystemTime)

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a system time SystemTime.

Errors: None.

See also: DateTimeToFileDate ([1320](#)), SystemTimeToDateTime ([1400](#)), DateTimeToTimeStamp ([1323](#))

Listing: ./sysutex/ex5.pp

Program Example5;

{ This program demonstrates the DateTimeToSystemTime function }

```

Uses sysutils;

Var ST : TSystemTime;

Begin
  DateTimeToSystemTime(Now,ST);
  With St do
    begin
      Writeln ( 'Today is      ',year,'/',month,'/',Day);
      Writeln ( 'The time is  ',Hour,':',minute,':',Second,'.',MilliSecond);
    end;
End.

```

30.12.56 DateTimeToTimeStamp

Synopsis: Converts a TDateTime value to a TimeStamp structure.

Declaration: function DateTimeToTimeStamp(DateTime: TDateTime) : TTimeStamp

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a TTimeStamp format.

Errors: None.

See also: DateTimeToFileDate ([1320](#)), SystemTimeToDateTime ([1400](#)), DateTimeToSystemTime ([1322](#))

Listing: ./sysutex/ex6.pp

Program Example6;

{ This program demonstrates the DateTimeToTimeStamp function }

Uses sysutils;

Var TS : TTimeStamp;

Begin

TS:=DateTimeToTimeStamp (**Now**);

With TS **do**

begin

Writeln ('Now is ',**time**, ' millisecond past midnight');

Writeln ('Today is ',**Date**, ' days past 1/1/0001');

end;

End.

30.12.57 DateToStr

Synopsis: Converts a TDateTime value to a date string with a predefined format.

Declaration: function DateToStr(Date: TDateTime) : String

Visibility: default

Description: DateToStr converts Date to a string representation. It uses ShortDateFormat as it's formatting string. It is hence completely equivalent to a FormatDateTime('dddd', Date).

Errors: None.

See also: [TimeToStr \(1403\)](#), [DateTimeToStr \(1321\)](#), [FormatDateTime \(1358\)](#), [StrToDate \(1394\)](#)

Listing: ./sysutex/ex7.pp

Program Example7;

{ This program demonstrates the DateToStr function }

Uses sysutils;

Begin

WriteIn (**Format** ('Today is: %s', [**DateToStr** (**Date**)]));

End.

30.12.58 DayOfWeek

Synopsis: Returns the day of the week.

Declaration: `function DayOfWeek (DateTime: TDateTime) : Integer`

Visibility: default

Description: `DayOfWeek` returns the day of the week from `DateTime`. Sunday is counted as day 1, Saturday is counted as day 7. The result of `DayOfWeek` can serve as an index to the `LongDayNames` constant array, to retrieve the name of the day.

Errors: None.

See also: [Date \(1320\)](#), [DateToStr \(1323\)](#)

Listing: ./sysutex/ex8.pp

Program Example8;

{ This program demonstrates the DayOfWeek function }

Uses sysutils;

Begin

WriteIn ('Today 's day is ', LongDayNames[**DayOfWeek** (**Date**)]);

End.

30.12.59 DecodeDate

Synopsis: Decode a `TDateTime` to a year,month,day triplet

Declaration: `procedure DecodeDate (Date: TDateTime; var Year: Word; var Month: Word; var Day: Word)`

Visibility: default

Description: `DecodeDate` decodes the Year, Month and Day stored in `Date`, and returns them in the Year, Month and Day variables.

Errors: None.

See also: [EncodeDate \(1329\)](#), [DecodeTime \(1325\)](#)

Listing: ./sysutex/ex9.pp

Program Example9;

{ This program demonstrates the DecodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin

DecodeDate(**Date** ,YY,MM,DD);

WriteLn (**Format** ('Today is %d/%d/%d' ,[dd,mm,yy]));

End.

30.12.60 DecodeDateFully

Synopsis: Decode a date with additional date of the week.

Declaration: `function DecodeDateFully(const DateTime: TDateTime;var Year: Word;
 var Month: Word;var Day: Word;var DOW: Word)
 : Boolean`

Visibility: default

Description: `DecodeDateFully`, like `DecodeDate` ([1324](#)), decodes `DateTime` in its parts and returns these in `Year`, `Month`, `Day` but in addition returns the day of the week in `DOW`.

Errors: None.

See also: [EncodeDate \(1329\)](#), [TryEncodeDate \(1406\)](#), [DecodeDate \(1324\)](#)

30.12.61 DecodeTime

Synopsis: Decode a `TDateTime` to a hour,minute,second,millisecond quartet

Declaration: `procedure DecodeTime(Time: TDateTime;var Hour: Word;var Minute: Word;
 var Second: Word;var MilliSecond: Word)`

Visibility: default

Description: `DecodeDate` decodes the hours, minutes, second and milliseconds stored in `Time`, and returns them in the `Hour`, `Minute` and `Second` and `MilliSecond` variables.

Errors: None.

See also: [EncodeTime \(1329\)](#), [DecodeDate \(1324\)](#)

Listing: ./sysutex/ex10.pp

Program Example10;

{ This program demonstrates the DecodeTime function }

Uses sysutils;

```

Var HH,MM,SS,MS: Word;

Begin
  DecodeTime(Time,HH,MM,SS,MS);
  WriteLn (format( 'The time is %d:%d:%d.%d' ,[hh,mm,ss,ms]));
End.

```

30.12.62 DeleteFile

Synopsis: Delete a file from the filesystem.

Declaration: `function DeleteFile(const FileName: String) : Boolean`

Visibility: default

Description: `DeleteFile` deletes file `FileName` from disk. The function returns `True` if the file was successfully removed, `False` otherwise.

Errors: On error, `False` is returned.

See also: `FileCreate` ([1337](#)), `FileExists` ([1338](#))

Listing: `./sysutex/ex31.pp`

```

Program Example31;

{ This program demonstrates the DeleteFile function }

Uses sysutils;

Var
  Line : String;
  F,I : Longint;

Begin
  F:= FileCreate( 'test.txt' );
  Line:= 'Some string line.'#10;
  For I:=1 to 10 do
    FileWrite (F,Line[I],Length(Line));
  FileClose(F);
  DeleteFile( 'test.txt' );
End.

```

30.12.63 DirectoryExists

Synopsis: Check whether a directory exists in the file system.

Declaration: `function DirectoryExists(const Directory: String) : Boolean`

Visibility: default

Description: `DirectoryExists` checks whether `Directory` exists in the filesystem and is actually a directory. If this is the case, the function returns `True`, otherwise `False` is returned.

See also: `FileExists` ([1338](#))

30.12.64 DiskFree

Synopsis: Return the amount of free disk space

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the free space (in bytes) on disk `Drive`. `Drive` is the number of the disk drive:

- 0** for the current drive.
- 1** for the first floppy drive.
- 2** for the second floppy drive.
- 3** for the first hard-disk partition.
- 4-26** for all other drives and partitions.

Remark: Under linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` and `DiskSize` (1327) functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` (1298).

Errors: On error, -1 is returned.

See also: `DiskSize` (1327), `AddDisk` (1298)

Listing: `./sysutex/ex27.pp`

Program `Example27`;

{ This program demonstrates the DiskFree function }

Uses `sysutils`;

Begin

```
Write ('Size of current disk      : ', DiskSize(0));
Writeln (' (= ', DiskSize(0) div 1024, 'k) ');
Write ('Free space of current disk : ', DiskFree(0));
Writeln (' (= ', DiskFree(0) div 1024, 'k) ');
```

End.

30.12.65 DiskSize

Synopsis: Return the total amount of disk space.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the size (in bytes) of disk `Drive`. `Drive` is the number of the disk drive:

- 0** for the current drive.
- 1** for the first floppy drive.
- 2** for the second floppy drive.
- 3** for the first hard-disk partition.
- 4-26** for all other drives and partitions.

Remark: Under linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` (1327) and `DiskSize` functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` (1298)

For an example, see `DiskFree` (1327).

Errors: On error, -1 is returned.

See also: `DiskFree` (1327), `AddDisk` (1298)

30.12.66 DisposeStr

Synopsis: Dispose an ansistring from the heap.

Declaration: `procedure DisposeStr(S: PString)`

Visibility: default

Description: `DisposeStr` removes the dynamically allocated string `S` from the heap, and releases the occupied memory.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

For an example, see `DisposeStr` (1328).

Errors: None.

See also: `NewStr` (1373), `AppendStr` (1311), `AssignStr` (1312)

30.12.67 DoDirSeparators

Synopsis: Convert known directory separators to the current directory separator.

Declaration: `procedure DoDirSeparators(var FileName: String)`

Visibility: default

Description: This function replaces all known directory separators in `FileName` to the directory separator character for the current system. The list of known separators is specified in the `DirSeparators` (1284) constant.

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335)

Listing: `./sysutex/ex32.pp`

Program `Example32`;

```
{ This program demonstrates the DoDirSeparators function }
{$H+}
```

Uses `sysutils`;

Procedure `Testit (F : String)`;

```
begin
  Writeln ( 'Before : ',F);
```

```

    DoDirSeparators (F);
    Writeln ( 'After  : ',F);
end;

Begin
    Testit ( GetCurrentDir );
    Testit ( 'c:\pp\bin\win32' );
    Testit ( '/usr/lib/fpc' );
    Testit ( '\usr\lib\fpc' );
End.

```

30.12.68 EncodeDate

Synopsis: Encode a Year,Month,Day to a TDateTime value.

Declaration: `function EncodeDate(Year: Word;Month: Word;Day: Word) : TDateTime`

Visibility: default

Description: `EncodeDate` encodes the Year, Month and Day variables to a date in TDateTime format. It does the opposite of the `DecodeDate` ([1324](#)) procedure.

The parameters must lie withing valid ranges (boundaries included):

Year must be between 1 and 9999.

Month must be within the range 1-12.

Days must be between 1 and 31.

Errors: In case one of the parameters is out of it's valid range, an `EConvertError` ([1413](#)) exception is raised.

See also: `EncodeTime` ([1329](#)), `DecodeDate` ([1324](#))

Listing: `./sysutex/ex11.pp`

Program Example11;

{ This program demonstrates the EncodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin

DecodeDate (Date,YY,MM,DD);

WriteLn ('Today is : ',**FormatDateTime** ('dd mmmm yyyy ',**EncodeDate**(YY,Mm,Dd)));

End.

30.12.69 EncodeTime

Synopsis: Encode a Hour,Min,Sec,millisecond to a TDateTime value.

Declaration: `function EncodeTime(Hour: Word;Minute: Word;Second: Word;MilliSecond: Word) : TDateTime`

Visibility: default

Description: `EncodeTime` encodes the `Hour`, `Minute`, `Second`, `MilliSecond` variables to a `TDateTime` format result. It does the opposite of the `DecodeTime` (1325) procedure.

The parameters must have a valid range (boundaries included):

Hour must be between 0 and 23.

Minute, **second** must both be between 0 and 59.

Millisecond must be between 0 and 999.

Errors: In case one of the parameters is out of its valid range, an `EConvertError` (1413) exception is raised.

See also: `EncodeDate` (1329), `DecodeTime` (1325)

Listing: `./sysutex/ex12.pp`

Program `Example12`;

{ This program demonstrates the EncodeTime function }

Uses `sysutils`;

Var `Hh,MM,SS,MS` : `Word`;

Begin

`DeCodeTime (Time ,Hh,MM,SS,MS) ;`

`WriteLn ('Present Time is : ',FormatDateTime ('hh:mm:ss ',EnCodeTime (Hh,MM,SS,MS))) ;`

End.

30.12.70 ExceptAddr

Synopsis: Current exception address.

Declaration: `function ExceptAddr : Pointer`

Visibility: `default`

Description: `ExceptAddr` returns the address from the currently treated exception object when an exception is raised, and the stack is unwound.

See also: `ExceptObject` (1331), `ExceptionErrorMessage` (1331), `ShowException` (1378)

30.12.71 ExceptFrameCount

Synopsis: Number of frames included in an exception backtrace

Declaration: `function ExceptFrameCount : LongInt`

Visibility: `default`

Description: `ExceptFrameCount` returns the number of frames that are included in an exception stack frame backtrace. The function returns 0 if there is currently no exception being handled. (i.e. it only makes sense to call this function in an `finally..end` or `except..end` block.

Errors: None.

See also: `ExceptFrames` (1331), `ExceptAddr` (1330), `ExceptObject` (1331), `ExceptProc` (1278)

30.12.72 ExceptFrames

Synopsis:

Declaration: `function ExceptFrames : PPointer`

Visibility: default

Description:

Errors:

See also: `ExceptFrameCount` ([1330](#)), `ExceptAddr` ([1330](#)), `ExceptObject` ([1331](#)), `ExceptProc` ([1278](#))

30.12.73 ExceptionErrorMessage

Synopsis: Return a message describing the exception.

Declaration: `function ExceptionErrorMessage(ExceptObject: TObject;
 ExceptAddr: Pointer; Buffer: PChar;
 Size: Integer) : Integer`

Visibility: default

Description: `ExceptionErrorMessage` creates a string that describes the exception object `ExceptObject` at address `ExceptAddr`. It can be used to display exception messages. The string will be stored in the memory pointed to by `Buffer`, and will at most have `Size` characters.

The routine checks whether `ExceptObject` is a `Exception` ([1418](#)) object or not, and adapts the output accordingly.

See also: `ExceptObject` ([1331](#)), `ExceptAddr` ([1330](#)), `ShowException` ([1378](#))

30.12.74 ExceptObject

Synopsis: Current Exception object.

Declaration: `function ExceptObject : TObject`

Visibility: default

Description: `ExceptObject` returns the currently treated exception object when an exception is raised, and the stack is unwound.

Errors: If there is no exception, the function returns `Nil`

See also: `ExceptAddr` ([1330](#)), `ExceptionErrorMessage` ([1331](#)), `ShowException` ([1378](#))

30.12.75 ExcludeTrailingBackslash

Synopsis: Strip trailing directory separator from a pathname, if needed.

Declaration: `function ExcludeTrailingBackslash(const Path: String) : String`

Visibility: default

Description: `ExcludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `ExcludeTrailingPathDelimiter` ([1332](#)) instead.

See also: `IncludeTrailingPathDelimiter` ([1366](#)), `ExcludeTrailingPathDelimiter` ([1332](#)), `PathDelim` ([1288](#)), `IsPathDelimiter` ([1370](#))

30.12.76 ExcludeTrailingPathDelimiter

Synopsis: Strip trailing directory separator from a pathname, if needed.

Declaration: `function ExcludeTrailingPathDelimiter(const Path: String) : String`

Visibility: default

Description: `ExcludeTrailingPathDelimiter` removes the trailing path delimiter character (`PathDelim` (1288)) from `Path` if it is present, and returns the result.

See also: `ExcludeTrailingBackslash` (1331), `IncludeTrailingPathDelimiter` (1366), `PathDelim` (1288), `IsPathDelimiter` (1370)

30.12.77 ExecuteProcess

Synopsis: Execute another process (program).

Declaration: `function ExecuteProcess(const Path: AnsiString;
 const ComLine: AnsiString) : Integer
function ExecuteProcess(const Path: AnsiString;
 const ComLine: Array[] of AnsiString) : Integer`

Visibility: default

Description: `ExecuteProcess` will execute the program in `Path`, passing it the arguments in `ComLine`. `ExecuteProcess` will then wait for the program to finish, and will return the exit code of the executed program. In case `ComLine` is a single string, it will be split out in an array of strings, taking into account common whitespace and quote rules.

Errors: In case the program could not be executed or an other error occurs, an `EOSError` (1416) exception will be raised.

See also: `EOSError` (1416)

30.12.78 ExpandFileName

Synopsis: Expand a relative filename to an absolute filename.

Declaration: `function ExpandFileName(const FileName: String) : String`

Visibility: default

Description: `ExpandFileName` expands the filename to an absolute filename. It changes all directory separator characters to the one appropriate for the system first.

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335), `ExtractFileDir` (1333), `ExtractFileDrive` (1334), `ExtractFileExt` (1334), `ExtractRelativePath` (1335)

Listing: `./sysutex/ex33.pp`

Program `Example33;`

{ This program demonstrates the ExpandFileName function }

Uses `sysutils;`

```

Procedure Testit (F : String);

begin
    WriteIn (F, ' expands to : ', ExpandFileName(F));
end;

Begin
    Testit('ex33.pp');
    Testit(ParamStr(0));
    Testit('/pp/bin/win32/ppc386');
    Testit('\pp\bin\win32\ppc386');
    Testit('.');
End.

```

30.12.79 ExpandUNCFileName

Synopsis: Expand a relative filename to an absolute UNC filename.

Declaration: `function ExpandUNCFileName(const FileName: String) : String`

Visibility: default

Description: `ExpandUNCFileName` runs `ExpandFileName` (1332) on `FileName` and then attempts to replace the driveletter by the name of a shared disk.

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335), `ExtractFileDir` (1333), `ExtractFileDrive` (1334), `ExtractFileExt` (1334), `ExtractRelativePath` (1335)

30.12.80 ExtractFileDir

Synopsis: Extract the drive and directory part of a filename.

Declaration: `function ExtractFileDir(const FileName: String) : String`

Visibility: default

Description: `ExtractFileDir` returns only the directory part of `FileName`, including a driveletter. The directory name has NO ending directory separator, in difference with `ExtractFilePath` (1335).

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335), `ExtractFileDir` (1333), `ExtractFileDrive` (1334), `ExtractFileExt` (1334), `ExtractRelativePath` (1335)

Listing: `./sysutex/ex34.pp`

Program Example34;

```

{ This program demonstrates the ExtractFileName function }
{$H+}
Uses sysutils;

```

```

Procedure Testit(F : String);

```

```

begin

```

```

Writeln ( 'FileName      : ', F);
Writeln ( 'Has Name      : ', ExtractFileName(F));
Writeln ( 'Has Path      : ', ExtractFilePath(F));
Writeln ( 'Has Extension : ', ExtractFileExt(F));
Writeln ( 'Has Directory : ', ExtractFileDir(F));
Writeln ( 'Has Drive     : ', ExtractFileDrive(F));
end;

Begin
  Testit ( Paramstr(0));
  Testit ( '/usr/local/bin/mysqld' );
  Testit ( 'c:\pp\bin\win32\ppc386.exe' );
  Testit ( '/pp/bin/win32/ppc386.exe' );
End.

```

30.12.81 ExtractFileDrive

Synopsis: Extract the drive part from a filename.

Declaration: `function ExtractFileDrive(const FileName: String) : String`

Visibility: default

Description: `ExtractFileDrive` extracts the drive letter from a filename. Note that some operating systems do not support drive letters.

For an example, see `ExtractFileDir` ([1333](#)).

Errors:

See also: `ExtractFileName` ([1334](#)), `ExtractFilePath` ([1335](#)), `ExtractFileDir` ([1333](#)), `ExtractFileDrive` ([1334](#)), `ExtractFileExt` ([1334](#)), `ExtractRelativePath` ([1335](#))

30.12.82 ExtractFileExt

Synopsis: Return the extension from a filename.

Declaration: `function ExtractFileExt(const FileName: String) : String`

Visibility: default

Description: `ExtractFileExt` returns the extension (including the `.` (dot) character) of `FileName`.

For an example, see `ExtractFileDir` ([1333](#)).

Errors: None.

See also: `ExtractFileName` ([1334](#)), `ExtractFilePath` ([1335](#)), `ExtractFileDir` ([1333](#)), `ExtractFileDrive` ([1334](#)), `ExtractFileExt` ([1334](#)), `ExtractRelativePath` ([1335](#))

30.12.83 ExtractFileName

Synopsis: Extract the filename part from a full path filename.

Declaration: `function ExtractFileName(const FileName: String) : String`

Visibility: default

Description: `ExtractFileName` returns the filename part from `FileName`. The filename consists of all characters after the last directory separator character ('/' or '\') or drive letter.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` (1335) and `ExtractFileName`.

For an example, see `ExtractFileDir` (1333).

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335), `ExtractFileDir` (1333), `ExtractFileDrive` (1334), `ExtractFileExt` (1334), `ExtractRelativePath` (1335)

30.12.84 ExtractFilePath

Synopsis: Extract the path from a filename.

Declaration: `function ExtractFilePath(const FileName: String) : String`

Visibility: default

Description: `ExtractFilePath` returns the path part (including driveletter) from `FileName`. The path consists of all characters before the last directory separator character ('/' or '\'), including the directory separator itself. In case there is only a drive letter, that will be returned.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` and `ExtractFileName` (1334).

For an example, see `ExtractFileDir` (1333).

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335), `ExtractFileDir` (1333), `ExtractFileDrive` (1334), `ExtractFileExt` (1334), `ExtractRelativePath` (1335)

30.12.85 ExtractRelativepath

Synopsis: Extract a relative path from a filename, given a base directory.

Declaration: `function ExtractRelativepath(const BaseName: String;
const DestName: String) : String`

Visibility: default

Description: `ExtractRelativePath` constructs a relative path to go from `BaseName` to `DestName`. If `DestName` is on another drive (Not on Linux) then the whole `Destname` is returned. *Note:* This function does not exist in the Delphi unit.

Errors: None.

See also: `ExtractFileName` (1334), `ExtractFilePath` (1335), `ExtractFileDir` (1333), `ExtractFileDrive` (1334), `ExtractFileExt` (1334)

Listing: `./sysutex/ex35.pp`

Program `Example35;`

{ This program demonstrates the ExtractRelativePath function }

Uses `sysutils;`

```

Procedure Testit (FromDir, ToDir : String);

begin
  Write ( 'From "', FromDir, '" to "', ToDir, '" via " ');
  WriteLn ( ExtractRelativePath (FromDir, ToDir), ' ');
end;

Begin
  Testit ( '/pp/src/compiler', '/pp/bin/win32/ppc386' );
  Testit ( '/pp/bin/win32/ppc386', '/pp/src/compiler' );
  Testit ( 'e:/pp/bin/win32/ppc386', 'd:/pp/src/compiler' );
  Testit ( 'e:\pp\bin\win32\ppc386', 'd:\pp\src\compiler' );
End.

```

30.12.86 FileAge

Synopsis: Return the timestamp of a file.

Declaration: `function FileAge(const FileName: String) : LongInt`

Visibility: default

Description: `FileAge` returns the last modification time of file `FileName`. The `FileDate` format can be transformed to `TDateTime` format with the `FileDateToDateTime` (1338) function.

Errors: In case of errors, -1 is returned.

See also: `FileDateToDateTime` (1338), `FileExists` (1338), `FileGetAttr` (1339)

Listing: ./sysutex/ex36.pp

Program Example36;

{ This program demonstrates the FileAge function }

Uses sysutils;

Var S : TDateTime;
fa : Longint;

Begin
fa := **FileAge** ('ex36.pp');
If fa <> -1 **then**
 begin
 S := **FileDateToDateTime** (fa);
 WriteLn ('I'm from ', **DateTimeToStr**(S))
 end;
End.

30.12.87 FileClose

Synopsis: Close a file handle.

Declaration: `procedure FileClose(Handle: THandle)`

Visibility: default

Description: `FileClose` closes the file handle `Handle`. After this call, attempting to read or write from the handle will result in an error.

For an example, see `FileCreate` (1337)

Errors: None.

See also: `FileCreate` (1337), `FileWrite` (1344), `FileOpen` (1341), `FileRead` (1341), `FileTruncate` (1344), `FileSeek` (1342)

30.12.88 FileCreate

Synopsis: Create a new file and return a handle to it.

Declaration: `function FileCreate(const FileName: String) : THandle`
`function FileCreate(const FileName: String; Mode: Integer) : THandle`

Visibility: default

Description: `FileCreate` creates a new file with name `FileName` on the disk and returns a file handle which can be used to read or write from the file with the `FileRead` (1341) and `FileWrite` (1344) functions. If a file with name `FileName` already existed on the disk, it is overwritten.

Errors: If an error occurs (e.g. disk full or non-existent path), the function returns `-1`.

See also: `FileClose` (1336), `FileWrite` (1344), `FileOpen` (1341), `FileRead` (1341), `FileTruncate` (1344), `FileSeek` (1342)

Listing: `./sysutex/ex37.pp`

Program Example37;

{ This program demonstrates the FileCreate function }

Uses sysutils;

Var I, J, F : Longint;

Begin

```

F:=FileCreate ( 'test.dat' );
If F=-1 then
  Halt(1);
For I:=0 to 100 do
  FileWrite(F,I,SizeOf(i));
FileClose(f);
F:=FileOpen ( 'test.dat',fmOpenRead);
For I:=0 to 100 do
  begin
    FileRead (F,J,SizeOf(J));
    If J<>I then
      Writeln ( 'Mismatch at file position ',I)
    end;
  FileSeek(F,0,fsFromBeginning);
  Randomize;
  Repeat
    FileSeek(F,Random(100)*4,fsFromBeginning);
    FileRead (F,J,SizeOf(J));
    Writeln ( 'Random read : ',j);
  Until J>80;

```

```

FileClose(F);
F:=FileOpen('test.dat',fmOpenWrite);
l:=50*SizeOf(LongInt);
If FileTruncate(F,l) then
  WriteLn('Successfully truncated file to ',l,' bytes.');
```

```

FileClose(F);
End.
```

30.12.89 FileDateToDateTime

Synopsis: Convert a FileDate value to a TDateTime value.

Declaration: function FileDateToDateTime(Filedate: LongInt) : TDateTime

Visibility: default

Description: FileDateToDateTime converts the date/time encoded in filedate to a TDateTime encoded form. It can be used to convert date/time values returned by the FileAge (1336) or FindFirst (1345)/FindNext (1346) functions to TDateTime form.

Errors: None.

See also: DateTimeToFileDate (1320)

Listing: ./sysutex/ex13.pp

Program Example13;

{ This program demonstrates the FileDateToDateTime function }

Uses sysutils;

Var

 ThisAge : LongInt;

Begin

 Write ('ex13.pp created on :');

 ThisAge:=FileAge('ex13.pp');

 WriteLn (DateTimeToStr(FileDateToDateTime(ThisAge)));

End.

30.12.90 FileExists

Synopsis: Check whether a file exists in the filesystem.

Declaration: function FileExists(const FileName: String) : Boolean

Visibility: default

Description: FileExists returns True if a file with name FileName exists on the disk, False otherwise.

Errors: None.

See also: FileAge (1336), FileGetAttr (1339), FileSetAttr (1343)

Listing: ./sysutex/ex38.pp

```

Program Example38;

{ This program demonstrates the FileExists function }

Uses sysutils;

Begin
  If FileExists(ParamStr(0)) Then
    Writeln ('All is well, I seem to exist. ');
End.

```

30.12.91 FileGetAttr

Synopsis: Return attributes of a file.

Declaration: `function FileGetAttr(const FileName: String) : LongInt`

Visibility: default

Description: `FileGetAttr` returns the attribute settings of file `FileName`. The attribute is a OR-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On unix, this means that the filename starts with a dot)

faSysFileThe file is a system file (On unix, this means that the file is a character, block or FIFO file).

faVolumeIdVolume Label. Not possible under unix.

faDirectoryFile is a directory.

faArchivefile is an archive. Not possible on Unix

Errors: In case of error, -1 is returned.

See also: `FileSetAttr` ([1343](#)), `FileAge` ([1336](#)), `FileGetDate` ([1340](#))

Listing: ./sysutex/ex40.pp

```

Program Example40;

{ This program demonstrates the FileGetAttr function }

Uses sysutils;

Procedure Testit (Name : String);

Var F : Longint;

Begin
  F:= FileGetAttr(Name);
  If F<>-1 then
    begin
      Writeln ('Testing : ',Name);
      If (F and faReadOnly)<>0 then
        Writeln ('File is ReadOnly');
      If (F and faHidden)<>0 then
        Writeln ('File is hidden');
      If (F and faSysFile)<>0 then

```

```

    Writeln ( 'File is a system file ');
    If (F and faVolumeID)<>0 then
      Writeln ( 'File is a disk label ');
    If (F and faArchive)<>0 then
      Writeln ( 'File is artchive file ');
    If (F and faDirectory)<>0 then
      Writeln ( 'File is a directory ');
    end
  else
    Writeln ( 'Error reading attribites of ',Name);
  end;

begin
  testit ( 'ex40.pp ');
  testit ( ParamStr(0));
  testit ( '. ');
  testit ( '/' );
End.

```

30.12.92 FileGetDate

Synopsis: Return the file time of an opened file.

Declaration: `function FileGetDate(Handle: THandle) : LongInt`

Visibility: default

Description: `FileGetdate` returns the filetype of the opened file with filehandle `Handle`. It is the same as `FileAge` (1336), with this difference that `FileAge` only needs the file name, while `FilegetDate` needs an open file handle.

Errors: On error, -1 is returned.

See also: `FileAge` (1336)

Listing: `./sysutex/ex39.pp`

Program Example39;

{ This program demonstrates the FileGetDate function }

Uses sysutils;

Var F,D : Longint;

Begin

F:=FileCreate('test.dat ');

D:=FileGetDate(F);

Writeln ('File created on ',DateTimeToStr(FileDateToDateTime(D)));

FileClose(F);

DeleteFile('test.dat ');

End.

30.12.93 FileIsReadOnly

Synopsis: Check whether a file is read-only.

Declaration: `function FileIsReadOnly(const FileName: String) : Boolean`

Visibility: default

Description: `FileIsReadOnly` checks whether `FileName` exists in the filesystem and is a read-only file. If this is the case, the function returns `True`, otherwise `False` is returned.

See also: `FileExists` ([1338](#))

30.12.94 FileOpen

Synopsis: Open an existing file and return a filehandle

Declaration: `function FileOpen(const FileName: String; Mode: Integer) : THandle`

Visibility: default

Description: `FileOpen` opens a file with name `FileName` with mode `Mode`. `Mode` can be one of the following constants:

`fmOpenRead` The file is opened for reading.

`fmOpenWrite` The file is opened for writing.

`fmOpenReadWrite` The file is opened for reading and writing.

If the file has been successfully opened, it can be read from or written to (depending on the `Mode` parameter) with the `FileRead` ([1341](#)) and `FileWrite` functions.

Remark: Remark that you cannot open a file if it doesn't exist yet, i.e. it will not be created for you. If you want to create a new file, or overwrite an old one, use the `FileCreate` ([1337](#)) function.

For an example, see `FileOpen` ([1341](#))

Errors: On Error, -1 is returned.

See also: `FileClose` ([1336](#)), `FileWrite` ([1344](#)), `FileCreate` ([1337](#)), `FileRead` ([1341](#)), `FileTruncate` ([1344](#)), `FileSeek` ([1342](#))

30.12.95 FileRead

Synopsis: Read data from a filehandle in a buffer.

Declaration: `function FileRead(Handle: THandle; var Buffer; Count: LongInt) : LongInt`

Visibility: default

Description: `FileRead` reads `Count` bytes from file-handle `Handle` and stores them into `Buffer`. `Buffer` must be at least `Count` bytes long. No checking on this is performed, so be careful not to overwrite any memory. `Handle` must be the result of a `FileOpen` ([1341](#)) call.

The function returns the number of bytes actually read, or -1 on error.

For an example, see `FileCreate` ([1337](#))

Errors: On error, -1 is returned.

See also: `FileClose` ([1336](#)), `FileWrite` ([1344](#)), `FileCreate` ([1337](#)), `FileOpen` ([1341](#)), `FileTruncate` ([1344](#)), `FileSeek` ([1342](#))

30.12.96 FileSearch

Synopsis: Search for a file in a path.

Declaration: `function FileSearch(const Name: String;const DirList: String) : String`

Visibility: default

Description: `FileSearch` looks for the file `Name` in `DirList`, where `dirlist` is a list of directories, separated by semicolons or colons. It returns the full filename of the first match found.

Errors: On error, an empty string is returned.

See also: `ExpandFileName` ([1332](#)), `FindFirst` ([1345](#))

Listing: `./sysutex/ex41.pp`

Program `Example41`;

{ Program to demonstrate the FileSearch function. }

Uses `Sysutils`;

Const

{ \$ifdef unix }

`FN = 'find' ;`

`P = './bin:/usr/bin' ;`

{ \$else }

`FN = 'find.exe' ;`

`P = 'c:\dos;c:\windows;c:\windows\system;c:\windows\system32' ;`

{ \$endif }

begin

`WriteLn ('find is in : ',FileSearch (FN,P));`

end.

30.12.97 FileSeek

Synopsis: Set the current file position on a file handle.

Declaration: `function FileSeek(Handle: THandle;FOffset: LongInt;Origin: LongInt)
: LongInt`

`function FileSeek(Handle: THandle;FOffset: Int64;Origin: Int64) : Int64`

Visibility: default

Description: `FileSeek` sets the file pointer on position `Offset`, starting from `Origin`. `Origin` can be one of the following values:

fsFromBeginning `Offset` is relative to the first byte of the file. This position is zero-based. i.e. the first byte is at offset 0.

fsFromCurrent `Offset` is relative to the current position.

fsFromEnd `Offset` is relative to the end of the file. This means that `Offset` can only be zero or negative in this case.

If successful, the function returns the new file position, relative to the beginning of the file.

Remark: The abovementioned constants do not exist in Delphi.

Errors: On error, -1 is returned.

See also: [FileClose \(1336\)](#), [FileWrite \(1344\)](#), [FileCreate \(1337\)](#), [FileOpen \(1341\)](#), [FileRead \(1341\)](#), [FileTruncate \(1344\)](#)

Listing: ./sysutex/ex42.pp

Program Example42;

{ This program demonstrates the FileSetAttr function }

Uses sysutils;

Begin

```
  If FileSetAttr ( 'ex40.pp',faReadOnly or faHidden)=0 then
    Writeln ( 'Successfully made file hidden and read-only.')
  else
    Writeln ( 'Couldn't make file hidden and read-only.');
```

End.

30.12.98 FileSetAttr

Synopsis: Set the attributes of a file.

Declaration: `function FileSetAttr(const Filename: String;Attr: LongInt) : LongInt`

Visibility: default

Description: `FileSetAttr` sets the attributes of `FileName` to `Attr`. If the function was successful, 0 is returned, -1 otherwise. `Attr` can be set to an OR-ed combination of the pre-defined `faXXX` constants.

This function is not implemented on Unixes.

Errors: On error, -1 is returned (always on Unixes).

See also: [FileGetAttr \(1339\)](#), [FileGetDate \(1340\)](#), [FileSetDate \(1343\)](#)

30.12.99 FileSetDate

Synopsis: Set the date of a file.

Declaration: `function FileSetDate(Handle: THandle;Age: LongInt) : LongInt`
`function FileSetDate(const FileName: String;Age: LongInt) : LongInt`

Visibility: default

Description: `FileSetDate` sets the file date of the file with handle `Handle` to `Age`, where `Age` is a DOS date-and-time stamp value.

The function returns zero if successful. (not on unixes, where it is not implemented)

Errors: On Unix, -1 is always returned, since this is impossible to implement. On Windows and DOS, a negative error code is returned.

30.12.100 FileTruncate

Synopsis: Truncate an open file to a given size.

Declaration: `function FileTruncate(Handle: THandle; Size: LongInt) : Boolean`

Visibility: default

Description: `FileTruncate` truncates the file with handle `Handle` to `Size` bytes. The file must have been opened for writing prior to this call. The function returns `True` is successful, `False` otherwise.

For an example, see `FileCreate` (1337).

Errors: On error, the function returns `False`.

See also: `FileClose` (1336), `FileWrite` (1344), `FileCreate` (1337), `FileOpen` (1341), `FileRead` (1341), `FileSeek` (1342)

30.12.101 FileWrite

Synopsis: Write data from a buffer to a given filehandle.

Declaration: `function FileWrite(Handle: THandle; const Buffer; Count: LongInt)
: LongInt`

Visibility: default

Description: `FileWrite` writes `Count` bytes from `Buffer` to the file with handle `Handle`. Prior to this call, the file must have been opened for writing. `Buffer` must be at least `Count` bytes large, or a memory access error may occur.

The function returns the number of bytes written, or -1 in case of an error.

For an example, see `FileCreate` (1337).

Errors: In case of error, -1 is returned.

See also: `FileClose` (1336), `FileCreate` (1337), `FileOpen` (1341), `FileRead` (1341), `FileTruncate` (1344), `FileSeek` (1342)

30.12.102 FindClose

Synopsis: Close a find handle

Declaration: `procedure FindClose(var F: TSearchRec)`

Visibility: default

Description: `FindClose` ends a series of `FindFirst` (1345)/`FindNext` (1346) calls, and frees any memory used by these calls. It is *absolutely* necessary to do this call, or huge memory losses may occur.

For an example, see `FindFirst` (1345).

Errors: None.

See also: `FindFirst` (1345), `FindNext` (1346)

30.12.103 FindCmdLineSwitch

Synopsis: Check whether a certain switch is present on the command-line.

Declaration:

```
function FindCmdLineSwitch(const Switch: String;
                           const Chars: TSysCharSet; IgnoreCase: Boolean)
                           : Boolean
function FindCmdLineSwitch(const Switch: String; IgnoreCase: Boolean)
                           : Boolean
function FindCmdLineSwitch(const Switch: String) : Boolean
```

Visibility: default

Description: FindCmdLineSwitch will check all command-line arguments for the presence of the option Switch. It will return True if it was found, False otherwise. Characters that appear in Chars (default is SwitchChars (1290)) are assumed to indicate an option (switch). If the parameter IgnoreCase is True, case will be ignored when looking for the switch. Default is to search case sensitive.

Errors: None.

See also: SwitchChars (1290)

30.12.104 FindFirst

Synopsis: Start a file search and return a findhandle

Declaration:

```
function FindFirst(const Path: String; Attr: LongInt;
                  out Rslt: TSearchRec) : LongInt
```

Visibility: default

Description: FindFirst looks for files that match the name (possibly with wildcards) in Path and attributes Attr. It then fills up the Rslt record with data gathered about the file. It returns 0 if a file matching the specified criteria is found, a nonzero value (-1 on linux) otherwise.

The Rslt record can be fed to subsequent calls to FindNext, in order to find other files matching the specifications.

Remark: A FindFirst call must *always* be followed by a FindClose (1344) call with the same Rslt record. Failure to do so will result in memory loss.

Errors: On error the function returns -1 on linux, a nonzero error code on Windows.

See also: FindClose (1344), FindNext (1346)

Listing: ./sysutex/ex43.pp

Program Example43;

{ This program demonstrates the FindFirst function }

Uses SysUtils;

Var Info : TSearchRec;
 Count : Longint;

Begin

```
Count:=0;
If FindFirst ( '*',faAnyFile and faDirectory ,Info)=0 then
begin
```

```

Repeat
  Inc(Count);
  With Info do
    begin
      If (Attr and faDirectory) = faDirectory then
        Write('Dir : ');
        WriteLn (Name:40,Size:15);
      end;
    Until FindNext(info)<>0;
  end;
FindClose(Info);
WriteLn ('Finished search. Found ',Count,' matches');

End.

```

30.12.105 FindNext

Synopsis: Find the next entry in a findhandle.

Declaration: `function FindNext(var Rslt: TSearchRec) : LongInt`

Visibility: default

Description: `FindNext` finds a next occurrence of a search sequence initiated by `FindFirst`. If another record matching the criteria in `Rslt` is found, 0 is returned, a nonzero constant is returned otherwise.

Remark: The last `FindNext` call must *always* be followed by a `FindClose` call with the same `Rslt` record. Failure to do so will result in memory loss.

For an example, see `FindFirst` ([1345](#))

Errors: On error (no more file is found), a nonzero constant is returned.

See also: `FindFirst` ([1345](#)), `FindClose` ([1344](#))

30.12.106 FloattoCurr

Synopsis: Convert a float to a Currency value.

Declaration: `function FloattoCurr(const Value: Extended) : Currency`

Visibility: default

Description: `FloatToCurr` converts the `Value` floating point value to a `Currency` value. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` ([1288](#)) and `MaxCurrency` ([1287](#))). If not, an `EConvertError` ([1413](#)) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` ([1413](#)) exception is raised.

See also: `EConvertError` ([1413](#)), `TryFloatToCurr` ([1406](#)), `MinCurrency` ([1288](#)), `MaxCurrency` ([1287](#))

30.12.107 FloatToDateTime

Synopsis: Convert a float to a `TDateTime` value.

Declaration: `function FloatToDateTime(const Value: Extended) : TDateTime`

Visibility: default

Description: `FloatToDateTime` converts the `Value` floating point value to a `TDateTime` value. It checks whether `Value` is in the valid range of dates (determined by `MinDateTime` (1288) and `MaxDateTime` (1287)). If not, an `EConvertError` (1413) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1413) exception is raised.

See also: `EConvertError` (1413), `MinDateTime` (1288), `MaxDateTime` (1287)

30.12.108 FloatToDecimal

Synopsis: Convert a float value to a `TFloatRec` value.

Declaration: `procedure FloatToDecimal (var Result: TFloatRec; Value: Extended;
Precision: Integer; Decimals: Integer)`

Visibility: default

Description: `FloatToDecimal` converts the float `Value` to a float description in the `ResultTFloatRec` (1293) format. It will store `Precision` digits in the `Digits` field, of which at most `Decimal` decimals.

Errors: None.

See also: `TFloatRec` (1293)

30.12.109 FloatToStr

Synopsis: Convert a float value to a string using a fixed format.

Declaration: `function FloatToStr (Value: Double) : String
function FloatToStr (Value: Single) : String
function FloatToStr (Value: Currency) : String
function FloatToStr (Value: Comp) : String
function FloatToStr (Value: Int64) : String`

Visibility: default

Description: `FloatToStr` converts the floating point variable `Value` to a string representation. It will choose the shortest possible notation of the two following formats:

Fixed format will represent the string in fixed notation,

Decimal format will represent the string in scientific notation.

More information on these formats can be found in `FloatToStrF` (1348). `FloatToStr` is completely equivalent to the following call:

```
FloatToStrF (Value, ffGeneral, 15, 0);
```

Errors: None.

See also: `FloatToStrF` (1348), `FormatFloat` (1359), `StrToFloat` (1395)

Listing: `./sysutex/ex67.pp`

```

Program Example67;

{ This program demonstrates the FloatToStr function }

Uses sysutils;

Procedure Testit (Value : Extended);

begin
    WriteLn (Value, ' -> ', FloatToStr (Value));
    WriteLn (-Value, ' -> ', FloatToStr (-Value));
end;

Begin
    Testit (0.0);
    Testit (1.1);
    Testit (1.1e-3);
    Testit (1.1e-20);
    Testit (1.1e-200);
    Testit (1.1e+3);
    Testit (1.1e+20);
    Testit (1.1e+200);
End.

```

30.12.110 FloatToStrF

Synopsis: Convert a float value to a string using a given format.

Declaration:

```

function FloatToStrF(Value: Double;format: TFloatFormat;
    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Single;format: TFloatFormat;
    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Comp;format: TFloatFormat;
    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Currency;format: TFloatFormat;
    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Int64;format: TFloatFormat;
    Precision: Integer;Digits: Integer) : String

```

Visibility: default

Description: FloatToStrF converts the floating point number value to a string representation, according to the settings of the parameters Format, Precision and Digits.

The meaning of the Precision and Digits parameter depends on the Format parameter. The format is controlled mainly by the Format parameter. It can have one of the following values:

ffcurrencyMoney format. Value is converted to a string using the global variables CurrencyString, CurrencyFormat and NegCurrencyFormat. The Digits parameter specifies the number of digits following the decimal point and should be in the range -1 to 18. If Digits equals -1, CurrencyDecimals is assumed. The Precision parameter is ignored.

ffExponentScientific format. Value is converted to a string using scientific notation: 1 digit before the decimal point, possibly preceded by a minus sign if Value is negative. The number of digits after the decimal point is controlled by Precision and must lie in the range 0 to 15.

ffFixedFixed point format. Value is converted to a string using fixed point notation. The result is composed of all digits of the integer part of Value, preceded by a minus sign if Value is negative. Following the integer part is DecimalSeparator and then the fractional part of Value, rounded off to Digits numbers. If the number is too large then the result will be in scientific notation.

ffGeneralGeneral number format. The argument is converted to a string using ffExponent or ffFixed format, depending on which one gives the shortest string. There will be no trailing zeroes. If Value is less than 0.00001 or if the number of decimals left of the decimal point is larger than Precision then scientific notation is used, and Digits is the minimum number of digits in the exponent. Otherwise Digits is ignored.

ffnumberIs the same as ffFixed, except that thousand separators are inserted in the resultig string.

Errors: None.

See also: FloatToStr ([1347](#)), FloatToText ([1350](#))

Listing: ./sysutex/ex68.pp

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of** **string**[10] =
 ('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
 FF : TFloatFormat;

begin

For I:=5 **to** 15 **do**

For J:=1 **to** 4 **do**

For FF:=ffgeneral **to** ffcurrency **do**

begin

Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

Writeln (FloatToStrF(Value, FF, I, J));

Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

Writeln (FloatToStrF(-Value, FF, I, J));

end;

end;

Begin

 Testit (1.1);

 Testit (1.1E1);

 Testit (1.1E-1);

 Testit (1.1E5);

 Testit (1.1E-5);

 Testit (1.1E10);

 Testit (1.1E-10);

 Testit (1.1E15);

 Testit (1.1E-15);

 Testit (1.1E100);

 Testit (1.1E-100);

End.

30.12.111 FloatToText

Synopsis: Return a string representation of a float, with a given format.

Declaration: `function FloatToText (Buffer: PChar; Value: Extended; format: TFloatFormat;
Precision: Integer; Digits: Integer) : LongInt`

Visibility: default

Description: `FloatToText` converts the floating point variable `Value` to a string representation and stores it in `Buffer`. The conversion is governed by `format`, `Precision` and `Digits`. more information on these parameters can be found in `FloatToStrF` (1348). `Buffer` should point to enough space to hold the result. No checking on this is performed.

The result is the number of characters that was copied in `Buffer`.

Errors: None.

See also: `FloatToStr` (1347), `FloatToStrF` (1348)

Listing: ./sysutex/ex69.pp

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of** **string**[10] =
('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
FF : TFloatFormat;
S : ShortString;

begin

For I:=5 to 15 do

For J:=1 to 4 do

For FF:=ffgeneral to ffcurrency do

begin

Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

SetLength(S, **FloatToText** (@S[1], Value, FF, I, J));

Writeln (S);

Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

SetLength(S, **FloatToText** (@S[1], -Value, FF, I, J));

Writeln (S);

end;

end;

Begin

Testit (1.1);

Testit (1.1E1);

Testit (1.1E-1);

Testit (1.1E5);

Testit (1.1E-5);

Testit (1.1E10);

Testit (1.1E-10);

Testit (1.1E15);

```

Testit (1.1E-15);
Testit (1.1E100);
Testit (1.1E-100);
End.

```

30.12.112 FloatToTextFmt

Synopsis: Convert a float value to a string using a given mask.

Declaration: `function FloatToTextFmt (Buffer: PChar; Value: Extended; format: PChar)
: Integer`

Visibility: default

Description: `FloatToTextFmt` returns a textual representation of `Value` in the memory location pointed to by `Buffer`. it uses the formatting specification in `Format` to do this. The return value is the number of characters that were written in the buffer.

For a list of valid formatting characters, see `FormatFloat` ([1359](#))

Errors: No length checking is performed on the buffer. The buffer should point to enough memory to hold the complete string. If this is not the case, an access violation may occur.

See also: `FormatFloat` ([1359](#))

30.12.113 FmtStr

Synopsis: Format a string with given arguments.

Declaration: `procedure FmtStr (var Res: String; const Fmt: String;
const args: Array[] of const)`

Visibility: default

Description: `FmtStr` calls `Format` ([1352](#)) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `Format` ([1352](#)).

Errors: In case of error, a `EConvertError` exception is raised.

See also: `Format` ([1352](#)), `FormatBuf` ([1357](#))

Listing: `./sysutex/ex70.pp`

Program Example70;

{ This program demonstrates the FmtStr function }

Uses sysutils;

Var S : AnsiString;

Begin

S := '';

FmtStr (S, 'For some nice examples of fomatting see %s.', ['Format']);

WriteLn (S);

End.

30.12.114 ForceDirectories

Synopsis: Create a chain of directories

Declaration: `function ForceDirectories(const Dir: String) : Boolean`

Visibility: default

Description: `ForceDirectories` tries to create any missing directories in `Dir` till the whole path in `Dir` exists. It returns `True` if `Dir` already existed or was created successfully. If it failed to create any of the parts, `False` is returned.

30.12.115 Format

Synopsis: Format a string with given arguments.

Declaration: `function Format(const Fmt: String; const Args: Array[] of const) : String`

Visibility: default

Description: `Format` replaces all placeholders in `Fmt` with the arguments passed in `Args` and returns the resulting string. A placeholder looks as follows:

`'%' [Index ':'] ['-'] [Width] ['.' Precision] ArgType`

elements between single quotes must be typed as shown without the quotes, and elements between square brackets `[]` are optional. The meaning of the different elements is shown below:

`'%'` starts the placeholder. If you want to insert a literal `%` character, then you must insert two of them: `%%`.

Index `'.'` takes the `Index`-th element in the argument array as the element to insert.

`'-'` tells `Format` to left-align the inserted text. The default behaviour is to right-align inserted text. This can only take effect if the `Width` element is also specified.

Width the inserted string must have at least have `Width` characters. If not, the inserted string will be padded with spaces. By default, the string is left-padded, resulting in a right-aligned string. This behaviour can be changed by the `'-'` character.

`'.'` **Precision** Indicates the precision to be used when converting the argument. The exact meaning of this parameter depends on `ArgType`.

The `Index`, `Width` and `Precision` parameters can be replaced by `*`, in which case their value will be read from the next element in the `Args` array. This value must be an integer, or an `EConvertError` exception will be raised.

The argument type is determined from `ArgType`. It can have one of the following values (case insensitive):

D Decimal format. The next argument in the `Args` array should be an integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

E Scientific format. The next argument in the `Args` array should be a Floating point value. The argument is converted to a decimal string using scientific notation, using `FloatToStrF` (1348), where the optional precision is used to specify the total number of decimals. (default a value of 15 is used). The exponent is formatted using maximally 3 digits.

In short, the `E` specifier formats it's argument as follows:

`FloatToStrF (Argument, ffexponent, Precision, 3)`

FFixed point format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string, using fixed notation (see `FloatToStrF` (1348)). `Precision` indicates the number of digits following the decimal point.

In short, the `F` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffFixed, ffixed, 9999, Precision)
```

GGeneral number format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string using fixed point notation or scientific notation, depending on which gives the shortest result. `Precision` is used to determine the number of digits after the decimal point.

In short, the `G` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffGeneral, Precision, 3)
```

MMurrency format. the next argument in the `var{Args}` array must be a floating point value. The argument is converted to a decimal string using currency notation. This means that fixed-point notation is used, but that the currency symbol is appended. If precision is specified, then then it overrides the `CurrencyDecimals` global variable used in the `FloatToStrF` (1348)

In short, the `M` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffCurrency, 9999, Precision)
```

NNumber format. This is the same as fixed point format, except that thousand separators are inserted in the resulting string.

PPointer format. The next argument in the `Args` array must be a pointer (typed or untyped). The pointer value is converted to a string of length 8, representing the hexadecimal value of the pointer.

SString format. The next argument in the `Args` array must be a string. The argument is simply copied to the result string. If `Precision` is specified, then only `Precision` characters are copied to the result string.

UUnsigned decimal format. The next argument in the `Args` array should be an unsigned integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

XX hexadecimal format. The next argument in the `Args` array must be an integer. The argument is converted to a hexadecimal string with just enough characters to contain the value of the integer. If `Precision` is specified then the resulting hexadecimal representation will have at least `Precision` characters in it (with a maximum value of 32).

Errors: In case of error, an `EConversionError` exception is raised. Possible errors are:

- 1.Errors in the format specifiers.
- 2.The next argument is not of the type needed by a specifier.
- 3.The number of arguments is not sufficient for all format specifiers.

See also: `FormatBuf` (1357)

Listing: `./sysutex/ex71.pp`

Program `example71`;

```
{ $mode objfpc }
```

```
{ This program demonstrates the Format function }
```

Uses sysutils;

Var P : Pointer;
 fmt,S : **string**;

Procedure TestInteger;

```

begin
  Try
    Fmt:= '%d'; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%%' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%10d' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    fmt:= '%.4d' ; S:=Format (fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%10.4d' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:d' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:10d' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:10.4d' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:-10d' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:-10.4d' ; S:=Format (fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%-*.d' ; S:=Format (fmt,[4,5,10]); writeln(Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ( 'Exception caught : ',E.Message);
      end;
    end;
    writeln ( 'Press enter ');
    readln;
  end;

```

Procedure TestHexadecimal;

```

begin
  try
    Fmt:= '%x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%10x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%10.4x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:10x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:10.4x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:-10x' ; S:=Format (Fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%0:-10.4x' ; S:=Format (fmt,[10]); writeln(Fmt:12, ' => ',s);
    Fmt:= '%-*.x' ; S:=Format (fmt,[4,5,10]); writeln(Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ( 'Exception caught : ',E.Message);
      end;
    end;
    writeln ( 'Press enter ');
    readln;
  end;

```

Procedure TestPointer;

```

begin
  P:=Pointer(1234567);
  try

```

```

Fmt:= '[0x%p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%10p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%10.4p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:10p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:10.4p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:-10p]'; S:= Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:-10.4p]'; S:= Format (fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[%-*.*p]'; S:= Format (fmt,[4,5,P]); writeln (Fmt:12, ' => ',s);
except
  On E : Exception do
    begin
      Writeln ('Exception caught : ',E.Message);
    end;
end;
writeln ('Press enter');
readln;
end;

Procedure TestString;

begin
  try
    Fmt:= '[%s]'; S:= Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%0:s]'; s:= Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%0:18s]'; s:= Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%0:-18s]'; s:= Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%0:18.12s]'; s:= Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%-*.*s]'; s:= Format(fmt,[18,12,'This is a string']); Writeln(fmt:12, '=> ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
    writeln ('Press enter');
    readln;
  end;

Procedure TestExponential;

begin
  Try
    Fmt:= '[%e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10.4e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10.4e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10e]'; S:= Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10.4e]'; S:= Format (fmt,[1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%-*.*e]'; S:= Format (fmt,[4,5,1.234]); writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;

```



```

    writeln ( 'Press enter' );
    readln;
end;

```

Procedure TestNegativeExponential;

```

begin
  Try
    Fmt:= '%e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10.4e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10.4e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10e' ;S:=Format ( Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10.4e' ;S:=Format ( fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%-*.*e' ;S:=Format ( fmt,[4,5, -1.234]);writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ( 'Exception caught : ',E.Message);
      end;
    end;
    writeln ( 'Press enter' );
    readln;
end;

```

Procedure TestSmallExponential;

```

begin
  Try
    Fmt:= '%e' ;S:=Format ( Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10e' ;S:=Format ( Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10.4e' ;S:=Format ( Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:e' ;S:=Format ( Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10e' ;S:=Format ( Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10.4e' ;S:=Format ( Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10e' ;S:=Format ( Fmt,[0.0123]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10.4e' ;S:=Format ( fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%-*.*e' ;S:=Format ( fmt,[4,5,0.01234]);writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ( 'Exception caught : ',E.Message);
      end;
    end;
    writeln ( 'Press enter' );
    readln;
end;

```

Procedure TestSmallNegExponential;

```

begin
  Try
    Fmt:= '%e' ;S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10e' ;S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10.4e' ;S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:e' ;S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12, ' => ',s);

```

```

    Fmt:= '[%0:10e]';S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '[%0:10.4e]';S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '[%0:-10e]';S:=Format ( Fmt,[ -0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '[%0:-10.4e]';S:=Format ( fmt,[ -0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '[%-*.e]';S:=Format ( fmt,[4,5, -0.01234]);writeln (Fmt:12,' => ',s);
except
  On E : Exception do
    begin
      Writeln ( 'Exception caught : ',E.Message);
    end;
end;
writeln ( 'Press enter ');
readln;
end;

begin
  TestInteger;
  TestHexadecimal;
  TestPointer;
  TestExponential;
  TestNegativeExponential;
  TestSmallExponential;
  TestSmallNegExponential;
  teststring;
end.

```

30.12.116 FormatBuf

Synopsis: Format a string with given arguments and store the result in a buffer.

Declaration: `function FormatBuf(var Buffer;BufLen: Cardinal;const Fmt;
 fmtLen: Cardinal;const Args: Array[] of const)
 : Cardinal`

Visibility: default

Description: `FormatBuf` calls `Format` ([1352](#)) and stores the result in `Buf`.

See also: `Format` ([1352](#))

Listing: `./sysutex/ex72.pp`

Program Example72;

{ This program demonstrates the FormatBuf function }

Uses sysutils;

Var

 S : ShortString;

Const

 Fmt : ShortString = 'For some nice examples of fomattting see %s.';

Begin

 S:= '';

 SetLength(S,**FormatBuf** (S[1],255,Fmt[1],**Length**(Fmt),['Format']));

```

WriteLn (S);
End.

```

30.12.117 FormatCurr

Synopsis: Format a currency

Declaration: `function FormatCurr(const Format: String; Value: Currency) : String`

Visibility: default

Description: `FormatCurr` formats the currency `Value` according to the formatting rule in `Format`, and returns the resulting string.

For an explanation of the formatting characters, see `FormatFloat` ([1359](#)).

See also: `FormatFloat` ([1359](#)), `FloatToText` ([1350](#))

30.12.118 FormatDateTime

Synopsis: Return a string representation of a `TDateTime` value with a given format.

Declaration: `function FormatDateTime(FormatStr: String; DateTime: TDateTime) : String`

Visibility: default

Description: `FormatDateTime` formats the date and time encoded in `DateTime` according to the formatting given in `FormatStr`. The complete list of formatting characters can be found in `formatchars` ([1281](#)).

Errors: On error (such as an invalid character in the formatting string), and `EConvertError` exception is raised.

See also: `DateTimeToStr` ([1321](#)), `DateToStr` ([1323](#)), `TimeToStr` ([1403](#)), `StrToDateTime` ([1394](#))

Listing: `./sysutex/ex14.pp`

Program Example14;

```
{ This program demonstrates the FormatDateTime function }
```

```
Uses sysutils;
```

```
Var ThisMoment : TDateTime;
```

```
Begin
```

```
  ThisMoment:=Now;
```

```
  WriteLn ( 'Now : ', FormatDateTime( 'hh:nn ', ThisMoment ));
```

```
  WriteLn ( 'Now : ', FormatDateTime( 'DD MM YYYY ', ThisMoment ));
```

```
  WriteLn ( 'Now : ', FormatDateTime( 'c ', ThisMoment ));
```

```
End.
```

30.12.119 FormatFloat

Synopsis: Format a float according to a certain mask.

Declaration: `function FormatFloat(const Format: String; Value: Extended) : String`

Visibility: default

Description: `FormatFloat` formats the floating-point value given by `Value` using the format specifications in `Format`. The format specifier can give format specifications for positive, negative or zero values (separated by a semicolon).

If the format specifier is empty or the value needs more than 18 digits to be correctly represented, the result is formatted with a call to `FloatToStrF` (1348) with the `ffGeneral` format option.

The following format specifiers are supported:

0 is a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the 0. If not, the 0 is left as-is.

is also a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the #. If not, it is removed. by a space.

. determines the location of the decimal point. Only the first '.' character is taken into account. If the value contains digits after the decimal point, then it is replaced by the value of the `DecimalSeparator` character.

, determines the use of the thousand separator character in the output string. If the format string contains one or more ',' characters, then thousand separators will be used. The `ThousandSeparator` character is used.

E determines the use of scientific notation. If 'E+' or 'E-' (or their lowercase counterparts) are present then scientific notation is used. The number of digits in the output string is determined by the number of 0 characters after the 'E+'.

; This character separates sections for positive, negative, and zero numbers in the format string.

Errors: If an error occurs, an exception is raised.

See also: `FloatToStr` (1347)

Listing: `./sysutex/ex89.pp`

Program Example89;

{ This program demonstrates the FormatFloat function }

Uses sysutils;

Const

```
NrFormat=9;
FormatStrings : Array[1..NrFormat] of string = (
    '',
    '0',
    '0.00',
    '#.##',
    '#,##0.00',
    '#,##0.00;(#,##0.00)',
    '#,##0.00;;Zero',
    '0.000E+00',
    '#.###E-0');
NrValue = 5;
FormatValues : Array[1..NrValue] of Double =
```

```

(1234, -1234, 0.5, 0, -0.5);

Width  = 12;
FWidth = 20;

Var
  I, J : Integer;
  S : String;

begin
  Write( 'Format':FWidth);
  For I:=1 to NrValue do
    Write(FormatValues[I]:Width:2);
  WriteLn;
  For I:=1 to NrFormat do
    begin
      Write(FormatStrings[I]:FWidth);
      For J:=1 to NrValue do
        begin
          S:=FormatFloat(FormatStrings[I], FormatValues[J]);
          Write(S:Width);
        end;
      WriteLn;
    end;
End.

```

30.12.120 FreeAndNil

Synopsis: Free object if needed, and set object reference to Nil

Declaration: `procedure FreeAndNil(var obj)`

Visibility: default

Description: `FreeAndNil` will free the object in `Obj` and will set the reference in `Obj` to `Nil`. The reference is set to `Nil` first, so if an exception occurs in the destructor of the object, the reference will be `Nil` anyway.

Errors: Exceptions that occur during the destruction of `Obj` are not caught.

30.12.121 GetAppConfigDir

Synopsis: Return the appropriate directory for the application's configuration files.

Declaration: `function GetAppConfigDir(Global: Boolean) : String`

Visibility: default

Description: `GetAppConfigDir` returns the name of a directory in which the application should store its configuration files on the current OS. If the parameter `Global` is `True` then the directory returned is a global directory, i.e. valid for all users on the system. If the parameter `Global` is false, then the directory is specific for the user who is executing the program. On systems that do not support multi-user environments, these two directories may be the same.

The directory which is returned is the name of the directory where the application is supposed to store files. This does not mean that the directory exists, or that the user can write in this directory (especially if `Global=True`). It just returns the name of the appropriate location.

On systems where the operating system provides a call to determine this location, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1312) call, but can be configured by means of the `OnGetApplicationName` (1297) callback.

Errors: None.

See also: `GetAppConfigFile` (1361), `ApplicationName` (1312), `OnGetApplicationName` (1297), `CreateDir` (1318), `SysConfigDir` (1290)

30.12.122 `GetAppConfigFile`

Synopsis: Return an appropriate name for an application configuration file.

Declaration: `function GetAppConfigFile(Global: Boolean) : String`
`function GetAppConfigFile(Global: Boolean;SubDir: Boolean) : String`

Visibility: default

Description: `GetAppConfigFile` returns the name of a file in which the application can store its configuration parameters. The `Global` parameter determines whether it is a global configuration file (value `True`) or a personal configuration file (value `False`). The parameter `SubDir`, in case it is set to `True`, will insert the name of a directory before the filename. This can be used in case the application needs to store other data than configuration data in an application-specific directory. Default behaviour is to set this to `False`.

No assumptions should be made about the existence or writeability of this file, or the directory where the file should reside.

On systems where the operating system provides a call to determine the location of configuration files, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1312) call, but can be configured by means of the `OnGetApplicationName` (1297) callback.

Errors: None.

See also: `GetAppConfigDir` (1360), `OnGetApplicationName` (1297), `ApplicationName` (1312), `CreateDir` (1318), `ConfigExtension` (1283), `SysConfigDir` (1290)

30.12.123 `GetCurrentDir`

Synopsis: Return the current working directory of the application.

Declaration: `function GetCurrentDir : String`

Visibility: default

Description: `GetCurrentDir` returns the current working directory.

Errors: None.

See also: `SetCurrentDir` (1377), `DiskFree` (1327), `DiskSize` (1327)

Listing: `./sysutex/ex28.pp`

Program Example28;

```
{ This program demonstrates the GetCurrentDir function }
```

```
Uses sysutils;
```

Begin

```
WriteLn ( 'Current Directory is : ',GetCurrentDir);
```

```
End.
```

30.12.124 GetDirs

: Return a list of directory names from a path.

```

: function GetDirs(var DirName: String; var Dirs: Array[] of pchar)
                : LongInt

```

: default

:GetDirs splits DirName in a null-byte separated list of directory names, Dirs is an array of PChars, pointing to these directory names. The function returns the number of directories found, or -1 if none were found. DirName must contain only OSDirSeparator as Directory separator chars.

: None.

```

: ExtractRelativePath (1335)

```

Listing: ./sysutex/ex45.pp

Program Example45;

```
{ This program demonstrates the GetDirs function }
{$H+}
```

```
Uses sysutils;
```

```
Var Dirs : Array[0..127] of pchar;
```

```
l,Count : longint;
```

Dir, NewDir : **String**;

Begin

```
Dir := GetCurrDir;
```

```
WriteLn ( 'Dir : ', Dir );
```

```
NewDir:= '';
```

```
count:=GetDirs ( Dir , Dirs );
```

```

For i:=0 to Count-1 do

```

begin

```
NewDir:=NewDir+'/' + StrPas( Dirs [ I ] );
```

```
WriteIn ( NewDir );
```

```
end;
```

End.

30.12.125 GetEnvironmentString

: Return an environment variable by index.

Declaration: `function GetEnvironmentString(Index: Integer) : String`

Visibility: default

Description: `GetEnvironmentString` returns the `Index`-th environment variable. The index is 1 based, and is bounded from above by the result of `GetEnvironmentVariableCount` (1363).

For an example, `GetEnvironmentVariableCount` (1363).

Errors: If there is no environment, -1 may be returned.

See also: `GetEnvironmentVariable` (1363), `GetEnvironmentVariableCount` (1363)

30.12.126 GetEnvironmentVariable

Synopsis: Return the value of an environment variable.

Declaration: `function GetEnvironmentVariable(const EnvVar: String) : String`

Visibility: default

Description: `GetEnvironmentVariable` returns the value of the `EnvVar` environment variable. If the specified variable does not exist or `EnvVar` is empty, an empty string is returned.

See also: `GetEnvironmentString` (1362), `GetEnvironmentVariableCount` (1363)

30.12.127 GetEnvironmentVariableCount

Synopsis: Return the number of variables in the environment.

Declaration: `function GetEnvironmentVariableCount : Integer`

Visibility: default

Description: `GetEnvironmentVariableCount` returns the number of variables in the environment. The number is 1 based, but the result may be zero if there are no environment variables.

Errors: If there is no environment, -1 may be returned.

See also: `GetEnvironmentString` (1362), `GetEnvironmentVariable` (1363)

Listing: `./sysutex/ex92.pp`

```
{ $h+ }
program example92;

{ This program demonstrates the
  GetEnvironmentVariableCount function }

uses sysutils;

Var
  I : Integer;

begin
  For I:=1 to GetEnvironmentVariableCount do
    Writeln(i:3, ' : ', GetEnvironmentString(i));
end.
```

30.12.128 GetFileHandle

Synopsis: Extract OS handle from an untyped file or text file.

Declaration: `function GetFileHandle(var f: File) : LongInt`
`function GetFileHandle(var f: Text) : LongInt`

Visibility: default

Description: `GetFileHandle` returns the operating system handle for the file descriptor `F`. It can be used in various file operations which are not directly supported by the pascal language.

30.12.129 GetLastOSError

Synopsis: Return the last code from the OS.

Declaration: `function GetLastOSError : Integer`

Visibility: default

Description: `GetLastOSError` returns the error code from the last operating system call. It does not reset this code. In general, it should be called when an operating system call reported an error condition. In that case, `GetLastOSError` gives extended information about the error.

No assumptions should be made about the resetting of the error code by subsequent OS calls. This may be platform dependent.

See also: `RaiseLastOSError` ([1375](#))

30.12.130 GetLocalTime

Synopsis: Get the local time.

Declaration: `procedure GetLocalTime(var SystemTime: TSystemTime)`

Visibility: default

Description: `GetLocalTime` returns the system time in a `TSystemTime` ([1296](#)) format.

Errors: None.

See also: `Now` ([1374](#)), `Date` ([1320](#)), `Time` ([1402](#)), `TSystemTime` ([1296](#))

30.12.131 GetTempDir

Synopsis: Return name of system's temporary directory

Declaration: `function GetTempDir(Global: Boolean) : String`
`function GetTempDir : String`

Visibility: default

Description: `GetTempDir` returns the temporary directory of the system. If `Global` is `True` (the default value) it returns the system temporary directory, if it is `False` then a directory private to the user is returned. The returned name will end with a directory delimiter character.

These directories may be the same. No guarantee is made that this directory exists or is writeable by the user.

The `OnGetTempDir` ([1297](#)) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

Errors: On error, an empty string is returned.

See also: OnGetTempDir ([1297](#)), GetTempFileName ([1365](#))

30.12.132 GetTempFileName

Synopsis: Return the name of a temporary file.

Declaration:

```
function GetTempFileName(const Dir: String;const Prefix: String)
                        : String
function GetTempFileName : String
function GetTempFileName(Dir: PChar;Prefix: PChar;uUnique: DWORD;
                        TempFileName: PChar) : DWORD
```

Visibility: default

Description: GetTempFileName returns the name of a temporary file in directory Dir. The name of the file starts with Prefix.

If Dir is empty, the value returned by GetTempDir is used, and if Prefix is empty, 'TMP' is used.

The OnGetTempFile ([1297](#)) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

Errors: On error, an empty string is returned.

See also: GetTempDir ([1364](#)), OnGetTempFile ([1297](#))

30.12.133 GUIDToString

Synopsis: Convert a TGUID to a string representation.

Declaration:

```
function GUIDToString(const GUID: TGUID) : String
```

Visibility: default

Description: GUIDToString converts the GUID identifier in GUID to a string representation in the form

```
{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}
```

Where each X is a hexadecimal digit.

Errors: None.

See also: Supports ([1400](#)), #rtl.system.TGUID ([1100](#)), StringToGUID ([1385](#)), IsEqualGuid ([1369](#))

30.12.134 HookSignal

Synopsis: Hook a specified signal

Declaration:

```
procedure HookSignal(RtlSigNum: Integer)
```

Visibility: default

Description: This function is declared for Kylix compatibility, but is not implemented.

30.12.135 IncludeTrailingBackslash

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration: `function IncludeTrailingBackslash(const Path: String) : String`

Visibility: default

Description: `IncludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `IncludeTrailingPathDelimiter` (1366) instead.

See also: `IncludeTrailingPathDelimiter` (1366), `ExcludeTrailingPathDelimiter` (1332), `PathDelim` (1288), `IsPathDelimiter` (1370)

30.12.136 IncludeTrailingPathDelimiter

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration: `function IncludeTrailingPathDelimiter(const Path: String) : String`

Visibility: default

Description: `IncludeTrailingPathDelimiter` adds a trailing path delimiter character (`PathDelim` (1288)) to `Path` if none is present yet, and returns the result. If `Path` is empty, nothing is added.

See also: `IncludeTrailingBackslash` (1366), `ExcludeTrailingPathDelimiter` (1332), `PathDelim` (1288), `IsPathDelimiter` (1370)

30.12.137 IncMonth

Synopsis: Increases the month in a `TDateTime` value with a given amount.

Declaration: `function IncMonth(const DateTime: TDateTime; NumberOfMonths: Integer) : TDateTime`

Visibility: default

Description: `IncMonth` increases the month number in `DateTime` with `NumberOfMonths`. It wraps the result as to get a month between 1 and 12, and updates the year accordingly. `NumberOfMonths` can be negative, and can be larger than 12 (in absolute value).

Errors: None.

See also: `Date` (1320), `Time` (1402), `Now` (1374)

Listing: `./sysutex/ex15.pp`

Program `Example15;`

{ This program demonstrates the IncMonth function }

Uses `sysutils;`

Var `ThisDay : TDateTime;`

Begin

`ThisDay := Date;`

`WriteLn ('ThisDay : ', DateToStr (ThisDay));`

`WriteLn ('6 months ago : ', DateToStr (IncMonth (ThisDay , -6)));`

```

WriteLn ( '6 months from now : ' , DateToStr(IncMonth(ThisDay,6)));
WriteLn ( '12 months ago : ' , DateToStr(IncMonth(ThisDay,-12)));
WriteLn ( '12 months from now : ' , DateToStr(IncMonth(ThisDay,12)));
WriteLn ( '18 months ago : ' , DateToStr(IncMonth(ThisDay,-18)));
WriteLn ( '18 months from now : ' , DateToStr(IncMonth(ThisDay,18)));
End.

```

30.12.138 InquireSignal

Synopsis: Check whether a signal handler is set

Declaration: `function InquireSignal(RtlSigNum: Integer) : TSignalState`

Visibility: default

Description: This function is declared for Kylix compatibility, but is not implemented.

30.12.139 InterLockedDecrement

Synopsis: Thread-safe integer decrement

Declaration: `function InterLockedDecrement(var Target: LongInt) : LongInt`

Visibility: default

Description: `InterLockedDecrement` decrements `Target` in a thread-safe way, and returns the new value of `Target`

See also: `InterlockedIncrement` ([1368](#)), `InterlockedExchange` ([1367](#)), `InterlockedExchangeAdd` ([1367](#))

30.12.140 InterLockedExchange

Synopsis: Thread-safe exchange of 2 values.

Declaration: `function InterLockedExchange(var Target: LongInt; Source: LongInt) : LongInt`

Visibility: default

Description: `InterlockedDecrement` replaces `Target` with `Source` in a thread-safe way, and returns the old value of `Target`

See also: `InterlockedIncrement` ([1368](#)), `InterlockedDecrement` ([1367](#)), `InterlockedExchange` ([1367](#)), `InterlockedExchangeAdd` ([1367](#))

30.12.141 InterLockedExchangeAdd

Synopsis: Thread-safe exchange of 2 values

Declaration: `function InterLockedExchangeAdd(var Target: LongInt; Source: LongInt) : LongInt`

Visibility: default

Description: `InterlockedDecrement` adds to `Target` the value of `Source` in a thread-safe way, and returns the old value of `Target`

See also: `InterlockedIncrement` ([1368](#)), `InterlockedDecrement` ([1367](#)), `InterlockedExchange` ([1367](#))

30.12.142 InterLockedIncrement

Synopsis: Thread-safe integer increment.

Declaration: `function InterLockedIncrement (var Target: LongInt) : LongInt`

Visibility: default

Description: `InterLockedIncrement` increments `Target` in a thread-safe way, and returns the new value of `Target`

See also: `InterlockedDecrement` ([1367](#)), `InterlockedExchange` ([1367](#)), `InterlockedExchangeAdd` ([1367](#))

30.12.143 IntToHex

Synopsis: Convert an integer value to a hexadecimal string.

Declaration: `function IntToHex (Value: Integer; Digits: Integer) : String`
`function IntToHex (Value: Int64; Digits: Integer) : String`

Visibility: default

Description: `IntToHex` converts `Value` to a hexadecimal string representation. The result will contain at least `Digits` characters. If `Digits` is less than the needed number of characters, the string will NOT be truncated. If `Digits` is larger than the needed number of characters, the result is padded with zeroes.

Errors: None.

See also: `IntToStr` ([1368](#))

Listing: `./sysutex/ex73.pp`

Program `Example73;`

{ This program demonstrates the IntToHex function }

Uses `sysutils;`

Var `I : longint;`

Begin

For `I:=0 to 31 do`

begin

WriteLn (`IntToHex(1 shl I,8)`);

WriteLn (`IntToHex(15 shl I,8)`)

end;

End.

30.12.144 IntToStr

Synopsis: Convert an integer value to a decimal string.

Declaration: `function IntToStr (Value: Integer) : String`
`function IntToStr (Value: Int64) : String`
`function IntToStr (Value: QWord) : String`

Visibility: default

Description: `IntToStr` converts `Value` to its string representation. The resulting string has only as much characters as needed to represent the value. If the value is negative a minus sign is prepended to the string.

Errors: None.

See also: `IntToHex` ([1368](#)), `StrToInt` ([1396](#))

Listing: `./sysutex/ex74.pp`

Program `Example74`;

{ This program demonstrates the `IntToStr` function }

Uses `sysutils`;

Var `I` : `longint`;

Begin

For `I:=0` to `31` **do**

begin

Writeln (`IntToStr(1 shl I)`);

Writeln (`IntToStr(15 shl I)`);

end;

End.

30.12.145 IsDelimiter

Synopsis: Check whether a given string is a delimiter character.

Declaration: `function IsDelimiter(const Delimiters: String;const S: String;
 Index: Integer) : Boolean`

Visibility: `default`

Description: `IsDelimiter` checks whether the `Index`-th character in the string `S` is a delimiter character as passed in `Delimiters`. If `Index` is out of range, `False` is returned.

Errors: None.

See also: `LastDelimiter` ([1371](#))

30.12.146 IsEqualGUID

Synopsis: Check whether two `TGUID` variables are equal.

Declaration: `function IsEqualGUID(const guid1: TGUID;const guid2: TGUID) : Boolean`

Visibility: `default`

Description: `IsEqualGUID` checks whether `guid1` and `guid2` are equal, and returns `True` if this is the case, or `False` otherwise.

Errors:

See also: `Supports` ([1400](#)), `#rtl.system.TGUID` ([1100](#)), `StringToGUID` ([1385](#)), `GuidToString` ([1365](#))

30.12.147 IsLeapYear

Synopsis: Determine whether a year is a leap year.

Declaration: `function IsLeapYear(Year: Word) : Boolean`

Visibility: default

Description: `IsLeapYear` returns `True` if `Year` is a leap year, `False` otherwise.

Errors: None.

See also: `IncMonth` ([1366](#)), `Date` ([1320](#))

Listing: `./sysutex/ex16.pp`

Program `Example16;`

{ This program demonstrates the IsLeapYear function }

Uses `sysutils;`

Var `YY,MM,dd : Word;`

Procedure `TestYear (Y : Word);`

begin

`WriteLn (Y, ' is leap year : ', IsLeapYear(Y));`
end;

Begin

`DeCodeDate (Date, YY,mm,dd);`
`TestYear(yy);`
`TestYear(2000);`
`TestYear(1900);`
`TestYear(1600);`
`TestYear(1992);`
`TestYear(1995);`

End.

30.12.148 IsPathDelimiter

Synopsis: Is the character at the given position a pathdelimiter ?

Declaration: `function IsPathDelimiter(const Path: String;Index: Integer) : Boolean`

Visibility: default

Description: `IsPathDelimiter` returns `True` if the character at position `Index` equals `PathDelim` ([1288](#)), i.e. if it is a path delimiter character for the current platform.

Errors: `IncludeTrailingPathDelimiter` ([1366](#))`ExcludeTrailingPathDelimiter` ([1332](#))`PathDelim` ([1288](#))

30.12.149 IsValidIdent

Synopsis: Check whether a string is a valid identifier name.

Declaration: `function IsValidIdent(const Ident: String) : Boolean`

Visibility: default

Description: IsValidIdent returns True if Ident can be used as a component name. It returns False otherwise. Ident must consist of a letter or underscore, followed by a combination of letters, numbers or underscores to be a valid identifier.

Errors: None.

Listing: ./sysutex/ex75.pp

Program Example75;

```
{ This program demonstrates the IsValidIdent function }
```

Uses `sysutils`;

```
Procedure Testit (S : String);
```

begin

Write (' " ' , S , ' " is ');

If not IsValidIdent(S) then

```
Write ( 'NOT' );
```

```
WriteIn ( 'a valid identifier');
```

end ;

Begin

```
Testit ( '_MyObj' );
```

```
Testit ( 'My_Obj1' );
```

```
Testit ( 'My_1_Obj' );
```

```
Testit ( '1MyObject' );
```

```
Testit ( 'My@Object' );
```

```
Testit ( 'M123' );
```

End.

30.12.150 LastDelimiter

Synopsis: Return the last occurrence of a set of delimiters in a string.

```
Declaration: function LastDelimiter(const Delimiters: String; const S: String)
                                     : Integer
```

Visibility: default

Description: LastDelimiter returns the *last* occurrence of any character in the set Delimiters in the string S.

Errors:

Listing: ./sysutex/ex88.pp

Program example88;

```
{ This program demonstrates the LastDelimiter function }
```

```
uses SysUtils;
```

begin

```
WriteIn (LastDelimiter ( '\.: ', 'c:\filename.ext' ));
```

end.

30.12.151 LeftStr

Synopsis: Return a number of characters starting at the left of a string.

Declaration: `function LeftStr(const S: String; Count: Integer) : String`

Visibility: default

Description: `LeftStr` returns the `Count` leftmost characters of `S`. It is equivalent to a call to `Copy (S, 1, Count)`.

Errors: None.

See also: `RightStr` ([1376](#)), `TrimLeft` ([1405](#)), `TrimRight` ([1405](#)), `Trim` ([1404](#))

Listing: `./sysutex/ex76.pp`

Program `Example76;`

{ This program demonstrates the LeftStr function }

Uses `sysutils;`

Begin

```
WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ', 20 ));
WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ', 15 ));
WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ', 1 ));
WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ', 200 ));
```

End.

30.12.152 LoadStr

Synopsis: Load a string from the resource tables.

Declaration: `function LoadStr(Ident: Integer) : String`

Visibility: default

Description: This function is not yet implemented. resources are not yet supported.

Errors:

30.12.153 LowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function LowerCase(const s: String) : String; Overload`
`function LowerCase(const V: variant) : String; Overload`

Visibility: default

Description: `LowerCase` returns the lowercase equivalent of `S`. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the lowercase function of the system unit, and is provided for compatibility only.

Errors: None.

See also: `AnsiLowerCase` ([1302](#)), `UpperCase` ([1409](#)), `AnsiUpperCase` ([1310](#))

Listing: `./sysutex/ex77.pp`

Program Example77;

{ This program demonstrates the LowerCase function }

Uses sysutils;

Begin

WriteLn (**LowerCase**('THIS WILL COME out all LoWeRcAsE !'));

End.

30.12.154 MSecsToTimeStamp

Synopsis: Convert a number of milliseconds to a TDateTime value.

Declaration: function MSecsToTimeStamp(MSecs: Comp) : TTimeStamp

Visibility: default

Description: MSecsToTimeStamp converts the given number of milliseconds to a TTimeStamp date/time notation.

Use TTimeStamp variables if you need to keep very precise track of time.

Errors: None.

See also: TimeStampToMSecs ([1403](#)), DateTimeToTimeStamp ([1323](#))

Listing: ./sysutex/ex17.pp

Program Example17;

{ This program demonstrates the MSecsToTimeStamp function }

Uses sysutils;

Var MS : Comp;

 TS : TTimeStamp;

 DT : TDateTime;

Begin

 TS:=DateTimeToTimeStamp(**Now**);

WriteLn ('Now in days since 1/1/0001 : ',TS.**Date**);

WriteLn ('Now in millisecs since midnight : ',TS.**Time**);

 MS:=TimeStampToMSecs(TS);

WriteLn ('Now in millisecs since 1/1/0001 : ',MS);

 MS:=MS-1000*3600*2;

 TS:=MSecsToTimeStamp(MS);

 DT:=TimeStampToDateTime(TS);

WriteLn ('Now minus 1 day : ',**DateTimeToStr**(DT));

End.

30.12.155 NewStr

Synopsis: Allocate a new ansistring on the heap.

Declaration: function NewStr(const S: String) : PString

Visibility: default

Description: `NewStr` assigns a new dynamic string on the heap, copies `S` into it, and returns a pointer to the newly assigned string.

This function is obsolete, and shouldn't be used any more. The `AnsiString` mechanism also allocates ansistrings on the heap, and should be preferred over this mechanism.

For an example, see `AssignStr` (1312).

Errors: If not enough memory is present, an `EOutOfMemory` exception will be raised.

See also: `AssignStr` (1312), `DisposeStr` (1328)

30.12.156 Now

Synopsis: Returns the current date and time.

Declaration: `function Now : TDateTime`

Visibility: default

Description: `Now` returns the current date and time. It is equivalent to `Date+Time`.

Errors: None.

See also: `Date` (1320), `Time` (1402)

Listing: `./sysutex/ex18.pp`

Program `Example18;`

{ This program demonstrates the Now function }

Uses `sysutils;`

Begin

`WriteLn ('Now : ', DateTimeToStr(Now));`

End.

30.12.157 OutOfMemoryError

Synopsis: Raise an `EOutOfMemory` exception

Declaration: `procedure OutOfMemoryError`

Visibility: default

Description: `OutOfMemoryError` raises an `EOutOfMemory` (1416) exception, with an exception object that has been allocated on the heap at program startup. The program should never create an `EOutOfMemory` (1416) exception, but always call this routine.

See also: `EOutOfMemory` (1416)

30.12.158 QuotedStr

Synopsis: Return a quotes version of a string.

Declaration: `function QuotedStr(const S: String) : String`

Visibility: default

Description: `QuotedStr` returns the string `S`, quoted with single quotes. This means that `S` is enclosed in single quotes, and every single quote in `S` is doubled. It is equivalent to a call to `AnsiQuotedStr(S, '"')`.

Errors: None.

See also: `AnsiQuotedStr` (1304), `AnsiExtractQuotedStr` (1301)

Listing: `./sysutex/ex78.pp`

Program `Example78`;

{ This program demonstrates the QuotedStr function }

Uses `sysutils`;

Var `S : AnsiString`;

Begin

`S := 'He said ''Hello'' and walked on';`

`Writeln (S);`

`Writeln (' becomes');`

`Writeln (QuotedStr(S));`

End.

30.12.159 RaiseLastError

Synopsis: Raise an exception with the last Operating System error code.

Declaration: `procedure RaiseLastError`

Visibility: default

Description: `RaiseLastError` raises an `EOSError` (1416) exception with the error code returned by `GetLastError`. If the Error code is nonzero, then the corresponding error message will be returned. If the error code is zero, a standard message will be returned.

Errors: This procedure may not be implemented on all platforms. If it is not, then a normal Exception (1418) will be raised.

See also: `EOSError` (1416), `GetLastError` (1364), Exception (1418)

30.12.160 RemoveDir

Synopsis: Remove a directory from the filesystem.

Declaration: `function RemoveDir(const Dir: String) : Boolean`

Visibility: default

Description: `RemoveDir` removes directory `Dir` from the disk. If the directory is not absolute, it is appended to the current working directory.

For an example, see `CreateDir` (1318).

Errors: In case of error (e.g. the directory isn't empty) the function returns `False`. If successful, `True` is returned.

30.12.161 `RenameFile`

Synopsis: Rename a file.

Declaration: `function RenameFile(const OldName: String;const NewName: String) : Boolean`

Visibility: default

Description: `RenameFile` renames a file from `OldName` to `NewName`. The function returns `True` if successful, `False` otherwise. *Remark:* you cannot rename across disks or partitions.

Errors: On Error, `False` is returned.

See also: `DeleteFile` (1326)

Listing: `./sysutex/ex44.pp`

Program `Example44`;

{ This program demonstrates the RenameFile function }

Uses `sysutils`;

Var `F` : `Longint`;
 `S` : **`String`**;

Begin

`S := 'Some short file.'`;
 `F := FileCreate ('test.dap')`;
 `FileWrite(F,S[1],Length(S))`;
 `FileClose(F)`;
 If `RenameFile ('test.dap', 'test.dat')` **then**
 `Writeln ('Successfully renamed files.'`);
End.

30.12.162 `RightStr`

Synopsis: Return a number of characters from a string, starting at the end.

Declaration: `function RightStr(const S: String;Count: Integer) : String`

Visibility: default

Description: `RightStr` returns the `Count` rightmost characters of `S`. It is equivalent to a call to `Copy (S, Length (S) + 1 - Count, Count)`.
 If `Count` is larger than the actual length of `S` only the real length will be used.

Errors: None.

See also: `LeftStr` (1372), `Trim` (1404), `TrimLeft` (1405), `TrimRight` (1405)

Listing: ./sysutex/ex79.pp

Program Example79;

{ This program demonstrates the RightStr function }

Uses sysutils;

Begin

WriteLn (RightStr('abcdefghijklmnopqrstuvwxyz',20));

WriteLn (RightStr('abcdefghijklmnopqrstuvwxyz',15));

WriteLn (RightStr('abcdefghijklmnopqrstuvwxyz',1));

WriteLn (RightStr('abcdefghijklmnopqrstuvwxyz',200));

End.

30.12.163 SameFileName

Synopsis: Are two filenames referring to the same file ?

Declaration: function SameFileName(const S1: String;const S2: String) : Boolean

Visibility: default

Description: SameFileName returns True if calling AnsiCompareFileName ([1299](#)) with arguments S1 and S2 returns 0, and returns False otherwise.

Errors: None.

See also: AnsiCompareFileName ([1299](#))

30.12.164 SameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: function SameText(const s1: String;const s2: String) : Boolean

Visibility: default

Description: SameText calls CompareText ([1317](#)) with S1 and S2 as parameters and returns True if the result of that call is zero, or False otherwise.

Errors: None.

See also: CompareText ([1317](#)), AnsiSameText ([1304](#)), AnsiSameStr ([1304](#))

30.12.165 SetCurrentDir

Synopsis: Set the current directory of the application.

Declaration: function SetCurrentDir(const NewDir: String) : Boolean

Visibility: default

Description: SetCurrentDir sets the current working directory of your program to NewDir. It returns True if the function was successful, False otherwise.

Errors: In case of error, False is returned.

See also: GetCurrentDir ([1361](#))

30.12.166 SetDirSeparators

Synopsis: Set the directory separators to the known directory separators.

Declaration: `function SetDirSeparators(const FileName: String) : String`

Visibility: default

Description: `SetDirSeparators` returns `FileName` with all possible `DirSeparators` replaced by `OSDirSeparator`.

Errors: None.

See also: `ExpandFileName` ([1332](#)), `ExtractFilePath` ([1335](#)), `ExtractFileDir` ([1333](#))

Listing: `./sysutex/ex47.pp`

Program `Example47;`

{ This program demonstrates the SetDirSeparators function }

Uses `sysutils;`

Begin

`WriteLn (SetDirSeparators (' /pp\bin /win32\ppc386 '));`

End.

30.12.167 ShowException

Synopsis: Show the current exception to the user.

Declaration: `procedure ShowException(ExceptObject: TObject; ExceptAddr: Pointer)`

Visibility: default

Description: `ShowException` shows a message stating that a `ExceptObject` was raised at address `ExceptAddr`.

It uses `ExceptionErrorMessage` ([1331](#)) to create the message, and is aware of the fact whether the application is a console application or a GUI application. For a console application, the message is written to standard error output. For a GUI application, `OnShowException` ([1297](#)) is executed.

Errors: If, for a GUI application, `OnShowException` ([1297](#)) is not set, no message will be displayed to the user.

The exception message can be at most 255 characters long: It is possible that no memory can be allocated on the heap, so ansistrings are not available, so a shortstring is used to display the message.

See also: `ExceptObject` ([1331](#)), `ExceptAddr` ([1330](#)), `ExceptionErrorMessage` ([1331](#))

30.12.168 Sleep

Synopsis: Suspend execution of a program for a certain time.

Declaration: `procedure Sleep(milliseconds: Cardinal)`

Visibility: default

Description: `Sleep` suspends the execution of the program for the specified number of milliseconds (`milliseconds`).

After the specified period has expired, program execution resumes.

Remark: The indicated time is not exact, i.e. it is a minimum time. No guarantees are made as to the exact duration of the suspension.

30.12.169 SScanf

Synopsis: Scan a string for substrings and return the substrings

Declaration: `function SScanf(const s: String; const fmt: String;
const Pointers: Array[] of Pointer) : Integer`

Visibility: default

Description: `SScanF` scans the string `S` for the elements specified in `Fmt`, and returns the elements in the pointers in `Pointers`. The `Fmt` can contain placeholders of the form `%X` where `X` can be one of the following characters:

dPlaceholder for a decimal number.

fPlaceholder for a floating point number (an extended)

sPlaceholder for a string of arbitrary length.

cPlaceholder for a single character

The `Pointers` array contains a list of pointers, each pointer should point to a memory location of a type that corresponds to the type of placeholder in that position:

dA pointer to an integer.

fA pointer to an extended.

sA pointer to an ansistring.

cA pointer to a single character.

Errors: No error checking is performed on the type of the memory location.

See also: `Format` ([1352](#))

30.12.170 StrAlloc

Synopsis: Allocate a null-terminated string on the heap.

Declaration: `function StrAlloc(Size: cardinal) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Additionally, `StrAlloc` allocates 4 extra bytes to store the size of the allocated memory. Therefore this function is NOT compatible with the `StrAlloc` ([1379](#)) function of the `Strings` unit.

For an example, see `StrBufSize` ([1380](#)).

Errors: None.

See also: `StrBufSize` ([1380](#)), `StrDispose` ([1382](#)), `StrAlloc` ([1379](#))

30.12.171 StrBufSize

Synopsis: Return the size of a null-terminated string allocated on the heap.

Declaration: `function StrBufSize(Str: PChar) : SizeUInt`

Visibility: default

Description: `StrBufSize` returns the memory allocated for `Str`. This function ONLY gives the correct result if `Str` was allocated using `StrAlloc` (1379).

Errors: If no more memory is available, a runtime error occurs.

See also: `StrAlloc` (1379), `StrDispose` (1382)

Listing: `./sysutex/ex46.pp`

Program `Example46`;

```
{ This program demonstrates the StrBufSize function }
{$H+}
```

Uses `sysutils`;

Const `S = 'Some nice string'`;

Var `P : Pchar`;

Begin

```
P:=StrAlloc (Length(S)+1);
```

```
StrPCopy(P,S);
```

```
Write (P, ' has length ',length(S));
```

```
WriteLn (' and buffer size ',StrBufSize(P));
```

```
StrDispose(P);
```

```
End.
```

30.12.172 StrByteType

Synopsis: Return the type of byte in a null-terminated string for a multi-byte character set

Declaration: `function StrByteType(Str: PChar;Index: Cardinal) : TmbcsByteType`

Visibility: default

Description: `StrByteType` returns the type of byte in the null-terminated string `Str` at (0-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TmbcsByteType` (1294), `ByteType` (1314)

30.12.173 strcat

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: pchar;source: pchar) : pchar`

Visibility: default

Description: Attaches Source to Dest and returns Dest.

Errors: No length checking is performed.

See also: StrLCat ([1386](#))

Listing: ./stringex/ex11.pp

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin

 P2:= StrAlloc (StrLen(P1)*2+1);

 StrMove (P2,P1, StrLen(P1)+1); { P2=P1 }

 StrCat (P2,P1); { Append P2 once more }

 Writeln ('P2 : ',P2);

 StrDispose(P2);

end.

30.12.174 StrCharLength

Synopsis: Return the length of a null-terminated string in characters.

Declaration: function StrCharLength(const Str: PChar) : Integer

Visibility: default

Description: StrCharLength returns the length of the null-terminated string Str (a widestring) in characters (not in bytes). It uses the widestringmanager to do this.

30.12.175 strcomp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: function strcomp(str1: pchar;str2: pchar) : SizeInt

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrLComp ([1386](#)).

Errors: None.

See also: StrLComp ([1386](#)), StrIComp ([1384](#)), StrLComp ([1389](#))

30.12.176 strcpy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: pchar;source: pchar) : pchar`

Visibility: default

Description: Copy the null terminated string in `Source` to `Dest`, and returns a pointer to `Dest`. `Dest` needs enough room to contain `Source`, i.e. `StrLen(Source)+1` bytes.

Errors: No length checking is performed.

See also: `StrPCopy` ([1391](#)), `StrLCopy` ([1387](#)), `StrECopy` ([1383](#))

Listing: `./stringex/ex4.pp`

Program `Example4`;

Uses `strings`;

{ Program to demonstrate the StrCopy function. }

Const `P : PChar = 'This is a PCHAR string.'`;

var `PP : PChar`;

begin

`PP:= StrAlloc (StrLen(P)+1);`

`StrCopy (PP,P);`

If `StrComp (PP,P)<>0` **then**

`Writeln ('Oh-oh problems ... ')`

else

`Writeln ('All is well : PP=',PP);`

`StrDispose(PP);`

end.

30.12.177 StrDispose

Synopsis: Dispose of a null-terminated string on the heap.

Declaration: `procedure StrDispose(Str: PChar)`

Visibility: default

Description: `StrDispose` frees any memory allocated for `Str`. This function will only function correctly if `Str` has been allocated using `StrAlloc` ([1379](#)) from the `SysUtils` unit.

For an example, see `StrBufSize` ([1380](#)).

Errors: If an invalid pointer is passed, or a pointer not allocated with `StrAlloc`, an error may occur.

See also: `StrBufSize` ([1380](#)), `StrAlloc` ([1379](#)), `StrDispose` ([1382](#))

30.12.178 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy(dest: pchar; source: pchar) : pchar`

Visibility: default

Description: Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` ([1387](#)), `StrCopy` ([1382](#))

Listing: `./stringex/ex6.pp`

Program Example6;

Uses strings;

{ Program to demonstrate the StrECopy function. }

Const P : PChar = 'This is a PCHAR string.';

Var PP : PChar;

begin

PP:=StrAlloc (StrLen(P)+1);

If Longint(StrECopy(PP,P)) – Longint(PP) <> StrLen(P) **then**

Writeln ('Something is wrong here !')

else

Writeln ('PP= ',PP);

StrDispose(PP);

end.

30.12.179 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the end of P. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1388](#))

Listing: `./stringex/ex7.pp`

Program Example6;

Uses strings;

{ Program to demonstrate the StrEnd function. }

Const P : PChar = 'This is a PCHAR string.';

```
begin
  If Longint(StrEnd(P)) - Longint(P) <> StrLen(P) then
    Writeln('Something is wrong here !')
  else
    Writeln('All is well..');
end.
```

30.12.180 StrFmt

Synopsis: Format a string with given arguments, store the result in a buffer.

Declaration: `function StrFmt(Buffer: PChar;Fmt: PChar;const args: Array[] of const) : Pchar`

Visibility: default

Description: `StrFmt` will format `fmt` with `Args`, as the `Format` (1352) function does, and it will store the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain the whole result.

Errors: for a list of errors, see `Format` (1352).

See also: `StrLFmt` (1388), `FmtStr` (1351), `Format` (1352), `FormatBuf` (1357)

Listing: `./sysutex/ex80.pp`

Program `Example80`;

{ This program demonstrates the StrFmt function }

Uses `sysutils`;

Var `S` : `AnsiString`;

Begin

`SetLength(S,80)`;

`Writeln (StrFmt (@S[1], 'For some nice examples of fomattng see %s.', ['Format']))`;

End.

30.12.181 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: pchar;str2: pchar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings `S1` and `S2`, ignoring case. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

Errors: None.

See also: StrLComp ([1386](#)), StrComp ([1381](#)), StrLComp ([1389](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
 P2 : PChar = 'This is the second string.';

Var L : Longint;

begin

Write ('P1 and P2 are ');
 If StrComp (P1,P2)<>0 **then write** ('NOT ');
 write ('equal. The first ');
 L:=1;
 While StrLComp(P1,P2,L)=0 **do inc** (L);
 dec(L);
 Writeln (L, ' characters are the same.');

end.

30.12.182 StringReplace

Synopsis: Replace occurrences of one substring with another in a string.

Declaration: function StringReplace(const S: String;const OldPattern: String;
 const NewPattern: String;Flags: TReplaceFlags)
 : String

Visibility: default

Description: StringReplace searches the string S for occurrences of the string OldPattern and, if it is found, replaces it with NewPattern. It returns the resulting string. The behaviour of StringReplace can be runed with Flags, which is of type TReplaceFlags ([1294](#)). Standard behaviour is to replace only the first occurrence of OldPattern, and to search case sensitively.

Errors: None.

See also: TReplaceFlags ([1294](#))

30.12.183 StringToGUID

Synopsis: Convert a string to a native TGUID type.

Declaration: function StringToGUID(const S: String) : TGUID

Visibility: default

Description: StringToGUID converts the string S to a valid GUID. The string S should be of the form

{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}

Where each X is a hexadecimal digit. The dashes and braces are required.

Errors: In case *S* contains an invalid GUID representation, a `EConvertError` ([1413](#)) exception is raised.

See also: `Supports` ([1400](#)), `#rtl.system.TGUID` ([1100](#)), `GUIDToString` ([1365](#)), `IsEqualGuid` ([1369](#))

30.12.184 `strlcat`

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Adds `MaxLen` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

Errors: None.

See also: `StrCat` ([1380](#))

Listing: `./stringex/ex12.pp`

Program `Example12;`

Uses `strings;`

{ Program to demonstrate the StrLCat function. }

Const `P1 : PChar = '1234567890';`

Var `P2 : PChar;`

begin

`P2:= StrAlloc (StrLen(P1)*2+1);`

`P2^:=#0; { Zero length }`

`StrCat (P2,P1);`

`StrLCat (P2,P1,5);`

`Writeln ('P2 = ',P2);`

`StrDispose(P2)`

end.

30.12.185 `strlcomp`

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum `L` characters of the null-terminated strings `S1` and `S2`. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

Errors: None.

See also: `StrComp` ([1381](#)), `StrIComp` ([1384](#)), `StrLComp` ([1389](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
 P2 : PChar = 'This is the second string.';

Var L : Longint;

begin
 Write ('P1 and P2 are ');
 If StrComp (P1,P2)<>0 **then write** ('NOT ');
 write ('equal. The first ');
 L:=1;
 While StrLComp(P1,P2,L)=0 **do inc** (L);
 dec(L);
 WriteLn (L, ' characters are the same.');

end.

30.12.186 strcpy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: function strcpy(dest: pchar;source: pchar;maxlen: SizeInt) : pchar

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([1382](#)), StrECopy ([1383](#))

Listing: ./stringex/ex5.pp

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
 PP:=StrAlloc(11);
 WriteLn ('First 10 characters of P : ',StrLCopy (PP,P,10));
 StrDispose(PP);
end.

30.12.187 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: pchar) : sizeint`

Visibility: default

Description: Returns the length of the null-terminated string P.

Errors: None.

See also: StrNew ([1390](#))

Listing: ./stringex/ex1.pp

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin

WriteLn ('P : ',p);

WriteLn ('length(P) : ',StrLen(P));

end.

30.12.188 StrLFmt

Synopsis: Format a string with given arguments, but with limited length.

Declaration: `function StrLFmt(Buffer: PChar;Maxlen: Cardinal;Fmt: PChar;
 const args: Array[] of const) : Pchar`

Visibility: default

Description: StrLFmt will format fmt with Args, as the Format ([1352](#)) function does, and it will store maximally Maxlen characters of the result in Buffer. The function returns Buffer. Buffer should point to enough space to contain MaxLen characters.

Errors: for a list of errors, see Format ([1352](#)).

See also: StrFmt ([1384](#)), FmtStr ([1351](#)), Format ([1352](#)), FormatBuf ([1357](#))

Listing: ./sysutex/ex81.pp

Program Example80;

{ This program demonstrates the StrFmt function }

Uses sysutils;

Var S : AnsiString;

Begin

 SetLength(S,80);

WriteLn (**StrLFmt** (@S[1],80,'For some nice examples of fomatting see %s.',['Format']));

End.

30.12.189 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrIComp ([1384](#))

Errors: None.

See also: StrLComp ([1386](#)), StrComp ([1381](#)), StrIComp ([1384](#))

30.12.190 strlower

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: StrUpper ([1399](#))

Listing: ./stringex/ex14.pp

Program Example14;

Uses strings;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';
P2 : PChar = 'this is a lowercase string';

begin

 WriteLn ('Uppercase : ',StrUpper(P2));

 StrLower (P1);

 WriteLn ('Lowercase : ',P1);

end.

30.12.191 strmove

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: `StrLCopy` ([1387](#)), `StrCopy` ([1382](#))

Listing: `./stringex/ex10.pp`

Program `Example10;`

Uses `strings;`

{ Program to demonstrate the StrMove function. }

Const `P1 : PCHAR = 'This is a pchar string.';`

Var `P2 : Pchar;`

begin

`P2:= StrAlloc (StrLen(P1)+1);`

`StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }`

`WriteLn ('P2 = ',P2);`

`StrDispose(P2);`

end.

30.12.192 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: pchar) : pchar`

Visibility: default

Description: Copies `P` to the Heap, and returns a pointer to the copy.

Errors: Returns `Nil` if no memory was available for the copy.

See also: `StrCopy` ([1382](#)), `StrDispose` ([1382](#))

Listing: `./stringex/ex16.pp`

Program `Example16;`

Uses `strings;`

{ Program to demonstrate the StrNew function. }

Const `P1 : PChar = 'This is a PChar string';`

```

var P2 : PChar;

begin
  P2:=StrNew (P1);
  If P1=P2 then
    writeln ( 'This can''t be happening ... ')
  else
    writeln ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

30.12.193 StrPas

Synopsis: Convert a null-terminated string to an ansistring.

Declaration: `function StrPas(Str: PChar) : String`

Visibility: default

Description: Converts a null terminated string in `Str` to an `Ansistring`, and returns this string. This string is NOT truncated at 255 characters as is the

Errors: None.

See also: `StrPCopy` ([1391](#)), `StrPLCopy` ([1391](#))

30.12.194 StrPCopy

Synopsis: Copy an ansistring to a null-terminated string.

Declaration: `function StrPCopy(Dest: PChar;Source: String) : PChar`

Visibility: default

Description: `StrPCopy` Converts the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `Source`.

See also: `StrPLCopy` ([1391](#)), `StrPas` ([1391](#))

30.12.195 StrPLCopy

Synopsis: Copy a limited number of characters from an ansistring to a null-terminated string.

Declaration: `function StrPLCopy(Dest: PChar;Source: String;MaxLen: SizeUInt) : PChar`

Visibility: default

Description: `StrPLCopy` Converts maximally `MaxLen` characters of the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the characters.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `L` characters of `Source`.

See also: `StrPCopy` ([1391](#))

30.12.196 strpos

Synopsis: Find position of one null-terminated substring in another.

Declaration: `function strpos(str1: pchar; str2: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1392](#)), StrRScan ([1392](#))

Listing: ./stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';

 S : Pchar = 'is';

begin

WriteLn ('Position of ''is'' in P : ', longint(**StrPos**(P,S)) - Longint(P));

end.

30.12.197 strrscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strrscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan ([1392](#)).

Errors: None.

See also: StrScan ([1392](#)), StrPos ([1392](#))

30.12.198 strscan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan ([1392](#)), StrPos ([1392](#))

Listing: ./stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const P : PChar = 'This is a PCHAR string.';
 S : Char = 's' ;

begin

WriteLn ('P, starting from first 's' : ', **StrScan**(P,s));

WriteLn ('P, starting from last 's' : ', **StrRScan**(P,s));

end.

30.12.199 StrToBool

Synopsis: Convert a string to a boolean value

Declaration: function StrToBool(const S: String) : Boolean

Visibility: default

Description: StrToBool will convert the string S to a boolean value. The string S can contain one of 'True', 'False' (case is ignored) or a numerical value. If it contains a numerical value, 0 is converted to False, all other values result in True. If the string S contains no valid boolean, then an EConvertError (1413) exception is raised.

Errors: On error, an EConvertError (1413) exception is raised.

See also: BoolToStr (1313)

30.12.200 StrToCurr

Synopsis: Convert a string to a currency value

Declaration: function StrToCurr(const S: String) : Currency

Visibility: default

Description: StrToCurr converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, an EConvertError (1413) exception is raised.

Errors: On error, an EConvertError (1413) exception is raised.

See also: CurrToStr (1319), StrToCurrDef (1393)

30.12.201 StrToCurrDef

Synopsis: Convert a string to a currency value, using a default value

Declaration: function StrToCurrDef(const S: String; Default: Currency) : Currency

Visibility: default

Description: `StrToCurrDef` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, the fallback `Default` value is returned.

Errors: On error, the `Default` value is returned.

See also: `CurrToStr` ([1319](#)), `StrToCurr` ([1393](#))

30.12.202 StrToDate

Synopsis: Convert a date string to a `TDateTime` value.

Declaration: `function StrToDate(const S: String) : TDateTime`

Visibility: default

Description: `StrToDate` converts the string `S` to a `TDateTime` date value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToTime` ([1399](#)), `DateToStr` ([1323](#)), `TimeToStr` ([1403](#))

Listing: `./sysutex/ex19.pp`

Program Example19;

{ This program demonstrates the StrToDate function }

Uses sysutils;

Procedure TestStr (S : String);

begin

 WriteLn (S, ' : ', DateToStr(StrToDate(S)));
end;

Begin

 WriteLn ('ShortDateFormat ', ShortDateFormat);
 TestStr(DateTimeToStr(Date));
 TestStr('05/05/1999');
 TestStr('5/5');
 TestStr('5');
End.

30.12.203 StrToDateTime

Synopsis: Convert a date/time string to a `TDateTime` value.

Declaration: `function StrToDateTime(const S: String) : TDateTime`

Visibility: default

Description: `StrToDateTime` converts the string `S` to a `TDateTime` date and time value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToDate` ([1394](#)), `StrToTime` ([1399](#)), `DateTimeToStr` ([1321](#))

Listing: `./sysutex/ex20.pp`

Program `Example20`;

{ This program demonstrates the StrToDateTime function }

Uses `sysutils`;

Procedure `TestStr (S : String)`;

begin

`WriteLn (S, ' : ', DateTimeToStr(StrToDateTime(S)))`;
end;

Begin

`WriteLn ('ShortDateFormat ', ShortDateFormat)`;
 `TestStr(DateTimeToStr(Now))`;
 `TestStr('05-05-1999 15:50')`;
 `TestStr('5-5 13:30')`;
 `TestStr('5 1:30PM')`;
End.

30.12.204 StrToFloat

Synopsis: Convert a string to a floating-point value.

Declaration: `function StrToFloat(const S: String) : Extended`

Visibility: `default`

Description: `StrToFloat` converts the string `S` to a floating point value. `S` should contain a valid stroing representation of a floating point value (either in decimal or scientific notation). If the string contains a decimal value, then the decimal separator character can either be a `'.'` or the value of the `DecimalSeparator` variable.

Errors: If the string `S` doesn't contain a valid floating point string, then an exception will be raised.

See also: `TextToFloat` ([1401](#)), `FloatToStr` ([1347](#)), `FormatFloat` ([1359](#)), `StrToInt` ([1396](#))

Listing: `./sysutex/ex90.pp`

Program `Example90`;

{ This program demonstrates the StrToFloat function }
{ \$mode objfpc }
{ \$h+ }

```

Uses SysUtils;

Const
  NrValues = 5;
  TestStr : Array[1..NrValues] of string =
    ( '1,1 ', '-0,2 ', '1,2E-4 ', '0 ', '1E4 ' );

Procedure Testit;

Var
  I : Integer;
  E : Extended;

begin
  WriteLn('Using DecimalSeparator : ', DecimalSeparator);
  For I:=1 to NrValues do
    begin
      WriteLn('Converting : ', TestStr[I]);
      Try
        E:=StrToFloat(TestStr[I]);
        WriteLn('Converted value : ', E);
      except
        On E : Exception do
          WriteLn('Exception when converting : ', E.Message);
        end;
      end;
    end;

Begin
  DecimalSeparator:= ',';
  Testit;
  DecimalSeparator:= '.';
  Testit;
End.

```

30.12.205 StrToFloatDef

Synopsis: Convert a string to a float, with a default value.

Declaration: function StrToFloatDef(const S: String; const Default: Extended)
: Extended

Visibility: default

Description: StrToFloatDef tries to convert the string S to a floating point value, and returns this value. If the conversion fails for some reason, the value Default is returned instead.

Errors: None. On error, the Default value is returned.

30.12.206 StrToInt

Synopsis: Convert a string to an integer value.

Declaration: function StrToInt(const s: String) : Integer

Visibility: default

Description: `StrToInt` will convert the string `S` to an integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` is raised.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: In case of error, an `EConvertError` is raised.

See also: `IntToStr` ([1368](#)), `StrToIntDef` ([1398](#))

Listing: `./sysutex/ex82.pp`

Program `Example82`;

```
{ $mode objfpc }

{ This program demonstrates the StrToInt function }

Uses sysutils;

Begin
  Writeln ( StrToInt ( '1234' ) );
  Writeln ( StrToInt ( '-1234' ) );
  Writeln ( StrToInt ( '0' ) );
  Try
    Writeln ( StrToInt ( '12345678901234567890' ) );
  except
    On E : EConvertError do
      Writeln ( 'Invalid number encountered' );
  end;
End.
```

30.12.207 `StrToInt64`

Synopsis: Convert a string to an `Int64` value.

Declaration: `function StrToInt64(const s: String) : Int64`

Visibility: `default`

Description: `StrToInt64` converts the string `S` to a `Int64` value, and returns this value. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: On error, a `EConvertError` ([1413](#)) exception is raised.

See also: `TryStrToInt64` ([1408](#)), `StrToInt64Def` ([1397](#)), `StrToInt` ([1396](#)), `TryStrToInt` ([1408](#)), `StrToIntDef` ([1398](#))

30.12.208 `StrToInt64Def`

Synopsis: Convert a string to an `Int64` value, with a default value

Declaration: `function StrToInt64Def(const S: String; Default: Int64) : Int64`

Visibility: `default`

Description: `StrToInt64Def` tries to convert the string `S` to a `Int64` value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

See also: `StrToInt64` ([1397](#)), `TryStrToInt64` ([1408](#)), `StrToInt` ([1396](#)), `TryStrToInt` ([1408](#)), `StrToIntDef` ([1398](#))

30.12.209 StrToIntDef

Synopsis: Convert a string to an integer value, with a default value.

Declaration: `function StrToIntDef(const S: String; Default: Integer) : Integer`

Visibility: default

Description: `StrToIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: None.

See also: `IntToStr` ([1368](#)), `StrToInt` ([1396](#))

Listing: `./sysutex/ex83.pp`

Program `Example82;`

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

Uses `sysutils;`

Begin

`Writeln (StrToIntDef ('1234' , 0));`

`Writeln (StrToIntDef ('-1234' , 0));`

`Writeln (StrToIntDef ('0' , 0));`

`Try`

`Writeln (StrToIntDef ('12345678901234567890' , 0));`

`except`

`On E : EConvertError do`

`Writeln ('Invalid number encountered');`

`end;`

`End.`

30.12.210 StrToQWord

Synopsis: Convert a string to a `QWord`.

Declaration: `function StrToQWord(const s: String) : QWord`

Visibility: default

Description: `TryStrToQWord` converts the string `S` to a valid `QWord` (unsigned 64-bit) value, and returns the result.

Errors: If the string `S` does not contain a valid `QWord` value, a `EConvertError` ([1413](#)) exception is raised.

See also: `TryStrToQWord` ([1409](#)), `StrToQWordDef` ([1399](#)), `StrToInt64` ([1397](#)), `StrToInt` ([1396](#))

30.12.211 StrToQWordDef

Synopsis: Try to convert a string to a QWord, returning a default value in case of failure.

Declaration: `function StrToQWordDef(const S: String; Default: QWord) : QWord`

Visibility: default

Description: `StrToQWordDef` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and returns the result. If the conversion fails, the function returns the value passed in `Def`.

See also: `StrToQWord` ([1398](#)), `TryStrToQWord` ([1409](#)), `StrToInt64Def` ([1397](#)), `StrToIntDef` ([1398](#))

30.12.212 StrToTime

Synopsis: Convert a time string to a `TDateTime` value.

Declaration: `function StrToTime(const S: String) : TDateTime`

Visibility: default

Description: `StrToTime` converts the string `S` to a `TDateTime` time value. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToDate` ([1394](#)), `StrDateTime` ([1394](#)), `TimeToStr` ([1403](#))

Listing: `./sysutex/ex21.pp`

Program `Example21`;

{ This program demonstrates the StrToTime function }

Uses `sysutils`;

Procedure `TestStr (S : String)`;

begin

`WriteLn (S, ' : ', TimeToStr(StrToTime(S)));`
end;

Begin

`teststr (TimeToStr(Time));`
 `teststr ('12:00');`
 `teststr ('15:30');`
 `teststr ('3:30PM');`

End.

30.12.213 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see `StrLower` ([1389](#))

Errors: None.

See also: `StrLower` ([1389](#))

30.12.214 Supports

Synopsis: Check whether a class or given interface supports an interface

Declaration:

```
function Supports(const Instance: IInterface; const IID: TGUID; out Intf)
    : Boolean; Overload
function Supports(const Instance: TObject; const IID: TGUID; out Intf)
    : Boolean; Overload
function Supports(const Instance: IInterface; const IID: TGUID) : Boolean
    ; Overload
function Supports(const Instance: TObject; const IID: TGUID) : Boolean
    ; Overload
function Supports(const AClass: TClass; const IID: TGUID) : Boolean
    ; Overload
```

Visibility: default

Description: `Supports` checks whether `Instance` supports the interface identified by `IID`. It returns `True` if it is supported, `False`. Optionally, a pointer to the interface is returned to `Intf`.

Errors: None.

See also: `StringToGUID` ([1385](#))

30.12.215 SysErrorMessage

Synopsis: Format a system error message.

Declaration: `function SysErrorMessage(ErrorCode: Integer) : String`

Visibility: default

Description: `SysErrorMessage` returns a string that describes the operating system error code `ErrorCode`.

Errors: This routine may not be implemented on all platforms.

See also: `EOSError` ([1416](#))

30.12.216 SystemTimeToDateTime

Synopsis: Convert a system time to a `TDateTime` value.

Declaration: `function SystemTimeToDateTime(const SystemTime: TSystemTime) : TDateTime`

Visibility: default

Description: `SystemTimeToDateTime` converts a `TSystemTime` record to a `TDateTime` style date/time indication.

Errors: None.

See also: [DateTimeToSystemTime \(1322\)](#)

Listing: ./sysutex/ex22.pp

Program Example22;

```
{ This program demonstrates the SystemTimeToDateTime function }
```

Uses sysutils;

```
Var ST : TSystemTime;
```

Begin

DateTimeToSystemTime(**Now**,ST):

With St do

begin

```
WriteIn ( 'Today is      ',year,' / ',month,' / ',Day);
```

```
WriteIn ( 'The time is ',Hour,':',minute,':',Second,'.',',MilliSecond);
```

end :

```
WriteIn ( 'Converted : ',DateTimeToStr(SystemTimeToDateTime(ST)) );
```

End .

30.12.217 TextToFloat

Synopsis: Convert a buffer to a float value.

```
Declaration: function TextToFloat(Buffer: PChar;var Value: Extended) : Boolean
              function TextToFloat(Buffer: PChar;var Value;ValueType: TFloatValue)
                  : Boolean
```

Visibility: default

Description: `TextToFloat` converts the string in `Buffer` to a floating point value. `Buffer` should contain a valid stroing representation of a floating point value (either in decimal or scientific notation). If the buffer contains a decimal value, then the decimal separator character can either be a '.' or the value of the `DecimalSeparator` variable.

The function returns `True` if the conversion was successful.

Errors: If there is an invalid character in the buffer, then the function returns `False`

See also: [StrToFloat \(1395\)](#), [FloatToStr \(1347\)](#), [FormatFloat \(1359\)](#)

Listing: ./sysutex/ex91.pp

Program Example91 ;

```
{ This program demonstrates the TextToFloat function }
```

```
{ $mode objfpc }
```

 $\{ \$h + \}$

Uses SysUtils;

Const

NrValues = 5:

```
TestStr : Array[1..NrValues] of pchar =  
    ('1,1', '-0,2', '1,2E-4', '0', '1E4');
```

```

Procedure Testit;

Var
  I : Integer;
  E : Extended;

begin
  Writeln('Using DecimalSeparator : ',DecimalSeparator);
  For I:=1 to NrValues do
    begin
      Writeln('Converting : ',TestStr[i]);
      If TextToFloat(TestStr[i],E) then
        Writeln('Converted value : ',E)
      else
        Writeln('Unable to convert value. ');
      end;
    end;

  Begin
    DecimalSeparator:= ',';
    Testit;
    DecimalSeparator:= '.';
    Testit;
  End.

```

30.12.218 Time

Synopsis: Returns the current time.

Declaration: `function Time : TDateTime`

Visibility: default

Description: `Time` returns the current time in `TDateTime` format. The date part of the `TDateTimeValue` is set to zero.

Errors: None.

See also: `Now` ([1374](#)), `Date` ([1320](#))

Listing: `./sysutex/ex23.pp`

```

Program Example23;

{ This program demonstrates the Time function }

Uses sysutils;

Begin
  Writeln('The time is : ',TimeToStr(Time));
End.

```

30.12.219 TimeStampToDateTime

Synopsis: Convert a `TimeStamp` value to a `TDateTime` value.

Declaration: `function TimeStampToDateTime(const TimeStamp: TTimeStamp) : TDateTime`

Visibility: default

Description: `TimeStampToDateTime` converts `TimeStamp` to a `TDateTime` format variable. It is the inverse operation of `DateTimeToTimeStamp` (1323).

Errors: None.

See also: `DateTimeToTimeStamp` (1323), `TimeStampToMSecs` (1403)

Listing: `./sysutex/ex24.pp`

Program `Example24`;

{ This program demonstrates the TimeStampToDateTime function }

Uses `sysutils`;

Var `TS : TTimeStamp;`
`DT : TDateTime;`

Begin

`TS:=DateTimeToTimeStamp (Now);`

With `TS do`

begin

`WriteLn ('Now is ',time,' millisecond past midnight');`

`WriteLn ('Today is ',Date,' days past 1/1/0001');`

end;

`DT:=TimeStampToDateTime(TS);`

`WriteLn ('Together this is : ',DateTimeToStr(DT));`

End.

30.12.220 TimeStampToMSecs

Synopsis: Converts a timestamp to a number of milliseconds.

Declaration: `function TimeStampToMSecs(const TimeStamp: TTimeStamp) : comp`

Visibility: default

Description: `TimeStampToMSecs` converts `TimeStamp` to the number of seconds since 1/1/0001.

Use `TTimeStamp` variables if you need to keep very precise track of time.

For an example, see `MSecsToTimeStamp` (1373).

Errors: None.

See also: `MSecsToTimeStamp` (1373), `TimeStampToDateTime` (1402)

30.12.221 TimeToStr

Synopsis: Convert a `TDateTime` time to a string using a predefined format.

Declaration: `function TimeToStr(Time: TDateTime) : String`

Visibility: default

Description: `TimeToStr` converts the time in `Time` to a string. It uses the `ShortTimeFormat` variable to see what formatting needs to be applied. It is therefor entirely equivalent to a `FormatDateTime('t', Time)` call.

Errors: None.

Listing: `./sysutex/ex25.pp`

Program `Example25;`

{ This program demonstrates the TimeToStr function }

Uses `sysutils;`

Begin

`WriteLn ('The current time is : ', TimeToStr(Time));`
End.

30.12.222 Trim

Synopsis: Trim whitespace from the ends of a string.

Declaration: `function Trim(const S: String) : String`
`function Trim(const S: widestring) : widestring`

Visibility: default

Description: `Trim` strips blank characters (spaces) at the beginning and end of `S` and returns the resulting string. Only #32 characters are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `TrimLeft` ([1405](#)), `TrimRight` ([1405](#))

Listing: `./sysutex/ex84.pp`

Program `Example84;`

{ This program demonstrates the Trim function }

Uses `sysutils;`

`{ $H+ }`

Procedure `Testit (S : String);`

begin

`WriteLn ('"', Trim(S), '"');`
end;

Begin

`Testit (' ha ha what gets lost ? ');`
`Testit (#10#13'haha ');`
`Testit (' ');`

End.

30.12.223 TrimLeft

Synopsis: Trim whitespace from the beginning of a string.

Declaration: `function TrimLeft(const S: String) : String`
`function TrimLeft(const S: widestring) : widestring`

Visibility: default

Description: `TrimLeft` strips blank characters (spaces) at the beginning of `S` and returns the resulting string. Only #32 characters are stripped. If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1404](#)), `TrimRight` ([1405](#))

Listing: `./sysutex/ex85.pp`

Program `Example85;`

{ This program demonstrates the TrimLeft function }

Uses `sysutils;`
`{ $H+ }`

Procedure `Testit (S : String);`

begin
`WriteLn (' ', TrimLeft(S), ' ');`
end;

Begin
`Testit (' ha ha what gets lost ? ');`
`Testit (#10#13'haha ');`
`Testit (' ');`
End.

30.12.224 TrimRight

Synopsis: Trim whitespace from the end of a string.

Declaration: `function TrimRight(const S: String) : String`
`function TrimRight(const S: widestring) : widestring`

Visibility: default

Description: `Trim` strips blank characters (spaces) at the end of `S` and returns the resulting string. Only #32 characters are stripped. If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1404](#)), `TrimLeft` ([1405](#))

Listing: `./sysutex/ex86.pp`

Program `Example86;`

{ This program demonstrates the TrimRight function }

```

Uses sysutils;
{$H+}

Procedure Testit (S : String);

begin
  WriteLn ( ' ', TrimRight(S), ' ');
end;

Begin
  Testit ( '  ha ha what gets lost ? ');
  Testit (#10#13'haha ');
  Testit ( '          ');
End.

```

30.12.225 TryEncodeDate

Synopsis: Try to encode a date, and indicate success.

Declaration: `function TryEncodeDate(Year: Word;Month: Word;Day: Word;
var Date: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeDate will check the validity of the Year, Month and Day arguments, and if they are all valid, then they will be encoded as a TDateTime value and returned in D. The function will return True in this case. If an invalid argument is passed, then False will be returned.

Errors: None. If an error occurs during the encoding, False is returned.

See also: EncodeDate ([1329](#)), DecodeDateFully ([1325](#)), DecodeDate ([1324](#)), TryEncodeTime ([1406](#))

30.12.226 TryEncodeTime

Synopsis: Try to encode a time, and indicate success.

Declaration: `function TryEncodeTime(Hour: Word;Min: Word;Sec: Word;MSec: Word;
var Time: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeTime will check the validity of the Hour, Min, Sec and MSec arguments, and will encode them in a TDateTime value which is returned in T. If the arguments are valid, then True is returned, otherwise False is returned.

Errors: None. If an error occurs during the encoding, False is returned.

See also: EncodeTime ([1329](#)), DecodeTime ([1325](#)), TryEncodeDate ([1406](#))

30.12.227 TryFloatToCurr

Synopsis: Try to convert a float value to a currency value and report on success.

Declaration: `function TryFloatToCurr(const Value: Extended;var AResult: Currency)
: Boolean`

Visibility: default

Description: `TryFloatToCurr` tries convert the `Value` floating point value to a `Currency` value. If successful, the function returns `True` and the resulting currency value is returned in `AResult`. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` (1288) and `MaxCurrency` (1287)). If not, `False` is returned.

Errors: If `Value` is out of range, `False` is returned.

See also: `FloatToCurr` (1346), `MinCurrency` (1288), `MaxCurrency` (1287)

30.12.228 TryStrToCurr

Synopsis: Try to convert a string to a currency

Declaration: `function TryStrToCurr(const S: String; var Value: Currency) : Boolean`

Visibility: default

Description: `TryStrToCurr` converts the string `S` to a currency value and returns the value in `Value`. The function returns `True` if it was successful, `False` if not. This is contrary to `StrToCurr` (1393), which raises an exception when the conversion fails.

The function takes into account locale information.

See also: `StrToCurr` (1393), `TextToFloat` (1401)

30.12.229 TryStrToDate

Synopsis: Try to convert a string with a date indication to a `TDateTime` value

Declaration: `function TryStrToDate(const S: String; out Value: TDateTime) : Boolean`

Visibility: default

Description: `TryStrToDate` tries to convert the string `S` to a `TDateTime` date value, and stores the date in `Value`. The `Date` must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

The function returns `True` if the string contained a valid date indication, `False` otherwise.

See also: `StrToDate` (1394), `StrToTime` (1399), `TryStrToTime` (1409), `TryStrToDateTime` (1407), `DateToStr` (1323), `TimeToStr` (1403)

30.12.230 TryStrToDateTime

Synopsis: Try to convert a string with date/time indication to a `TDateTime` value

Declaration: `function TryStrToDateTime(const S: String; out Value: TDateTime)
: Boolean`

Visibility: default

Description: `TryStrToDateTime` tries to convert the string `S` to a `TDateTime` date and time value, and stores the result in `Value`. The date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month (This is *not* supported in Delphi). The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid date and time indication, `False` otherwise.

See also: `TryStrToDate` (1407), `TryStrToTime` (1409), `StrToDateTime` (1394), `StrToTime` (1399), `DateToStr` (1323), `TimeToStr` (1403)

30.12.231 TryStrToFloat

Synopsis: Try to convert a string to a float.

Declaration: `function TryStrToFloat(const S: String; var Value: Single) : Boolean`
`function TryStrToFloat(const S: String; var Value: Double) : Boolean`

Visibility: default

Description: `TryStrToFloat` tries to convert the string `S` to a floating point value, and stores the result in `Value`. It returns `True` if the operation was successful, and `False` if it failed. This operation takes into account the system settings for floating point representations.

Errors: On error, `False` is returned.

See also: `StrToFloat` (1395)

30.12.232 TryStrToInt

Synopsis: Try to convert a string to an integer, and report on success.

Declaration: `function TryStrToInt(const s: String; var i: Integer) : Boolean`

Visibility: default

Description: `TryStrToInt` tries to convert the string `S` to an integer, and returns `True` if this was successful. In that case the converted integer is returned in `I`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` (1396), `TryStrToInt64` (1408), `StrToIntDef` (1398), `StrToInt64` (1397), `StrToInt64Def` (1397)

30.12.233 TryStrToInt64

Synopsis: Try to convert a string to an int64 value, and report on success.

Declaration: `function TryStrToInt64(const s: String; var i: Int64) : Boolean`

Visibility: default

Description: `TryStrToInt64` tries to convert the string `S` to a `Int64` value, and returns this value in `I` if successful. If the conversion was successful, the function result is `True`, or `False` otherwise. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: None. On error, `False` is returned.

See also: `StrToInt64` ([1397](#)), `StrToInt64Def` ([1397](#)), `StrToInt` ([1396](#)), `TryStrToInt` ([1408](#)), `StrToIntDef` ([1398](#))

30.12.234 TryStrToQWord

Synopsis: Try to convert a string to a `QWord` value, and report on success

Declaration: `function TryStrToQWord(const s: String; var Q: QWord) : Boolean`

Visibility: default

Description: `TryStrToQWord` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and stores the result in `I`. If the conversion fails, the function returns `False`, else it returns `True`.

See also: `StrToQWord` ([1398](#)), `StrToQWordDef` ([1399](#)), `TryStrToInt64` ([1408](#)), `TryStrToInt` ([1408](#))

30.12.235 TryStrToTime

Synopsis: Try to convert a string with a time indication to a `TDateTime` value

Declaration: `function TryStrToTime(const S: String; out Value: TDateTime) : Boolean`

Visibility: default

Description: `TryStrToTime` tries to convert the string `S` to a `TDateTime` time value, and stores the result in `Value`. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid time indication, `False` otherwise.

See also: `TryStrToDate` ([1407](#)), `TryStrToDateTime` ([1407](#)), `StrToDate` ([1394](#)), `StrToTime` ([1399](#)), `DateToStr` ([1323](#)), `TimeToStr` ([1403](#))

30.12.236 UnhookSignal

Synopsis: `UnHook` a specified signal

Declaration: `procedure UnhookSignal(RtlSigNum: Integer; OnlyIfHooked: Boolean)`

Visibility: default

Description: This function is declared for Kylix compatibility, but is not implemented.

30.12.237 UpperCase

Synopsis: Return an uppercase version of a string.

Declaration: `function UpperCase(const s: String) : String`

Visibility: default

Description: `UpperCase` returns the uppercase equivalent of `S`. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the `UpCase` function of the system unit, and is provided for compatibility only.

Errors: None.

See also: [AnsiLowerCase \(1302\)](#), [LowerCase \(1372\)](#), [AnsiUpperCase \(1310\)](#)

Listing: ./sysutex/ex87.pp

Program Example87;

{ This program demonstrates the UpperCase function }

Uses sysutils;

Begin

WriteLn (**UpperCase**('this will come OUT ALL uPpErCaSe !'));

End.

30.12.238 WideCompareStr

Synopsis: Compare two widestrings (case sensitive)

Declaration: `function WideCompareStr(const s1: WideString;const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1<S2`.

`0` if `S1=S2`.

`> 0` if `S1>S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareText` ([1410](#)), the comparison is case sensitive.

Errors: None.

See also: `WideCompareText` ([1410](#)), `WideSameStr` ([1412](#)), `WideSameText` ([1412](#))

30.12.239 WideCompareText

Synopsis: Compare two widestrings (ignoring case).

Declaration: `function WideCompareText(const s1: WideString;const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1<S2`.

`0` if `S1=S2`.

`> 0` if `S1>S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareStr` ([1410](#)), the comparison is case insensitive.

Errors: None.

See also: `WideCompareStr` ([1410](#)), `WideSameStr` ([1412](#)), `WideSameText` ([1412](#))

30.12.240 WideFmtStr

Synopsis: Widestring format

Declaration: `procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
const args: Array[] of const)`

Visibility: default

Description: `WideFmtStr` formats `Args` according to the format string in `Fmt` and returns the resulting string in `Res`.

See also: `WideFormat` (1411), `WideFormatBuf` (1411), `Format` (1352)

30.12.241 WideFormat

Synopsis: Format a wide string.

Declaration: `function WideFormat(const Fmt: WideString; const Args: Array[] of const)
: WideString`

Visibility: default

Description: `WideFormat` does the same as `Format` (1352) but accepts as a formatting string a `WideString`. The resulting string is also a `WideString`.

For more information about the used formatting characters, see the `Format` (1352) string.

See also: `Format` (1352)

30.12.242 WideFormatBuf

Synopsis: Format widestring in a buffer.

Declaration: `function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
fmtLen: Cardinal; const Args: Array[] of const)
: Cardinal`

Visibility: default

Description: `WideFormatBuf` calls simply `WideFormat` (1411) with `Fmt` (with length `FmtLen` bytes) and stores maximum `BufLen` bytes in the buffer `buf`. It returns the number of copied bytes.

See also: `WideFmtStr` (1411), `WideFormat` (1411), `Format` (1352), `FormatBuf` (1357)

30.12.243 WideLowerCase

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideLowerCase(const s: WideString) : WideString`

Visibility: default

Description: `WideLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On linux, no language setting is taken in account yet.

Errors: None.

See also: `WideUpperCase` (1412)

30.12.244 WideSameStr

Synopsis: Check whether two widestrings are the same (case sensitive)

Declaration: `function WideSameStr(const s1: WideString;const s2: WideString)
: Boolean`

Visibility: default

Description: `WideSameStr` returns `True` if `WideCompareStr` (1410) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameText` (1412), `WideCompareStr` (1410), `WideCompareText` (1410), `AnsiSameStr` (1304)

30.12.245 WideSameText

Synopsis: Check whether two widestrings are the same (ignoring case)

Declaration: `function WideSameText(const s1: WideString;const s2: WideString)
: Boolean`

Visibility: default

Description: `WideSameText` returns `True` if `WideCompareText` (1410) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameStr` (1412), `WideCompareStr` (1410), `WideCompareText` (1410), `AnsiSameText` (1304)

30.12.246 WideUpperCase

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideUpperCase(const s: WideString) : WideString`

Visibility: default

Description: `WideUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On linux, no language setting is taken in account yet.

Errors: None.

See also: `WideLowerCase` (1411)

30.12.247 WrapText

Synopsis: Word-wrap a text.

Declaration: `function WrapText(const Line: String;const BreakStr: String;
const BreakChars: TSysCharSet;MaxCol: Integer) : String
function WrapText(const Line: String;MaxCol: Integer) : String`

Visibility: default

Description: `WrapText` does a wordwrap at column `MaxCol` of the string in `Line`. It breaks the string only at characters which are in `BreakChars` (default whitespace and hyphen) and inserts then the string `BreakStr` (default the lineending character for the current OS).

See also: `StringReplace` (1385)

30.13 EAbort

30.13.1 Description

`EAbort` is raised by the `Abort` ([1297](#)) procedure. It is not displayed in GUI applications, and serves only to immediately abort the current procedure, and return control to the main program loop.

30.14 EAbstractError

30.14.1 Description

`EAbstractError` is raised when an abstract error occurs, i.e. when an unimplemented abstract method is called.

30.15 EAccessViolation

30.15.1 Description

`EAccessViolation` is raised when the OS reports an Access Violation, i.e. when invalid memory is accessed.

30.16 EAssertionFailed

30.16.1 Description

`EAssertionFailed` is raised when an application that is compiled with assertions, encounters an invalid assertion.

30.17 EBusError

30.17.1 Description

`EBusError` is raised in case of a bus error.

30.18 EControlC

30.18.1 Description

`EControlC` is raised when the user has pressed CTRL-C in a console application.

30.19 EConvertError

30.19.1 Description

`EConvertError` is raised by the various conversion routines in the `SysUtils` unit. The message will contain more specific error information.

30.20 EDivByZero

30.20.1 Description

`EDivByZero` is used when the operating system or CPU signals a division by zero error.

30.21 EExternal

30.21.1 Description

`EExternal` is the base exception for all external exceptions, as reported by the CPU or operating system, as opposed to internal exceptions, which are raised by the program itself. The `SysUtils` unit converts all operating system errors to descendents of `EExternal`.

30.22 EExternalException

30.22.1 Description

`EExternalException` is raised when an external routine raises an exception.

30.23 EFormatError

30.23.1 Description

`EFormatError` is raised in case of an error in one of the various `Format` ([1352](#)) functions.

30.24 EHeapMemoryError

30.24.1 Description

`EHeapMemoryError` is raised when an error occurs in heap (dynamically allocated) memory.

30.25 EInOutError

30.25.1 Description

`EInOutError` is raised when a IO routine of Free Pascal returns an error. The error is converted to an `EInOutError` only if the input/output checking feature of FPC is turned on. The error code of the input/output operation is returned in `ErrorCode` (??).

30.26 EIntError

30.26.1 Description

`EIntError` is used when the operating system or CPU signals an integer operation error, e.g., an overflow.

30.27 EIntfCastError

30.27.1 Description

`EIntfCastError` is raised when an invalid interface cast is encountered.

30.28 EIntOverflow

30.28.1 Description

`EIntOverflow` is used when the operating system or CPU signals a integer overflow error.

30.29 EInvalidCast

30.29.1 Description

`EInvalidCast` is raised when an invalid typecast error (using the `as` operator) is encountered.

30.30 EInvalidContainer

30.30.1 Description

`EInvalidContainer` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

30.31 EInvalidInsert

30.31.1 Description

`EInvalidInsert` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

30.32 EInvalidOp

30.32.1 Description

`EInvalidOp` is raised when an invalid operation is encountered.

30.33 EInvalidPointer

30.33.1 Description

`EInvalidPointer` is raised when an invalid heap pointer is used.

30.34 EMathError

30.34.1 Description

`EMathError` is used when the operating system or CPU signals a floating point overflow error.

30.35 ENoThreadSupport

30.35.1 Description

`ENoThreadSupport` is raised when some thread routines are invoked, and thread support was not enabled when the program was compiled.

30.36 EOSError

30.36.1 Description

`EOSError` is raised when some Operating System call fails. The `ErrorCode` (??) property contains the operating system error code.

30.37 EOutOfMemory

30.37.1 Description

`EOutOfMemory` occurs when memory can no longer be allocated on the heap. An instance of `EOutOfMemory` is allocated on the heap at program startup, so it is available when needed.

30.38 EOverflow

30.38.1 Description

`EOverflow` occurs when a float operation overflows. (i.e. result is too big to represent).

30.39 EPackageError

30.39.1 Description

`EPackageError` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

30.40 EPrivilege

30.40.1 Description

`EPrivilege` is raised when the OS reports that an invalid instruction was executed.

30.41 EPropReadOnly

30.41.1 Description

EPropReadOnly is raised when an attempt is made to write to a read-only property.

30.42 EPropWriteOnly

30.42.1 Description

EPropWriteOnly is raised when an attempt is made to read from a write-only property.

30.43 ERangeError

30.43.1 Description

ERangeError is raised by the Free Pascal runtime library if range checking is on, and a range check error occurs.

30.44 ESafecallException

30.44.1 Description

ESafecallException is not yet used by Free Pascal, and is provided for Delphi compatibility only.

30.45 EStackOverflow

30.45.1 Description

EStackOverflow occurs when the stack has grown too big (e.g. by infinite recursion).

30.46 EUnderflow

30.46.1 Description

EOverflow occurs when a float operation underflows (i.e. result is too small to represent).

30.47 EVariantError

30.47.1 Description

EVariantError is raised by the internal variant routines.

30.47.2 Method overview

Page	Property	Description
1418	CreateCode	Create an instance of EVariantError with a particular error code.

30.47.3 EVariantError.CreateCode

Synopsis: Create an instance of `EVariantError` with a particular error code.

Declaration: `constructor CreateCode(Code: LongInt)`

Visibility: `default`

Description: `CreateCode` calls the inherited constructor, and sets the `ErrCode` (??) property to `Code`.

See also: `EVariantError.ErrCode` (??)

30.48 Exception

30.48.1 Description

`Exception` is the base class for all exception handling routines in the RTL and FCL. While it is possible to raise an exception with any class descending from `TObject`, it is recommended to use `Exception` as the basis of exception class objects: the `Exception` class introduces properties to associate a message and a help context with the exception being raised. What is more, the `SysUtils` unit sets the necessary hooks to catch and display unhandled exceptions: in such cases, the message displayed to the end user, will be the message stored in the exception class.

30.48.2 Method overview

Page	Property	Description
1418	<code>Create</code>	Constructs a new exception object with a given message.
1419	<code>CreateFmt</code>	Constructs a new exception object and formats a new message.
1420	<code>CreateFmtHelp</code>	Constructs a new exception object and sets the help context and formats the message
1419	<code>CreateHelp</code>	Constructs a new exception object and sets the help context.
1419	<code>CreateRes</code>	Constructs a new exception object and gets the message from a resource.
1419	<code>CreateResFmt</code>	Constructs a new exception object and formats the message from a resource.
1420	<code>CreateResFmtHelp</code>	Constructs a new exception object and sets the help context and formats the message from a resource
1420	<code>CreateResHelp</code>	Constructs a new exception object and sets the help context and gets the message from a resource

30.48.3 Property overview

Page	Property	Access	Description
1420	<code>HelpContext</code>	<code>rw</code>	Help context associated with the exception.
1421	<code>Message</code>	<code>rw</code>	Message associated with the exception.

30.48.4 Exception.Create

Synopsis: Constructs a new exception object with a given message.

Declaration: `constructor Create(const msg: String)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.CreateFmt` ([1419](#)), `Exception.Message` ([1421](#))

30.48.5 `Exception.CreateFmt`

Synopsis: Constructs a new exception object and formats a new message.

Declaration: `constructor CreateFmt(const msg: String; const args: Array[] of const)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` ([1418](#)), `Exception.Message` ([1421](#)), `Format` ([1352](#))

30.48.6 `Exception.CreateRes`

Synopsis: Constructs a new exception object and gets the message from a resource.

Declaration: `constructor CreateRes(ResString: PString)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` ([1418](#)), `Exception.CreateFmt` ([1419](#)), `Exception.CreateResFmt` ([1419](#)), `Exception.Message` ([1421](#))

30.48.7 `Exception.CreateResFmt`

Synopsis: Constructs a new exception object and formats the message from a resource.

Declaration: `constructor CreateResFmt(ResString: PString;
const Args: Array[] of const)`

Visibility: public

Description: `CreateResFmt` does the same as `CreateFmt` ([1419](#)), but fetches the message from the resource string `ResString`.

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` ([1418](#)), `Exception.CreateFmt` ([1419](#)), `Exception.CreateRes` ([1419](#)), `Exception.Message` ([1421](#))

30.48.8 `Exception.CreateHelp`

Synopsis: Constructs a new exception object and sets the help context.

Declaration: `constructor CreateHelp(const Msg: String; AHelpContext: Integer)`

Visibility: public

Description: `CreateHelp` does the same as the `Create` ([1418](#)) constructor, but additionally stores `AHelpContext` in the `HelpContext` ([1420](#)) property.

See also: `Exception.Create` ([1418](#))

30.48.9 Exception.CreateFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message

Declaration: constructor `CreateFmtHelp(const Msg: String;
const Args: Array[] of const;
AHelpContext: Integer)`

Visibility: public

Description: `CreateFmtHelp` does the same as the `CreateFmt` (1419) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1420) property.

See also: `Exception.CreateFmt` (1419)

30.48.10 Exception.CreateResHelp

Synopsis: Constructs a new exception object and sets the help context and gets the message from a resource

Declaration: constructor `CreateResHelp(ResString: PString; AHelpContext: Integer)`

Visibility: public

Description: `CreateResHelp` does the same as the `CreateRes` (1419) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1420) property.

See also: `Exception.CreateRes` (1419)

30.48.11 Exception.CreateResFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message from a resource

Declaration: constructor `CreateResFmtHelp(ResString: PString;
const Args: Array[] of const;
AHelpContext: Integer)`

Visibility: public

Description: `CreateResFmtHelp` does the same as the `CreateResFmt` (1419) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1420) property.

See also: `Exception.CreateResFmt` (1419)

30.48.12 Exception.HelpContext

Synopsis: Help context associated with the exception.

Declaration: Property `HelpContext` : LongInt

Visibility: public

Access: Read, Write

Description: `HelpContext` is the help context associated with the exception, and can be used to provide context-sensitive help when the exception error message is displayed. It should be set in the exception constructor.

See also: `Exception.CreateHelp` (1419), `Exception.Message` (1421)

30.48.13 Exception.Message

Synopsis: Message associated with the exception.

Declaration: `Property Message : String`

Visibility: `public`

Access: `Read, Write`

Description: `Message` provides additional information about the exception. It is shown to the user in e.g. the `ShowException` (1378) routine, and should be set in the constructor when the exception is raised.

See also: `Exception.Create` (1418), `Exception.HelpContext` (1420)

30.49 EZeroDivide

30.49.1 Description

`EZeroDivide` occurs when a float division by zero occurs.

30.50 IReadWriteSync

30.50.1 Description

`IReadWriteSync` is an interface for synchronizing read/write operations. Writers are always guaranteed to have exclusive access: readers may or may not have simultaneous access, depending on the implementation.

30.50.2 Method overview

Page	Property	Description
1421	<code>BeginRead</code>	Start a read operation.
1422	<code>BeginWrite</code>	Start a write operation.
1422	<code>EndRead</code>	End a read operation
1422	<code>EndWrite</code>	End a write operation.

30.50.3 IReadWriteSync.BeginRead

Synopsis: Start a read operation.

Declaration: `procedure BeginRead`

Visibility: `default`

Description: `BeginRead` indicates that a read operation is about to be started. If a write operation is in progress, then the call will block until the write operation finished. Depending on the implementation the call may also block if another read operation is in progress.

After `BeginRead`, any write operation started with `BeginWrite` (1422) will block until `EndRead` (1422) is called.

See also: `IReadWriteSync.EndRead` (1422), `IReadWriteSync.BeginWrite` (1422), `IReadWriteSync.EndWrite` (1422)

30.50.4 IReadWriteSync.EndRead

Synopsis: End a read operation

Declaration: `procedure EndRead`

Visibility: `default`

Description: `EndRead` signals the end of a read operation. If there was any blocked write operation, that will be unblocked by a call to `EndRead`.

See also: `IReadWriteSync.BeginRead` ([1421](#)), `IReadWriteSync.BeginWrite` ([1422](#)), `IReadWriteSync.EndWrite` ([1422](#))

30.50.5 IReadWriteSync.BeginWrite

Synopsis: Start a write operation.

Declaration: `function BeginWrite : Boolean`

Visibility: `default`

Description: `BeginWrite` signals the begin of a write operation. This call will block if any other read or write operation is currently in progress. It will resume only after all other read or write operations have finished.

See also: `IReadWriteSync.EndRead` ([1422](#)), `IReadWriteSync.EndWrite` ([1422](#)), `IReadWriteSync.BeginRead` ([1421](#))

30.50.6 IReadWriteSync.EndWrite

Synopsis: End a write operation.

Declaration: `procedure EndWrite`

Visibility: `default`

Description: `EndWrite` signals the end of a write operation. After the call to `EndWrite` any other read or write operations can start.

See also: `IReadWriteSync.EndRead` ([1422](#)), `IReadWriteSync.EndWrite` ([1422](#)), `IReadWriteSync.BeginRead` ([1421](#))

30.51 TMultiReadExclusiveWriteSynchronizer

30.51.1 Description

`TMultiReadExclusiveWriteSynchronizer` is a default implementation of the `IReadWriteSync` ([1421](#)) interface. It uses a single mutex to protect access to the read/write resource, resulting in a single thread having access to the resource.

30.51.2 Method overview

Page	Property	Description
1424	Beginread	Request read access to the resource
1423	Beginwrite	Request write access to the resource.
1423	Create	Create a new instance of the <code>TMultiReadExclusiveWriteSynchronizer</code> class
1423	Destroy	Destroys the <code>TMultiReadExclusiveWriteSynchronizer</code> instance
1424	Endread	Release read access to the resource
1424	Endwrite	Release write access to the resource

30.51.3 `TMultiReadExclusiveWriteSynchronizer.Create`

Synopsis: Create a new instance of the `TMultiReadExclusiveWriteSynchronizer` class

Declaration: `constructor Create; Virtual`

Visibility: `public`

Description: `Create` creates a new instance of `TMultiReadExclusiveWriteSynchronizer`. It initializes a `TRTLCriticalSection`.

Errors: None.

See also: `#rtl.system.TRTLCriticalSection` ([1102](#))

30.51.4 `TMultiReadExclusiveWriteSynchronizer.Destroy`

Synopsis: Destroys the `TMultiReadExclusiveWriteSynchronizer` instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Create` destroys the instance of `TMultiReadExclusiveWriteSynchronizer`. It frees the `TRTLCriticalSection` it initialized, and calls the inherited destructor.

Errors: None.

See also: `#rtl.system.TRTLCriticalSection` ([1102](#))

30.51.5 `TMultiReadExclusiveWriteSynchronizer.Beginwrite`

Synopsis: Request write access to the resource.

Declaration: `function Beginwrite : Boolean`

Visibility: `public`

Description: `Beginwrite` is the implementation of `IReadWriteSync.BeginWrite`. It simply enters the critical section, and returns `True`.

Errors: None.

See also: `IReadWriteSync.BeginWrite` ([1422](#)), `TMultiReadExclusiveWriteSynchronizer.EndWrite` ([1424](#))

30.51.6 TMultiReadExclusiveWriteSynchronizer.Endwrite

Synopsis: Release write access to the resource

Declaration: `procedure Endwrite`

Visibility: `public`

Description: `Beginwrite` is the implementation of `IReadWriteSync.EndWrite`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndWrite` ([1422](#)), `TMultiReadExclusiveWriteSynchronizer.BeginWrite` ([1423](#))

30.51.7 TMultiReadExclusiveWriteSynchronizer.Beginread

Synopsis: Request read access to the resource

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` is the implementation of `IReadWriteSync.BeginRead`. It simply attempts to enter the critical section.

Errors: None.

See also: `IReadWriteSync.BeginRead` ([1421](#)), `TMultiReadExclusiveWriteSynchronizer.EndRead` ([1424](#))

30.51.8 TMultiReadExclusiveWriteSynchronizer.Endread

Synopsis: Release read access to the resource

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` is the implementation of `IReadWriteSync.EndRead`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndRead` ([1422](#)), `TMultiReadExclusiveWriteSynchronizer.BeginRead` ([1424](#))

Chapter 31

Reference for unit 'typinfo'

31.1 Auxiliary functions

Other typinfo related functions.

Table 31.1:

Name	Description
GetEnumName (1433)	Get an enumerated type element name
GetEnumValue (1435)	Get ordinal number of an enumerated type, based on the name.
GetEnumNameCount (1434)	Get number of elements in an enumerated type.
GetTypeData (1447)	Skip type name and return a pointer to the type data
SetToString (1455)	Convert a set to its string representation
StringToSet (1457)	Convert a string representation of a set to a set

31.2 Getting or setting property values

Functions to set or set a property's value.

31.3 Examining published property information

Functions for retrieving or examining property information

31.4 Used units

31.5 Overview

The `TypeInfo` unit contains many routines which can be used for the querying of the Run-Time Type Information (RTTI) which is generated by the compiler for classes that are compiled under the `{ $M+ }` switch. This information can be used to retrieve or set property values for published properties for totally unknown classes. In particular, it can be used to stream classes. The `TPersistent`

Table 31.2:

Name	Description
<code>GetEnumProp</code> (1434)	Return the value of an enumerated type property
<code>GetFloatProp</code> (1436)	Return the value of a float property
<code>GetInt64Prop</code> (1437)	Return the value of an Int64 property
<code>GetMethodProp</code> (1437)	Return the value of a procedural type property
<code>GetObjectProp</code> (1439)	Return the value of an object property
<code>GetOrdProp</code> (1441)	Return the value of an ordinal type property
<code>GetPropValue</code> (1444)	Return the value of a property as a variant
<code>GetSetProp</code> (1445)	Return the value of a set property
<code>GetStrProp</code> (1446)	Return the value of a string property
<code>GetWideStrProp</code> (1447)	Return the value of a widestring property
<code>GetVariantProp</code> (1447)	Return the value of a variant property
<code>SetEnumProp</code> (1451)	Set the value of an enumerated type property
<code>SetFloatProp</code> (1452)	Set the value of a float property
<code>SetInt64Prop</code> (1452)	Set the value of an Int64 property
<code>SetMethodProp</code> (1452)	Set the value of a procedural type property
<code>SetObjectProp</code> (1453)	Set the value of an object property
<code>SetOrdProp</code> (1453)	Set the value of an ordinal type property
<code>SetPropValue</code> (1454)	Set the value of a property through a variant
<code>SetSetProp</code> (1454)	Set the value of a set property
<code>SetStrProp</code> (1455)	Set the value of a string property
<code>SetWideStrProp</code> (1456)	Set the value of a widestring property
<code>SetVariantProp</code> (1456)	Set the value of a variant property

class in the **Classes** unit is compiled in the `{ $M+ }` state and serves as the base class for all classes that need to be streamed.

The unit should be compatible to the Delphi 5 unit with the same name. The only calls that are still missing are the Variant calls, since Free Pascal does not support the variant type yet.

The examples in this chapter use a `rttiobj` file, which contains an object that has a published property of all supported types. It also contains some auxiliary routines and definitions.

31.6 Constants, types and variables

31.6.1 Constants

```
BooleanIdents : Array[Boolean] of String = ('False', 'True' )
```

Names for boolean values

```
DotSep : String = '.'
```

Name separator character

```
OnGetPropValue : TGetPropValue = nil
```

This callback is set by the variants unit to enable reading of properties as a variant. If set, it is called by the `GetPropValue` (1444) function.

Table 31.3:

Name	Description
FindPropInfo (1432)	Getting property type information, With error checking.
GetPropInfo (1442)	Getting property type information, No error checking.
GetPropInfos (1442)	Find property information of a certain kind
GetObjectPropClass (1440)	Return the declared class of an object property
GetPropList (1443)	Get a list of all published properties
IsPublishedProp (1448)	Is a property published
IsStoredProp (1449)	Is a property stored
PropIsType (1450)	Is a property of a certain kind
PropType (1450)	Return the type of a property

Table 31.4: Used units by unit 'typinfo'

Name	Page
sysutils	1278

OnGetVariantprop : TGetVariantProp = nil

This callback is set by the variants unit to enable reading of variant properties. If set, it is called by the GetVariantProp (1447) function.

OnSetPropValue : TSetPropValue = nil

This callback is set by the variants unit to enable writing of properties as a variant. If set, it is called by the SetPropValue (1454) function.

OnSetVariantprop : TSetVariantProp = nil

This callback is set by the variants unit to enable writing of variant properties. If set, it is called by the GetVariantProp (1447) function.

ptConst = 3

Constant used in acces method

ptField = 0

Property acces directly from field

ptStatic = 1

Property acces via static method

ptVirtual = 2

Property acces via virtual method


```
tkAny = [Low ( TTypeKind ) ..High ( TTypeKind ) ]
```

Any property type

```
tkMethods = [tkMethod]
```

Only method properties. (event handlers)

```
tkProperties = tkAny - tkMethods - [tkUnknown]
```

Real properties. (not methods)

```
tkString = tkSString
```

Alias for the `tsSString` enumeration value

31.6.2 Types

```
PPropInfo = ^TPropInfo
```

Pointer to TPropInfo (1431) record

```
PPropList = ^TPropList
```

Pointer to TPropList (1431)

```
PTypeInfo = ^PTypeInfo
```

Pointer to PTypeInfo (1428) pointer

```
PTypeData = ^TTypeData
```

Pointer to TTypeData (1431) record.

```
PTypeInfo = ^TTypeInfo
```

Pointer to TTypeInfo (1431) record

```
TFloatType = (ftSingle, ftDouble, ftExtended, ftComp, ftCurr)
```

Table 31.5: Enumeration values for type TFloatType

Value	Explanation
ftComp	Comp-type float
ftCurr	Currency-type float
ftDouble	Double-sized float
ftExtended	Extended-size float
ftSingle	Single-sized float

The size of a float type.

```
TGetPropValue = function(Instance: TObject;const PropName: String;
                        PreferStrings: Boolean) : Variant
```

The callback function must return the property with name `PropName` of instance `Instance`. If `PreferStrings` is true, it should favour converting the property to a string value. The function needs to return the variant with the property value.

```
TGetVariantProp = function(Instance: TObject;PropInfo: PPropInfo)
                    : Variant
```

The callback function must return the variant property with name `PropName` of instance `Instance`.

```
TIntfFlag = (ifHasGuid,ifDispInterface,ifDispatch,ifHasStrGUID)
```

Table 31.6: Enumeration values for type `TIntfFlag`

Value	Explanation
<code>ifDispatch</code>	Interface is a dispatch interface
<code>ifDispInterface</code>	Interface is a dual dispatch interface
<code>ifHasGuid</code>	Interface has GUID identifier
<code>ifHasStrGUID</code>	Interface has a string GUID identifier

Type of interface.

```
TIntfFlags= Set of (ifDispatch,ifDispInterface,ifHasGuid,ifHasStrGUID)
```

Set of `TIntfFlag` ([1429](#)).

```
TIntfFlagsBase= Set of (ifDispatch,ifDispInterface,ifHasGuid,
                        ifHasStrGUID)
```

Set of `TIntfFlag` ([1429](#)).

```
TMethodKind = (mkProcedure,mkFunction,mkConstructor,mkDestructor,
               mkClassProcedure,mkClassFunction)
```

Table 31.7: Enumeration values for type `TMethodKind`

Value	Explanation
<code>mkClassFunction</code>	Class function
<code>mkClassProcedure</code>	Class procedure
<code>mkConstructor</code>	Class constructor
<code>mkDestructor</code>	Class Desctructor
<code>mkFunction</code>	Function method
<code>mkProcedure</code>	Procedure method.

Method type description

```
TOrdType = (otSByte,otUByte,otSWord,otUWord,otSLong,otULong)
```

Table 31.8: Enumeration values for type TOrdType

Value	Explanation
otSByte	Signed byte
otSLong	Signed longint
otSWord	Signed word
otUByte	Unsigned byte
otULong	Unsigned longint (Cardinal)
otUWord	Unsigned word

Table 31.9: Enumeration values for type TParamFlag

Value	Explanation
pfAddress	Parameter is passed by address
pfArray	Parameter is an array parameter
pfConst	Parameter is a const parameter (i.e. cannot be modified)
pfOut	Parameter is a string parameter
pfReference	Parameter is passed by reference
pfVar	Parameter is a var parameter (passed by reference)

If the property is and ordinal type, then TOrdType determines the size and sign of the ordinal type:

```
TParamFlag = (pfVar, pfConst, pfArray, pfAddress, pfReference, pfOut)
```

TParamFlag describes a parameter.

```
TParamFlags= Set of (pfAddress, pfArray, pfConst, pfOut, pfReference, pfVar)
```

The kind of parameter for a method

```
TProcInfoProc = procedure (PropInfo: PPropInfo) of object
```

Property info callback method

```
TPropData = packed record
  PropCount : Word;
  PropList : record
    _alignmentdummy : ptring;
  end;
end
```

The TPropData record is not used, but is provided for completeness and compatibility with Delphi.

```
TPropInfo = packed record
  PropType : PTypeInfo;
  GetProc : Pointer;
  SetProc : Pointer;
  StoredProc : Pointer;
```

```

    Index : Integer;
    Default : LongInt;
    NameIndex : SmallInt;
    PropProcs : Byte;
    Name : ShortString;
end

```

The `TPropInfo` record describes one published property of a class. The property information of a class are stored as an array of `TPropInfo` records.

The `Name` field is stored not with 255 characters, but with just as many characters as required to store the name.

```
TPropList = Array[0..65535] of PPropInfo
```

Array of property information pointers

```
TSetPropValue = procedure (Instance: TObject; const PropName: String;
                           const Value: Variant)
```

The callback function must set the property with name `PropName` of instance `Instance` to `Value`.

```
TSetVariantProp = procedure (Instance: TObject; PropInfo: PPropInfo;
                             const Value: Variant)
```

The callback function must set the variant property with name `PropName` of instance to `Value`.

```
TTypeData = packed record
end
```

If the typeinfo kind is `tkClass`, then the property information follows the `UnitName` string, as an array of `TPropInfo` (1431) records.

```
TTypeInfo = record
    Kind : TTypeKind;
    Name : ShortString;
end
```

The `TypeInfo` function returns a pointer to a `TTypeInfo` record.

Note that the `Name` field is stored with as much bytes as needed to store the name, it is not padded to 255 characters. The type data immediately follows the `TTypeInfo` record as a `TTypeData` (1431) record.

```
TTypeKind = (tkUnknown, tkInteger, tkChar, tkEnumeration, tkFloat, tkSet,
             tkMethod, tkSString, tkLString, tkAString, tkWString, tkVariant,
             tkArray, tkRecord, tkInterface, tkClass, tkObject, tkWChar,
             tkBool, tkInt64, tkQWord, tkDynArray, tkInterfaceRaw)
```

Type of a property.

Table 31.10: Enumeration values for type TTypeKind

Value	Explanation
tkArray	Array property.
tkAString	Ansistring property.
tkBool	Boolean property.
tkChar	Char property.
tkClass	Class property.
tkDynArray	Dynamical array property.
tkEnumeration	Enumeration type property.
tkFloat	Float property.
tkInt64	Int64 property.
tkInteger	Integer property.
tkInterface	Interface property.
tkInterfaceRaw	Raw interface property.
tkLString	Longstring property.
tkMethod	Method property.
tkObject	Object property.
tkQWord	QWord property.
tkRecord	Record property.
tkSet	Set property.
tkSString	Shortstring property.
tkUnknown	Unknown property type.
tkVariant	Variant property.
tkWChar	Widechar property.
tkWString	Widestring property.

```
TTypeKinds= Set of (tkArray,tkAString,tkBool,tkChar,tkClass,tkDynArray,
tkEnumeration,tkFloat,tkInt64,tkInteger,tkInterface,
tkInterfaceRaw,tkLString,tkMethod,tkObject,tkQWord,
tkRecord,tkSet,tkSString,tkUnknown,tkVariant,
tkWChar,tkWString)
```

Set of TTypeKind (1431) enumeration.

31.7 Procedures and functions

31.7.1 FindPropInfo

Synopsis: Return property information by property name.

Declaration: `function FindPropInfo(Instance: TObject;const PropName: String)`
`: PPropInfo`
`function FindPropInfo(AClass: TClass;const PropName: String) : PPropInfo`

Visibility: default

Description: `FindPropInfo` examines the published property information of a class and returns a pointer to the property information for property `PropName`. The class to be examined can be specified in one of two ways:

`AClass` class pointer.

Instance an instance of the class to be investigated.

If the property does not exist, a `EPropertyError` exception will be raised. The `GetPropInfo` (1442) function has the same function as the `FindPropInfo` function, but returns `Nil` if the property does not exist.

Errors: Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetPropInfo` (1442), `GetPropList` (1443), `GetPropInfos` (1442)

Listing: ./typinfex/ex14.pp

Program example13;

{ This program demonstrates the FindPropInfo function }

{ \$mode objfpc }

uses

rttiobj, typinfo, sysutils;

Var

O : TMyTestObject;

PT : PTypeData;

PI : PPropInfo;

I, J : Longint;

PP : PPropList;

pri : PPropInfo;

begin

O := TMyTestObject.Create;

PI := FindPropInfo(O, 'BooleanField');

WriteLn('FindPropInfo(Instance, BooleanField) : ', PI^.Name);

PI := FindPropInfo(O.ClassType, 'ByteField');

WriteLn('FindPropInfo(Class, ByteField) : ', PI^.Name);

Write('FindPropInfo(Class, NonExistingProp) : ');

Try

PI := FindPropInfo(O, 'NonExistingProp');

except

On E: Exception **do**

WriteLn('Caught exception "', E.ClassName, '" with message : ', E.Message);

end;

O.Free;

end.

31.7.2 GetEnumName

Synopsis: Return name of enumeration constant.

Declaration: `function GetEnumName(TypeInfo: PTypeInfo; Value: Integer) : String`

Visibility: default

Description: `GetEnumName` scans the type information for the enumeration type described by `TypeInfo` and returns the name of the enumeration constant for the element with ordinal value equal to `Value`.

If `Value` is out of range, the first element of the enumeration type is returned. The result is lower-cased, but this may change in the future.

This can be used in combination with `GetOrdProp` to stream a property of an enumerated type.

Errors: No check is done to determine whether `TypeInfo` really points to the type information for an enumerated type.

See also: `GetOrdProp` ([1441](#)), `GetEnumValue` ([1435](#))

Listing: `./typinfex/ex9.pp`

```

program example9;

{ This program demonstrates the GetEnumName, GetEnumValue functions }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  TI : PTypeInfo;

begin
  O := TMyTestObject.Create;
  TI := GetPropInfo(O, 'MyEnumField')^.PropType;
  WriteLn ( 'GetEnumName          : ', GetEnumName(TI, Ord(O.MyEnumField)));
  WriteLn ( 'GetEnumValue(mefirst) : ', GetEnumName(TI, GetEnumValue(TI, 'mefirst')));
  O.Free;
end.

```

31.7.3 GetEnumNameCount

Synopsis: Return number of names in an enumerated type

Declaration: `function GetEnumNameCount(enum1: PTypeInfo) : SizeInt`

Visibility: default

Description: `GetEnumNameCount` returns the number of values (names) in the enumerated type, described by `enum1`

Errors: No checking is done to see whether `Enum1` is really type information of an enumerated type.

See also: `GetEnumValue` ([1435](#)), `GetEnumName` ([1433](#))

31.7.4 GetEnumProp

Synopsis: Return the value of an enumeration type property.

Declaration: `function GetEnumProp(Instance: TObject; const PropName: String) : String`
`function GetEnumProp(Instance: TObject; const PropInfo: PPropInfo)`
`: String`

Visibility: default

Description: `GetEnumProp` returns the value of an property of an enumerated type and returns the name of the enumerated value for the object `Instance`. The property whose value must be returned can be specified by its property info in `PropInfo` or by its name in `PropName`

Errors: No check is done to determine whether `PropInfo` really points to the property information for an enumerated type. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetEnumProp` (1451), `GetOrdProp` (1441), `GetStrProp` (1446), `GetInt64Prop` (1437), `GetMethodProp` (1437), `GetSetProp` (1445), `GetObjectProp` (1439), `GetEnumProp` (1434)

Listing: `./typinfex/ex2.pp`

```

program example2;

{ This program demonstrates the GetEnumProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  TI : PTypeInfo;

begin
  O := TMyTestObject.Create;
  PI := GetPropInfo(O, 'MyEnumField');
  TI := PI^.PropType;
  Writeln('Enum property      : ');
  Writeln('Value                : ', GetEnumName(TI, Ord(O.MyEnumField)));
  Writeln('Get (name)                 : ', GetEnumProp(O, 'MyEnumField'));
  Writeln('Get (propinfo)             : ', GetEnumProp(O, PI));
  SetEnumProp(O, 'MyEnumField', 'meFirst');
  Writeln('Set (name, meFirst)         : ', GetEnumName(TI, Ord(O.MyEnumField)));
  SetEnumProp(O, PI, 'meSecond');
  Writeln('Set (propinfo, meSecond)    : ', GetEnumName(TI, Ord(O.MyEnumField)));
  O.Free;
end.

```

31.7.5 GetEnumValue

Synopsis: Get ordinal value for enumerated type by name

Declaration: `function GetEnumValue(TypeInfo: PTypeInfo; const Name: String) : Integer`

Visibility: default

Description: `GetEnumValue` scans the type information for the enumeration type described by `TypeInfo` and returns the ordinal value for the element in the enumerated type that has identifier `Name`. The identifier is searched in a case-insensitive manner.

This can be used to set the value of enumerated properties from a stream.

For an example, see `GetEnumName` (1433).

Errors: If `Name` is not found in the list of enumerated values, then -1 is returned. No check is done whether `TypeInfo` points to the type information for an enumerated type.

See also: `GetEnumName` (1433), `SetOrdProp` (1453)

31.7.6 GetFloatProp

Synopsis: Return value of floating point property

Declaration: `function GetFloatProp(Instance: TObject; PropInfo: PPropInfo) : Extended`
`function GetFloatProp(Instance: TObject; const PropName: String)`
`: Extended`

Visibility: default

Description: `GetFloatProp` returns the value of the float property described by `PropInfo` or with name `Propname` for the object `Instance`. All float types are converted to extended.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetFloatProp` (1452), `GetOrdProp` (1441), `GetStrProp` (1446), `GetInt64Prop` (1437), `GetMethodProp` (1437), `GetSetProp` (1445), `GetObjectProp` (1439), `GetEnumProp` (1434)

Listing: `./typinfex/ex4.pp`

```

program example4;

{ This program demonstrates the GetFloatProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O := TMyTestObject.Create;
  Writeln('Real property : ');
  PI := GetPropInfo(O, 'RealField');
  Writeln('Value           : ', O.RealField);
  Writeln('Get (name)         : ', GetFloatProp(O, 'RealField'));
  Writeln('Get (propinfo)       : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'RealField', system.Pi);
  Writeln('Set (name, pi)       : ', O.RealField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e) : ', O.RealField);
  Writeln('Extended property : ');
  PI := GetPropInfo(O, 'ExtendedField');
  Writeln('Value           : ', O.ExtendedField);
  Writeln('Get (name)         : ', GetFloatProp(O, 'ExtendedField'));
  Writeln('Get (propinfo)       : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'ExtendedField', system.Pi);
  Writeln('Set (name, pi)       : ', O.ExtendedField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e) : ', O.ExtendedField);
  O.Free;
end.

```

31.7.7 GetInt64Prop

Synopsis: return value of an Int64 property

Declaration: `function GetInt64Prop(Instance: TObject; PropInfo: PPropInfo) : Int64`
`function GetInt64Prop(Instance: TObject; const PropName: String) : Int64`

Visibility: default

Description: Publishing of Int64 properties is not yet supported by Free Pascal. This function is provided for Delphi compatibility only at the moment.

`GetInt64Prop` returns the value of the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception

See also: `SetInt64Prop` (1452), `GetOrdProp` (1441), `GetStrProp` (1446), `GetFloatProp` (1436), `GetMethodProp` (1437), `GetSetProp` (1445), `GetObjectProp` (1439), `GetEnumProp` (1434)

Listing: `./typinfex/ex15.pp`

```

program example15;

{ This program demonstrates the GetInt64Prop function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O := TMyTestObject.Create;
  Writeln('Int64 property : ');
  PI := GetPropInfo(O, 'Int64Field');
  Writeln('Value           : ', O.Int64Field);
  Writeln('Get (name)         : ', GetInt64Prop(O, 'Int64Field'));
  Writeln('Get (propinfo)       : ', GetInt64Prop(O, PI));
  SetInt64Prop(O, 'Int64Field', 12345);
  Writeln('Set (name,12345)     : ', O.Int64Field);
  SetInt64Prop(O, PI, 54321);
  Writeln('Set (propinfo,54321) : ', O.Int64Field);
  O.Free;
end.

```

31.7.8 GetMethodProp

Synopsis: Return value of a method property

Declaration: `function GetMethodProp(Instance: TObject; PropInfo: PPropInfo) : TMethod`
`function GetMethodProp(Instance: TObject; const PropName: String)`
`: TMethod`

Visibility: default

Description: `GetMethodProp` returns the method the property described by `PropInfo` or with name `Propname` for object `Instance`. The return type `TMethod` is defined in the `SysUtils` unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

`Data` points to the instance of the class with the method `Code`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1452), `GetOrdProp` (1441), `GetStrProp` (1446), `GetFloatProp` (1436), `GetInt64Prop` (1437), `GetSetProp` (1445), `GetObjectProp` (1439), `GetEnumProp` (1434)

Listing: `./typinfex/ex6.pp`

```
program example6;

{ This program demonstrates the GetMethodProp function }

{$mode objfpc}

uses rttiobj, typinfo, sysutils;

Type
  TNotifyObject = Class(TObject)
    Procedure Notification1(Sender : TObject);
    Procedure Notification2(Sender : TObject);
  end;

Procedure TNotifyObject.Notification1(Sender : TObject);

begin
  Write('Received notification 1 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Procedure TNotifyObject.Notification2(Sender : TObject);

begin
  Write('Received notification 2 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO : TNotifyObject;
  M : TMethod;

Procedure PrintMethod (Const M : TMethod);

begin
  If (M.Data=Pointer(NO)) Then
    If (M.Code=Pointer(@TNotifyObject.Notification1)) then
      WriteLn('Notification1')
```


Description: `GetObjectProp` returns the object which the property described by `PropInfo` with name `Propname` points to for object `Instance`.

If `MinClass` is specified, then if the object is not descendent of class `MinClass`, then `Nil` is returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1452), `GetOrdProp` (1441), `GetStrProp` (1446), `GetFloatProp` (1436), `GetInt64Prop` (1437), `GetSetProp` (1445), `GetObjectProp` (1439), `GetEnumProp` (1434)

Listing: `./typinfex/ex5.pp`

```

program example5;

{ This program demonstrates the GetObjectProp function }

{$mode objfpc}

uses rttiobj , typinfo ;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO1, NO2 : TNamedObject;

begin
  O := TMyTestObject.Create;
  NO1 := TNamedObject.Create;
  NO1.ObjectName := 'First named object';
  NO2 := TNamedObject.Create;
  NO2.ObjectName := 'Second named object';
  O.ObjField := NO1;
  Writeln('Object property : ');
  PI := GetPropInfo(O, 'ObjField');
  Write('Property class      : ');
  Writeln(GetObjectPropClass(O, 'ObjField').ClassName);
  Write('Value                  : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  Write('Get (name)                : ');
  Writeln((GetObjectProp(O, 'ObjField') as TNamedObject).ObjectName);
  Write('Get (propinfo)             : ');
  Writeln((GetObjectProp(O, PI, TObject) as TNamedObject).ObjectName);
  SetObjectProp(O, 'ObjField', NO2);
  Write('Set (name, NO2)            : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  SetObjectProp(O, PI, NO1);
  Write('Set (propinfo, NO1)        : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  O.Free;
end.

```

31.7.10 GetObjectPropClass

Synopsis: Return class of property.

Declaration: `function GetObjectPropClass(Instance: TObject; const PropName: String)
: TClass`

Visibility: default

Description: `GetObjectPropClass` returns the declared class of the property with name `PropName`. This may not be the actual class of the property value.

For an example, see `GetObjectProp` (1439).

Errors: No checking is done whether `Instance` is non-nil. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1452), `GetOrdProp` (1441), `GetStrProp` (1446), `GetFloatProp` (1436), `GetInt64Prop` (1437)

31.7.11 GetOrdProp

Synopsis: Get the value of an ordinal property

Declaration: `function GetOrdProp(Instance: TObject; PropInfo: PPropInfo) : Int64
function GetOrdProp(Instance: TObject; const PropName: String) : Int64`

Visibility: default

Description: `GetOrdProp` returns the value of the ordinal property described by `PropInfo` or with name `PropName` for the object `Instance`. The value is returned as a longint, which should be typecasted to the needed type.

Ordinal properties that can be retrieved include:

Integers and subranges of integers The value of the integer will be returned.

Enumerated types and subranges of enumerated types The ordinal value of the enumerated type will be returned.

Sets If the base type of the set has less than 31 possible values. If a bit is set in the return value, then the corresponding element of the base ordinal class of the set type must be included in the set.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetOrdProp` (1453), `GetStrProp` (1446), `GetFloatProp` (1436), `GetInt64Prop` (1437), `GetMethodProp` (1437), `GetSetProp` (1445), `GetObjectProp` (1439), `GetEnumProp` (1434)

Listing: `./typinfex/ex1.pp`

```
program example1;

{ This program demonstrates the GetOrdProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
```

```

begin
  O:=TMyTestObject.Create;
  Writeln('Boolean property   : ');
  Writeln('Value              : ',O.BooleanField);
  Writeln('Ord(Value)           : ',Ord(O.BooleanField));
  Writeln('Get (name)               : ',GetOrdProp(O,'BooleanField'));
  PI:=GetPropInfo(O,'BooleanField');
  Writeln('Get (propinfo)           : ',GetOrdProp(O,PI));
  SetOrdProp(O,'BooleanField',Ord(False));
  Writeln('Set (name,false)         : ',O.BooleanField);
  SetOrdProp(O,PI,Ord(True));
  Writeln('Set (propinfo,true)      : ',O.BooleanField);
  O.Free;
end.

```

31.7.12 GetPropInfo

Synopsis: Return property type information, by property name.

Declaration: `function GetPropInfo(TypeInfo: PTypeInfo;const PropName: String) : PPropInfo`

```

function GetPropInfo(TypeInfo: PTypeInfo;const PropName: String;
  AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(Instance: TObject;const PropName: String;
  AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(Instance: TObject;const PropName: String)
  : PPropInfo
function GetPropInfo(AClass: TClass;const PropName: String;
  AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(AClass: TClass;const PropName: String) : PPropInfo

```

Visibility: default

Description: `GetPropInfo` returns a pointer to the `TPropInfo` record for a the `PropName` property of a class. The class to examine can be specified in one of three ways:

InstanceAn instance of the class.

AClassA class pointer to the class.

TypeInfoA pointer to the type information of the class.

In each of these three ways, if `AKinds` is specified, if the property has `TypeKind` which is not included in `Akinds`, `Nil` will be returned.

For an example, see most of the other functions.

Errors: If the property `PropName` does not exist, `Nil` is returned.

See also: `GetPropInfos` ([1442](#)), `GetPropList` ([1443](#))

31.7.13 GetPropInfos

Synopsis: Return a list of published properties.

Declaration: `procedure GetPropInfos(TypeInfo: PTypeInfo;PropList: PPropList)`

Visibility: default

Description: `GetPropInfos` stores pointers to the property information of all published properties of a class with class info `TypeInfo` in the list pointed to by `PropList`. The `PropList` pointer must point to a memory location that contains enough space to hold all properties of the class and its parent classes.

Errors: No checks are done to see whether `PropList` points to a memory area that is big enough to hold all pointers.

See also: `GetPropInfo` (1442), `GetPropList` (1443)

Listing: `./typinfex/ex12.pp`

Program `example12`;

{ This program demonstrates the GetPropInfos function }

uses

`rttiobj , typinfo ;`

Var

`O : TMyTestObject;`

`PT : PTypeData;`

PI : PTypeInfo;

`I, J : Longint;`

`PP : PPropList;`

`pri : PPropInfo;`

begin

`O := TMyTestObject.Create;`

PI := O.ClassInfo;

`PT := GetTypeData(PI);`

WriteIn('Property Count : ', PT^.PropCount);

GetMem (PP, PT^.PropCount***SizeOf**(Pointer));

`GetPropInfos(PI, PP);`

For I := 0 **to** PT^.PropCount-1 **do**

begin

With PP^[I]^ **do**

begin

Write('Property ', I+1:3, ': ', **name**:30);

writeln(' Type: ', TypeName[typinfo.PropertyType(O, **Name**)]);

end;

end;

FreeMem(PP);

O.**Free**;

end.

31.7.14 GetPropList

Synopsis: Return a list of a certain type of published properties.

Declaration: `function GetPropList (TypeInfo: PTypeInfo; TypeKinds: TTypeKinds;
PropList: PPropList; Sorted: Boolean) : LongInt`
`function GetPropList (TypeInfo: PTypeInfo; out PropList: PPropList)
: SizeInt`
`function GetPropList (AObject: TObject; out PropList: PPropList) : Integer`

Visibility: default

Description: Due to missing Variant support, GetPropValue is not yet implemented. The declaration is provided for compatibility with Delphi.

Errors:

31.7.16 GetSetProp

Synopsis: Return the value of a set property.

Declaration:

```
function GetSetProp(Instance: TObject; const PropName: String) : String
function GetSetProp(Instance: TObject; const PropName: String;
                    Brackets: Boolean) : String
function GetSetProp(Instance: TObject; const PropInfo: PPropInfo;
                    Brackets: Boolean) : String
```

Visibility: default

Description: GetSetProp returns the contents of a set property as a string. The property to be returned can be specified by its name in PropName or by its property information in PropInfo.

The returned set is a string representation of the elements in the set as returned by SetToString (1455). The Brackets option can be used to enclose the string representation in square brackets.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid ordinal property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: SetSetProp (1454), GetStrProp (1446), GetFloatProp (1436), GetInt64Prop (1437), GetMethodProp (1437)

Listing: ./typinfex/ex7.pp

```
program example7;

{ This program demonstrates the GetSetProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

Function SetAsString (ASet : TMyEnums) : String;

Var
  i : TmyEnum;

begin
  result := '';
  For i := mefirst to methird do
    If i in ASet then
      begin
        If (Result <> '') then
          Result := Result + ', ';
        Result := Result + MyEnumNames[i];
      end;
end;
```

```

        end;
end;

Var
    S : TMyEnums;

begin
    O:=TMyTestObject.Create;
    O.SetField:=[ mefirst ,meSecond,meThird];
    Writeln('Set property      : ');
    Writeln('Value                               : ',SetAsString(O.SetField));
    Writeln('Ord(Value)                               : ',Longint(O.SetField));
    Writeln('Get (name)                               : ',GetSetProp(O,'SetField'));
    PI:=GetPropInfo(O,'SetField');
    Writeln('Get (propinfo)                           : ',GetSetProp(O,PI,false));
    S:=[ meFirst ,meThird];
    SetOrdProp(O,'SetField',Integer(S));
    Write('Set (name,[ mefirst ,methird ]) : ');
    Writeln(SetAsString(O.SetField));
    S:=[meSecond];
    SetOrdProp(O,PI,Integer(S));
    Write('Set (propinfo,[meSecond])      : ');
    Writeln(SetAsString(O.SetField));
    O.Free;
end.

```

31.7.17 GetStrProp

Synopsis: Return the value of a string property.

Declaration: `function GetStrProp(Instance: TObject;PropInfo: PPropInfo) : Ansistring`
`function GetStrProp(Instance: TObject;const PropName: String) : String`

Visibility: default

Description: `GetStrProp` returns the value of the string property described by `PropInfo` or with name `PropName` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid string property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetStrProp` ([1455](#)), `SetWideStrProp` ([1456](#)), `GetOrdProp` ([1441](#)), `GetFloatProp` ([1436](#)), `GetInt64Prop` ([1437](#)), `GetMethodProp` ([1437](#))

Listing: `./typinfex/ex3.pp`

```

program example3;

{ This program demonstrates the GetStrProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
    O : TMyTestObject;

```

```

PI : PPropInfo;

begin
  O:= TMyTestObject.Create;
  PI:= GetPropInfo(O, 'AnsiStringField');
  Writeln('String property : ');
  Writeln('Value           : ',O.AnsiStringField);
  Writeln('Get (name)       : ',GetStrProp(O, 'AnsiStringField'));
  Writeln('Get (propinfo)    : ',GetStrProp(O, PI));
  SetStrProp(O, 'AnsiStringField', 'First');
  Writeln('Set (name, ''First'') : ',O.AnsiStringField);
  SetStrProp(O, PI, 'Second');
  Writeln('Set (propinfo, ''Second'') : ',O.AnsiStringField);
  O.Free;
end.

```

31.7.18 GetTypeData

Synopsis: Return a pointer to type data, based on type information.

Declaration: `function GetTypeData(TypeInfo: PTypeInfo) : PTypeData`

Visibility: default

Description: `GetTypeData` returns a pointer to the `TTypeData` record that follows after the `TTypeInfo` record pointed to by `TypeInfo`. It essentially skips the `Kind` and `Name` fields in the `TTypeInfo` record.

Errors: None.

31.7.19 GetVariantProp

Synopsis: Return the value of a variant property.

Declaration: `function GetVariantProp(Instance: TObject; PropInfo: PPropInfo) : Variant`
`function GetVariantProp(Instance: TObject; const PropName: String)`
`: Variant`

Visibility: default

Description: Due to missing Variant support, the `GetVariantProp` function is not yet implemented. Provided for Delphi compatibility only.

Errors:

See also: `SetVariantProp` ([1456](#))

31.7.20 GetWideStrProp

Synopsis: Read a widestring property

Declaration: `function GetWideStrProp(Instance: TObject; PropInfo: PPropInfo)`
`: WideString`
`function GetWideStrProp(Instance: TObject; const PropName: String)`
`: WideString`

Visibility: default

Description: `GetWideStrProp` returns the value of the widestring property described by `PropInfo` or with name `PropName` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid widestring property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetStrProp` (1446), `SetWideStrProp` (1456), `GetOrdProp` (1441), `GetFloatProp` (1436), `GetInt64Prop` (1437), `GetMethodProp` (1437)

31.7.21 IsPublishedProp

Synopsis: Check whether a published property exists.

Declaration:

```
function IsPublishedProp(Instance: TObject; const PropName: String)
    : Boolean
function IsPublishedProp(AClass: TClass; const PropName: String)
    : Boolean
```

Visibility: default

Description: `IsPublishedProp` returns true if a class has a published property with name `PropName`. The class can be specified in one of two ways:

AClass A class pointer to the class.

Instance An instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsStoredProp` (1449), `PropIsType` (1450)

Listing: `./typinfex/ex10.pp`

```
program example10;

{ This program demonstrates the IsPublishedProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O := TMyTestObject.Create;
  Writeln('Property tests      : ');
  Write('IsPublishedProp(O, BooleanField)      : ');
  Writeln(IsPublishedProp(O, 'BooleanField'));
  Write('IsPublishedProp(Class, BooleanField) : ');
  Writeln(IsPublishedProp(O.ClassType, 'BooleanField'));
  Write('IsPublishedProp(O, SomeField)      : ');
  Writeln(IsPublishedProp(O, 'SomeField'));
  Write('IsPublishedProp(Class, SomeField) : ');
```

```

    WriteLn ( IsPublishedProp (O. ClassType , ' SomeField ' ) );
    O. Free ;
end .

```

31.7.22 IsStoredProp

Synopsis: Check whether a property is stored.

Declaration: `function IsStoredProp (Instance: TObject; PropInfo: PPropInfo) : Boolean`
`function IsStoredProp (Instance: TObject; const PropName: String)`
`: Boolean`

Visibility: default

Description: `IsStoredProp` returns `True` if the `Stored` modifier evaluates to `True` for the property described by `PropInfo` or with name `PropName` for object `Instance`. It returns `False` otherwise. If the function returns `True`, this indicates that the property should be written when streaming the object `Instance`.

If there was no `stored` modifier in the declaration of the property, `True` will be returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` ([1448](#)), `PropIsType` ([1450](#))

Listing: `./typinfex/ex11.pp`

```

program example11 ;

{ This program demonstrates the IsStoredProp function }

{$mode objfpc}

uses rttiobj , typinfo ;

Var
    O : TMyTestObject ;
    PI : PPropInfo ;

begin
    O := TMyTestObject . Create ;
    WriteLn ( 'Stored tests      : ' );
    Write ( 'IsStoredProp (O, StoredIntegerConstFalse)      : ' );
    WriteLn ( IsStoredProp (O, ' StoredIntegerConstFalse ' ) );
    Write ( 'IsStoredProp (O, StoredIntegerConstTrue)       : ' );
    WriteLn ( IsStoredProp (O, ' StoredIntegerConstTrue ' ) );
    Write ( 'IsStoredProp (O, StoredIntegerMethod)           : ' );
    WriteLn ( IsStoredProp (O, ' StoredIntegerMethod ' ) );
    Write ( 'IsStoredProp (O, StoredIntegerVirtualMethod)    : ' );
    WriteLn ( IsStoredProp (O, ' StoredIntegerVirtualMethod ' ) );
    O. Free ;
end .

```

31.7.23 PropIsType

Synopsis: Check the type of a published property.

Declaration: `function PropIsType(Instance: TObject; const PropName: String;
TypeKind: TTypeKind) : Boolean`
`function PropIsType(AClass: TClass; const PropName: String;
TypeKind: TTypeKind) : Boolean`

Visibility: default

Description: `PropIsType` returns `True` if the property with name `PropName` has type `TypeKind`. It returns `False` otherwise. The class to be examined can be specified in one of two ways:

AClass A class pointer.

Instance An instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (1448), `IsStoredProp` (1449), `PropType` (1450)

Listing: `./typinfex/ex16.pp`

```
program example16;

{ This program demonstrates the PropIsType function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;

begin
  O := TMyTestObject.Create;
  Writeln('Property tests      : ');
  Write('PropIsType(O, BooleanField, tkBool)      : ');
  Writeln(PropIsType(O, 'BooleanField', tkBool));
  Write('PropIsType(Class, BooleanField, tkBool) : ');
  Writeln(PropIsType(O.ClassType, 'BooleanField', tkBool));
  Write('PropIsType(O, ByteField, tkString)      : ');
  Writeln(PropIsType(O, 'ByteField', tkString));
  Write('PropIsType(Class, ByteField, tkString) : ');
  Writeln(PropIsType(O.ClassType, 'ByteField', tkString));
  O.Free;
end.
```

31.7.24 PropType

Synopsis: Return the type of a property

Declaration: `function PropType(Instance: TObject; const PropName: String) : TTypeKind`
`function PropType(AClass: TClass; const PropName: String) : TTypeKind`

Visibility: default

Description: `PropType` returns the type of the property `PropName` for a class. The class to be examined can be specified in one of 2 ways:

AClass A class pointer.

Instance An instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (1448), `IsStoredProp` (1449), `PropIsType` (1450)

Listing: `./typinfex/ex17.pp`

```

program example17;

{ This program demonstrates the PropType function }

{$mode objfpc}

uses rttiobj , typinfo ;

Var
  O : TMyTestObject ;

begin
  O := TMyTestObject.Create ;
  Writeln ( 'Property tests      : ' );
  Write ( 'PropType(O, BooleanField)      : ' );
  Writeln ( TypeName[ PropType(O, ' BooleanField' ) ] );
  Write ( 'PropType(Class , BooleanField) : ' );
  Writeln ( TypeName[ PropType(O.ClassType, ' BooleanField' ) ] );
  Write ( 'PropType(O, ByteField)      : ' );
  Writeln ( TypeName[ PropType(O, ' ByteField' ) ] );
  Write ( 'PropType(Class , ByteField)   : ' );
  Writeln ( TypeName[ PropType(O.ClassType, ' ByteField' ) ] );
  O.Free ;
end.

```

31.7.25 SetEnumProp

Synopsis: Set value of an enumerated-type property

Declaration:

```

procedure SetEnumProp(Instance: TObject; const PropName: String;
                      const Value: String)
procedure SetEnumProp(Instance: TObject; const PropInfo: PPropInfo;
                      const Value: String)

```

Visibility: default

Description: `SetEnumProp` sets the property described by `PropInfo` or with name `PropName` to `Value`. `Value` must be a string with the name of the enumerate value, i.e. it can be used as an argument to `GetEnumValue` (1435).

For an example, see `GetEnumProp` (1434).

Errors: No checks are done to ensure `Instance` or `PropInfo` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetEnumProp \(1434\)](#), [SetStrProp \(1455\)](#), [SetFloatProp \(1452\)](#), [SetInt64Prop \(1452\)](#), [SetMethodProp \(1452\)](#)

31.7.26 SetFloatProp

Synopsis: Set value of a float property.

Declaration:

```
procedure SetFloatProp(Instance: TObject; const PropName: String;
                      Value: Extended)
procedure SetFloatProp(Instance: TObject; PropInfo: PPropInfo;
                      Value: Extended)
```

Visibility: default

Description: `SetFloatProp` assigns `Value` to the property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see [GetFloatProp \(1436\)](#).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetFloatProp \(1436\)](#), [SetOrdProp \(1453\)](#), [SetStrProp \(1455\)](#), [SetInt64Prop \(1452\)](#), [SetMethodProp \(1452\)](#)

31.7.27 SetInt64Prop

Synopsis: Set value of a Int64 property

Declaration:

```
procedure SetInt64Prop(Instance: TObject; PropInfo: PPropInfo;
                      const Value: Int64)
procedure SetInt64Prop(Instance: TObject; const PropName: String;
                      const Value: Int64)
```

Visibility: default

Description: `SetInt64Prop` assigns `Value` to the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see [GetInt64Prop \(1437\)](#).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetInt64Prop \(1437\)](#), [GetMethodProp \(1437\)](#), [SetOrdProp \(1453\)](#), [SetStrProp \(1455\)](#), [SetFloatProp \(1452\)](#)

31.7.28 SetMethodProp

Synopsis: Set the value of a method property

Declaration:

```
procedure SetMethodProp(Instance: TObject; PropInfo: PPropInfo;
                      const Value: TMethod)
procedure SetMethodProp(Instance: TObject; const PropName: String;
                      const Value: TMethod)
```

Visibility: default

Description: `SetMethodProp` assigns `Value` to the method the property described by `PropInfo` or with name `Propname` for object `Instance`.

The type `TMethod` of the `Value` parameter is defined in the `SysUtils` unit as:

```
TMethod = packed record
    Code, Data: Pointer;
end;
```

`Data` should point to the instance of the class with the method `Code`.

For an example, see `GetMethodProp` (1437).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetMethodProp` (1437), `SetOrdProp` (1453), `SetStrProp` (1455), `SetFloatProp` (1452), `SetInt64Prop` (1452)

31.7.29 SetObjectProp

Synopsis: Set the value of an object-type property.

Declaration:

```
procedure SetObjectProp(Instance: TObject; const PropName: String;
    Value: TObject)
procedure SetObjectProp(Instance: TObject; PropInfo: PPropInfo;
    Value: TObject)
```

Visibility: default

Description: `SetObjectProp` assigns `Value` to the the object property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetObjectProp` (1439).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetObjectProp` (1439), `SetOrdProp` (1453), `SetStrProp` (1455), `SetFloatProp` (1452), `SetInt64Prop` (1452), `SetMethodProp` (1452)

31.7.30 SetOrdProp

Synopsis: Set value of an ordinal property

Declaration:

```
procedure SetOrdProp(Instance: TObject; PropInfo: PPropInfo; Value: Int64)
procedure SetOrdProp(Instance: TObject; const PropName: String;
    Value: Int64)
```

Visibility: default

Description: `SetOrdProp` assigns `Value` to the the ordinal property described by `PropInfo` or with name `Propname` for the object `Instance`.

Ordinal properties that can be set include:

Integers and subranges of integersThe actual value of the integer must be passed.

Enumerated types and subranges of enumerated typesThe ordinal value of the enumerated type must be passed.

Subrange typesof integers or enumerated types. Here the ordinal value must be passed.

SetsIf the base type of the set has less than 31 possible values. For each possible value; the corresponding bit of `Value` must be set.

For an example, see `GetOrdProp` (1441).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetOrdProp` (1441), `SetStrProp` (1455), `SetFloatProp` (1452), `SetInt64Prop` (1452), `SetMethodProp` (1452)

31.7.31 SetPropValue

Synopsis: Set property value as variant

Declaration:

```
procedure SetPropValue(Instance: TObject; const PropName: String;
                      const Value: Variant)
```

Visibility: default

Description: Due to missing Variant support, this function is not yet implemented; it is provided for Delphi compatibility only.

Errors:

31.7.32 SetSetProp

Synopsis: Set value of set-typed property.

Declaration:

```
procedure SetSetProp(Instance: TObject; const PropName: String;
                    const Value: String)
procedure SetSetProp(Instance: TObject; const PropInfo: PPropInfo;
                    const Value: String)
```

Visibility: default

Description: `SetSetProp` sets the property specified by `PropInfo` or `PropName` for object `Instance` to `Value`. `Value` is a string which contains a comma-separated list of values, each value being a string-representation of the enumerated value that should be included in the set. The value should be accepted by the `StringToSet` (1457) function.

The value can be formed using the `SetToString` (1455) function.

For an example, see `GetSetProp` (1445).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetSetProp` (1445), `SetOrdProp` (1453), `SetStrProp` (1455), `SetFloatProp` (1452), `SetInt64Prop` (1452), `SetMethodProp` (1452), `SetToString` (1455), `StringToSet` (1457)

31.7.33 SetStrProp

Synopsis: Set value of a string property

Declaration: `procedure SetStrProp(Instance: TObject; const PropName: String;
 const Value: AnsiString)
 procedure SetStrProp(Instance: TObject; PropInfo: PPropInfo;
 const Value: Ansistring)`

Visibility: default

Description: `SetStrProp` assigns `Value` to the string property described by `PropInfo` or with name `Propname` for object `Instance`.

For an example, see `GetStrProp` ([1446](#))

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid string property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetStrProp` ([1446](#)), `SetWideStrProp` ([1456](#)), `SetOrdProp` ([1453](#)), `SetFloatProp` ([1452](#)), `SetInt64Prop` ([1452](#)), `SetMethodProp` ([1452](#))

31.7.34 SetToString

Synopsis: Convert set to a string description

Declaration: `function SetToString(TypeInfo: PTypeInfo; Value: Integer;
 Brackets: Boolean) : String
 function SetToString(PropInfo: PPropInfo; Value: Integer;
 Brackets: Boolean) : String
 function SetToString(PropInfo: PPropInfo; Value: Integer) : String`

Visibility: default

Description: `SetToString` takes an integer representation of a set (as received e.g. by `GetOrdProp`) and turns it into a string representing the elements in the set, based on the type information found in the `PropInfo` property information. By default, the string representation is not surrounded by square brackets. Setting the `Brackets` parameter to `True` will surround the string representation with brackets.

The function returns the string representation of the set.

Errors: No checking is done to see whether `PropInfo` points to valid property information.

See also: `GetEnumName` ([1433](#)), `GetEnumValue` ([1435](#)), `StringToSet` ([1457](#))

Listing: `./typinfex/ex18.pp`

```
program example18;

{ This program demonstrates the SetToString function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
```

```

    I : longint;

begin
    O:=TMyTestObject.Create;
    PI:=GetPropInfo(O,'SetField');
    O.SetField :=[ mefirst ,meSecond,meThird];
    I:=GetOrdProp(O,PI);
    WriteLn('Set property to string : ');
    WriteLn('Value   : ',SetToString(PI,I,False));
    O.SetField :=[ mefirst ,meSecond];
    I:=GetOrdProp(O,PI);
    WriteLn('Value   : ',SetToString(PI,I,True));
    I:=StringToSet(PI,'mefirst');
    SetOrdProp(O,PI,I);
    I:=GetOrdProp(O,PI);
    WriteLn('Value   : ',SetToString(PI,I,False));
    I:=StringToSet(PI,'[mesecond, methird]');
    SetOrdProp(O,PI,I);
    I:=GetOrdProp(O,PI);
    WriteLn('Value   : ',SetToString(PI,I,True));
    O.Free;
end.

```

31.7.35 SetVariantProp

Synopsis: Set value of a variant property

Declaration: `procedure SetVariantProp(Instance: TObject;const PropName: String;
 const Value: Variant)
 procedure SetVariantProp(Instance: TObject;PropInfo: PPropInfo;
 const Value: Variant)`

Visibility: default

Description: Due to missing Variant support, this function is not yet implemented. Provided for Delphi compatibility only.

Errors:

31.7.36 SetWideStrProp

Synopsis: Set a widestring property

Declaration: `procedure SetWideStrProp(Instance: TObject;const PropName: String;
 const Value: WideString)
 procedure SetWideStrProp(Instance: TObject;PropInfo: PPropInfo;
 const Value: WideString)`

Visibility: default

Description: SetWideStrProp assigns Value to the widestring property described by PropInfo or with name Propname for object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid widestring property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: [GetWideStrProp \(1447\)](#), [SetStrProp \(1455\)](#), [SetOrdProp \(1453\)](#), [SetFloatProp \(1452\)](#), [SetInt64Prop \(1452\)](#), [SetMethodProp \(1452\)](#)

31.7.37 StringToSet

Synopsis: Convert string description to a set.

Declaration: `function StringToSet (PropInfo: PPropInfo; const Value: String) : Integer`
`function StringToSet (TypeInfo: PTypeInfo; const Value: String) : Integer`

Visibility: default

Description: `StringToSet` converts the string representation of a set in `Value` to a integer representation of the set, using the property information found in `PropInfo`. This property information should point to the property information of a set property. The function returns the integer representation of the set. (i.e, the set value, typecast to an integer)

The string representation can be surrounded with square brackets, and must consist of the names of the elements of the base type of the set. The base type of the set should be an enumerated type. The elements should be separated by commas, and may be surrounded by spaces. each of the names will be fed to the [GetEnumValue \(1435\)](#) function.

For an example, see [SetToString \(1455\)](#).

Errors: No checking is done to see whether `PropInfo` points to valid property information. If a wrong name is given for an enumerated value, then an `EPropertyError` will be raised.

See also: [GetEnumName \(1433\)](#), [GetEnumValue \(1435\)](#), [SetToString \(1455\)](#)

31.8 EPropertyError

31.8.1 Description

Exception raised in case of an error in one of the functions.

Chapter 32

Reference for unit 'Unix'

32.1 Used units

Table 32.1: Used units by unit 'Unix'

Name	Page
BaseUnix	91
unixtype	1492

32.2 Constants, types and variables

32.2.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`fs_ext = $137d`

File system type (StatFS ([1488](#))): (ext) Extended

`fs_ext2 = $ef53`

File system type (StatFS ([1488](#))): (ext2) Second extended

`fs_iso = $9660`

File system type (StatFS ([1488](#))): ISO 9660

`fs_minix = $137f`

File system type (StatFS ([1488](#))): Minix

`fs_minix_30 = $138f`

File system type (StatFS (1488)): Minix 3.0

`fs_minix_V2 = $2468`

File system type (StatFS (1488)): Minix V2

`fs_msdos = $4d44`

File system type (StatFS (1488)): MSDOS (FAT)

`fs_nfs = $6969`

File system type (StatFS (1488)): NFS

`fs_old_ext2 = $ef51`

File system type (StatFS (1488)): (ext2) Old second extended

`fs_proc = $9fa0`

File system type (StatFS (1488)): PROC fs

`fs_xia = $012FD16D`

File system type (StatFS (1488)): XIA

`IOctl_TCGETS = $5401`

IOCTL call number: get Terminal Control settings

`LOCK_EX = 2`

FpFlock (1479) Exclusive lock

`LOCK_NB = 4`

FpFlock (1479) Non-blocking operation

`LOCK_SH = 1`

FpFlock (1479) Shared lock

`LOCK_UN = 8`

FpFlock (1479) unlock

`MAP_DENYWRITE = $800`

FpMMap (1458) option: Ignored.

`MAP_EXECUTABLE = $1000`

FpMMap (1458) option: Ignored.

MAP_FIXED = \$10

FpMMap (1458) map type: Interpret addr exactly

MAP_GROWSDOWN = \$100

FpMMap (1458) option: Memory grows downward (like a stack)

MAP_LOCKED = \$2000

FpMMap (1458) option: lock the pages in memory.

MAP_NORESERVE = \$4000

FpMMap (1458) option: Do not reserve swap pages for this memory.

MAP_SHARED = \$1

FpMMap (1458) map type: Share changes

MAP_TYPE = \$f

FpMMap (1458) map type: Bitmask for type of mapping

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

Open_Accmode = 3

Bitmask to determine access mode in open flags.

Open_Append = 2 shl 9

File open mode: Append to file

Open_Creat = 1 shl 6

File open mode: Create if file does not yet exist.

Open_Direct = 4 shl 12

File open mode: Minimize caching effects

Open_Directory = 2 shl 15

File open mode: File must be directory.

Open_Excl = 2 shl 6

File open mode: Open exclusively

`Open_LargeFile = 1 shl 15`

File open mode: Open for 64-bit I/O

`Open_NDelay = Open_NonBlock`

File open mode: Alias for `Open_NonBlock` ([1461](#))

`Open_NoCtty = 4 shl 6`

File open mode: No TTY control.

`Open_NoFollow = 4 shl 15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4 shl 9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1 shl 12`

File open mode: Write to disc at once

`Open_Trunc = 1 shl 9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`PROT_EXEC = $4`

`FpMMap` ([1458](#)) memory access: page can be executed

`PROT_NONE = $0`

FpMMap (1458) memory access: page can not be accessed

PROT_READ = \$1

FpMMap (1458) memory access: page can be read

PROT_WRITE = \$2

FpMMap (1458) memory access: page can be written

P_IN = 1

Input file descriptor of pipe pair.

P_OUT = 2

Output file descriptor of pipe pair.

SIG_MAXSIG = UnixType.SIG_MAXSIG

Maximum system signal number.

STAT_IFBLK = \$6000

File (#rtl.baseunix.stat (120) record) mode: Block device

STAT_IFCHR = \$2000

File (#rtl.baseunix.stat (120) record) mode: Character device

STAT_IFDIR = \$4000

File (#rtl.baseunix.stat (120) record) mode: Directory

STAT_IFIFO = \$1000

File (#rtl.baseunix.stat (120) record) mode: FIFO

STAT_IFLNK = \$a000

File (#rtl.baseunix.stat (120) record) mode: Link

STAT_IFMT = \$f000

File (#rtl.baseunix.stat (120) record) mode: File type bit mask

STAT_IFREG = \$8000

File (#rtl.baseunix.stat (120) record) mode: Regular file

STAT_IFSOCK = \$c000

File (#rtl.baseunix.stat (120) record) mode: Socket

STAT_IRGRP = STAT_IROTH shl 3

File (#rtl.baseunix.stat (120) record) mode: Group read permission

STAT_IROTH = \$4

File (#rtl.baseunix.stat (120) record) mode: Other read permission

STAT_IRUSR = STAT_IROTH shl 6

File (#rtl.baseunix.stat (120) record) mode: Owner read permission

STAT_IRWXG = STAT_IRW XO shl 3

File (#rtl.baseunix.stat (120) record) mode: Group permission bits mask

STAT_IRW XO = \$7

File (#rtl.baseunix.stat (120) record) mode: Other permission bits mask

STAT_IRWXU = STAT_IRW XO shl 6

File (#rtl.baseunix.stat (120) record) mode: Owner permission bits mask

STAT_ISGID = \$0400

File (#rtl.baseunix.stat (120) record) mode: GID bit set

STAT_ISUID = \$0800

File (#rtl.baseunix.stat (120) record) mode: UID bit set

STAT_ISVTX = \$0200

File (#rtl.baseunix.stat (120) record) mode: Sticky bit set

STAT_IWGRP = STAT_IWOTH shl 3

File (#rtl.baseunix.stat (120) record) mode: Group write permission

STAT_IWOTH = \$2

File (#rtl.baseunix.stat (120) record) mode: Other write permission

STAT_IWUSR = STAT_IWOTH shl 6

File (#rtl.baseunix.stat (120) record) mode: Owner write permission

STAT_IXGRP = STAT_IXOTH shl 3

File (#rtl.baseunix.stat (120) record) mode: Others execute permission

```
STAT_IXOTH = $1
```

File (#rtl.baseunix.stat (120) record) mode: Others execute permission

```
STAT_IXUSR = STAT_IXOTH shl 6
```

File (#rtl.baseunix.stat (120) record) mode: Others execute permission

```
SYS_NMLN = UnixType.SYS_NMLN
```

Max system name length.

```
Wait_Any = -1
```

#rtl.baseunix.fpWaitPID (176): Wait on any process

```
Wait_Clone = $800000000
```

#rtl.baseunix.fpWaitPID (176): Wait on clone processes only.

```
Wait_MyPGRP = 0
```

#rtl.baseunix.fpWaitPID (176): Wait processes from current process group

```
Wait_NoHang = 1
```

#rtl.baseunix.fpWaitPID (176): Do not wait

```
Wait_UnTraced = 2
```

#rtl.baseunix.fpWaitPID (176): Also report stopped but untraced processes

32.2.2 Types

```
cchar = UnixType.cchar
```

Alias for #rtl.UnixType.cchar (1493)

```
cDouble = UnixType.cDouble
```

Double precision real format.

```
cFloat = UnixType.cFloat
```

Floating-point real format

```
cInt = UnixType.cInt
```

C type: integer (natural size)

`cInt16 = UnixType.cInt16`

C type: 16 bits sized, signed integer.

`cInt32 = UnixType.cInt32`

C type: 32 bits sized, signed integer.

`cInt64 = UnixType.cInt64`

C type: 64 bits sized, signed integer.

`cInt8 = UnixType.cInt8`

C type: 8 bits sized, signed integer.

`clDouble = UnixType.clDouble`

Long double precision real format (Extended)

`clock_t = UnixType.clock_t`

Clock ticks type

`cLong = UnixType.cLong`

C type: long signed integer (double sized)

`cshort = UnixType.cshort`

C type: short signed integer (half sized)

`cuchar = UnixType.cuchar`

Alias for `#rtl.UnixType.cuchar` ([1494](#))

`cUInt = UnixType.cUInt`

C type: unsigned integer (natural size)

`cUInt16 = UnixType.cUInt16`

C type: 16 bits sized, unsigned integer.

`cUInt32 = UnixType.cUInt32`

C type: 32 bits sized, unsigned integer.

`cUInt64 = UnixType.cUInt64`

C type: 64 bits sized, unsigned integer.

```
cUInt8 = UnixType.cUInt8
```

C type: 8 bits sized, unsigned integer.

```
cuLong = UnixType.cuLong
```

C type: long unsigned integer (double sized)

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([1495](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
mode_t = UnixType.mode_t
```

Inode mode type.

```
nlink_t = UnixType.nlink_t
```

Number of links type.

```
off_t = UnixType.off_t
```

Offset type.

```
pcchar = UnixType.pcchar
```

Alias for `#rtl.UnixType.pcchar` ([1496](#))

```
pcDouble = UnixType.pcDouble
```

Pointer to `cdouble` ([112](#)) type.

```
pcFloat = UnixType.pcFloat
```

Pointer to cfloat (112) type.

```
pcInt = UnixType.pcInt
```

Pointer to cInt (1465) type.

```
pclDouble = UnixType.pclDouble
```

Pointer to cldouble (112) type.

```
pClock = UnixType.pClock
```

Pointer to TClock (1469) type.

```
pcLong = UnixType.pcLong
```

Pointer to cLong (1465) type.

```
pcshort = UnixType.pcsshort
```

Pointer to cShort (1465) type.

```
pcuchar = UnixType.pcuchar
```

Alias for #rtl.UnixType.pcuchar (1496)

```
pcUInt = UnixType.pcUInt
```

Pointer to cUInt (1465) type.

```
pculong = UnixType.pculong
```

Pointer to cuLong (1466) type.

```
pcunsigned = UnixType.pcunsigned
```

Alias for #rtl.unixtype.pcunsigned (1497)

```
pcushort = UnixType.pcushort
```

Pointer to cuShort (1466) type.

```
pDev = UnixType.pDev
```

Pointer to TDev (1469) type.

```
pGid = UnixType.pGid
```

Pointer to TGid (1470) type.

```
pid_t = UnixType.pid_t
```


Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (1470) type.

```
pMode = UnixType.pMode
```

Pointer to TMode (1470) type.

```
pnLink = UnixType.pnLink
```

Pointer to TnLink (1470) type.

```
pOff = UnixType.pOff
```

Pointer to TOff (1470) type.

```
pPid = UnixType.pPid
```

Pointer to TPid (1470) type.

```
pSize = UnixType.pSize
```

Pointer to TSize (1470) type.

```
pSocklen = UnixType.pSocklen
```

Pointer to TSockLen (1470) type.

```
psSize = UnixType.psSize
```

Pointer to TsSize (1470) type

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (1471) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (1470) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (1470) type.

```
ptime_t = UnixType.ptime_t
```

Pointer to time_t (1470) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (1471) type.

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
TClock = UnixType.TClock
```

Alias for clock_t (1465) type.

```
TDev = UnixType.TDev
```

Alias for dev_t (1466) type.

```
TFSearchOption = (NoCurrentDirectory, CurrentDirectoryFirst,  
                  CurrentDirectoryLast)
```

Table 32.2: Enumeration values for type TFSearchOption

Value	Explanation
CurrentDirectoryFirst	Search the current directory first, before all directories in the search path.
CurrentDirectoryLast	Search the current directory last, after all directories in the search path
NoCurrentDirectory	Do not search the current directory unless it is specified in the search path.

Describes the search strategy used by FSearch (1480)

```
TGid = UnixType.TGid
```

Alias for `gid_t` (1466) type.

```
timespec = UnixType.timespec
```

Short time specification type.

```
timeval = UnixType.timeval
```

Time specification type.

```
time_t = UnixType.time_t
```

Time span type

```
TIno = UnixType.TIno
```

Alias for `ino_t` (1466) type.

```
TMode = UnixType.TMode
```

Alias for `mode_t` (1466) type.

```
TnLink = UnixType.TnLink
```

Alias for `nlink_t` (1466) type.

```
TOff = UnixType.TOff
```

Alias for `off_t` (1466) type.

```
TPid = UnixType.TPid
```

Alias for `pid_t` (1468) type.

```
Tpipe = baseunix.tfildes
```

Array describing a pipe pair of filedescriptors.

```
TSize = UnixType.TSize
```

Alias for `size_t` (1469) type

```
TSocklen = UnixType.TSocklen
```

Alias for `socklen_t` (1469) type.

```
TsSize = UnixType.TsSize
```

Alias for `ssize_t` (1469) type

```
tstatfs = UnixType.TStatFs
```

Record describing a file system in the `baseunix.fpstatfs` (1458) call.

`TTime = UnixType.TTime`

Alias for `TTime` (1471) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (1470) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (1470) type.

`TUId = UnixType.TUId`

Alias for `uid_t` (1471) type.

`uid_t = UnixType.uid_t`

User ID type

32.2.3 Variables

`tzdaylight : Boolean`

Indicates whether daylight savings time is active.

`tzname : Array[boolean] of pchar`

Timezone name.

32.3 Procedures and functions

32.3.1 AssignPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function AssignPipe(var pipe_in: cInt; var pipe_out: cInt) : cInt`
`function AssignPipe(var pipe_in: text; var pipe_out: text) : cInt`
`function AssignPipe(var pipe_in: file; var pipe_out: file) : cInt`

Visibility: default

Description: `AssignPipe` creates a pipe, i.e. two file objects, one for input, one for output. What is written to `Pipe_out`, can be read from `Pipe_in`.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual `Readln(Pipe_in, ...)` and `Writeln(Pipe_out, ...)` procedures.

The function returns `True` if everything went successfully, `False` otherwise.

Errors: In case the function fails and returns `False`, extended error information is returned by the `FpGetErrno` (140) function:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `POpen` (1485), `#rtl.baseunix.FpMkFifo` (148)

Listing: `./unixex/ex36.pp`

Program `Example36`;

{ Program to demonstrate the AssignPipe function. }

Uses `BaseUnix, Unix`;

Var `pipi, pipo : Text;`
 `s : String;`

```
begin
  Writeln ( 'Assigning Pipes.' );
  If assignpipe (pipi, pipo) <> 0 then
    Writeln ( 'Error assigning pipes !', fpgeterrno );
  Writeln ( 'Writing to pipe, and flushing.' );
  Writeln ( pipo, 'This is a textstring' ); close (pipo);
  Writeln ( 'Reading from pipe.' );
  While not eof (pipi) do
    begin
      Readln ( pipi, s );
      Writeln ( 'Read from pipe : ', s );
    end;
  close ( pipi );
  writeln ( 'Closed pipes.' );
  writeln
end.
```

32.3.2 AssignStream

Synopsis: Assign stream for in and output to a program

Declaration:

```
function AssignStream (var StreamIn: text; var Streamout: text;
                      const Prog: ansiString;
                      const args: Array[] of ansistring) : cInt
function AssignStream (var StreamIn: text; var Streamout: text;
                      var streamerr: text; const Prog: ansiString;
                      const args: Array[] of ansistring) : cInt
```

Visibility: default

Description: `AssignStream` creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output, (and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of `Prog`. `Prog` is the name of a program (including path) with options, which will be executed.

What is written to `StreamOut`, will go to the standard input of `Prog`. Whatever is written by `Prog` to its standard output can be read from `StreamIn`. Whatever is written by `Prog` to its standard error read from `StreamErr`, if present.

Reading and writing happens through the usual `Readln (StreamIn, ...)` and `Writeln (StreamOut, ...)` procedures.

Remark: You should *not* use `Reset` or `Rewrite` on a file opened with `POpen`. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: Extended error information is returned by the `FpGetErrno` (140) function.

sys_emfile Too many file descriptors for this process.

sys_emfile The system file table is full.

Other errors include the ones by the `fork` and `exec` programs

See also: `AssignPipe` (1471), `POpen` (1485)

Listing: ./unixex/ex38.pp

Program Example38;

{ Program to demonstrate the AssignStream function. }

Uses BaseUnix, Unix;

Var Si, So : Text;

S : **String**;

i : longint;

begin

if not (paramstr(1) = '-son') then

begin

Writeln ('Calling son');

Assignstream (Si, So, './ex38 -son');

if fpgeterrno <> 0 then

begin

writeln ('AssignStream failed !');

halt(1);

end;

Writeln ('Speaking to son');

For i:=1 to 10 do

begin

writeln (so, 'Hello son !');

if ioreult <> 0 then writeln ('Can''t speak to son...');

end;

For i:=1 to 3 do writeln (so, 'Hello chap !');

close (so);

while not eof(Si) do

begin

readln (Si, s);

writeln ('Father: Son said : ', S);

end;

Writeln ('Stopped conversation');

Close (Si);

Writeln ('Put down phone');

end

Else

begin

Writeln ('This is the son');

While not eof (input) do

```

begin
  readln (s);
  if pos ('Hello son !',S)<>0 then
    Writeln ('Hello Dad !')
  else
    writeln ('Who are you ?');
  end;
  close (output);
end
end.

```

32.3.3 FpExecL

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecL(const PathName: AnsiString;
const S: Array[] of AnsiString) : cInt`

Visibility: default

Description: `FpExecL` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The current process' environment is passed to the program. On success, `FpExecL` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fpexecve` (134), `FpExecv` (1476), `FpExecvp` (1477), `FpExecle` (1475), `FpExeclp` (1475), `#rtl.baseunix.FpFork` (137)

Listing: `./unixex/ex77.pp`

Program Example77;

{ Program to demonstrate the FPExecL function. }

Uses Unix, strings;

```

begin
  { Execute 'ls -l', with current environment. }
  { 'ls' is NOT looked for in PATH environment variable. }
  FpExecL ('/bin/ls', ['-l']);
end.

```

32.3.4 FpExecLE

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecLE(const PathName: AnsiString;
const S: Array[] of AnsiString; MyEnv: ppchar) : cInt`

Visibility: default

Description: `FpExecLE` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The environment in `MyEnv` is passed to the program. On success, `FpExecLE` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fpexecve` (134), `FpExecv` (1476), `FpExecvp` (1477), `FpExecl` (1474), `FpExeclp` (1475), `#rtl.baseunix.FpFork` (137)

Listing: `./unixex/ex11.pp`

Program Example11;

{ Program to demonstrate the Execle function. }

Uses Unix, strings;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is NOT looked for in PATH environment variable. }
{ envp is defined in the system unit. }
 Execle ('/bin/ls -l', envp);

end.

32.3.5 FpExecLP

Synopsis: Execute process (using argument list, environment; search path)

Declaration: `function FpExecLP(const PathName: AnsiString;
const S: Array[] of AnsiString) : cInt`

Visibility: default

Description: `FpExecLP` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, `FpExecLP` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eLOOPThe path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fplexecve` (134), `FpExecv` (1476), `FpExecvp` (1477), `FpExecle` (1475), `FpExecl` (1474), `#rtl.baseunix.FpFork` (137)

Listing: `./unixex/ex76.pp`

Program `Example76`;

{ Program to demonstrate the FpExeclp function. }

Uses `Unix`, `strings`;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
{ envp is defined in the system unit. }
`FpExeclp ('ls', ['-l']);`

end.

32.3.6 FpExecV

Synopsis: Execute process

Declaration: `function FpExecV(const PathName: AnsiString; args: ppchar) : cInt`

Visibility: default

Description: `FpExecV` replaces the currently running program with the program, specified in `PathName`. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `FpExecV` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdir A component of the path is not a directory.

sys_eloop The path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fpexecve` (134), `FpExecvp` (1477), `FpExecle` (1475), `FpExecl` (1474), `FpExeclp` (1475), `#rtl.baseunix.FpFork` (137)

Listing: ./unixex/ex8.pp

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/lS';
Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP, 3 * **SizeOf** (Pchar));

 PP[0] := Arg0;

 PP[1] := Arg1;

 PP[3] := **Nil**;

{ Execute '/bin/lS -l', with current environment }

 fpExecv ('/bin/lS', pp);

end.

32.3.7 FpExecVP

Synopsis: Execute process, search path

Declaration: `function FpExecVP(const PathName: AnsiString; args: ppchar) : cInt`

Visibility: default

Description: `FpExecVP` replaces the currently running program with the program, specified in `PathName`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. The current environment is passed to the program. On success, `execvp` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

sys_eaccess File is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_eperm The file system is mounted *noexec*.

sys_e2big Argument list too big.

sys_enoexec The magic number in the file is incorrect.

sys_enoent The file does not exist.

sys_enomem Not enough memory for kernel.

sys_enotdir A component of the path is not a directory.

sys_eloop The path contains a circular reference (via symlinks).

See also: [#rtl.baseunix.fplexecve \(134\)](#), [FpExecv \(1476\)](#), [FpExecle \(1475\)](#), [FpExecl \(1474\)](#), [FpExeclp \(1475\)](#), [#rtl.baseunix.FpFork \(137\)](#)

Listing: ./unixex/ex79.pp

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix , strings ;

```
Const Arg0 : PChar = 'ls';
        Arg1 : Pchar = '-l';
```

```
Var PP : PPchar;
```

```
begin
  GetMem (PP,3*SizeOf(Pchar));
  PP[0]:=Arg0;
  PP[1]:=Arg1;
  PP[2]:=Nil;
  { Execute 'ls -l', with current environment. }
  { 'ls' is looked for in PATH environment variable. }
  fpExecvp ('ls',pp);
end.
```

32.3.8 FpExecVPE

Synopsis: Execute process, search path using environment

```
Declaration: function FpExecVPE(const PathName: AnsiString;args: ppchar;env: ppchar)
                : cInt
```

Visibility: default

Description: `FpExecVP` replaces the currently running program with the program, specified in `PathName`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. The environment in `Env` is passed to the program. On success, `execvp` does not return.

Errors: Extended error information is returned by the `FpGetErrno` ([140](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: #rtl.baseunix.fpexecve (134), FpExecv (1476), FpExecle (1475), FpExecl (1474), FpExeclp (1475), #rtl.baseunix.FpFork (137)

Listing: ./unixex/ex79.pp

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP, 3*SizeOf (Pchar));
PP[0] := Arg0;
PP[1] := Arg1;
PP[2] := Nil;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
fpExecvp ('ls', pp);

end.

32.3.9 fpFlock

Synopsis: Lock a file (advisory lock)

Declaration: function fpFlock(fd: cInt; mode: cInt) : cInt
function fpFlock(var T: text; mode: cInt) : cInt
function fpFlock(var F: File; mode: cInt) : cInt

Visibility: default

Description: FpFlock implements file locking. it sets or removes a lock on the file F. F can be of type Text or File, or it can be a linux filedescriptor (a longint) Mode can be one of the following constants :

LOCK_SH sets a shared lock.

LOCK_EX sets an exclusive lock.

LOCK_UN unlocks the file.

LOCK_NB This can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns zero if successful, a nonzero return value indicates an error.

Errors: Extended error information is returned by the FpGetErrno (140) function:

See also: #rtl.baseunix.FpFcntl (135), FSync (1482)

32.3.10 fpgettimeofday

Synopsis: Return kernel time of day in GMT

Declaration: `function fpgettimeofday(tp: ptimeval;tzp: ptimzone) : cInt`

Visibility: default

Description: `FpGetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

Errors: None.

32.3.11 fpSystem

Synopsis: Execute and feed command to system shell

Declaration: `function fpSystem(const Command: AnsiString) : cInt`

Visibility: default

Description: `Shell` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the `FpFork` (137) or `FpExecve` (134) calls.

Errors: Errors are reported in `LinuxError`.

See also: `POpen` (1485), `Shell` (1487), `#rtl.baseunix.FpFork` (137), `#rtl.baseunix.fpexecve` (134)

Listing: `./unixex/ex80.pp`

```

program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  Writeln ( 'Output of ls -l *.pp' );
  S:=fpSystem( 'ls -l *.pp' );
  Writeln ( 'Command exited with status : ',S);
end.

```

32.3.12 FSearch

Synopsis: Search for file in search path.

Declaration: `function FSearch(const path: AnsiString;dirlist: Ansistring;
CurrentDirStrategy: TFSearchOption) : AnsiString`
`function FSearch(const path: AnsiString;dirlist: AnsiString)
: AnsiString`

Visibility: default

Description: `FSearch` searches in `DirList`, a colon separated list of directories, for a file named `Path`. It then returns a path to the found file.

The `CurrentDirStrategy` determines how the current directory is treated when searching:

NoCurrentDirectory Do not search the current directory unless it is specified in the search path.

CurrentDirectoryFirstSearch the current directory first, before all directories in the search path.

CurrentDirectoryLastSearch the current directory last, after all directories in the search path

It is mainly provided to mimic DOS search path behaviour. Default behaviour is to search the current directory first.

Errors: An empty string if no such file was found.

See also: `#rtl.unixutil.FNMatch` ([1507](#))

Listing: `./unixex/ex46.pp`

Program `Example46`;

{ Program to demonstrate the FSearch function. }

Uses `BaseUnix`, `Unix`, `Strings`;

begin

WriteLn ('Is is in : ', `FSearch` ('Is', **strpas**(`fpGetenv`('PATH'))));

end.

32.3.13 fStatFS

Synopsis: Retrieve filesystem information from a file descriptor.

Declaration: `function fStatFS(Fd: cInt; var Info: tstatfs) : cInt`

Visibility: `default`

Description: `fStatFS` returns in `Info` information about the filesystem on which the file with file descriptor `fd` resides. `Info` is of type `TStatFS` ([1502](#)).

The function returns zero if the call was succesful, a nonzero value is returned if the call failed.

Errors: Extended error information is returned by the `FpGetErrno` ([140](#)) function:

sys_enotdir A component of `Path` is not a directory.

sys_einval Invalid character in `Path`.

sys_enoent `Path` does not exist.

sys_eaccess Search permission is denied for component in `Path`.

sys_eloop A circular symbolic link was encountered in `Path`.

sys_eio An error occurred while reading from the filesystem.

See also: `StatFS` ([1488](#)), `#rtl.baseunix.FpLStat` ([146](#))

Listing: `./unixex/ex91.pp`

```

program Example30;

{ Program to demonstrate the FSStat function. }

uses BaseUnix, Unix, UnixType;

var s : string;
    fd : cint;
    info : tstatfs;

begin
    writeln ( 'Info about current partition : ' );
    s := ' . ' ;
    while s <> 'q' do
        begin
            Fd := fpOpen(S, O_RDONLY);
            if (fd >= 0) then
                begin
                    if fstatfs (fd, info) <> 0 then
                        begin
                            writeln ( 'Fstat failed. Errno : ', fpgeterrno );
                            halt (1);
                        end;
                    FpClose(fd);
                    writeln;
                    writeln ( 'Result of fsstat on file ' ''', s, ''' . ' );
                    writeln ( 'fstype   : ', info.fstype );
                    writeln ( 'bsize    : ', info.bsize );
                    writeln ( 'bfree    : ', info.bfree );
                    writeln ( 'bavail   : ', info.bavail );
                    writeln ( 'files     : ', info.files );
                    writeln ( 'ffree    : ', info.ffree );
                    { $ifdef FreeBSD }
                    writeln ( 'fsid      : ', info.fsid [0] );
                    { $else }
                    writeln ( 'fsid      : ', info.fsid [0] );
                    writeln ( 'Namelen  : ', info.namelen );
                    { $endif }
                    write ( 'Type name of file to do fsstat. (q quits) : ' );
                    readln (s)

                end;
            end;
        end.

```

32.3.14 fsync

Synopsis: Synchronize file's kernel data with disk.

Declaration: `function fsync(fd: cInt) : cInt`

Visibility: default

Description: `FSync` synchronizes the kernel data for file `fd` (the cache) with the disk. The call will not return till all file data was written to disk.

If the call was succesfull, 0 is returned. On failure, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

See also: `FpFLock` (1479)

32.3.15 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : String`

Visibility: default

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` (1483)

Listing: `./unixex/ex39.pp`

Program `Example39;`

{ Program to demonstrate the GetDomainName function. }

Uses `Unix;`

begin

`WriteLn ('Domain name of this machine is : ',GetDomainName);`
end.

32.3.16 GetHostName

Synopsis: Return host name

Declaration: `function GetHostName : String`

Visibility: default

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: `GetDomainName` (1483)

Listing: `./unixex/ex40.pp`

Program `Example40;`

{ Program to demonstrate the GetHostName function. }

Uses `unix;`

begin

`WriteLn ('Name of this machine is : ',GetHostName);`
end.

32.3.17 GetLocalTimezone

Synopsis: Return local timzeone information

Declaration: `procedure GetLocalTimezone(timer: cInt; var leap_correct: cInt;
var leap_hit: cInt)
procedure GetLocalTimezone(timer: cInt)`

Visibility: default

Description: `GetLocalTimezone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` ([1484](#)), `ReadTimezoneFile` ([1486](#))

32.3.18 GetTimezoneFile

Synopsis: Return name of timezone information file

Declaration: `function GetTimezoneFile : String`

Visibility: default

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` ([1486](#))

32.3.19 PClose

Synopsis: Close file opened with `POpen` ([1485](#))

Declaration: `function PClose(var F: file) : cInt
function PClose(var F: text) : cInt`

Visibility: default

Description: `PClose` closes a file opened with `POpen` ([1485](#)). It waits for the command to complete, and then returns the exit status of the command.

For an example, see `POpen` ([1485](#))

Errors: Extended error information is returned by the `FpGetErrno` ([140](#)) function.

See also: `POpen` ([1485](#))

32.3.20 POpen

Synopsis: Pipe file to standard input/output of program

Declaration: `function POpen(var F: text;const Prog: Ansistring;rw: Char) : cInt`
`function POpen(var F: file;const Prog: Ansistring;rw: Char) : cInt`

Visibility: default

Description: `POpen` runs the command specified in `Prog`, and redirects the standard in or output of the command to the other end of the pipe `F`. The parameter `rw` indicates the direction of the pipe. If it is set to 'W', then `F` can be used to write data, which will then be read by the command from `stdin`. If it is set to 'R', then the standard output of the command can be read from `F`. `F` should be reset or rewritten prior to using it. `F` can be of type `Text` or `File`. A file opened with `POpen` can be closed with `Close`, but also with `PClose` (1484). The result is the same, but `PClose` returns the exit status of the command `Prog`.

Errors: Extended error information is returned by the `FpGetErrno` (140) function. Errors are essentially those of the `Execve`, `Dup` and `AssignPipe` commands.

See also: `AssignPipe` (1471), `PClose` (1484)

Listing: `./unixex/ex37.pp`

Program Example37;

{ Program to demonstrate the Popen function. }

uses BaseUnix, Unix;

var f : text;
i : longint;

begin

```
writeln ('Creating a shell script to which echoes its arguments');
writeln ('and input back to stdout');
assign (f, 'test21a ');
rewrite (f);
writeln (f, '#!/bin/sh');
writeln (f, 'echo this is the child speaking.... ');
writeln (f, 'echo got arguments \*"${*}"\* ');
writeln (f, 'cat');
writeln (f, 'exit 2');
writeln (f);
close (f);
fpchmod ('test21a ', &755);
popen (f, './test21a arg1 arg2 ', 'W');
if fpgeterrno <> 0 then
  writeln ('error from POpen : errno : ', fpgeterrno);
for i:=1 to 10 do
  writeln (f, 'This is written to the pipe , and should appear on stdout. ');
Flush(f);
Writeln ('The script exited with status : ', PClose (f));
writeln;
writeln ('Press <return> to remove shell script. ');
readln;
assign (f, 'test21a ');
erase (f)
```

end.

32.3.21 ReadTimezoneFile

Synopsis: Read the timezone file and initialize time routines

Declaration: `procedure ReadTimezoneFile(fn: String)`

Visibility: default

Description: `ReadTimezoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimezoneFile` (1484), `GetLocalTimezone` (1484)

32.3.22 SeekDir

Synopsis: Seek to position in directory

Declaration: `procedure SeekDir(p: pDir; loc: cLong)`

Visibility: default

Description: `SeekDir` sets the directory pointer to the `loc`-th entry in the directory structure pointed to by `p`.

For an example, see `#rtl.baseunix.fpOpenDir` (153).

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

See also: `#rtl.baseunix.fpCloseDir` (130), `#rtl.baseunix.fpReadDir` (157), `#rtl.baseunix.fpOpenDir` (153), `TellDir` (1489)

32.3.23 SelectText

Synopsis: Wait for event on text file.

Declaration: `function SelectText(var T: Text; TimeOut: ptimeval) : cInt`
`function SelectText(var T: Text; TimeOut: cInt) : cInt`

Visibility: default

Description: `SelectText` executes the `FpSelect` (160) call on a file of type `Text`. You can specify a timeout in `TimeOut`. The `SelectText` call determines itself whether it should check for read or write, depending on how the file was opened : With `Reset` it is checked for reading, with `Rewrite` and `Append` it is checked for writing.

Errors: See `#rtl.baseunix.FpSelect` (160). `SYS_EBADF` can also mean that the file wasn't opened.

See also: `#rtl.baseunix.FpSelect` (160)

32.3.24 Shell

Synopsis: Execute and feed command to system shell

Declaration: `function Shell(const Command: String) : cInt`
`function Shell(const Command: AnsiString) : cInt`

Visibility: default

Description: `Shell` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the `FpFork` (137) or `FpExecve` (134) calls.

Errors: Extended error information is returned by the `FpGetErrno` (140) function:

See also: `POpen` (1485), `FpSystem` (1480), `#rtl.baseunix.FpFork` (137), `#rtl.baseunix.fpexecve` (134)

Listing: `./unixex/ex56.pp`

```

program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  WriteLn ( 'Output of ls -l *.pp' );
  S:=Shell ( 'ls -l *.pp' );
  WriteLn ( 'Command exited with status : ',S);
end.

```

32.3.25 SigRaise

Synopsis: Raise a signal (send to current process)

Declaration: `procedure SigRaise(sig: Integer)`

Visibility: default

Description: `SigRaise` sends a `Sig` signal to the current process.

Errors: None.

See also: `#rtl.baseunix.FpKill` (144), `#rtl.baseunix.FpGetPid` (142)

Listing: `./unixex/ex65.pp`

```

Program example64;

{ Program to demonstrate the SigRaise function. }

uses Unix, BaseUnix;

Var
  oa, na : PSigActionRec;

Procedure DoSig(sig : Longint); cdecl;

```

```

begin
  writeln('Receiving signal: ',sig);
end;

begin
  new(na);
  new(oa);
  na^.sa_handler:=TSigaction(@DoSig);
  fillchar(na^.Sa_Mask,sizeof(na^.Sa_Mask),#0);
  na^.Sa_Flags:=0;
  {$ifdef Linux}
  // this member is linux only, and afaik even there arcane
  na^.Sa_Restorer:=Nil;
  {$endif}
  if fpSigAction(SigUsr1,na,oa)<>0 then
    begin
      writeln('Error: ',fpgeterrno);
      halt(1);
    end;
    Writeln('Sending USR1 (',sigusr1,') signal to self. ');
    SigRaise(sigusr1);
  end.

```

32.3.26 StatFS

Synopsis: Retrieve filesystem information from a path.

Declaration: `function StatFS(Path: pchar;var Info: tstatfs) : cInt`
`function StatFS(Path: ansistring;var Info: tstatfs) : cInt`

Visibility: default

Description: StatFS returns in Info information about the filesystem on which the file Path resides. Info is of type TStatFS (1502).

The function returns zero if the call was succesful, a nonzero value is returned if the call failed.

Errors: Extended error information is returned by the FpGetErrno (140) function:

sys_enotdirA component of Path is not a directory.
sys_einvalInvalid character in Path.
sys_enoentPath does not exist.
sys_eaccessSearch permission is denied for component inPath.
sys_eloopA circular symbolic link was encountered in Path.
sys_eioAn error occurred while reading from the filesystem.

See also: #rtl.baseunix.FpStat (168), #rtl.baseunix.FpLStat (146)

Listing: ./unixex/ex91.pp

```

program Example30;

{ Program to demonstrate the FSStat function. }

uses BaseUnix, Unix, UnixType;

```

```

var s : string;
    fd : cint;
    info : tstatfs;

begin
    writeln ( 'Info about current partition : ' );
    s:= '.';
    while s<>'q' do
        begin
            Fd:=fpOpen(S,O_RDONLY);
            if (fd>=0) then
                begin
                    if fstatfs (fd,info)<>0 then
                        begin
                            writeln('Fstat failed. Errno : ',fpgeterrno);
                            halt (1);
                        end;
                    FpClose(fd);
                    writeln;
                    writeln ( 'Result of fsstat on file ',s,'.' );
                    writeln ( 'fstype   : ',info.fstype);
                    writeln ( 'bsize    : ',info.bsize);
                    writeln ( 'bfree   : ',info.bfree);
                    writeln ( 'bavail  : ',info.bavail);
                    writeln ( 'files   : ',info.files);
                    writeln ( 'ffree   : ',info.ffree);
                    {$ifdef FreeBSD}
                    writeln ( 'fsid     : ',info.fsid[0]);
                    {$else}
                    writeln ( 'fsid     : ',info.fsid[0]);
                    writeln ( 'Namelen  : ',info.namelen);
                    {$endif}
                    write ( 'Type name of file to do fsstat. (q quits) : ');
                    readln (s)

                end;
            end;
        end;
    end.

```

32.3.27 Telldir

Synopsis: Return current location in a directory

Declaration: `function Telldir(p: pDir) : TOff`

Visibility: default

Description: `Telldir` returns the current location in the directory structure pointed to by `p`. It returns -1 on failure.

For an example, see `#rtl.baseunix.fpOpenDir` ([153](#)).

Errors:

See also: `#rtl.baseunix.fpCloseDir` ([130](#)), `#rtl.baseunix.fpReadDir` ([157](#)), `#rtl.baseunix.fpOpenDir` ([153](#)), `SeekDir` ([1486](#))

32.3.28 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: `function WaitProcess(Pid: cInt) : cInt`

Visibility: default

Description: `WaitProcess` waits for process `PID` to exit. `WaitProcess` is equivalent to the `#rtl.baseunix.FpWaitPID` (176) call:

```
FpWaitPid(PID, @result, 0)
```

Handles of Signal interrupts (`errno=EINTR`), and returns the Exitcode of Process `PID` (`>=0`) or - Status if it was terminated

Errors: None.

See also: `#rtl.baseunix.FpWaitPID` (176), `#rtl.baseunix.WTERMSIG` (178), `#rtl.baseunix.WSTOPSIG` (178), `#rtl.baseunix.WIFEXITED` (177), `WIFSTOPPED` (1490), `#rtl.baseunix.WIFSIGNALED` (178), `W_EXITCODE` (1490), `W_STOPCODE` (1491), `#rtl.baseunix.WEXITSTATUS` (177)

32.3.29 WIFSTOPPED

Synopsis: Check whether the process is currently stopped.

Declaration: `function WIFSTOPPED(Status: Integer) : Boolean`

Visibility: default

Description: `WIFSTOPPED` checks `Status` and returns `true` if the process is currently stopped. This is only possible if `WUNTRACED` was specified in the options of `FpWaitPID` (176).

See also: `#rtl.baseunix.FpWaitPID` (176), `WaitProcess` (1490), `#rtl.baseunix.WTERMSIG` (178), `#rtl.baseunix.WSTOPSIG` (178), `#rtl.baseunix.WIFEXITED` (177), `#rtl.baseunix.WIFSIGNALED` (178), `W_EXITCODE` (1490), `W_STOPCODE` (1491), `#rtl.baseunix.WEXITSTATUS` (177)

32.3.30 W_EXITCODE

Synopsis: Construct an exit status based on an return code and signal.

Declaration: `function W_EXITCODE(ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

Description: `W_EXITCODE` combines `ReturnCode` and `Signal` to a status code fit for `WaitPid`.

See also: `#rtl.baseunix.FpWaitPID` (176), `WaitProcess` (1490), `#rtl.baseunix.WTERMSIG` (178), `#rtl.baseunix.WSTOPSIG` (178), `#rtl.baseunix.WIFEXITED` (177), `WIFSTOPPED` (1490), `#rtl.baseunix.WIFSIGNALED` (178), `W_EXITCODE` (1490), `W_STOPCODE` (1491), `#rtl.baseunix.WEXITSTATUS` (177)

32.3.31 W_STOPCODE

Synopsis: Construct an exit status based on a signal.

Declaration: `function W_STOPCODE(Signal: Integer) : Integer`

Visibility: default

Description: `W_STOPCODE` constructs an exit status based on `Signal`, which will cause `WIFSIGNALED` (178) to return `True`

See also: `#rtl.baseunix.FpWaitPID` (176), `WaitProcess` (1490), `#rtl.baseunix.WTERMSIG` (178), `#rtl.baseunix.WSTOPSIG` (178), `#rtl.baseunix.WIFEXITED` (177), `WIFSTOPPED` (1490), `#rtl.baseunix.WIFSIGNALED` (178), `W_EXITCODE` (1490), `#rtl.baseunix.WEXITSTATUS` (177)

Chapter 33

Reference for unit 'unixtype'

33.1 Overview

The `unixtype` unit contains the definitions of basic unix types. It was initially implemented by Marco van de Voort.

When porting to a new unix platform, this unit should be adapted to the sizes and conventions of the platform to which the compiler is ported.

33.2 Constants, types and variables

33.2.1 Constants

`ARG_MAX = 131072`

Max number of command-line arguments.

`NAME_MAX = 255`

Max length (in bytes) of filename

`PATH_MAX = 4095`

Max length (in bytes) of pathname

`Prio_PGrp = 1`

`rtl.unix.fpGetPriority` ([1492](#)) option: Get process group priority.

`Prio_Process = 0`

`#rtl.unix.fpGetPriority` ([1458](#)) option: Get process priority.

`Prio_User = 2`

`#rtl.unix.fpGetPriority` ([1458](#)) option: Get user priority.

`SIG_MAXSIG = 128`

Maximum signal number.

`SYS_NMLN = 65`

Max system namelength

`_PTHREAD_MUTEX_ADAPTIVE_NP = 3`

Mutex options:

`_PTHREAD_MUTEX_DEFAULT = _PTHREAD_MUTEX_NORMAL`

Mutex options:

`_PTHREAD_MUTEX_ERRORCHECK = _PTHREAD_MUTEX_ERRORCHECK_NP`

Mutex options:

`_PTHREAD_MUTEX_ERRORCHECK_NP = 2`

Mutex options: double lock returns an error code.

`_PTHREAD_MUTEX_FAST_NP = _PTHREAD_MUTEX_ADAPTIVE_NP`

Mutex options: Fast mutex

`_PTHREAD_MUTEX_NORMAL = _PTHREAD_MUTEX_TIMED_NP`

Mutex options:

`_PTHREAD_MUTEX_RECURSIVE = _PTHREAD_MUTEX_RECURSIVE_NP`

Mutex options:

`_PTHREAD_MUTEX_RECURSIVE_NP = 1`

Mutex options: recursive mutex

`_PTHREAD_MUTEX_TIMED_NP = 0`

Mutex options: ?

33.2.2 Types

`cchar = ShortInt`

C type: 8-bit signed integer

`cDouble = Double`

Double precision real format.

`cFloat = Single`

Floating-point real format

`cInt = LongInt`

C type: integer (natural size)

`cInt16 = SmallInt`

C type: 16 bits sized, signed integer.

`cInt32 = LongInt`

C type: 32 bits sized, signed integer.

`cInt64 = Int64`

C type: 64 bits sized, signed integer.

`cInt8 = ShortInt`

C type: 8 bits sized, signed integer.

`clDouble = Extended`

Long double precision real format (Extended)

`clock_t = cuLong`

Clock ticks type

`cLong = LongInt`

C type: long signed integer (double sized)

`clonglong = Int64`

C type: 64-bit (double long) signed integer.

`cshort = SmallInt`

C type: short signed integer (half sized)

`cuchar = Byte`

C type: 8-bit unsigned integer

`cUInt = Cardinal`

C type: unsigned integer (natural size)

`cUInt16 = Word`

C type: 16 bits sized, unsigned integer.

`cUInt32 = cardinal`

C type: 32 bits sized, unsigned integer.

`cUInt64 = qword`

C type: 64 bits sized, unsigned integer.

`cUInt8 = Byte`

C type: 8 bits sized, unsigned integer.

`cuLong = Cardinal`

C type: long unsigned integer (double sized)

`culonglong = qword`

C type: 64-bit (double long) unsigned integer.

`cunsigned = cUInt`

Alias for `#rtl.unixtype.cuint` ([1495](#))

`cushort = Word`

C type: short unsigned integer (half sized)

`dev_t = cUInt64`

Device descriptor type.

`gid_t = cUInt32`

Group ID type.

`ino_t = cLong`

Inode type.

`kDev_t = cushort`

Kernel device type

`mode_t = cUInt32`

Inode mode type.

`nlink_t = cUInt32`

Number of links type.

`off_t = cInt`

Offset type.

`pcchar = ^cchar`

Pointer to `#rtl.UnixType.cchar` (1493)

`pcDouble = ^cDouble`

Pointer to `cdouble` (1494) type.

`pcFloat = ^cFloat`

Pointer to `cfloat` (1494) type.

`pcInt = ^cInt`

Pointer to `cInt` (1494) type.

`pclDouble = ^clDouble`

Pointer to `cldouble` (1494) type.

`pClock = ^clock_t`

Pointer to `TClock` (1500) type.

`pcLong = ^cLong`

Pointer to `cLong` (1494) type.

`pcshort = ^cshort`

Pointer to `cShort` (1494) type.

`pcuchar = ^cuchar`

Pointer to `#rtl.UnixType.cuchar` (1494)

`pcUInt = ^cUInt`

Pointer to `cUInt` (1495) type.

`pculong = ^cuLong`

Pointer to `cuLong` (1495) type.

`pcunsigned = ^cunsigned`

Pointer to `#rtl.unixtype.cunsigned` (1495)

`pcushort = ^cushort`

Pointer to `cuShort` (1495) type.

`pDev = ^dev_t`

Pointer to `TDev` (1501) type.

`pGid = ^gid_t`

Pointer to `TGid` (1501) type.

`pid_t = cInt32`

Process ID type.

`pIno = ^ino_t`

Pointer to `TIno` (1501) type.

`pkDev = ^kDev_t`

Pointer to `TkDev` (1501) type.

`pMode = ^mode_t`

Pointer to `TMode` (1501) type.

`pnLink = ^nlink_t`

Pointer to `TnLink` (1501) type.

`pOff = ^off_t`

Pointer to `TOff` (1501) type.

`pPid = ^pid_t`

Pointer to `TPid` (1501) type.

`pSize = ^size_t`

Pointer to `TSize` (1502) type.

```
pSize_t = pSize
```

Pointer to size_t (1492) type.

```
pSockLen = ^socklen_t
```

Pointer to TSockLen (1502) type.

```
pSSize = ^ssize_t
```

Pointer to TsSize (1502) type

```
PStatFS = ^TStatfs
```

Pointer to TStatFS (1502) type.

```
pthread_attr_t = record
  __detachstate : cInt;
  __schedpolicy : cInt;
  __schedparam : sched_param;
  __inheritsched : cInt;
  __scope : cInt;
  __guardsize : size_t;
  __stackaddr_set : cInt;
  __stackaddr : pointer;
  __stacksize : size_t;
end
```

pthread_attr_t describes the thread attributes. It should be considered an opaque record, the names of the fields can change anytime. Use the appropriate functions to set the thread attributes.

```
pthread_condattr_t = record
  __dummy : cInt;
end
```

pthread_condattr_t describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_cond_t = record
  __c_lock : _pthread_fastlock;
  __c_waiting : pointer;
  __padding : Array[0..48-1-sizeof(_pthread_fastlock)-sizeof(pointer)-sizeof(clonglong)];
  __align : clonglong;
end
```

pthread_cond_t describes a thread conditional variable. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_key_t = cUInt
```

Thread local storage key (opaque)

```
pthread_mutexattr_t = record
  __mutexkind : cInt;
end
```

`pthread_mutexattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_mutex_t = record
  __m_reserved : cInt;
  __m_count : cInt;
  __m_owner : pointer;
  __m_kind : cInt;
  __m_lock : _pthread_fastlock;
end
```

`_pthread_mutex_t` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlockattr_t = record
  __lockkind : cInt;
  __pshared : cInt;
end
```

`pthread_rwlockattr_t` describes the attributes of a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlock_t = record
  __rw_readers : cInt;
  __rw_writer : pointer;
  __rw_read_waiting : pointer;
  __rw_write_waiting : pointer;
  __rw_kind : cInt;
  __rw_pshared : cInt;
end
```

`pthread_rwlock_t` describes a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_t = cuLong
```

Thread description record

```
pTime = ^time_t
```

Pointer to TTime ([1502](#)) type.

```
ptimespec = ^timespec
```


Pointer to timespec (1501) record.

```
ptimeval = ^timeval
```

Pointer to timeval (1501) record.

```
ptime_t = ^time_t
```

Pointer to time_t (1501) type.

```
pUId = ^uid_t
```

Pointer to TUid (1502) type.

```
pwchar_t = ^wchar_t
```

Pointer to wchar_t (1492) type.

```
sched_param = record  
  __sched_priority : cInt;  
end
```

Scheduling parameter description record.

```
sem_t = record  
  __sem_lock : _pthread_fastlock;  
  __sem_value : cInt;  
  __sem_waiting : pointer;  
end
```

`sem_t` describes a thread semaphore. It should be considered an opaque record, the names of the fields can change anytime.

```
size_t = cUInt32
```

Size specification type.

```
socklen_t = cUInt32
```

Socket address length type.

```
ssize_t = cInt32
```

Small size type.

```
TClock = clock_t
```

Alias for clock_t (1494) type.

TDev = dev_t

Alias for dev_t (1495) type.

TGid = gid_t

Alias for gid_t (1495) type.

```
timespec = packed record
  tv_sec : time_t;
  tv_nsec : cLong;
end
```

Record specifying time interval.

```
timeval = packed record
  tv_sec : cLong;
  tv_usec : cLong;
end
```

Time specification type.

time_t = cLong

Time span type

TIno = ino_t

Alias for ino_t (1495) type.

TkDev = kDev_t

Alias for kDev_t (1495) type.

TMode = mode_t

Alias for mode_t (1496) type.

TnLink = nlink_t

Alias for nlink_t (1496) type.

TOff = off_t

Alias for off_t (1496) type.

TPid = pid_t

Alias for pid_t (1497) type.

TSize = size_t

Alias for size_t (1500) type

TSockLen = socklen_t

Alias for socklen_t (1500) type.

TSSize = ssize_t

Alias for ssize_t (1500) type

```
TStatfs = packed record
  fstype : cInt;
  bsize : cInt;
  blocks : cLong;
  bfree : cLong;
  bavail : cLong;
  files : cLong;
  ffree : cLong;
  fsid : Array[0..1] of cInt;
  namelen : cLong;
  spare : Array[0..5] of cLong;
end
```

Record describing a file system in the baseunix.fpstatfs (1492) call.

TTime = time_t

Alias for TTime (1502) type.

TTimeSpec = timespec

Alias for TimeSpec (1501) type.

TTimeVal = timeval

Alias for TimeVal (1501) record.

TUId = uid_t

Alias for uid_t (1502) type.

uid_t = cUInt32

User ID type

wchar_t = wchar

Wide character type.

```
wint_t = cInt32
```

Wide character size type.

```
_pthread_fastlock = record  
  __status : cLong;  
  __spinlock : cInt;  
end
```

`_pthread_fastlock` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

Chapter 34

Reference for unit 'unixutil'

34.1 Overview

The UnixUtil unit contains some of the routines that were present in the old Linux unit, but which do not really belong in the unix ([1458](#)) or baseunix ([91](#)) units.

Most of the functions described here have cross-platform counterparts in the SysUtils ([1278](#)) unit. It is therefore recommended to use that unit.

34.2 Constants, types and variables

34.2.1 Types

`ComStr =`

Command-line string type.

`DirStr =`

Filename directory part string type.

`ExtStr =`

Filename extension part string type.

`NameStr =`

Filename name part string type.

`PathStr =`

Filename full path string type.

34.2.2 Variables

`Tzseconds : LongInt`

Seconds west of GMT

34.3 Procedures and functions

34.3.1 ArrayStringToPPchar

Synopsis: Convert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array[] of AnsiString;
reserveentries: LongInt) : ppchar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1510](#))

34.3.2 Basename

Synopsis: Return basename of a file

Declaration: `function Basename(const path: PathStr;const suf: PathStr) : PathStr`

Visibility: default

Description: Returns the filename part of `Path`, stripping off `Suf` if it exists. The filename part is the whole name if `Path` contains no slash, or the part of `Path` after the last slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: `DirName` ([1506](#))

Listing: `./unutilx/ex48.pp`

Program `Example48`;

{ Program to demonstrate the BaseName function. }

Uses `Unix, UnixUtil`;

Var `S : String`;

begin

`S:=FExpand(Paramstr(0));`

`Writeln ('This program is called : ',Basename(S,''));`

end.

34.3.3 Dirname

Synopsis: Extract directory part from filename

Declaration: `function Dirname(const path: PathStr) : PathStr`

Visibility: default

Description: Returns the directory part of `Path`. The directory is the part of `Path` before the last slash, or empty if there is no slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: `BaseName` ([1505](#))

Listing: ./unutilx/ex47.pp

Program Example47;

{ Program to demonstrate the DirName function. }

Uses Unix, UnixUtil;

Var S : **String**;

begin

 S:=FExpand(**Paramstr**(0));

WriteLn ('This program is in directory : ',Dirname(S));

end.

34.3.4 EpochToLocal

Synopsis: Convert epoch time to local time

Declaration: `procedure EpochToLocal(epoch: LongInt; var year: Word; var month: Word; var day: Word; var hour: Word; var minute: Word; var second: Word)`

Visibility: default

Description: Converts the epoch time (=Number of seconds since 00:00:00 , January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timzone settings of your system.

Errors: None

See also: `LocalToEpoch` ([1509](#))

Listing: ./unutilx/ex3.pp

Program Example3;

{ Program to demonstrate the EpochToLocal function. }

Uses Unix, UnixUtil;

Var Year, month, day, hour, minute, seconds : **Word**;

```

begin
  EpochToLocal ( GetEpochTime , Year , month , day , hour , minute , seconds );
  Writeln ( ' Current date : ', Day:2 , '/' , Month:2 , '/' , Year:4 );
  Writeln ( ' Current time : ', Hour:2 , ':' , minute:2 , ':' , seconds:2 );
end.

```

34.3.5 FNMatch

Synopsis: Check whether filename matches wildcard specification

Declaration: `function FNMatch(const Pattern: String;const Name: String) : Boolean`

Visibility: default

Description: `FNMatch` returns `True` if the filename in `Name` matches the wildcard pattern in `Pattern`, `False` otherwise.

`Pattern` can contain the wildcards `*` (match zero or more arbitrary characters) or `?` (match a single character).

Errors: None.

See also: `#rtl.unix.FSearch` ([1480](#))

Listing: `./unutilx/ex69.pp`

Program Example69;

{ Program to demonstrate the FNMatch function. }

Uses unixutil;

Procedure TestMatch(Pattern ,Name : String);

```

begin
  Write ( ' " ', Name, ' " ');
  If FNMatch ( Pattern ,Name) then
    Write ( ' matches ')
  else
    Write ( ' does not match ');
  Writeln( ' " ', Pattern, ' " ');
end;

begin
  TestMatch( '* ', 'FileName ');
  TestMatch( '. * ', 'FileName ');
  TestMatch( '* a * ', 'FileName ');
  TestMatch( '? ile * ', 'FileName ');
  TestMatch( '? ', 'FileName ');
  TestMatch( '. ? ', 'FileName ');
  TestMatch( '? a * ', 'FileName ');
  TestMatch( '? ? * me ? ', 'FileName ');
end.

```

34.3.6 FSplit

Synopsis: Split filename into path, name and extension

Declaration: `procedure FSplit(const Path: PathStr; var Dir: DirStr; var Name: NameStr;
var Ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A Path, a Name and an extension (in `ext`). The extension is taken to be all letters after the last dot (.).

Errors: None.

See also: `#rtl.unix.FSearch` ([1480](#))

Listing: `./unutilx/ex67.pp`

Program `Example67;`

`uses UnixUtil;`

`{ Program to demonstrate the FSplit function. }`

`var`

`Path, Name, Ext : string;`

`begin`

`FSplit(ParamStr(1), Path, Name, Ext);`

`WriteLn('Split ', ParamStr(1), ' in:');`

`WriteLn('Path : ', Path);`

`WriteLn('Name : ', Name);`

`WriteLn('Extension : ', Ext);`

`end.`

34.3.7 GetFS

Synopsis: Return file selector

Declaration: `function GetFS(var T: Text) : LongInt`
`function GetFS(var F: File) : LongInt`

Visibility: default

Description: `GetFS` returns the file selector that the kernel provided for your file. In principle you don't need this file selector. Only for some calls it is needed, such as the `#rtl.baseunix.fpSelect` ([160](#)) call or so.

Errors: In case the file was not opened, then -1 is returned.

See also: `#rtl.baseunix.fpSelect` ([160](#))

Listing: `./unutilx/ex34.pp`

Program `Example33;`

`{ Program to demonstrate the SelectText function. }`

`Uses Unix;`

```

Var tv : TimeVal;

begin
  Writeln ( 'Press the <ENTER> to continue the program.' );
  { Wait until File descriptor 0 (=Input) changes }
  SelectText ( Input, nil );
  { Get rid of <ENTER> in buffer }
  readln;
  Writeln ( 'Press <ENTER> key in less than 2 seconds...' );
  tv.tv_sec:=2;
  tv.tv_sec:=0;
  if SelectText ( Input, @tv) > 0 then
    Writeln ( 'Thank you !' )
  else
    Writeln ( 'Too late !' );
end.

```

34.3.8 GregorianToJulian

Synopsis: Converts a gregorian date to a julian date

Declaration: `function GregorianToJulian(Year: LongInt; Month: LongInt; Day: LongInt)
: LongInt`

Visibility: default

Description: `GregorianToJulian` takes a gregorian date and converts it to a Julian day.

Errors: None.

See also: `JulianToGregorian` ([1509](#))

34.3.9 JulianToGregorian

Synopsis: Converts a julian date to a gregorian date

Declaration: `procedure JulianToGregorian(JulianDN: LongInt; var Year: Word;
var Month: Word; var Day: Word)`

Visibility: default

Description: `JulianToGregorian` takes a julian day and converts it to a gregorian date. (Start of the Julian Date count is from 0 at 12 noon 1 JAN -4712 (4713 BC),)

Errors: None.

See also: `GregorianToJulian` ([1509](#))

34.3.10 LocalToEpoch

Synopsis: Convert local time to epoch (unix) time

Declaration: `function LocalToEpoch(year: Word; month: Word; day: Word; hour: Word;
minute: Word; second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00 , January 1, 1970).

Errors: None

See also: EpochToLocal ([1506](#))

Listing: ./unutilex/ex4.pp

Program Example4:

```
{ Program to demonstrate the LocalToEpoch function. }
```

Uses UnixUtil;

```
Var year, month, day, hour, minute, second : Word;
```

begin

```
Write ( 'Year      : ' ); readln ( Year );
```

```
Write ( 'Month' : ' '); readIn (Month);
```

```
Write ( 'Day      : ' ); readln ( Day );
```

```
Write ( 'Hour' : ' '); readIn ( Hour );
```

```
Write ( 'Minute' : ' '); readIn (Minute);
```

```
Write ( 'Seonds : ' ); readIn (Second);
```

```
Write ( 'This is : ' );
```

```
Write (LocalToEpoch(year, month, day, hour, minute, second));
```

```
WriteIn ( ' seconds past 00:00 1/1/1980' );
```

end.

34.3.11 StringToPPChar

Synopsis: Split string in list of null-terminated strings

```
Declaration: function StringToPPChar(S: PChar; ReserveEntries: Integer) : ppchar
            function StringToPPChar(var S: String; ReserveEntries: Integer) : ppchar
            function StringToPPChar(var S: AnsiString; ReserveEntries: Integer)
                : ppchar
```

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of `pchars` that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various `Exec` calls.

Errors: None.

See also: [ArrayStringToPPchar \(1505\)](#), [#rtl.baseunix.FpExecve \(134\)](#)

Listing: ./unutilx/ex70.pp

Program Example70;

```
{ Program to demonstrate the StringToPPchar function. }
```

Uses UnixUtil;

Var S : **String**;
 P : PPChar;
 I : longint;

begin
 // remark whitespace at end.
 S:= 'This is a string with words. ';
 P:=StringToPPChar(S,0);
 I:=0;
 While P[I]<>Nil **do**
 begin
 Writeln('Word ',i, ' : ',P[I]);
 Inc(I);
 end;
 FreeMem(P, i***SizeOf**(Pchar));
end.

Chapter 35

Reference for unit 'video'

35.1 Examples utility unit

The examples in this section make use of the unit `vidutil`, which contains the `TextOut` function. This function writes a text to the screen at a given location. It looks as follows:

35.2 Writing a custom video driver

Writing a custom video driver is not difficult, and generally means implementing a couple of functions, which should be registered with the `SetVideoDriver` (1530) function. The various functions that can be implemented are located in the `TVideoDriver` (1519) record:

```
TVideoDriver = Record
  InitDriver      : Procedure;
  DoneDriver      : Procedure;
  UpdateScreen    : Procedure (Force : Boolean);
  ClearScreen     : Procedure;
  SetVideoMode    : Function (Const Mode : TVideoMode) : Boolean;
  GetVideoModeCount : Function : Word;
  GetVideoModeData : Function (Index : Word; Var Data : TVideoMode) : Boolean;
  SetCursorPos    : procedure (NewCursorX, NewCursorY: Word);
  GetCursorType   : function : Word;
  SetCursorType   : procedure (NewType: Word);
  GetCapabilities : Function : Word;
end;
```

Not all of these functions must be implemented. In fact, the only absolutely necessary function to write a functioning driver is the `UpdateScreen` function. The general calls in the `Video` unit will check which functionality is implemented by the driver.

The functionality of these calls is the same as the functionality of the calls in the `video` unit, so the expected behaviour can be found in the previous section. Some of the calls, however, need some additional remarks.

InitDriver Called by `InitVideo`, this function should initialize any data structures needed for the functionality of the driver, maybe do some screen initializations. The function is guaranteed to be called only once; It can only be called again after a call to `DoneVideo`. The variables

`ScreenWidth` and `ScreenHeight` should be initialized correctly after a call to this function, as the `InitVideo` call will initialize the `VideoBuf` and `OldVideoBuf` arrays based on their values.

DoneDriver This should clean up any structures that have been initialized in the `InitDriver` function. It should possibly also restore the screen as it was before the driver was initialized. The `VideoBuf` and `OldVideoBuf` arrays will be disposed of by the general `DoneVideo` call.

UpdateScreen This is the only required function of the driver. It should update the screen based on the `VideoBuf` array's contents. It can optimize this process by comparing the values with values in the `OldVideoBuf` array. After updating the screen, the `UpdateScreen` procedure should update the `OldVideoBuf` by itself. If the `Force` parameter is `True`, the whole screen should be updated, not just the changed values.

ClearScreen If there is a faster way to clear the screen than to write spaces in all character cells, then it can be implemented here. If the driver does not implement this function, then the general routines will write spaces in all video cells, and will call `UpdateScreen (True)`.

SetVideoMode Should set the desired video mode, if available. It should return `True` if the mode was set, `False` if not.

GetVideoModeCount Should return the number of supported video modes. If no modes are supported, this function should not be implemented; the general routines will return 1. (for the current mode)

GetVideoModeData Should return the data for the `Index`-th mode; `Index` is zero based. The function should return `true` if the data was returned correctly, `false` if `Index` contains an invalid index. If this is not implemented, then the general routine will return the current video mode when `Index` equals 0.

GetCapabilities If this function is not implemented, zero (i.e. no capabilities) will be returned by the general function.

The following unit shows how to override a video driver, with a driver that writes debug information to a file. The unit can be used in any of the demonstration programs, by simply including it in the `uses` clause. Setting `DetailedVideoLogging` to `True` will create a more detailed log (but will also slow down functioning)

35.3 Overview

The `Video` unit implements a screen access layer which is system independent. It can be used to write on the screen in a system-independent way, which should be optimal on all platforms for which the unit is implemented.

The working of the `Video` is simple: After calling `InitVideo` (1527), the array `VideoBuf` contains a representation of the video screen of size `ScreenWidth*ScreenHeight`, going from left to right and top to bottom when walking the array elements: `VideoBuf[0]` contains the character and color code of the top-left character on the screen. `VideoBuf[ScreenWidth]` contains the data for the character in the first column of the second row on the screen, and so on.

To write to the 'screen', the text to be written should be written to the `VideoBuf` array. Calling `UpdateScreen` (1531) will then cp the text to the screen in the most optimal way. (an example can be found further on).

The color attribute is a combination of the foreground and background color, plus the blink bit. The bits describe the various color combinations:

bits 0-3 The foreground color. Can be set using all color constants.

bits 4-6 The background color. Can be set using a subset of the color constants.

bit 7 The blinking bit. If this bit is set, the character will appear blinking.

Each possible color has a constant associated with it, see the constants section for a list of constants.

The foreground and background color can be combined to a color attribute with the following code:

```
Attr:=ForeGroundColor + (BackGroundColor shl 4);
```

The color attribute can be logically or-ed with the blink attribute to produce a blinking character:

```
Attr:=Attr or blink;
```

But not all drivers may support this.

The contents of the `VideoBuf` array may be modified: This is 'writing' to the screen. As soon as everything that needs to be written in the array is in the `VideoBuf` array, calling `UpdateScreen` will copy the contents of the array screen to the screen, in a manner that is as efficient as possible.

The updating of the screen can be prohibited to optimize performance; To this end, the `LockScreenUpdate` (1528) function can be used: This will increment an internal counter. As long as the counter differs from zero, calling `UpdateScreen` (1531) will not do anything. The counter can be lowered with `UnlockScreenUpdate` (1531). When it reaches zero, the next call to `UpdateScreen` (1531) will actually update the screen. This is useful when having nested procedures that do a lot of screen writing.

The video unit also presents an interface for custom screen drivers, thus it is possible to override the default screen driver with a custom screen driver, see the `SetVideoDriver` (1530) call. The current video driver can be retrieved using the `GetVideoDriver` (1525) call.

Remark: The video unit should *not* be used together with the CRT unit. Doing so will result in very strange behaviour, possibly program crashes.

35.4 Constants, types and variables

35.4.1 Constants

`Black = 0`

Black color attribute

`Blink = 128`

Blink attribute

`Blue = 1`

Blue color attribute

`Brown = 6`

Brown color attribute

`cpBlink = $0002`

Video driver supports blink attribute

`cpChangeCursor = $0020`

Video driver supports changing cursor shape.

`cpChangeFont = $0008`

Video driver supports changing screen font.

`cpChangeMode = $0010`

Video driver supports changing mode

`cpColor = $0004`

Video driver supports color

`cpUnderLine = $0001`

Video driver supports underline attribute

`crBlock = 2`

Block cursor

`crHalfBlock = 3`

Half block cursor

`crHidden = 0`

Hide cursor

`crUnderLine = 1`

Underline cursor

`Cyan = 3`

Cyan color attribute

`DarkGray = 8`

Dark gray color attribute

`errOk = 0`

No error


```
ErrorCode : LongInt = ErrOK
```

Error code returned by the last operation.

```
ErrorHandler : TErrorHandler = @DefaultErrorHandler
```

The `ErrorHandler` variable can be set to a custom-error handling function. It is set by default to the `DefaultErrorHandler` (1522) function.

```
ErrorInfo : Pointer = nil
```

Pointer to extended error information.

```
errVioBase = 1000
```

Base value for video errors

```
errVioInit = errVioBase + 1
```

Video driver initialization error.

```
errVioNoSuchMode = errVioBase + 3
```

Invalid video mode

```
errVioNotSupported = errVioBase + 2
```

Unsupported video function

```
FVMaxWidth = 132
```

Maximum screen buffer width.

```
Green = 2
```

Green color attribute

```
iso_codepages = [iso01, iso02, iso03, iso04, iso05, iso06, iso07, iso08, iso09, iso10, iso13, i
```

`iso_codepages` is a set containing all code pages that use an ISO encoding.

```
LightBlue = 9
```

Light Blue color attribute

```
LightCyan = 11
```

Light cyan color attribute

```
LightGray = 7
```

Light gray color attribute

```
LightGreen = 10
```

Light green color attribute

```
LightMagenta = 13
```

Light magenta color attribute

```
LightRed = 12
```

Light red color attribute

```
LowAscii = true
```

On some systems, the low 32 values of the DOS code page are necessary for the ASCII control codes and cannot be displayed by programs. If LowAscii is true, you can use the low 32 ASCII values. If it is false, you must avoid using them.

LowAscii can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to LowAscii, or take its address.

```
Magenta = 5
```

Magenta color attribute

```
NoExtendedFrame = false
```

The VT100 character set only has line drawing characters consisting of a single line. If this value is true, the line drawing characters with two lines will be automatically converted to single lines.

NoExtendedFrame can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to NoExtendedFrame, or take its address.

```
Red = 4
```

Red color attribute

```
ScreenHeight : Word = 0
```

Current screen height

```
ScreenWidth : Word = 0
```

Current screen Width

```
vga_codepages = [cp437, cp850, cp852, cp866]
```

vga_codepages is a set containing all code pages that can be considered a normal vga font (as in use on early VGA cards) Note that KOI8-R has line drawing characters in wrong place.

`vioOK = 0`

No errors occurred

`White = 15`

White color attribute

`Yellow = 14`

Yellow color attribute

35.4.2 Types

`PVideoBuf = ^TVideoBuf`

Pointer type to `TVideoBuf` ([1518](#))

`PVideoCell = ^TVideoCell`

Pointer type to `TVideoCell` ([1519](#))

`PVideoMode = ^TVideoMode`

Pointer to `TVideoMode` ([1520](#)) record.

`Tencoding = (cp437, cp850, cp852, cp866, koi8r, iso01, iso02, iso03, iso04, iso05, iso06, iso07, iso08, iso09, iso10, iso13, iso14, iso15)`

This type is available under Unix-like operating systems only.

`TErrorHandler = function(Code: LongInt; Info: Pointer)
: TErrorHandlerReturnValue`

The `TErrorHandler` function is used to register an own error handling function. It should be used when installing a custom error handling function, and must return one of the above values.

`Code` should contain the error code for the error condition, and the `Info` parameter may contain any data type specific to the error code passed to the function.

`TErrorHandlerReturnValue = (errRetry, errAbort, errContinue)`

Type used to report and respond to error conditions

`TVideoBuf = Array[0..32759] of TVideoCell`

The `TVideoBuf` type represents the screen.

`TVideoCell = Word`

Table 35.1: Enumeration values for type Tencoding

Value	Explanation
cp437	Codepage 437
cp850	Codepage 850
cp852	Codepage 852
cp866	Codepage 866
iso01	ISO 8859-1
iso02	ISO 8859-2
iso03	ISO 8859-3
iso04	ISO 8859-4
iso05	ISO 8859-5
iso06	ISO 8859-6
iso07	ISO 8859-7
iso08	ISO 8859-8
iso09	ISO 8859-9
iso10	ISO 8859-10
iso13	ISO 8859-13
iso14	ISO 8859-14
iso15	ISO 8859-15
koi8r	KOI8-R codepage

Table 35.2: Enumeration values for type TErrorHandlerReturnValue

Value	Explanation
errAbort	abort and return error code
errContinue	abort without returning an errorcode.
errRetry	retry the operation

TVideoCell describes one character on the screen. One of the bytes contains the color attribute with which the character is drawn on the screen, and the other byte contains the ASCII code of the character to be drawn. The exact position of the different bytes in the record is operating system specific. On most little-endian systems, the high byte represents the color attribute, while the low-byte represents the ASCII code of the character to be drawn.

```

TVideoDriver = record
  InitDriver : procedure;
  DoneDriver : procedure;
  UpdateScreen : procedure(Force: Boolean);
  ClearScreen : procedure;
  SetVideoMode : function(const Mode: TVideoMode) : Boolean;
  GetVideoModeCount : function : Word;
  GetVideoModeData : function(Index: Word;var Data: TVideoMode) : Boolean;
  SetCursorPos : procedure(NewCursorX: Word;NewCursorY: Word);
  GetCursorType : function : Word;
  SetCursorType : procedure(NewType: Word);
  GetCapabilities : function : Word;
end

```

`TVideoDriver` record can be used to install a custom video driver, with the `SetVideoDriver` (1530) call.

An explanation of all fields can be found there.

```
TVideoMode = record
  Col : Word;
  Row : Word;
  Color : Boolean;
end
```

The `TVideoMode` record describes a videomode. Its fields are self-explaining: `Col`, `Row` describe the number of columns and rows on the screen for this mode. `Color` is `True` if this mode supports colors, or `False` if not.

```
TVideoModeSelector = function(const VideoMode: TVideoMode;
                               Params: LongInt) : Boolean
```

Video mode selection callback prototype.

35.4.3 Variables

```
CursorLines : Byte
```

`CursorLines` is a bitmask which determines which cursor lines are visible and which are not. Each set bit corresponds to a cursorline being shown.

This variable is not supported on all platforms, so it should be used sparingly.

```
CursorX : Word
```

Current horizontal position in the screen where items will be written.

```
CursorY : Word
```

Current vertical position in the screen where items will be written.

```
external_codepage : Tencoding
```

This variable is for internal use only and should not be used.

```
internal_codepage : Tencoding
```

This variable is for internal use only and should not be used.

```
OldVideoBuf : PVideoBuf
```

The `OldVideoBuf` contains the state of the video screen after the last screen update. The `UpdateScreen` (1531) function uses this array to decide which characters on screen should be updated, and which not.

Note that the `OldVideoBuf` array may be ignored by some drivers, so it should not be used. The Array is in the interface section of the video unit mainly so drivers that need it can make use of it.

ScreenColor : Boolean

ScreenColor indicates whether the current screen supports colors.

VideoBuf : PVideoBuf

VideoBuf forms the heart of the Video unit: This variable represents the physical screen. Writing to this array and calling UpdateScreen (1531) will write the actual characters to the screen.

VideoBufSize : LongInt

Current size of the video buffer pointed to by VideoBuf (1521)

35.5 Procedures and functions

35.5.1 ClearScreen

Synopsis: Clear the video screen.

Declaration: `procedure ClearScreen`

Visibility: default

Description: `ClearScreen` clears the entire screen, and calls `UpdateScreen` (1531) after that. This is done by writing spaces to all character cells of the video buffer in the default color (lightgray on black, color attribute \07).

Errors: None.

See also: `InitVideo` (1527), `UpdateScreen` (1531)

Listing: ./videoex/ex3.pp

```

program testvideo ;

uses video , keyboard , vidutil ;

{ $ifndef cpu86 }
{ $error This example only works on intel 80x86 machines }
{ $endif }

Var
  i : longint ;
  k : TKeyEvent ;

begin
  InitVideo ;
  InitKeyboard ;
  For i:=1 to 10 do
    TextOut(i,i, 'Press any key to clear screen') ;
    UpdateScreen(false) ;
    K:=GetKeyEvent ;
    ClearScreen ;
    TextOut(1,1, 'Cleared screen. Press any key to end') ;
    UpdateScreen(true) ;
    K:=GetKeyEvent ;

```

```

    DoneKeyBoard;
    DoneVideo;
end.
```

35.5.2 DefaultErrorHandler

Synopsis: Default error handling routine.

Declaration: `function DefaultErrorHandler (AErrorCode: LongInt; AErrorInfo: Pointer)
: TErrorHandlerReturnValue`

Visibility: default

Description: `DefaultErrorHandler` is the default error handler used by the video driver. It simply sets the error code `AErrorCode` and `AErrorInfo` in the global variables `ErrorCode` and `ErrorInfo` and returns `errContinue`.

Errors: None.

35.5.3 DoneVideo

Synopsis: Disable video driver.

Declaration: `procedure DoneVideo`

Visibility: default

Description: `DoneVideo` disables the Video driver if the video driver is active. If the videodriver was already disabled or not yet initialized, it does nothing. Disabling the driver means it will clean up any allocated resources, possibly restore the screen in the state it was before `InitVideo` was called. Particularly, the `VideoBuf` and `OldVideoBuf` arrays are no longer valid after a call to `DoneVideo`.

The `DoneVideo` should always be called if `InitVideo` was called. Failing to do so may leave the screen in an unusable state after the program exits.

For an example, see most other functions.

Errors: Normally none. If the driver reports an error, this is done through the `ErrorCode` variable.

See also: `InitVideo` ([1527](#))

35.5.4 GetCapabilities

Synopsis: Get current driver capabilities.

Declaration: `function GetCapabilities : Word`

Visibility: default

Description: `GetCapabilities` returns the capabilities of the current driver. It is an or-ed combination of the following constants:

cpUnderLineVideo driver supports underline attribute

cpBlinkVideo driver supports blink attribute

cpColorVideo driver supports color

cpChangeFontVideo driver supports changing screen font.

cpChangeMode Video driver supports changing mode

cpChangeCursor Video driver supports changing cursor shape.

Note that the video driver should not yet be initialized to use this function. It is a property of the driver.

Errors: None.

See also: [GetCursorType \(1523\)](#), [GetVideoDriver \(1525\)](#)

Listing: ./videoex/ex4.pp

Program Example4;

{ Program to demonstrate the GetCapabilities function. }

Uses video;

Var

W: Word;

Procedure TestCap(Cap: Word; Msg : **String**);

begin

Write(Msg, ' : ');

If (W **and** Cap=Cap) **then**

WriteLn('Yes')

else

WriteLn('No');

end;

begin

 W:=GetCapabilities;

WriteLn('Video driver supports following functionality');

 TestCap(cpUnderLine, 'Underlined characters');

 TestCap(cpBlink, 'Blinking characters');

 TestCap(cpColor, 'Color characters');

 TestCap(cpChangeFont, 'Changing font');

 TestCap(cpChangeMode, 'Changing video mode');

 TestCap(cpChangeCursor, 'Changing cursor shape');

end.

35.5.5 GetCursorType

Synopsis: Get screen cursor type

Declaration: `function GetCursorType : Word`

Visibility: default

Description: `GetCursorType` returns the current cursor type. It is one of the following values:

crHidden Hide cursor

crUnderLine Underline cursor

crBlock Block cursor

crHalfBlock Half block cursor

Note that not all drivers support all types of cursors.

Errors: None.

See also: `SetCursorType` ([1529](#)), `GetCapabilities` ([1522](#))

Listing: `./videoex/ex5.pp`

Program `Example5`;

{ Program to demonstrate the GetCursorType function. }

Uses `video, keyboard, vidutil`;

Const

`CursorTypes : Array[crHidden..crHalfBlock] of string =`
`('Hidden', 'UnderLine', 'Block', 'HalfBlock');`

begin

`InitVideo;`
`InitKeyboard;`
`TextOut(1,1,'Cursor type: '+CursorTypes[GetCursorType]);`
`TextOut(1,2,'Press any key to exit.');`
`UpdateScreen(False);`
`GetKeyEvent;`
`DoneKeyboard;`
`DoneVideo;`

end.

35.5.6 GetLockScreenCount

Synopsis: Get the screen lock update count.

Declaration: `function GetLockScreenCount : Integer`

Visibility: `default`

Description: `GetLockScreenCount` returns the current lock level. When the lock level is zero, a call to `UpdateScreen` ([1531](#)) will actually update the screen.

Errors: None.

See also: `LockScreenUpdate` ([1528](#)), `UnlockScreenUpdate` ([1531](#)), `UpdateScreen` ([1531](#))

Listing: `./videoex/ex6.pp`

Program `Example6`;

{ Program to demonstrate the GetLockScreenCount function. }

Uses `video, keyboard, vidutil`;

Var

`I : Longint;`
`S : String;`

begin

`InitVideo;`

```

InitKeyboard;
TextOut(1,1,'Press key till new text appears. ');
UpdateScreen(False);
Randomize;
For I:=0 to Random(10)+1 do
  LockScreenUpdate;
I:=0;
While GetLockScreenCount<>0 do
begin
  Inc(I);
  Str(I,S);
  UnlockScreenUpdate;
  GetKeyEvent;
  TextOut(1,1,'UnLockScreenUpdate had to be called '+S+' times');
  UpdateScreen(False);
end;
TextOut(1,2,'Press any key to end. ');
UpdateScreen(False);
GetKeyEvent;
DoneKeyboard;
DoneVideo;
end.

```

35.5.7 GetVideoDriver

Synopsis: Get a copy of the current video driver.

Declaration: `procedure GetVideoDriver(var Driver: TVideoDriver)`

Visibility: default

Description: `GetVideoMode` returns the settings of the currently active video mode. The `row`, `col` fields indicate the dimensions of the current video mode, and `Color` is true if the current video supports colors.

Errors: None.

See also: `SetVideoMode` ([1530](#)), `GetVideoModeData` ([1527](#))

Listing: `./videoex/ex7.pp`

Program Example7;

{ Program to demonstrate the GetVideoMode function. }

Uses video, keyboard, vidutil;

Var

M : TVideoMode;
S : **String**;

begin

InitVideo;
InitKeyboard;
GetVideoMode(M);
if M.Color **then**
 TextOut(1,1,'Current mode has color')
else

```

    TextOut(1,1,'Current mode does not have color');
    Str(M.Row,S);
    TextOut(1,2,'Number of rows      : '+S);
    Str(M.Col,S);
    TextOut(1,3,'Number of columns : '+S);
    Textout(1,4,'Press any key to exit. ');
    UpdateScreen(False);
    GetKeyEvent;
    DoneKeyboard;
    DoneVideo;
end.

```

35.5.8 GetVideoMode

Synopsis: Return current video mode

Declaration: `procedure GetVideoMode(var Mode: TVideoMode)`

Visibility: default

Description: Return current video mode

35.5.9 GetVideoModeCount

Synopsis: Get the number of video modes supported by the driver.

Declaration: `function GetVideoModeCount : Word`

Visibility: default

Description: `GetVideoModeCount` returns the number of video modes that the current driver supports. If the driver does not support switching of modes, then 1 is returned.

This function can be used in conjunction with the `GetVideoModeData` ([1527](#)) function to retrieve data for the supported video modes.

Errors: None.

See also: `GetVideoModeData` ([1527](#)), `GetVideoMode` ([1526](#))

Listing: `./videoex/ex8.pp`

Program Example8;

{ Program to demonstrate the GetVideoModeCount function. }

Uses video, keyboard, vidutil;

Procedure DumpMode (M : TVideoMode; Index : Integer);

Var

S : String;

begin

Str(Index:2,S);

inc(Index);

TextOut(1,Index,'Data for mode '+S+' : ');

if M.Color then

```

    TextOut(19, Index, '  color , ')
  else
    TextOut(19, Index, 'No color , ');
  Str(M.Row:3, S);
  TextOut(28, Index, S+ ' rows ');
  Str(M.Col:3, S);
  TextOut(36, index, S+ ' columns ');
end;

Var
  i, Count : Integer;
  m : TVideoMode;

begin
  InitVideo;
  InitKeyboard;
  Count:=GetVideoModeCount;
  For I:=1 to Count do
    begin
      GetVideoModeData(I-1, M);
      DumpMode(M, I-1);
    end;
    TextOut(1, Count+1, 'Press any key to exit ');
    UpdateScreen( False );
    GetKeyEvent;
    DoneKeyboard;
    DoneVideo;
  end.

```

35.5.10 GetVideoModeData

Synopsis: Get the specifications for a video mode

Declaration: `function GetVideoModeData(Index: Word; var Data: TVideoMode) : Boolean`

Visibility: default

Description: `GetVideoModeData` returns the characteristics of the `Index`-th video mode in `Data`. `Index` is zero based, and has a maximum value of `GetVideoModeCount-1`. If the current driver does not support setting of modes (`GetVideoModeCount=1`) and `Index` is zero, the current mode is returned.

The function returns `True` if the mode data was retrieved succesfully, `False` otherwise.

For an example, see `GetVideoModeCount` ([1526](#)).

Errors: In case `Index` has a wrong value, `False` is returned.

See also: `GetVideoModeCount` ([1526](#)), `SetVideoMode` ([1530](#)), `GetVideoMode` ([1526](#))

35.5.11 InitVideo

Synopsis: Initialize video driver.

Declaration: `procedure InitVideo`

Visibility: default

Description: `InitVideo` Initializes the video subsystem. If the video system was already initialized, it does nothing. After the driver has been initialized, the `VideoBuf` and `OldVideoBuf` pointers are initialized, based on the `ScreenWidth` and `ScreenHeight` variables. When this is done, the screen is cleared.

For an example, see most other functions.

Errors: if the driver fails to initialize, the `ErrorCode` variable is set.

See also: `DoneVideo` (1522)

35.5.12 LockScreenUpdate

Synopsis: Prevent further screen updates.

Declaration: `procedure LockScreenUpdate`

Visibility: `default`

Description: `LockScreenUpdate` increments the screen update lock count with one. As long as the screen update lock count is not zero, `UpdateScreen` (1531) will not actually update the screen.

This function can be used to optimize screen updating: If a lot of writing on the screen needs to be done (by possibly unknown functions), calling `LockScreenUpdate` before the drawing, and `UnlockScreenUpdate` (1531) after the drawing, followed by a `UpdateScreen` (1531) call, all writing will be shown on screen at once.

For an example, see `GetLockScreenCount` (1524).

Errors: None.

See also: `UpdateScreen` (1531), `UnlockScreenUpdate` (1531), `GetLockScreenCount` (1524)

35.5.13 SetCursorPos

Synopsis: Set write cursor position.

Declaration: `procedure SetCursorPos (NewCursorX: Word; NewCursorY: Word)`

Visibility: `default`

Description: `SetCursorPos` positions the cursor on the given position: Column `NewCursorX` and row `NewCursorY`. The origin of the screen is the upper left corner, and has coordinates `(0, 0)`.

The current position is stored in the `CursorX` and `CursorY` variables.

Errors: None.

See also: `SetCursorType` (1529)

Listing: `./videoex/ex2.pp`

```

program example2;

uses video , keyboard ;

{$ifndef cpu86}
{$error This example only works on intel 80x86 machines}
{$endif}

Var
```

```

P,PP,D : Integer;
K: TKeyEvent;

Procedure PutSquare (P : Integer; C : Char);

begin
  VideoBuf^[P]:=Ord(C)+($07 shl 8);
  VideoBuf^[P+ScreenWidth]:=Ord(c)+($07 shl 8);
  VideoBuf^[P+1]:=Ord(c)+($07 shl 8);
  VideoBuf^[P+ScreenWidth+1]:=Ord(c)+($07 shl 8);
end;

begin
  InitVideo;
  InitKeyBoard;
  P:=0;
  PP:=-1;
  Repeat
    If PP<>-1 then
      PutSquare(PP, ' ');
      PutSquare(P, '#');
      SetCursorPos(P Mod ScreenWidth,P div ScreenWidth);
      UpdateScreen(False);
      PP:=P;
    Repeat
      D:=0;
      K:=TranslateKeyEvent(GetKeyEvent);
      Case GetKeyEventCode(K) of
        kbdLeft : If (P Mod ScreenWidth)<>0 then
          D:=-1;
        kbdUp : If P>=ScreenWidth then
          D:=-ScreenWidth;
        kbdRight : If ((P+2) Mod ScreenWidth)<>0 then
          D:=1;
        kbdDown : if (P<(VideoBufSize div 2)-(ScreenWidth*2)) then
          D:=ScreenWidth;
      end;
    Until (D<>0) or (GetKeyEventChar(K)='q');
    P:=P+D;
  until GetKeyEventChar(K)='q';
  DoneKeyBoard;
  DoneVideo;
end.

```

35.5.14 SetCursorType

Synopsis: Set cursor type

Declaration: `procedure SetCursorType(NewType: Word)`

Visibility: default

Description: SetCursorType sets the cursor to the type specified in NewType.

crHidden Hide cursor

crUnderLine Underline cursor

crBlock Block cursor

crHalfBlockHalf block cursor

Errors: None.

See also: `SetCursorPos` ([1528](#))

35.5.15 SetVideoDriver

Synopsis: Install a new video driver.

Declaration: `function SetVideoDriver(const Driver: TVideoDriver) : Boolean`

Visibility: default

Description: `SetVideoDriver` sets the videodriver to be used to `Driver`. If the current videodriver is initialized (after a call to `InitVideo`) then it does nothing and returns `False`.

A new driver can only be installed if the previous driver was not yet activated (i.e. before a call to `InitVideo` ([1527](#))) or after it was deactivated (i.e after a call to `DoneVideo`).

For more information about installing a videodriver, see `viddriver` ([1512](#)).

For an example, see the section on writing a custom video driver.

Errors: If the current driver is initialized, then `False` is returned.

See also: `viddriver` ([1512](#))

35.5.16 SetVideoMode

Synopsis: Set current video mode.

Declaration: `function SetVideoMode(const Mode: TVideoMode) : Boolean`

Visibility: default

Description: `SetVideoMode` sets the video mode to the mode specified in `Mode`:

If the call was succesful, then the screen will have `Col` columns and `Row` rows, and will be displaying in color if `Color` is `True`.

The function returns `True` if the mode was set succesfully, `False` otherwise.

Note that the video mode may not always be set. E.g. a console on Linux or a telnet session cannot always set the mode. It is important to check the error value returned by this function if it was not succesful.

The mode can be set when the video driver has not yet been initialized (i.e. before `InitVideo` ([1527](#)) was called) In that case, the video mode will be stored, and after the driver was initialized, an attempt will be made to set the requested mode. Changing the video driver before the call to `InitVideo` will clear the stored video mode.

To know which modes are valid, use the `GetVideoModeCount` ([1526](#)) and `GetVideoModeData` ([1527](#)) functions. To retrieve the current video mode, use the `GetVideoMode` ([1526](#)) procedure.

Errors: If the specified mode cannot be set, then `errVioNoSuchMode` may be set in `ErrorCode`

See also: `GetVideoModeCount` ([1526](#)), `GetVideoModeData` ([1527](#)), `GetVideoMode` ([1526](#))

35.5.17 UnlockScreenUpdate

Synopsis: Unlock screen update.

Declaration: `procedure UnlockScreenUpdate`

Visibility: `default`

Description: `UnlockScreenUpdate` decrements the screen update lock count with one if it is larger than zero.

When the lock count reaches zero, the `UpdateScreen` (1531) will actually update the screen. No screen update will be performed as long as the screen update lock count is nonzero. This mechanism can be used to increase screen performance in case a lot of writing is done.

It is important to make sure that each call to `LockScreenUpdate` (1528) is matched by exactly one call to `UnlockScreenUpdate`

For an example, see `GetLockScreenCount` (1524).

Errors: None.

See also: `LockScreenUpdate` (1528), `GetLockScreenCount` (1524), `UpdateScreen` (1531)

35.5.18 UpdateScreen

Synopsis: Update physical screen with internal screen image.

Declaration: `procedure UpdateScreen(Force: Boolean)`

Visibility: `default`

Description: `UpdateScreen` synchronizes the actual screen with the contents of the `VideoBuf` internal buffer.

The parameter `Force` specifies whether the whole screen has to be redrawn (`Force=True`) or only parts that have changed since the last update of the screen.

The `Video` unit keeps an internal copy of the screen as it last wrote it to the screen (in the `OldVideoBuf` array). The current contents of `VideoBuf` are examined to see what locations on the screen need to be updated. On slow terminals (e.g. a linux telnet session) this mechanism can speed up the screen redraw considerably.

For an example, see most other functions.

Errors: None.

See also: `ClearScreen` (1521)

Chapter 36

Reference for unit 'x86'

36.1 Used units

Table 36.1: Used units by unit 'x86'

Name	Page
BaseUnix	91

36.2 Overview

The x86 unit contains some of the routines that were present in the 1.0.X Linux unit, and which were Intel (PC) architecture specific.

These calls have been preserved for compatibility, but should be considered deprecated: they are not portable and may not even work on future linux versions.

36.3 Procedures and functions

36.3.1 fpIOperm

Synopsis: Set permission on IO ports

Declaration: `function fpIOperm(From: Cardinal; Num: Cardinal; Value: cInt) : cInt`

Visibility: default

Description: `fpIOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns zero if the call was successful, a nonzero value otherwise.

Note:

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `FpFork` ([137](#)), the permissions are reset. When doing a `FpExecVE` ([134](#)) they are kept.

Errors: Extended error information can be retrieved with `FpGetErrno` ([140](#))

36.3.2 fpIoPL

Synopsis: Set I/O privilege level

Declaration: `function fpIoPL(Level: cInt) : cInt`

Visibility: default

Description: `FpIoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

36.3.3 ReadPort

Synopsis: Read data from a PC port

Declaration: `procedure ReadPort(Port: LongInt; var Value: Byte)`
`procedure ReadPort(Port: LongInt; var Value: LongInt)`
`procedure ReadPort(Port: LongInt; var Value: Word)`

Visibility: default

Description: `ReadPort` reads one Byte, Word or Longint from port `Port` into `Value`.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1532) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1532), `ReadPortB` (1533), `ReadPortW` (1534), `ReadPortL` (1534), `WritePort` (1534), `WritePortB` (1535), `WritePortL` (1535), `WritePortW` (1535)

36.3.4 ReadPortB

Synopsis: Read bytes from a PC port

Declaration: `function ReadPortB(Port: LongInt) : Byte`
`procedure ReadPortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortB` reads `Count` bytes from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` bytes.

The functional form of `ReadPortB` reads 1 byte from port `B` and returns the byte that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1532) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1532), `ReadPort` (1533), `ReadPortW` (1534), `ReadPortL` (1534), `WritePort` (1534), `WritePortB` (1535), `WritePortL` (1535), `WritePortW` (1535)

36.3.5 ReadPortL

Synopsis: Read longints from a PC port

Declaration: `function ReadPortL(Port: LongInt) : LongInt`
`procedure ReadPortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortL` reads `Count` longints from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` Longints.

The functional form of `ReadPortL` reads 1 longint from port `B` and returns the longint that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1532) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1532), `ReadPort` (1533), `ReadPortW` (1534), `ReadPortB` (1533), `WritePort` (1534), `WritePortB` (1535), `WritePortL` (1535), `WritePortW` (1535)

36.3.6 ReadPortW

Synopsis: Read Words from a PC port

Declaration: `function ReadPortW(Port: LongInt) : Word`
`procedure ReadPortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortW` reads `Count` words from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` words.

The functional form of `ReadPortW` reads 1 word from port `B` and returns the word that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1532) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1532), `ReadPort` (1533), `ReadPortB` (1533), `ReadPortL` (1534), `WritePort` (1534), `WritePortB` (1535), `WritePortL` (1535), `WritePortW` (1535)

36.3.7 WritePort

Synopsis: Write data to PC port

Declaration: `procedure WritePort(Port: LongInt; Value: Byte)`
`procedure WritePort(Port: LongInt; Value: LongInt)`
`procedure WritePort(Port: LongInt; Value: Word)`

Visibility: default

Description: `WritePort` writes `Value` – 1 byte, `Word` or longint – to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1532) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1532\)](#), [WritePortB \(1535\)](#), [WritePortL \(1535\)](#), [WritePortW \(1535\)](#), [ReadPortB \(1533\)](#), [ReadPortL \(1534\)](#), [ReadPortW \(1534\)](#)

36.3.8 WritePortB

Synopsis: Write byte to PC port

Declaration: `procedure WritePortB(Port: LongInt; Value: Byte)`
`procedure WritePortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1532\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1532\)](#), [WritePort \(1534\)](#), [WritePortL \(1535\)](#), [WritePortW \(1535\)](#), [ReadPortB \(1533\)](#), [ReadPortL \(1534\)](#), [ReadPortW \(1534\)](#)

36.3.9 WritePortL

Synopsis: Write longint to PC port.

Declaration: `procedure WritePortL(Port: LongInt; Value: LongInt)`
`procedure WritePortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1532\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1532\)](#), [WritePort \(1534\)](#), [WritePortB \(1535\)](#), [WritePortW \(1535\)](#), [ReadPortB \(1533\)](#), [ReadPortL \(1534\)](#), [ReadPortW \(1534\)](#)

36.3.10 WritePortW

Synopsis: Write Word to PC port

Declaration: `procedure WritePortW(Port: LongInt; Value: Word)`
`procedure WritePortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1532) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1532), `WritePort` (1534), `WritePortL` (1535), `WritePortB` (1535), `ReadPortB` (1533), `ReadPortL` (1534), `ReadPortW` (1534)